



ArcSight SmartConnectors

Software Version: 8.4.3

Configuration Guide for Tenable SecurityCenter XML File SmartConnector

Document Release Date: October 2023

Software Release Date: October 2023

Legal Notices

Open Text Corporation

275 Frank Tompa Drive, Waterloo, Ontario, Canada, N2L 0A1

Copyright Notice

Copyright 2023 Open Text.

The only warranties for products and services of Open Text and its affiliates and licensors (“Open Text”) are as may be set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Open Text shall not be liable for technical or editorial errors or omissions contained herein. The information contained herein is subject to change without notice.

Trademark Notices

“OpenText” and other Open Text trademarks and service marks are the property of Open Text or its affiliates. All other trademarks or service marks are the property of their respective owners.

Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number
- Document Release Date, which changes each time the document is updated
- Software Release Date, which indicates the release date of this version of the software

To check for recent updates or to verify that you are using the most recent edition of a document, go to:

<https://www.microfocus.com/support-and-services/documentation>

Contents

Configuration Guide for Tenable SecurityCenter XML File SmartConnector	5
Product Overview	6
Configuration	7
Configure SecurityCenter to Work with Nessus	7
Modes of Operation	7
Executing Scripts to Import Nessus Reports in Automatic Mode	8
Increase Memory Size for XML Reports	9
Install the SmartConnector	10
Prepare to Install Connector	10
Install Core Software	10
Set Global Parameters (optional)	11
Select Connector and Add Parameter Information	12
Select a Destination	12
Complete Installation and Configuration	13
Run the SmartConnector	14
Device Event Mapping to ArcSight Fields	15
Tenable SecurityCenter XML Open Ports Mappings	15
Tenable SecurityCenter XML URIs Mappings	16
Tenable SecurityCenter XML Vulnerabilities Mappings	17
Tenable SecurityCenter XML Scanner Mappings	19
Tenable SecurityCenter XML ARF URIs XQuery Mappings	19
Tenable SecurityCenter XML ARF XQuery Mappings	20
Tenable SecurityCenter XML ARF Vulnerabilities XQuery Mappings	20
Tenable SecurityCenter XML ASR XQuery Mappings	21
Troubleshooting	22

Send Documentation Feedback 23

Configuration Guide for Tenable SecurityCenter XML File SmartConnector

This guide provides information for installing the SmartConnector for Tenable SecurityCenter XML File and configuring the device for scan report event collection. For supported devices and versions, see [Technical Requirements](#).

Intended Audience

This guide provides information for IT administrators who are responsible for managing the ArcSight software and its environment.

Additional Documentation

The ArcSight SmartConnector documentation library includes the following resources:

- [Technical Requirements Guide for SmartConnector](#), which provides information about operating system, appliance, browser, and other support details for SmartConnector.
- [Installation and User Guide for SmartConnectors](#), which provides detailed information about installing SmartConnectors.
- [Configuration Guides for ArcSight SmartConnectors](#), which provides information about configuring SmartConnectors to collect events from different sources.
- [Configuration Guide for SmartConnector Load Balancer](#), which provides detailed information about installing Load Balancer.

For the most recent version of this guide and other ArcSight SmartConnector documentation resources, visit the [documentation site for ArcSight SmartConnectors 8.4](#).

Contact Information

We want to hear your comments and suggestions about this book and the other documentation included with this product. You can use the comment on this topic link at the bottom of each page of the online documentation, or send an email to MFI-Documentation-Feedback@opentext.com.

For specific product issues, [contact Open Text Support for Micro Focus products](#).

Product Overview

Tenable's SecurityCenter is a web-based management console that unifies the process of vulnerability detection and management, compliance monitoring, and reporting on all of the above. SecurityCenter enables communication of security events to IT, management, and audit teams.

Using the Nessus API (a custom implementation of the XML-RPC protocol), SecurityCenter communicates with associated Nessus scanners to send scanning instructions and receive results.

Configuration

This section provides instructions for configuring SecurityCenter to work with Nessus. For complete information about configuring Nessus, see Tenable's *Nessus Installation and Configuration Guide*, from which material in this section has been derived.

The SmartConnector for Tenable SecurityCenter XML File supports importing Nessus reports in XML format (not other files) for single or multiple host scans.

Configure SecurityCenter to Work with Nessus

A Nessus Server can be added through the SecurityCenter administration interface. SecurityCenter can be configured to access and control virtually any Nessus scanner.

- 1 Click the **Resources** tab and then click **Nessus Scanners**.
- 2 Click **Add** to open the **Add Scanner** dialog. The Nessus scanner's IP address, Nessus port (default 8834), administrative login ID, authentication type, and password (created while configuring Nessus) are required.

The password fields are not available if **SSL Certificate** authentication is selected. The ability to Verify Hostname is provided to check the CommonName (CN) of the SSL certificate presented by the Nessus server. The state of the Nessus scanner can be set to Enabled or Disabled as needed, with a default of Enabled. Zones to which the Nessus scanner may be assigned can be selected.

For more information, see Tenable's *Security Center Administration Guide*.

Modes of Operation

The SmartConnector for Tenable SecurityCenter XML File supports the following modes of operation:

- **Interactive Mode:**
This mode is valid for connectors installed in stand-alone mode only, not when installed as a service. In this mode, a graphical user interface shows the reports available for importing. You can choose reports to send to the SmartConnector by selecting individual report listings and clicking the **Send** button.
- **Automatic:**
This mode is designed to be used in conjunction with an automated procedure to

periodically run scans with the Nessus Vulnerability Scanner.

To use automatic mode, create a script to schedule the time Nessus should run scans. At the end of the scan, after the report is saved, create an empty file called **{reportname}.xml_done**, which tells the ArcSight SmartConnector that the report is ready for importing. The connector continues to search for .xml_done files and process the reports. The processed reports are renamed to {original report file} + "xml_processed".

Executing Scripts to Import Nessus Reports in Automatic Mode

The configuration of the SmartConnector for Tenable SecurityCenter XML in automatic mode lets you send Nessus reports automatically to ArcSight. To do this, create a shell script that executes the Nessus Vulnerability Scanner periodically and saves a report in XML format. Once the report is created, create a "triggering" file (can be any file) to indicate that the report can be sent to ArcSight. The extension for this file must be defined as .xml_done for XML-format report files.

The following is an sample script (samplenessusscript.sh) to use as a guideline in creating your own script. This sample directs the Nessus Vulnerability Scanner to generate an XML-format report and send it to ArcSight ESM (by automatically creating the .xml_done file).

For more information about creating scripts, see the documentation for the Nessus Vulnerability Scanner at <http://www.nessus.org/documentation/>.

```
#!/bin/sh
XML=xml
XML_DONE=xml_done
NESSUS=/usr/bin/nessus
usage() {
  echo "Usage: samplenessusscript.sh nessusserver port(usually 1241)
nessususer
  nessuspasswd filecontainingtargets reportname xml"
}
# Generate an xml report with the params passed in the command line
$NESSUS -q $1 $2 $3 $4 $5 $6.$7 -T$7
#Now create an empty .xml_done file to trigger the SmartConnector
touch <report-filename>.xml_done
```

To run a script to create an XML report, execute a command such as the following:


```
./<yourScriptName.sh> <yourServer> 1241 <yourUser> <yourPassword>  
<yourTarget.txt> <YourReport xml>
```

Increase Memory Size for XML Reports

The connector cannot process reports that are too lengthy. With the default 256M memory setting, the connector can safely process reports up to 250K in length. If memory is increased to the maximum limit of 1024M, the connector can process reports up to a million lines in length. Longer reports cannot be processed. ArcSight's recommendation for long reports is to split the scan into multiple smaller reports and import them individually.

To increase the memory size for stand-alone connectors from the command line, change the following line in \$ARCSIGHT_HOME\current\bin\scripts\connectors.bat (Windows) or \$ARCSIGHT_HOME/current/bin/scripts/connectors.sh (Unix)

```
ARCSIGHT_MEMORY_OPTIONS=" -Xms256m -Xmx256m "
```

to

```
ARCSIGHT_MEMORY_OPTIONS=" -Xms1024m -Xmx1024m "
```

To increase the memory size for connectors being run as a service, change the following lines in user/agent/agent.wrapper.conf from:

```
wrapper.java.initmemory=256  
wrapper.java.maxmemory=256
```

to:

```
wrapper.java.initmemory=1024  
wrapper.java.maxmemory=1024
```

To increase the memory size for connectors managed by the Connector Appliance/ArcSight Management Center, the heap size can be set using a container level command.

Install the SmartConnector

The following sections provide instructions for installing and configuring your selected SmartConnector.



Connector Appliance/ArcSight Management Center supports mounting for Network File System (NFS) and CIFS (Windows) shares. When you install this connector on one of these devices, establish a CIFS mount on the device before adding the connector. Provide this share name during connector configuration. For more information, see **Remote File Systems** in the Connector Appliance or ArcSight Management Center Administrator's Guide.

Prepare to Install Connector

Before you install any SmartConnectors, make sure that the ArcSight products with which the connectors will communicate have already been installed correctly (such as ArcSight ESM or ArcSight Logger).

For complete product information, read the *Administrator's Guide* as well as the *Installation and Configuration* guide for your ArcSight product before installing a new SmartConnector. If you are adding a connector to the ArcSight Management Center, see the *ArcSight Management Center Administrator's Guide* for instructions, and start the installation procedure at "Set Global Parameters (optional)" or "Select Connector and Add Parameter Information."

Before installing the SmartConnector, be sure the following are available:

- Local access to the machine where the SmartConnector is to be installed
- Administrator passwords

Install Core Software

Unless specified otherwise at the beginning of this guide, this SmartConnector can be installed on all ArcSight supported platforms; for the complete list, see the *SmartConnector Product and Platform Support* document, available from the SSO and Protect 724 sites.

- 1 Download the SmartConnector executable for your operating system from the SSO site.

2 Start the SmartConnector installation and configuration wizard by running the executable.

Follow the wizard through the following folder selection tasks and installation of the core connector software:

- Introduction
- Choose Install Folder
- Choose Shortcut Folder
- Pre-Installation Summary
- Installing...

Set Global Parameters (optional)

If you choose to perform any of the operations shown in the following table, do so before adding your connector. You can set the following parameters:

Parameter	Setting
FIPS mode	Select 'Enabled' to enable FIPS compliant mode. To enable FIPS Suite B Mode, see the SmartConnector User Guide under "Modifying Connector Parameters" for instructions. Initially, this value is set to 'Disabled'.
Remote Management	Select 'Enabled' to enable remote management from ArcSight Management Center. When queried by the remote management device, the values you specify here for enabling remote management and the port number will be used. Initially, this value is set to 'Disabled'.
Remote Management Listener Port	The remote management device will listen to the port specified in this field. The default port number is 9001.
Preferred IP Version	When both IPv4 and IPv6 IP addresses are available for the local host (the machine on which the connector is installed), you can choose which version is preferred. Otherwise, you will see only one selection. The initial setting is IPv4.

The following parameters should be configured only if you are using SecureData solutions to provide encryption. See the *SecureData Architecture Guide* for more information.

Parameter	Setting
Format Preserving Encryption	Data leaving the connector machine to a specified destination can be encrypted by selecting 'Enabled' to encrypt the fields identified in 'Event Fields to Encrypt' before forwarding events. If encryption is enabled, it cannot be disabled. Changing any of the encryption parameters again will require a fresh installation of the connector.
Format Preserving Policy URL	Enter the URL where the SecureData Server is installed.
Proxy Server (https)	Enter the proxy host for https connection if any proxy is enabled for this machine.
Proxy Port	Enter the proxy port for https connection if any proxy is enabled for this machine.
Format Preserving Identity	The SecureData client software allows client applications to protect and access data based on key names. This key name is referred to as the identity. Enter the user identity configured for SecureData.
Format Preserving Secret	Enter the secret configured for SecureData to use for encryption.
Event Fields to Encrypt	Recommended fields for encryption are listed; delete any fields you do not want encrypted and add any string or numeric fields you want encrypted. Encrypting more fields can affect performance, with 20 fields being the maximum recommended. Also, because encryption changes the value, rules or categorization could also be affected. Once encryption is enabled, the list of event fields cannot be edited.

After making your selections, click **Next**. A summary screen is displayed. Review the summary of your selections and click **Next**. Click **Continue** to return to proceed with "Add a Connector" window. Continue the installation procedure with "Select Connector and Add Parameter Information."

Select Connector and Add Parameter Information

- 1 Select **Add a Connector** and click **Next**. If applicable, you can enable FIPS mode and enable remote management later in the wizard after SmartConnector configuration.
- 2 Select **Tenable SecurityCenter XML File** and click **Next**.

Select a Destination

- 1 The next window asks for the destination type; select a destination and click **Next**. For information about the destinations listed, see the *ArcSight SmartConnector User Guide*.

- 2 Enter values for the destination. For the ArcSight Manager destination, the values you enter for **User** and **Password** should be the same ArcSight user name and password you created during the ArcSight Manager installation. Click **Next**.
- 3 Enter a name for the SmartConnector and provide other information identifying the connector's use in your environment. Click **Next**. The connector starts the registration process.
- 4 If you have selected ArcSight Manager as the destination, the certificate import window for the ArcSight Manager is displayed. Select **Import the certificate to the connector from destination** and click **Next**. (If you select **Do not import the certificate to connector from destination**, the connector installation will end.) The certificate is imported and the **Add connector Summary** window is displayed.

Complete Installation and Configuration

- 1 Review the **Add Connector Summary** and click **Next**. If the summary is incorrect, click **Previous** to make changes.
- 2 The wizard now prompts you to choose whether you want to run the SmartConnector as a stand-alone process or as a service. If you choose to run the connector as a stand-alone process, select **Leave as a standalone application**, click **Next**, and continue with step 5.
- 3 If you chose to run the connector as a service, with **Install as a service** selected, click **Next**. The wizard prompts you to define service parameters. Enter values for **Service Internal Name** and **Service Display Name** and select **Yes** or **No** for **Start the service automatically**. The **Install Service Summary** window is displayed when you click **Next**.
- 4 Click **Next** on the summary window.
- 5 To complete the installation, choose **Exit** and Click **Next**.

For instructions about upgrading the connector or modifying parameters, see the *SmartConnector User Guide*.

Run the SmartConnector

SmartConnectors can be installed and run in stand-alone mode, on Windows platforms as a Windows service, or on UNIX platforms as a UNIX daemon, depending upon the platform supported. On Windows platforms, SmartConnectors also can be run using shortcuts and optional Start menu entries.

If the connector is installed in stand-alone mode, it must be started manually and is not automatically active when a host is restarted. If installed as a service or daemon, the connector runs automatically when the host is restarted. For information about connectors running as services or daemons, see the *ArcSight SmartConnector User Guide*.

To run all SmartConnectors installed in stand-alone mode on a particular host, open a command window, go to `$ARCSIGHT_HOME\current\bin` and run: `arcsight connectors`

To view the SmartConnector log, read the file `$ARCSIGHT_HOME\current\logs\agent.log`; to stop all SmartConnectors, enter `Ctrl+C` in the command window.

Device Event Mapping to ArcSight Fields

The following section lists the mappings of ArcSight data fields to the device's specific event definitions. See the *ArcSight Console User's Guide* for more information about the ArcSight data fields.

Tenable SecurityCenter XML Open Ports Mappings

ArcSight ESM Field	Device-Specific Field
Additional data	EndTime
Additional data	LocalChecksProto
Additional data	netbiosName
Additional data	ReportName
Additional data	smbLoginUsed
Agent (Connector) Severity	Very High = High or Hole; High = Medium or Warning; Medium = Low or Informational; Low = Open Port
Application Protocol	ServicesName
Category Technique	VulnerabilityCategory(1)
Destination Address	One of (TargetIpAddress, TargetHostName)
Destination Host Name	One of (TargetHostNameFQDN, TargetHostName)
Destination Mac Address	TargetMacAddress
Destination Port	Port
Destination Process Name	ServicesName
Device Custom String 1	cwe (Common Weakness Enumeration)
Device Custom String 2	pluginName (Plugin Name)
Device Custom String 3	Revision
Device Event Category	EventCategory
Device Event Class ID	Both ('Nessus', NessusID)
Device Outbound Interface	One of (TargetHostNameFQDN, TargetHostName)
Device Product	'Nessus'
Device Receipt Time	DetectTime

ArcSight ESM Field	Device-Specific Field
Device Severity	Risk (0=Open Port, 1=Low or Informational, 2=Medium or Warning, 3=High or Hole)
Device Vendor	'Nessus'
End Time	EndTime
File Name	fname
Message	Description
Name	All of ('Open Port:', ServicesName, Port, Protocol)
Start Time	DetectTime
Transport Protocol	Protocol

Tenable SecurityCenter XML URIs Mappings

ArcSight ESM Field	Device-Specific Field
Additional data	EndTime
Additional data	localChecksProto
Additional data	netbiosName
Additional data	ReportName
Additional data	smbLoginUsed
Agent (Connector) Severity	Low = Operating System
Category Technique	VulnerabilityCategory(4)
Destination Address	One of (TargetIpAddress, TargetHostName)
Destination Host Name	One of (TargetHostNameFQDN, TargetHostName)
Destination Mac Address	TargetMacAddress
Device Event Class ID	Both ('Nessus', NessusID)
Device Outbound Interface	One of (TargetHostNameFQDN, TargetHostName)
Device Product	'Nessus'
Device Severity	Operating System
Device Vendor	'Nessus'
File Path	OS
Name	Both ('Operating System', OS)

Tenable SecurityCenter XML Vulnerabilities Mappings

ArcSight ESM Field	Device-Specific Field
Additional data	CVE
Additional data	cvssBaseScore
Additional data	cvssVector
Additional data	Exploitability_ease
Additional data	Exploit_framework_canvas
Additional data	localChecksProto
Additional data	netbiosName
Additional data	PatchPublicationDate
Additional data	PluginModificationDate
Additional data	PluginOutput
Additional data	PluginPublicationDate
Additional data	PluginVersion
Additional data	ReportName
Additional data	RiskFactor
Additional data	smbLoginUsed
Additional data	Solution
Additional data	Synopsis
Additional data	VulnPublicationDate
Agent (Connector) Severity	Very High = 3,4; High = 2, Medium = 1, Low = 0
Application Protocol	ServicesName
Category Technique	VulnerabilityCategory(0)
Destination Address	One of (TargetIpAddress, TargetHostName)
Destination Host Name	One of (TargetHostNameFQDN, TargetHostName)
Destination Mac Address	TargetMacAddress
Destination Port	Port
Destination Process Name	ServicesName
Device Custom Number 1	cert (CERT)

ArcSight ESM Field	Device-Specific Field
Device Custom String 1	cwe (Common Weakness Enumeration)
Device Custom String 2	CVE
Device Custom String 3	Revision
Device Custom String 4	XREF
Device Custom String 5	BugtraqID
Device Custom String 6	cvssBaseScore
Device Domain	'Network'
Device Event Category	EventCategory
Device Event Class ID	All of ('Nessus', NessusID, pluginName, Risk, Description, Synopsis, Solution, XREF, URL, CVE)
Device Outbound Interface	One of (TargetHostNameFQDN, TargetHostName)
Device Product	'Nessus'
Device Receipt Time	DetectTime
Device Severity	Risk
Device Vendor	'Nessus'
Device Version	'V2'
End Time	EndTime
File Name	fname
Flex Number 1	DetectTime
Flex Number 2	EndTime
Flex String 1	Description
Flex String 2	Solution
Message	Description
Name	Both ('Vulnerability', Name)
Old File Name	Attachment
Old File Path	_FILE_PATH
Request Client Application	CommonPlatformEnumeration
Request Context	Exploit_available
Request URL	URL
Start Time	DetectTime
Transport Protocol	Protocol

Tenable SecurityCenter XML Scanner Mappings

ArcSight ESM Field	Device-Specific Field
Destination Address	One of (TargetIpAddress, TargetHostName)
Destination Host Name	One of (TargetHostNameFQDN, TargetHostName)
Destination Mac Address	TargetMacAddress
Device Outbound Interface	One of (TargetHostNameFQDN, TargetHostName)

Tenable SecurityCenter XML ARF URIs XQuery Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Category Technique	__getVulnerabilityCategory(4)
Destination Address	IPV4
Destination FQDN	All of (HostName, REALM)
Destination Host Name	HostName
Destination Mac Address	mac
Device Custom Number 1	AttributesRecordIdentifier
Device Custom String 3	Resource
Device Custom String 4	Assessedname
Device Event Class ID	Asset Created
Device Inbound Interface	Interface
Device Product	'Nessus'
Device Receipt Time	times
Device Severity	Low
Device Vendor	'Tenable'
File Path	Assessedname
Name	All of ("Operating System: (Assessedname, "No OS name available", Assessedname)

Tenable SecurityCenter XML ARF XQuery Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Category Technique	__getVulnerabilityCategory(0)
Destination Address	IPV4
Destination FQDN	All of (HostName, REALM)
Destination Host Name	HostName
Destination Mac Address	mac
Device Custom Number 1	AttributesRecordedIdentifier
Device Custom String 3	Resource
Device Custom String 4	Assessedname
Device Event Class ID	Asset report object created
Device Inbound Interface	Interface
Device Product	'Nessus'
Device Receipt Time	times
Device Severity	Low
Device Vendor	'Tenable'
Name	Asset report object created

Tenable SecurityCenter XML ARF Vulnerabilities XQuery Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	veryhigh = fail, Fail; medium = Warning; low = success, Success
Category Technique	__getVulnerabilityCategory(0)
Destination Host Name	record_identifier
Device Custom String 2	all_record_identifiers
Device Custom String 4	ruleID
Device Event Class ID	All of (Nessus = ruleID, all of(ruleResult, count, CVE))

ArcSight ESM Field	Device-Specific Field
Device Product	'Nessus'
Device Severity	ruleResult
Device Vendor	'Tenable'
Event Outcome	ruleResult
Name	ASR: ruleID

Tenable SecurityCenter XML ASR XQuery Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	veryhigh = fail, Fail; medium = Warning; low = success, Success
Category Technique	__getVulnerabilityCategory(0)
Destination Host Name	record_identifier
Device Custom String 4	ruleID
Device Event Class ID	All of (Nessus = ruleID,all of(ruleResult,count, CVE))
Device Product	'Nessus'
Device Severity	ruleResult
Device Vendor	'Tenable'
Event Outcome	ruleResult

Troubleshooting

What if I stop the processing of a vulnerability scan XML file?

When a user kills the SmartConnector in the middle of processing a vulnerability scan XML file, asset population cannot be completed. Restarting the SmartConnector does not resolve this problem. The workaround is to rename the XML file to its original file name and then restart the SmartConnector.

please confirm that when customer used MySQL JDBC driver 5.1.38, they had issue to receive events. And the workaround is to apply older driver 5.0.8, after that connector is able to receive events.

Send Documentation Feedback

If you have comments about this document, you can [contact the documentation team](#) by email. If an email client is configured on this computer, click the link above and an email window opens with the following information in the subject line:

Feedback on Configuration Guide for Tenable SecurityCenter XML File SmartConnector (SmartConnectors 8.4.3)

Just add your feedback to the email and click send.

If no email client is available, copy the information above to a new message in a web mail client, and send your feedback to MFI-Documentation-Feedback@opentext.com.

We appreciate your feedback!