



ArcSight Model Import Connector

Software Version: 8.4.0

MISP - Open Source Threat Intelligence and Sharing Platform Solution

Document Release Date: February 2022

Software Release Date: February 2022

Legal Notices

Open Text Corporation

275 Frank Tompa Drive, Waterloo, Ontario, Canada, N2L 0A1

Copyright Notice

Copyright 2016-2024 Open Text.

The only warranties for products and services of Open Text and its affiliates and licensors (“Open Text”) are as may be set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Open Text shall not be liable for technical or editorial errors or omissions contained herein. The information contained herein is subject to change without notice.

Trademark Notices

“OpenText” and other Open Text trademarks and service marks are the property of Open Text or its affiliates. All other trademarks or service marks are the property of their respective owners.

Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number
- Document Release Date, which changes each time the document is updated
- Software Release Date, which indicates the release date of this version of the software

To check for recent updates or to verify that you are using the most recent edition of a document, go to:

<https://www.microfocus.com/support-and-services/documentation>

Support

Contact Information

Phone	A list of phone numbers is available on the Technical Support Page: https://softwaresupport.softwaregrp.com/support-contact-information
Support Web Site	https://softwaresupport.softwaregrp.com/
ArcSight Product Documentation	https://www.microfocus.com/documentation/arcsight/

Contents

- Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution) 4
- Product Overview 5
- Installing the Connector 5
- Model Import Connector Installation 5
- Setting up the Model Import User in ESM 9
- Running Connectors 10
- Starting and Stopping Data Import 10
- Administrative Tasks - Open Source Threat Intelligence and Sharing Platform Solution Using the ArcSight Console 11
- Features and Functional Summary 11
- Optional - Optimization of Data Transfer Using a Timer 12
- Optional - Reloading Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution) Data 12
- Connector Upgrade 13
- Troubleshooting 14
 - Duplicate Entries of ArcSight Wrapper Parameters in the "agent.wrapper.conf" File . 14
- Publication Status 14

- Send Documentation Feedback 15

Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution)

This guide describes installing the Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution) and configuring the device for data collection.

The Micro Focus Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution) uses Threat Intelligence to provide known bad of harmful domains, IP addresses, emails, hash values, and URLs to provide context to security events. The Micro Focus Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution) is a component which retrieves Threat Intelligence from the MISP (Open Source Threat Intelligence and Sharing Platform Solution) instance, processes this data, and forwards it to ArcSight ESM.



Note: The MISP Connector will be deprecated for the ArcSight 23.1 release, the first release of 2023. Customers using MISP today are strongly advised to migrate to the Galaxy Threat Acceleration Program (GTAP), which includes support for MISP and premium intelligence feeds. For more information, see the [Configuration Guide for CyberRes Galaxy Threat Acceleration Program SmartConnector](#).

Product Overview

The Micro Focus Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution) uses Threat Intelligence to detect Advance Persistent Threats, Ransomware, Phishing, Botnets and Cryptojacking. as well as provide context to security events. The Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution) is a component which retrieves Threat Intelligence from the MISP Open Source Threat Intelligence and Sharing Platform Solution) instance, processes this data, and forwards it to ArcSight ESM.

Installing the Connector

Before installing the connector, verify that ESM (the product with which the connector will communicate) and Console have already been installed correctly. It is recommended that the connector not be installed on the same machine as ESM. Also, be sure the following are available before proceeding to install the connector:

- Additional 2GB memory if the connector is running in a standalone mode.
- Local administrator access to the machine on which the connector will be installed.
- The machine, on which the connector will be installed, has external access over the Internet to any system over port 443 and connectivity to the ESM machine over port 8443 (default) or the configured port if the default was not used.
- Authorization key for the MISP server instance.
- ESM IP address, port, administrator user name, and password.



Note: When installing the connector as a Linux daemon, run the following command as root and ensure the -u parameter is a non-root user:

```
$ARCSIGHT_HOME/current/bin/arcsight agentsvc -i -u user -sn <service_name>
```

- The Threat Intelligence Platform package, in /All Packages/ArcSight Foundation/Threat Intelligence Platform is installed.

Model Import Connector Installation

This section provides instructions on how to install the Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution).



Note: Use a non-root account to install the Micro Focus Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution).

To install the OpenText Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution)

1. Download the Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution) installation executable from entitlement.microfocus.com
2. Start the connector installer by running the executable.



Note: The **OpenText Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution)** installation requires additional steps after the installation wizard has finished. See step 14 of this procedure and subsequent steps for details.

Follow the installation wizard through the following folder selection tasks and installation of the core connector software:

- Introduction
 - Choose Install Folder
 - Choose Shortcut Folder
 - Pre-Installation Summary
 - Installing
3. Select **Add a Connector**.
 4. **OpenText Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution)** is already selected. Click **Next**.
 5. Enter the required parameters to configure the connector, then click **Next**.

If you are installing the MISP connector in FIPS mode:

- a. Run the connector install up to the connector framework step and cancel the installation.
The connector install may be resumed using the `runagentsetup` script.
- b. Export the MISP Instance certificate from the browser as a DER encoded binary x.509 (.CER) file.
- c. Import the MISP Instance exported certificate into the connector framework FIPS keystore, using a command similar to the example below (run the command from the connector current directory):

```
./jre/bin/keytool -importcert -file /opt/certificate.cer -keystore $ARCSIGHT_HOME/current/user/agent/fips/bcfips_ks -storepass changeit -storetype BCFKS -providername BCFIPS -providerclass org.bouncycastle.jcajce.provider.BouncyCastleFipsProvider -providerpath $ARCSIGHT_HOME/current/lib/agent/fips/bc-fips-1.0.2.jar -J-Djava.security.egd=file:/dev/urandom -alias mispInstance
```

d. Complete the connector install by running `./current/bin/runagentsetup`.

The file extensions are:

- For Linux —.sh
- For Windows —.bat

Parameter Name	Description
Proxy Host(https)	Use this field and the following three fields only if you need the connector to use a proxy to access the Internet. Proceed with the proxy configuration: Enter the proxy host IP address.
Proxy Port	Enter the proxy port.
Proxy User Name	Enter the proxy user name. This value is populated when the proxy requires an authentication. Note: If you specify a proxy user name, you must also specify a proxy password.
Proxy Password	Enter the password of the proxy user. This value is populated when the proxy requires an authentication and if you have specified a proxy user name.
MISP URL	Enter the Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution) instance url.
Authorization Key	Enter the authorization key. To obtain the authorization key: <ol style="list-style-type: none"> Log in to the GUI of the Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution) instance. Go to Global Actions > My Profile. Click Authorization keys. Click Add Authentication Key. Enter MISP MIC in the comment box (optional). Set expiration date (optional). Click Submit. A new dialog opens with the generated API Key; the key is displayed only once.
Enforce Warning List	Remove any attributes from the result that would cause a hit on a warning list entry.

6. **ArcSight Manager (encrypted)** is selected. Click **Next**.

7. Enter destination parameters, including the host and port information, and click **Next**.

Parameter	Description
Manager Host Name	Enter the name or IP address of the host on which the Manager is installed.
Manager Port	Enter the network port from which the Manager is accepting requests. The default port is 8443 .
User Name	Enter a valid ArcSight user name to log in to configure the SmartConnector. This is the same user name you created during the Manager installation.
Password	Enter a valid ArcSight password to log in to configure the SmartConnector. This is the same password you created during the Manager installation.
AUP Master Destination	Select true or false .
Filter Out All Events	Select true or false .
Enable Demo CA	Select true or false .

8. Enter a **Name** for the connector and provide other information identifying the connector's use in your environment. Click **Next**.
9. Select whether to import a certificate.
10. Review the **Add connector Summary** and click **Next**. If the summary is incorrect, click **Previous** to make changes.

The wizard now prompts you to choose whether you want to run the connector as a stand-alone process or as a service. Choose either **Install as a service** or **Leave as a standalone application**. Click **Next**.

11. To close the installation wizard, choose **Exit** and click **Next**. There are further installation steps after you close the wizard. Be sure to continue with the subsequent installation steps.
12. Increase the java heap memory for the connector by doing the following (ARCSIGHT_HOME represents the name of the directory where the connector is installed):
 - a. If you running the connector as a Windows service or Linux daemon , set the heap size in the following file:~. . /current/user/agent.wrapper.conf
Set the following parameters:

```
#Initial Java Heap Size (in MB)
wrapper.java.initmemory=1024
#Maximum Java Heap Size (in MB)
wrapper.java.maxmemory=2048
```
 - b. If you are going to run the connector as Standalone mode:
 - i. For Linux - create the following shell script and be sure it is executable:

```
~/ARCSIGHT_HOME/current/user/agent/setmem.sh
```


with the following content:

```
ARCSIGHT_MEMORY_OPTIONS=" -Xms1024m -Xmx2048m "
```

- ii. For Windows - create the following batch file:

```
$ARCSIGHT_HOME\current\user\agent\setmem.bat
```

with the following content:

```
SET ARCSIGHT_MEMORY_OPTIONS= -Xms1024m -Xmx2048m
```

Use regular double quote characters in the file content in either the shell script or the batch file.

13. Verify that the connector is running. You can check the ArcSight Console Navigator in the Resources tab, under Connectors. If the connector is running, you will see **<connector_name> (running)** listed. See [Running Connectors](#).
14. Set up the Model Import user in ESM. See [Setting up the Model Import User in ESM](#).
15. Start the data import. See [Starting and Stopping Data Import](#).

Setting up the Model Import User in ESM

After installing, configuring, and starting the connector, from the ArcSight Console set the Model Import User for the connector (this must be a user with Console administrative privileges). Setting the user links the user to the resources, and that user is then treated as the “creator” of resources. The connector is then run on that user’s behalf.

1. From the ArcSight Console, go to the **Navigator** panel and choose the **Resources** tab.
2. Under **Resources**, choose the **Connectors** resource.
3. Under **All Connectors**, navigate to your **OpenText Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution)**.
4. Right click on the connector and select **Configure**.
5. On the **Inspect/Edit** panel, choose the **Connector** tab.
6. Under the **Connector** tab, go to **Model Import User** and select a user from the **Administrators** group.
7. Click **OK**.



Note: If a user that does not have administrator privileges is used, the import will fail.

Running Connectors

Connectors can be installed and run in standalone mode, on Windows platforms as a Windows service, or on UNIX platforms as a UNIX daemon, depending upon the platform supported. On Windows platforms, connectors also can be run using shortcuts and optional Start menu entries.

If installed standalone, the connector must be started manually, and is not automatically active when a host is restarted. If installed as a service or daemon, the connector runs automatically when the host is restarted. For information about connectors running as services or daemons, see the ArcSight SmartConnector User's Guide, Chapter 3, Installing SmartConnectors, in the section "Running SmartConnectors".

For connectors installed as standalone mode, to run the connector on a particular host, open a command window, go to `$ARCSIGHT_HOME\current\bin` and run: `./arcsight agents`

To view the connector log, read the file:

For Windows - `$ARCSIGHT_HOME\current\logs\agent.log`

For Linux - `~/ARCSIGHT_HOME/current/logs/agent.log`

To stop the connector, enter `Ctrl+C` in the command window.



Note: By default, the connector collects events starting one month prior to the installation day. This parameter can be changed by modifying the `start.date` field in the `../current/user/agent/agent.properties` file. The format of the field is `YYYY-MM-DD`. The connector can only collect up to 12 months from the installation date. If the `start.date` set, is a period longer than 12 months, the default time of one month will be used. The MISP Instance timezone is defined in the `PHP.ini` file on the MISP Instance host.

Starting and Stopping Data Import

By default the connector's data import capability is not started. You must start the import manually in the ArcSight Console.



Note: Data import needs to be started only once from the ArcSight Console. Unless it is stopped from the ArcSight Console, there is no need to restart the data import.

To start and stop import for the Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution):

1. Select the **Micro Focus Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution)** and right-click.
2. Select **Send Command > Model Import Connector > Start** or **Stop**.

Administrative Tasks - Open Source Threat Intelligence and Sharing Platform Solution Using the ArcSight Console

There are mandatory and optional administrative tasks. [Setting up the Model Import User in ESM](#) and [Starting and Stopping Data Import](#) are mandatory steps for connector installation, and are mentioned as part of the installation procedure. See [Installing the Connector](#) for details. You might also find that you need to perform these tasks outside of the context of the installation procedure.

Features and Functional Summary

The Micro Focus Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution) retrieves Threat Intelligence events/ attribute data and uploads it to ESM Active Lists found under /All Active Lists/ ArcSight Foundation/ Threat Intelligence Platform

These entries are:

- IP addresses
- Domains name
- Emails
- Hash values
- URLs

This connector supports only one ESM destination.

Optional - Optimization of Data Transfer Using a Timer

The time interval between archives sent by the connector to ESM can be controlled by the `buildmodeldelay` property. The default value is 1 minute.

To increase or decrease this time interval, you can add the `buildmodeldelay` property to the file `agent.properties` (located at `$ARCSIGHT_HOME\current\user\agent`). The property `buildmodeldelay` is expressed in milliseconds.

For example, the following property sets the time interval to 10 seconds:

```
agent.component[35].buildmodeldelay=10000
```

Optional - Reloading Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution) Data

To reload Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution) data:

1. If active, stop the connector.
2. Remove all files at:
Linux - `~/ARCSIGHT_HOME/current/user/agent/agentdata`
Windows - `$\ARCSIGHT_HOME\current\user\agent\agentdata`
3. At the ArcSight Console, clear all entries in the Suspicious Domain List, Suspicious Email List, Suspicious Hash List and Suspicious URL List. For each Active List:
 - a. Under **Threat Intelligence Platform**, select the, **Suspicious Domain List**, **Suspicious Addresses List**, **Suspicious Email List**, **Suspicious Hash List** and/ or the **Suspicious URL List** and right-click.
 - b. Select **Clear Entries**.
4. Restart the connector.

Connector Upgrade

Perform the following steps to upgrade the Micro Focus Model Import Connector for MISP (Open Source Threat Intelligence and Sharing Platform Solution):

1. Stop the connector.
 2. Run the connector installer.
 3. Select the location of the connector that you want to upgrade.
 4. Select the option to continue and upgrade the connector.
 5. The upgraded connector is installed in the `$ARCSIGHT_HOME\current` folder.
 6. The original installation folder is renamed by prefacing characters.
 7. Run the **runagentsetup.exe** file.
 8. Specify your ESM account credentials, when prompted.
- The connector upgrade completes successfully.

Troubleshooting

This section includes the following troubleshooting information:

Duplicate Entries of ArcSight Wrapper Parameters in the "agent.wrapper.conf" File

After upgrading the connector, the `agent.wrapper.conf` file will contain duplicate entries of the `wrapper.java.initmemory` and `wrapper.java.maxmemory` parameters. However, this issue does not occur in the fresh installation of SmartConnector 8.3.0 or later.

Workaround:

To fix this issue, delete the duplicate entries of the `wrapper.java.initmemory` and `wrapper.java.maxmemory` parameters from the `agent.wrapper.conf` file.

Publication Status

Released: NOT RELEASED

Send Documentation Feedback

If you have comments about this document, you can [contact the documentation team](#) by email. If an email client is configured on this computer, click the link above and an email window opens with the following information in the subject line:

Feedback on MISP - Open Source Threat Intelligence and Sharing Platform Solution (Model Import Connector 8.4.0)

Just add your feedback to the email and click send.

If no email client is available, copy the information above to a new message in a web mail client, and send your feedback to MFI-Documentation-Feedback@opentext.com.

We appreciate your feedback!