



# ArcSight SmartConnectors

Software Version: 8.4.3

## Configuration Guide for Juniper Steel-Belted Radius File SmartConnector

Document Release Date: October 2023

Software Release Date: October 2023

## Legal Notices

Open Text Corporation

275 Frank Tompa Drive, Waterloo, Ontario, Canada, N2L 0A1

## Copyright Notice

Copyright 2023 Open Text.

The only warranties for products and services of Open Text and its affiliates and licensors (“Open Text”) are as may be set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Open Text shall not be liable for technical or editorial errors or omissions contained herein. The information contained herein is subject to change without notice.

## Trademark Notices

“OpenText” and other Open Text trademarks and service marks are the property of Open Text or its affiliates. All other trademarks or service marks are the property of their respective owners.

## Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number
- Document Release Date, which changes each time the document is updated
- Software Release Date, which indicates the release date of this version of the software

To check for recent updates or to verify that you are using the most recent edition of a document, go to:

<https://www.microfocus.com/support-and-services/documentation>

# Contents

Configuration Guide for Juniper Steel-Belted Radius File SmartConnector .....	4
Product Overview .....	5
Configuring the Device for Event Collection .....	6
Authentication Log Files .....	6
Accounting Log Files .....	7
Authentication Acceptance Log Files .....	8
Authentication Rejection Log Files .....	8
Enabling and Disabling Log Files .....	9
Install the SmartConnector .....	10
Prepare to Install Connector .....	10
Install Core Software .....	10
Set Global Parameters (optional) .....	11
Select Connector and Add Parameter Information .....	12
Select a Destination .....	13
Complete Installation and Configuration .....	13
Log Rotation Scheme .....	15
Run the SmartConnector .....	16
Device Event Mapping to ArcSight Fields .....	17
Juniper Steel-Belted Radius ACCEPT Log Mappings .....	17
Juniper Steel-Belted Radius REJECT Log Mappings .....	17
Juniper Steel-Belted Radius ACCOUNTING Log Mappings .....	18
Juniper Steel-Belted Radius Authentication Log Mappings .....	19
Send Documentation Feedback .....	21

# Configuration Guide for Juniper Steel-Belted Radius File SmartConnector

This guide provides information for installing the SmartConnector for Juniper Steel-Belted Radius File and configuring the device for event collection.

## Intended Audience

This guide provides information for IT administrators who are responsible for managing the ArcSight software and its environment.

## Additional Documentation

The ArcSight SmartConnector documentation library includes the following resources:

- [Technical Requirements Guide for SmartConnector](#), which provides information about operating system, appliance, browser, and other support details for SmartConnector.
- [Installation and User Guide for SmartConnectors](#), which provides detailed information about installing SmartConnectors.
- [Configuration Guides for ArcSight SmartConnectors](#), which provides information about configuring SmartConnectors to collect events from different sources.
- [Configuration Guide for SmartConnector Load Balancer](#), which provides detailed information about installing Load Balancer.

For the most recent version of this guide and other ArcSight SmartConnector documentation resources, visit the [documentation site for ArcSight SmartConnectors 8.4](#).

## Contact Information

We want to hear your comments and suggestions about this book and the other documentation included with this product. You can use the comment on this topic link at the bottom of each page of the online documentation, or send an email to [MFI-Documentation-Feedback@opentext.com](mailto:MFI-Documentation-Feedback@opentext.com).

For specific product issues, [contact Open Text Support for Micro Focus products](#).

# Product Overview

Steel-Belted Radius is an implementation of the RADIUS (Remote Authentication Dial In User Service) protocol that runs in Windows, Solaris, or Linux environments. It interfaces with a wide variety of network access equipment and authenticates remote and WLAN users against numerous back-end databases, letting the administration of your remote and WLAN users be consolidated, however they connect to the network. Steel-Belted Radius records usage statistics in an accounting database for tracking and documenting user sessions for accounting and billing.

# Configuring the Device for Event Collection

The SmartConnector for Juniper Steel-Belted Radius supports the Accounting, Authentication, Authentication Accept, and Authentication Reject logs.



Only the default log format is supported; changing the format of these logs will cause parsing problems.

The following files establish settings for logging and reporting. For complete information, see the *Juniper Steel-Belted Radius Reference Guide* for details about these initialization files and "Logging and Reporting" in the *Juniper Steel-Belted Radius Administration Guide* for how to set up and use logging and reporting in Steel-Belted Radius.

File Name	Function
account.ini	Controls how RADIUS accounting attributes are logged.
authlog.ini	Controls how RADIUS authentication requests are logged.
authReport.ini	Controls what authentication logs are generated.
authReportAccept.ini	Controls options for the acceptance authentication log file.
authReportReject.ini	Controls options for the rejection authentication log file.

## Authentication Log Files

The `authlog.ini` initialization file contains information that controls how RADIUS authentication request attributes are logged in the comma-delimited `yyyymmdd.authlog` file.

The [Configuration] section of `authlog.ini` specifies the location of the `yyyymmdd.authlog` file. Use the `LogDir` parameter to specify the destination directory on the local host where `yyyymmdd.authlog` files are stored. The default value is the directory where Steel-Belted Radius is installed.

The [Settings] section of `authlog.ini` controls which entries are written to the authentication request log file, and ensures the compatibility of these entries with a variety of database systems.

Steel-Belted Radius writes all authentication request data to the current authentication request log file (`yyyymmddM.authlog`) until that log file is closed. When Steel-Belted Radius closes an authentication request log file, it immediately opens a new one and begins writing authentication request data to it. You can configure how often this rollover of the authentication request log file occurs.

The naming conventions of the authentication request log files support the fact that Steel-Belted Radius can create more than one file per day. The formats are as follows, where *y* = year digit, *m* = month digit, *d* = day digit, and *h* = hour digit. The extra sequence number `_nnnnn` starts at `_00000` each day.

File Generation Method	File Naming Convention
Default (24 hours)	<code>yyyymmdd.authlog</code>
Non 24-hour rollover	<code>yyyymmdd_hhmm.authlog</code>
Rollover due to size	<code>yyyymmdd_nnnnn.authlog</code>
Rollover due to size or startup when non-24-hour time is in effect	<code>yyyymmdd_hhmm_nnnnn.authlog</code>

## Accounting Log Files

The `account.ini` file contains information that controls how RADIUS accounting attributes are logged to a the comma-delimited text file by Steel-Belted Radius.

The [Configuration] section of `account.ini` specifies the location of the `yyyymmdd.act` file. Use the **LogDir** parameter to specify the destination directory on the local host where `yyyymmdd.act` files are stored. The default value is the directory where Steel-Belted Radius is installed.

The [Settings] section of `account.ini` controls which entries are written to the accounting log file, and ensures the compatibility of these entries with a variety of database systems.

Steel-Belted Radius writes all accounting data to the current accounting log file (`yyyymmddM=.act`) until that log file is closed. When Steel-Belted Radius closes an accounting log file, it immediately opens a new one and begins writing accounting data to it. You can configure how often this rollover of the accounting log file occurs.

The naming conventions of the accounting log files support the fact that Steel-Belted Radius can create more than one file per day. The formats are as follows, where *y* = year

digit, *m* = month digit, *d* = day digit, and *h* = hour digit. The extra sequence number *nnnnn* starts at *\_00000* each day.

File Generation Method	File Naming Convention
Default (24 hours)	yyyymmdd.act
Non 24-hour rollover	yyyymmdd_hhmm.act
Rollover due to size	yyyymmdd_nnnnn.act
Rollover due to size or startup when non-24-hour time is in effect	yyyymmdd_hhmm_nnnnn.act

## Authentication Acceptance Log Files

You can configure what is logged to the acceptance report by entering attributes in the [Attributes] section of `authReportAccept.ini` in the sequence in which they should appear.

The [Settings] section of `authReportAccept.ini` specifies the characteristics of the authentication acceptance report. If the `MaxMinutesPerFile` parameter is set to 0, the file name of the authentication acceptance report is `accepts_yyyymmdd.csv` (where `yyyymmdd` identifies the date the report was generated). If the `MaxMinutesPerFile` parameter is set to a value greater than 0, the file name of the report is `accepts_yyyymmdd_hhmm.csv` (where `yyyymmdd` identifies the date and `hhmm` identifies the time the report was generated).

## Authentication Rejection Log Files

You can configure what is logged to the authentication rejection report by entering attributes in the [Attributes] section in the sequence in which they should appear.

The [Settings] section of `authReportReject.ini` specifies the characteristics of the authentication rejection report. If the `MaxMinutesPerFile` parameter is set to 0, the file name of the authentication rejection report is `rejects_yyyymmdd.csv` (where `yyyymmdd` identifies the date the report was generated). If the `MaxMinutesPerFile` parameter is set to a value greater than 0, the file name of the report is `rejects_yyyymmdd_hhmm.csv` (where `yyyymmdd` identifies the date and `hhmm` identifies the time the report was generated).



## Enabling and Disabling Log Files

Use the **Enable** parameter in the [Settings] section of the appropriate initialization file to enable the log. If set to **1**, the log feature is enabled. If set to **0**, no log files are created on this server. The default value is 1 for Accounting logs and 0 for Authentication logs.

For Authentication logs, you also can enable or disable logging from the user interface:

- 1 Open the **Reports** panel and click the **Auth Logs** tab.
- 2 From the **Logs** drop-down list, select each authentication log file you want to enable, one at a time, and click the **Enable logging** checkbox.

# Install the SmartConnector

The following sections provide instructions for installing and configuring your selected SmartConnector.



Connector Appliance/ArcSight Management Center supports mounting for Network File System (NFS) and CIFS (Windows) shares. When you install this connector on one of these devices, establish a CIFS mount on the device before adding the connector. Provide this share name during connector configuration. For more information, see **Remote File Systems** in the Connector Appliance or ArcSight Management Center Administrator's Guide.

## Prepare to Install Connector

Before you install any SmartConnectors, make sure that the ArcSight products with which the connectors will communicate have already been installed correctly (such as ArcSight ESM or ArcSight Logger).

For complete product information, read the *Administrator's Guide* as well as the *Installation and Configuration* guide for your ArcSight product before installing a new SmartConnector. If you are adding a connector to the ArcSight Management Center, see the *ArcSight Management Center Administrator's Guide* for instructions, and start the installation procedure at "Set Global Parameters (optional)" or "Select Connector and Add Parameter Information."

Before installing the SmartConnector, be sure the following are available:

- Local access to the machine where the SmartConnector is to be installed
- Administrator passwords

## Install Core Software

Unless specified otherwise at the beginning of this guide, this SmartConnector can be installed on all ArcSight supported platforms; for the complete list, see the *SmartConnector Product and Platform Support* document, available from the Open Text SSO and Protect 724 sites.

**1** Download the SmartConnector executable for your operating system from the Open Text SSO site.

**2** Start the SmartConnector installation and configuration wizard by running the executable.

Follow the wizard through the following folder selection tasks and installation of the core connector software:

- Introduction
- Choose Install Folder
- Choose Shortcut Folder
- Pre-Installation Summary
- Installing...

## Set Global Parameters (optional)

If you choose to perform any of the operations shown in the following table, do so before adding your connector. You can set the following parameters:

Parameter	Setting
FIPS mode	Select 'Enabled' to enable FIPS compliant mode. To enable FIPS Suite B Mode, see the SmartConnector User Guide under "Modifying Connector Parameters" for instructions. Initially, this value is set to 'Disabled'.
Remote Management	Select 'Enabled' to enable remote management from ArcSight Management Center. When queried by the remote management device, the values you specify here for enabling remote management and the port number will be used. Initially, this value is set to 'Disabled'.
Remote Management Listener Port	The remote management device will listen to the port specified in this field. The default port number is 9001.
Preferred IP Version	When both IPv4 and IPv6 IP addresses are available for the local host (the machine on which the connector is installed), you can choose which version is preferred. Otherwise, you will see only one selection. The initial setting is IPv4.

The following parameters should be configured only if you are using Open Text SecureData solutions to provide encryption. See the *Open Text SecureData Architecture Guide* for more information.

Parameter	Setting
Format Preserving Encryption	Data leaving the connector machine to a specified destination can be encrypted by selecting 'Enabled' to encrypt the fields identified in 'Event Fields to Encrypt' before forwarding events. If encryption is enabled, it cannot be disabled. Changing any of the encryption parameters again will require a fresh installation of the connector.
Format Preserving Policy URL	Enter the URL where the Open Text SecureData Server is installed.
Proxy Server (https)	Enter the proxy host for https connection if any proxy is enabled for this machine.
Proxy Port	Enter the proxy port for https connection if any proxy is enabled for this machine.
Format Preserving Identity	The Open TextSecureData client software allows client applications to protect and access data based on key names. This key name is referred to as the identity. Enter the user identity configured for Open Text SecureData.
Format Preserving Secret	Enter the secret configured for Open Text SecureData to use for encryption.
Event Fields to Encrypt	Recommended fields for encryption are listed; delete any fields you do not want encrypted and add any string or numeric fields you want encrypted. Encrypting more fields can affect performance, with 20 fields being the maximum recommended. Also, because encryption changes the value, rules or categorization could also be affected. Once encryption is enabled, the list of event fields cannot be edited.

After making your selections, click **Next**. A summary screen is displayed. Review the summary of your selections and click **Next**. Click **Continue** to return to proceed with "Add a Connector" window. Continue the installation procedure with "Select Connector and Add Parameter Information."

## Select Connector and Add Parameter Information

- 1 Select **Add a Connector** and click **Next**. If applicable, you can enable FIPS mode and enable remote management later in the wizard after SmartConnector configuration.
- 2 Select **Juniper Steel-Belted Radius File** and click **Next**.
- 3 Enter the required SmartConnector parameters to configure the SmartConnector, then click **Next**.

Parameter	Description
Radius Log File Home Directory	Enter the path to and name of the directory containing the log files (for example, C:\Radius\Service).
Radius Log File Types	Select authentication log (authlog), accounting log (act), accept, reject, or any combination of log types. By default, all logs are selected.

## Select a Destination

- 1 The next window asks for the destination type; select a destination and click **Next**. For information about the destinations listed, see the *ArcSight SmartConnector User Guide*.
- 2 Enter values for the destination. For the ArcSight Manager destination, the values you enter for **User** and **Password** should be the same ArcSight user name and password you created during the ArcSight Manager installation. Click **Next**.
- 3 Enter a name for the SmartConnector and provide other information identifying the connector's use in your environment. Click **Next**. The connector starts the registration process.
- 4 If you have selected ArcSight Manager as the destination, the certificate import window for the ArcSight Manager is displayed. Select **Import the certificate to the connector from destination** and click **Next**. (If you select **Do not import the certificate to connector from destination**, the connector installation will end.) The certificate is imported and the **Add connector Summary** window is displayed.

## Complete Installation and Configuration

- 1 Review the **Add Connector Summary** and click **Next**. If the summary is incorrect, click **Previous** to make changes.
- 2 The wizard now prompts you to choose whether you want to run the SmartConnector as a stand-alone process or as a service. If you choose to run the connector as a stand-alone process, select **Leave as a standalone application**, click **Next**, and continue with step 5.
- 3 If you chose to run the connector as a service, with **Install as a service** selected, click **Next**. The wizard prompts you to define service parameters. Enter values for **Service Internal Name** and **Service Display Name** and select **Yes** or **No** for **Start the service automatically**. The **Install Service Summary** window is displayed when you click **Next**.
- 4 Click **Next** on the summary window.

**5** To complete the installation, choose **Exit** and Click **Next**.

For instructions about upgrading the connector or modifying parameters, see the *SmartConnector User Guide*.

# Log Rotation Scheme

The SmartConnector supports daily (24-hour) rotation scheme by default. However, non-daily rotation is supported by changing the internal parameter `rotationschemeparams`. The following is an overview.

File Generation Method	File Naming Convention	rotationschemeparams
Default (24 hours)	yyyymmdd.authlog	yyyyMMdd (by default)
Non 24-hour rollover	yyyymmdd_hhmm.authlog	yyyyMMdd_HHmm

After SmartConnector installation, you can update the `rotationschemeparams` parameter by editing the `agent.properties` file located at `$ARCSIGHT_HOME\current\user\agent`. Be sure to save the file and restart the connector for your changes to take effect.

## Run the SmartConnector

SmartConnectors can be installed and run in stand-alone mode, on Windows platforms as a Windows service, or on UNIX platforms as a UNIX daemon, depending upon the platform supported. On Windows platforms, SmartConnectors also can be run using shortcuts and optional Start menu entries.

If the connector is installed in stand-alone mode, it must be started manually and is not automatically active when a host is restarted. If installed as a service or daemon, the connector runs automatically when the host is restarted. For information about connectors running as services or daemons, see the *ArcSight SmartConnector User Guide*.

To run all SmartConnectors installed in stand-alone mode on a particular host, open a command window, go to `$ARCSIGHT_HOME\current\bin` and run: `arcsight connectors`

To view the SmartConnector log, read the file `$ARCSIGHT_HOME\current\logs\agent.log`; to stop all SmartConnectors, enter `Ctrl+C` in the command window.



## Device Event Mapping to ArcSight Fields

The following section lists the mappings of ArcSight data fields to the device's specific event definitions. See the *ArcSight Console User's Guide* for more information about the ArcSight data fields.

### Juniper Steel-Belted Radius ACCEPT Log Mappings

ArcSight ESM Field	Device-Specific Field
ArcSight Severity	Low when Device Severity = ACCEPT
Destination User Name	User-Name
Device Action	'ACCEPT'
Device Custom Number 3	NAS-Port-Type
Device Custom String 1	RAS-Client
Device Custom String 3	Full-Name
Device Event Class ID	'Authentication - ACCEPT'
Device Product	'Steel-Belted Radius'
Device Receipt Time	Date,Time
Device Severity	'ACCEPT'
Device Vendor	'Juniper'
Name	'Authentication - ACCEPT'
Source Address	NAS-IP-Address
Source Host Name	Calling-Station-Id

### Juniper Steel-Belted Radius REJECT Log Mappings

ArcSight ESM Field	Device-Specific Field
ArcSight Severity	Medium when Device Severity = REJECT
Destination User Name	User-Name
Device Action	'REJECT'
Device Custom String 1	RAS-Client

ArcSight ESM Field	Device-Specific Field
Device Event Class ID	'Authentication - REJECT'
Device Product	'Steel-Belted Radius'
Device Receipt Time	Date,Time
Device Severity	'REJECT'
Device Vendor	'Juniper'
Message	All of (Reject-Method, Reject-Reason, Reject-Log)
Name	'Authentication - REJECT'
Source Address	NAS-IP-Address

## Juniper Steel-Belted Radius ACCOUNTING Log Mappings

ArcSight ESM Field	Device-Specific Field
Additional data	FullNameWithDomain=Full-Name
Additional data	UserNameWithDomain=User-Name
ArcSight Severity	Low when Device Severity = Low
Bytes In	Acct-Input-Octets
Bytes Out	Acct-Output-Octets
Destination User Name	User-Name
Device Action	Record-Type
Device Custom Number 2	Acct-Session-Time
Device Custom String 1	Acct-Session-Id
Device Custom String 2	Service-Type
Device Custom String 3	Full-Name
Device Custom String 4	Acct-Input-Packets
Device Custom String 5	Acct-Output-Packets
Device Custom String 6	Called-Station-ID
Device Event Class ID	'Accounting - ' plus Record-Type
Device Product	'Steel-Belted Radius'

ArcSight ESM Field	Device-Specific Field
Device Receipt Time	Date,Time
Device Severity	'Low'
Device Vendor	Juniper'
External ID	Acct-Session-Id
Name	'Accounting -' plus Record-Type
Source Address	NAS-IP-Address
Source Host Name	NAS-Identifier
Source Translated Address	Framed-IP-Address

## Juniper Steel-Belted Radius Authentication Log Mappings

ArcSight ESM Field	Device-Specific Field
Additional Data	UserNameWithDomain=User-Name
ArcSight Severity	Medium when Device Severity = REJECT; Low when Device Severity = ACCEPT
Destination User Name	User-Name
Device Action	Acc/Rej
Device Custom String 1	RAS-Client
Device Custom String 2	Service-Type
Device Custom String 3	Full-Name
Device Custom String 6	Called-Station-ID
Device Event Class ID	'Authentication -' plus Acc/Rej
Device Product	'Steel-Belted Radius'
Device Receipt Time	Date,Time
Device Severity	Acc/Rej
Device Vendor	'Juniper'
External ID	Acct-Session-Id
Name	'Authentication -' plus Acc/Rej

ArcSight ESM Field	Device-Specific Field
Source Address	NAS-IP-Address
Source Host Name	NAS-Identifier
Source Translated Address	Framed-IP-Address

please confirm that when customer used MySQL JDBC driver 5.1.38, they had issue to receive events. And the workaround is to apply older driver 5.0.8, after that connector is able to receive events.

# Send Documentation Feedback

If you have comments about this document, you can [contact the documentation team](#) by email. If an email client is configured on this computer, click the link above and an email window opens with the following information in the subject line:

**Feedback on Configuration Guide for Juniper Steel-Belted Radius File SmartConnector (SmartConnectors 8.4.3)**

Just add your feedback to the email and click send.

If no email client is available, copy the information above to a new message in a web mail client, and send your feedback to [MFI-Documentation-Feedback@opentext.com](mailto:MFI-Documentation-Feedback@opentext.com).

We appreciate your feedback!