



# Micro Focus Security ArcSight Logger Forwarding

Software Version: 8.3.0

## Release Notes

Document Release Date: March 2022

Software Release Date: March 2022

## Legal Notices

### Copyright Notice

© Copyright 2022 Micro Focus or one of its affiliates

Confidential computer software. Valid license from Micro Focus required for possession, use or copying. The information contained herein is subject to change without notice.

The only warranties for Micro Focus products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Micro Focus shall not be liable for technical or editorial errors or omissions contained herein.

No portion of this product's documentation may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying, recording, or information storage and retrieval systems, for any purpose other than the purchaser's internal use, without the express written permission of Micro Focus.

Notwithstanding anything to the contrary in your license agreement for Micro Focus ArcSight software, you may reverse engineer and modify certain open source components of the software in accordance with the license terms for those particular components. See below for the applicable terms.

U.S. Governmental Rights. For purposes of your license to Micro Focus ArcSight software, "commercial computer software" is defined at FAR 2.101. If acquired by or on behalf of a civilian agency, the U.S. Government acquires this commercial computer software and/or commercial computer software documentation and other technical data subject to the terms of the Agreement as specified in 48 C.F.R. 12.212 (Computer Software) and 12.211 (Technical Data) of the Federal Acquisition Regulation ("FAR") and its successors. If acquired by or on behalf of any agency within the Department of Defense ("DOD"), the U.S. Government acquires this commercial computer software and/or commercial computer software documentation subject to the terms of the Agreement as specified in 48 C.F.R. 227.7202-3 of the DOD FAR Supplement ("DFARS") and its successors. This U.S. Government Rights Section 18.11 is in lieu of, and supersedes, any other FAR, DFARS, or other clause or provision that addresses government rights in computer software or technical data.

### Trademark Notices

Adobe™ is a trademark of Adobe Systems Incorporated.

Microsoft® and Windows® are U.S. registered trademarks of Microsoft Corporation.

UNIX® is a registered trademark of The Open Group.

## Support

### Contact Information

Phone	A list of phone numbers is available on the Technical Support Page: <a href="https://softwaresupport.softwaregrp.com/support-contact-information">https://softwaresupport.softwaregrp.com/support-contact-information</a>
Support Web Site	<a href="https://softwaresupport.softwaregrp.com/">https://softwaresupport.softwaregrp.com/</a>
ArcSight Product Documentation	<a href="https://community.softwaregrp.com/t5/ArcSight-Product-Documentation/ct-p/productdocs">https://community.softwaregrp.com/t5/ArcSight-Product-Documentation/ct-p/productdocs</a>

# Documentation Revision History

Date	Product Version	Description
06/25/2018	7.9.0.8088.0	Updated supported Logger versions.
06/25/2018	7.8.0.8072.0	Micro Focus rebranding Updated supported Logger versions.
08/30/2016	7.3.0.7837.0	HPE branding. Updated supported Logger versions.
02/15/2016	7.1.7.7609.0	Support for version 10.0. Installation support for Windows 2012 R2. Support for RHEL 7.1. Support for 64-bit on Linux and Windows platforms. Support for Logger 6.0.
09/28/2012	5.2.3.6287.0	Added support for selected HP H3C and HP ProCurve submessages. Added support for HP NNMi 9.20, patch 1 and a new connector installation wizard.  Event data is forwarded as CEF Syslog from Logger to the Logger Forwarding Connector for HP NNMi. The parsing is now enabled only in the corresponding release of the SmartConnectors. Forwarding events from supported devices such as Cisco Router, HP H3C, and HP ProCurve directly to the Logger Forwarding Connector without SmartConnectors or Logger is not a supported configuration.
05/15/2012	5.2.1.6206.0	Added support for selected Cisco Router sub-messages.
11/15/2011	5.1.7.6081.0	Added support for JRE 1.6.0_26.

# Contents

- Chapter 1: ArcSight Logger Forwarding Connector for NNMi ..... 5
  - About Micro Focus ArcSight Logger and Micro Focus NNMi ..... 5
  - Sending Events From Logger to NNMi ..... 6
  
- Chapter 2: Installing the Connector ..... 7
  - Configure for Micro Focus Network Node Manager (NNMi) .....10
  - NNMi Console ..... 12
  
- Chapter 3: Logger Forwarders ..... 14
  - Creating a Forwarder to Forward Events ..... 15
  
- Appendix A: Supported Cisco Router, Micro Focus H3C, and Micro Focus ProCurve Sub-Messages ..... 16
  - Cisco Router Sub-messages ..... 16
  - Micro Focus H3C Sub-messages ..... 18
  - Micro Focus ProCurve Sub-messages ..... 20
  
- Send Documentation Feedback ..... 21

# Chapter 1: ArcSight Logger Forwarding Connector for NNMi

This guide provides information on installing and configuring the ArcSight Logger Forwarding Connector for NNMi on Windows, Linux and Solaris platforms. This Logger Forwarding Connector software supports **Logger 6.2, 6.3, 6.4, 6.5 and 6.6**, and **NNMi 10.60**.

See ["Supported Cisco Router, Micro Focus H3C, and Micro Focus ProCurve Sub-Messages" on page 16](#) for details on supported Cisco Router sub-messages.

Note the following:

- You must upgrade to Micro Focus NNMi 10.60 or later to be able to use the current Logger Forwarding Connector for Micro Focus NNMi. If you have a previous version of Micro Focus NNMi installed, the current Logger Forwarding Connector for Micro Focus NNMi will not function.
- Use the latest version of the SmartConnector with the current Logger Forwarding Connector for NNMi. If you plan to process events from Micro Focus ProCurve devices, you must also install the latest SmartConnector build.

**Note:** The following changes start with the next release:

- Windows and Linux 64-bit operating systems will be supported.
- Solaris operating system will no longer be supported.

## About Micro Focus ArcSight Logger and Micro Focus NNMi

**Micro Focus ArcSight Logger** is a log management solution that is optimized for extremely high event throughput, efficient long-term storage, and rapid data analysis. Logger receives and stores events; supports search, retrieval, and reporting; and can forward selected events. The Micro Focus ArcSight Logger Forwarding Connector allows you to send these event logs from Logger to the Micro Focus Network Node Manager (Micro Focus NNMi).

**Micro Focus Network Node Manager (NNMi)** provides continual network discovery using unified fault, availability, and performance monitoring. Micro Focus NNMi enables network management teams to detect, locate, and diagnose faults and performance

degradations of the network quickly, analyze the business and service impact of outages, and increase network staff efficiency and productivity.

Using the Micro Focus ArcSight Logger Forwarding Connector and the Micro Focus NNMi integration install, network staff can view syslog messages from Logger in the NNMi console.

## Sending Events From Logger to NNMi

Logger sends events to the Logger Forwarding Connector using CEF Syslog, which then forwards the events to NNMi via SNMP. For Logger to send events to the Logger Forwarding Connector, a Logger forwarder must be created to send these events. For instructions on how to create a forwarder to send the events, see ["Creating a Forwarder to Forward Events" on page 15](#).

# Chapter 2: Installing the Connector

Before you install the connector, make sure that the ArcSight products with which the connectors will communicate have already been installed correctly (the ArcSight Logger, for example) and you have assigned appropriate privileges.

1. Download the Micro Focus ArcSight executable for your operating system from **My Updates** on the Micro Focus SSO site.
2. Start the Micro Focus ArcSight Installer by running the executable.

Follow the installation wizard through the following folder selection tasks and installation of the core connector software:

Introduction

Choose Install Folder


Choose Install Set

Choose Shortcut Folder


Pre-Installation Summary

Installing...

3. Select **Add a Connector**.




4. Click **Next**. **Logger to NNMi** is selected by default.
5. Click **Next**. Enter the Logger information.




Parameter	Description
Network Port	514 or another port that matches the Receiver (the port to which the Forwarding Connector sends events)
IP Address	IP or host name of the Logger
Protocol	UDP or Raw TCP <b>Note:</b> Whichever protocol you choose, it must match that of the forwarder type chosen during Logger Forwarder configuration.

6. Click **Next**. **Micro Focus NNMI** is selected by default.





7. Click **Next**. Fill in the parameter information required for connector configuration.




Parameter	Description
Host	Enter the Host name or IP address of the NNMI device.
Port	Enter the port to be used by the adaptor to forward events. The default port is <b>162</b> . To determine if the trap port monitored by NNMI is other than the default, use the NNMI command:  <code>\$NmInstallDir/bin/nmtrapconfig.ovpl -showProp</code>  See the <i>NNMI ArcSight Logger Integration Guide</i> , Micro Focus ArcSight Logger chapter for details on Micro Focus NNMI and Logger integration.
Version	Accept the default value of <b>SNMP_VERSION_2</b> . SNMP_VERSION_3 is not available at this time.
Read Community(v2)	Enter the SNMP Read Community name.
Write Community(v2)	Enter the SNMP Write Community name.
Authentication Username(v3)	For use with SNMP v3. This is not available at this time.
Authentication Password(v3)	Enter the authentication password.
Security Level(v3)	The default value is <b>AuthNoPriv</b>
Authentication Scheme(v3)	The default value is <b>MD5</b> .
Privacy Password(v3)	Enter the privacy password.
Context Engine Id(v3)	Enter the context engine.
Context name(v3)	Enter the context name.

8. Click **Next**. Enter a name for the connector and provide other information identifying the connector's use in your environment.
9. Click **Next**. Read the installation summary and click **Next**. If the summary is incorrect, click **Previous** to make changes.
10. When the connector completes its configuration, click **Next**. The Wizard now prompts you to choose whether you want to run the connector as a process or as a service.  
  
If you choose to run the connector as a service, the Wizard prompts you to define service parameters for the connector.
11. Click **Next**. Choose **Exit**, to complete the connector installation, or choose **Continue**, to continue to make connector modifications. Click **Next** to exit or continue.

## Configure for Micro Focus Network Node Manager (NNMI)

Add new node for the VM with the IP address where you want to receive trap.

Release Notes  
Chapter 2: Installing the Connector



The screenshot shows a web-based interface titled "Nodes". At the top, there is a toolbar with various icons and a search filter set to "<Empty Group filter>". Below the toolbar is a table with the following columns: Status, Device Name, Hostname, Management IP, System Location, Device Profile, Agent, Status Last Modified, and Notes. Two rows of data are visible, both with a green checkmark in the Status column.

Status	Device Name	Hostname	Management IP	System Location	Device Profile	Agent	Status Last Modified	Notes
OK	n15-214-197-h120	n15-214-197-h120.arst.usa.hp.com	10.214.197.120		hp2910ai-480	✓	16-Jun-2015 21:35:22	
OK	n15-214-195-h177	n15-214-195-h177.arst.usa.hp.com			ArcsightModel		17-Jun-2015 00:37:51	

# NNMi Console

These modules are automatically filled in the NNMi Console:

Name	Enabled	Root Cause	Deduplicati on Enabled	Rate Enabled	Sev erit y	Cat egor y	Fa mil y	Author	Message Format
ARP/3/ROUTECONFLICT	✓	-	✓	-	⚠	M	S	HP ArcSight	\$1.3.6.1.4.1.11937.1.42.1.3.1: \$1.3.6.1.4.1.11937.1.42.1.3.2
ARP/5/ARP_DUPVRRPIP	✓	-	✓	-	⚠	M	S	HP ArcSight	\$1.3.6.1.4.1.11937.1.42.1.3.1: \$1.3.6.1.4.1.11937.1.42.1.3.2
BFD/5/BFD_CHANGE_FSM	✓	-	✓	-	⚠	M	S	HP ArcSight	\$1.3.6.1.4.1.11937.1.42.1.3.1: \$1.3.6.1.4.1.11937.1.42.1.3.2
BGP-5-ADJCHANGE	✓	-	✓	-	🟢	M	S	HP ArcSight	\$1.3.6.1.4.1.11937.1.42.1.3.1: \$1.3.6.1.4.1.11937.1.42.1.3.2
BGP/5/BGP_RECHED_THRESHOI	✓	-	✓	-	⚠	M	S	HP ArcSight	\$1.3.6.1.4.1.11937.1.42.1.3.1: \$1.3.6.1.4.1.11937.1.42.1.3.2
CDP-4-DUPLEX_MISMATCH	✓	-	✓	-	🟢	M	S	HP ArcSight	\$1.3.6.1.4.1.11937.1.42.1.3.1: \$1.3.6.1.4.1.11937.1.42.1.3.2
CFM/5/CFM_SAVECONFIG_SUCC	✓	-	✓	-	🟢	N	S	HP ArcSight	\$1.3.6.1.4.1.11937.1.42.1.3.1: \$1.3.6.1.4.1.11937.1.42.1.3.2
DEV/4/BOARD_LOADING	✓	-	✓	-	🟢	M	S	HP ArcSight	\$1.3.6.1.4.1.11937.1.42.1.3.1: \$1.3.6.1.4.1.11937.1.42.1.3.2
DEV/4/FAN_FAILED	✓	-	✓	-	⚠	M	S	HP ArcSight	\$1.3.6.1.4.1.11937.1.42.1.3.1: \$1.3.6.1.4.1.11937.1.42.1.3.2
DEV/4/FAN_RECOVERED	✓	-	✓	-	🟢	M	S	HP ArcSight	\$1.3.6.1.4.1.11937.1.42.1.3.1: \$1.3.6.1.4.1.11937.1.42.1.3.2
DEV/4/LOAD_FINISHED	✓	-	✓	-	🟢	M	S	HP ArcSight	\$1.3.6.1.4.1.11937.1.42.1.3.1: \$1.3.6.1.4.1.11937.1.42.1.3.2

See ["Supported Cisco Router, Micro Focus H3C, and Micro Focus ProCurve Sub-Messages"](#) on page 16 for a complete list of supported sub-messages.

When events are sent from Forwarding Connector to NNMi, only events which contain attribute **mnemonic**, shown below, are parsed in **syslog message** incident.

```
CEF:0|HP|H3C|4800G|WROAM_ROAM_OUT_FAILED|WROAM_ROAM_OUT_FAILED|Medium|
eventId=809 msg=Client 001c-bf93-6f44, Failed to roam: Maximum roam-out clients reached.
rawEvent=Sep 6 11:15:17 hostname 2000 4800G %%10WROAM/4/WROAM_ROAM_OUT_FAILED:Client
001c-bf93-6f44, Failed to roam: Maximum roam-out clients reached. catdt=Switch art=1436623052291
cat=WLAN Roaming deviceSeverity=4 rt=1410027317000 cs1=2000
cs2=WROAM/4/WROAM_ROAM_OUT_FAILED cs3=10 cs1Label=Manufacturer cs2Label=Message Name
cs3Label=Syslog Version cs6Label=Group cn2Label=Slot ID cn3Label=VLAN ID ahost=agilis50-
bn.ARCPARTNERS.COM agt=15.215.8.66 agentZoneURI=/All Zones/ArcSight System/Public Address Space
Zones/Hewlett-Packard Company av=7.1.4.0.0 atz=America/Los Angeles
aid=3TQ1ffU4BABCAAmxwIRKx8A\=\= at=syslog dvchost=hostname dtz=America/Los Angeles
deviceFacility=WROAM _cefVer=0.1 ad.message=Client 001c-bf93-6f44, Failed to roam: Maximum roam-
out clients reached. ad.mnemonic=WROAM/4/WROAM_ROAM_OUT_FAILED
```

Incidents for these valid events would be shown in the incident view.

The screenshot shows the Syslog Messages interface. On the left is a navigation pane with categories like Dashboards, Incident Management, Topology Maps, Monitoring, Troubleshooting, Inventory, Management Mode, and Incident Browsing. The main area displays a table of Syslog Messages with columns for Severity, Lifecycle, Last Occurrence, Source Node, Source Object, Category, Family, Correlation, Message, and Notes. One message is highlighted: 'OSPF/5/OSPF\_NBR\_CHG: -DevIP 148.90.208.23'. Below the table, an 'Analysis' section provides details for the selected incident, including a summary, message text, severity (Minor), lifecycle state (Registered), and a list of custom attributes.

Severity	Lifecycle	Last Occurrence	Source Node	Source Object	Catg	Famil	Corr	Message	Notes
Info	OK	10/01/2015 01:08:40	none	10.208.255.138	CFM	CFM		CFM5/CFM_SAVECONFIG_SUCCESSFULLY: -D	
Warning	Warn	10/01/2015 01:08:40	none	10.208.255.138	NTP	NTP		NTP5/NTP_SOURCE_LOST: -DevIP 10.208.255.1	
Warning	Warn	10/01/2015 01:08:40	none	10.54.250.254	OSPF	OSPF		OSPF/5/OSPF_NBR_CHG: -DevIP 148.90.208.23	
Warning	Warn	10/01/2015 01:08:40	none	none	DEV	DEV		DEV/5/BOARD_REMOVED: Board is removed	
Warning	Warn	10/01/2015 01:08:40	none	none	DEV	DEV		DEV/5/BOARD_STATE_FAULT: Board state of	
Warning	Warn	10/01/2015 01:08:40	none	none	VRRP	VRRP		VRRP/6/VRRP_STATUS_CHANGE: -DevIP 128.2	
Warning	Warn	10/01/2015 01:08:40	none	none	MSTP	MSTP		MSTP/5/MSTP_BPDU_RECEIVE_EXPIRY: -DevIP	
Info	OK	10/01/2015 01:08:40	none	none	OPT	OPT		OPT/5/4/MODULE_IN: -DevIP 161.14.192.121-	
Warning	Warn	10/01/2015 01:08:40	none	10.54.250.1	OSPF	OSPF		OSPF/5/OSPF_LAST_NBR_DOWN: -DevIP 148.9	
Warning	Warn	10/01/2015 01:08:40	none	none	ARP	ARP		ARP/5/ARP_DUPVRRP: IP address 1.1.1.1 con	
Warning	Warn	10/01/2015 01:08:40	none	80.1.1.1	ARP	ARP		ARP/3/ROUTECONFLICT: Route conflict found, F	
Warning	Warn	10/01/2015 01:08:40	none	none	BFD	BFD		BFD/5/BFD_CHANGE_FSM: Sess(172.16.25.19)	

**Incident Summary: OSPF/5/OSPF\_NBR\_CHG**

**Message:** OSPF/5/OSPF\_NBR\_CHG: -DevIP 148.90.208.23; OSPF 1293 Neighbor 10.54.250.254(Vlan-interface1245) from Full to Down.

**Severity:** Minor

**Lifecycle State:** Registered

**RCA Active:** false

**Source Object:** 10.54.250.254 (Configuration Item)

**Created/Opened:** 11/07/2015 07:06 SA (Open for 2,8 days)

**Custom Attributes:**

- 1.3.6.1.4.1.11937.1.1 (asn\_octetst) 10
- 1.3.6.1.4.1.11937.1.46.10 (asn\_octetst)
- 1.3.6.1.4.1.11937.1.16 (asn\_octetst) Jan 10 01:08:40 n100-h008 2000 4800G %:100SPF/5/OSPF\_NBR\_CHG: -DevIP 148.90.208.23; OSPF 1293 Neighbor 10.54.250.254(Vlan-interface1245) from Full to Down.
- 1.3.6.1.4.1.11937.1.46.5 (asn\_octetst) OSPF\_NBR\_CHG
- 1.3.6.1.4.1.11937.1.46.4 (asn\_octetst) 10 Jan 2015 01:08:40 PST
- 1.3.6.1.4.1.11937.1.46.33 (asn\_octetst) HP
- 1.3.6.1.4.1.11937.1.46.34 (asn\_octetst) H3C

Detail of an incident:

The screenshot shows the 'Incident' detail view. The 'Basics' section displays the message: 'DEV/4/FAN\_RECOVERED: -Chassis 2-Slot 0; Chassis 2 Fan 1 recovered.' Below this, fields for Severity (Normal), Priority (None), Lifecycle State (Closed), Source Node (none), Source Object (none), and Assigned To are visible. The 'Notes' section is empty. The 'Custom Attributes' section shows a table of attributes:

Name	Type	Value
1.3.6.1.4.1.11937.1.1	asn_octetst	10
1.3.6.1.4.1.11937.1.46.10	asn_octetst	
1.3.6.1.4.1.11937.1.16	asn_octetst	Jan 10 01:08:40 n100-h008 2000 4800G %:100SPF/5/OSPF_NBR_CHG: -DevIP 148.90.208.23; OSPF 1293 Neighbor 10.54.250.254(Vlan-interface1245) from Full to Down.
1.3.6.1.4.1.11937.1.46.5	asn_octetst	FAN_RECOVERED
1.3.6.1.4.1.11937.1.46.4	asn_octetst	10 Jan 2015 01:08:40 PST
1.3.6.1.4.1.11937.1.46.33	asn_octetst	HP
1.3.6.1.4.1.11937.1.46.34	asn_octetst	H3C
1.3.6.1.4.1.11937.1.46.1	asn_octetst	
1.3.6.1.4.1.11937.1.46.2	asn_octetst	4
1.3.6.1.4.1.11937.1.42.1.1.1	asn_octetst	mnemonic
1.3.6.1.4.1.11937.1.42.1.3.1	asn_octetst	DEV/4/FAN_RECOVERED
1.3.6.1.4.1.11937.1.42.1.1.2	asn_octetst	message

Updated: 11/07/15 08:13:22 AM Total: 21 Selected: 0 Filter: OFF Auto refresh: Off

# Chapter 3: Logger Forwarders

Logger **Forwarders** allow you to send all events, or events which match a particular filter, to another destination, in this instance to the Logger Forwarding Connector for NNMi. For more detailed information on Logger Forwarders, see the *ArcSight Logger Administrator's Guide*.

**Note:** You cannot configure a Logger Forwarder to send data to a destination on the same system.

Logger forwarding uses several forwarder types, but the Logger Forwarding Connector operates with UDP and TCP forwarder types only.

- **UDP Forwarders** forward events as User Datagram Protocol messages, such as Syslog format datagrams.
- **TCP Forwarders** forward events as Transmission Control Protocol messages.

# Creating a Forwarder to Forward Events

In order to successfully forward events from Logger to NNMi, a Logger Forwarder must be created. To do so, complete the following steps in the Logger web application.

1. Click **Configuration** from the top-level menu bar.
2. Click **Event Input/Output** in the left panel.
3. Click the **Forwarder** tab, then click **Add**. The **Add Forwarder** page appears.
4. Enter a name for the new forwarder and choose either “UDP Forwarder” or “TCP Forwarder”.

**Caution:** Whichever forwarder type you choose, it must match that of the SmartConnector protocol and port chosen during installation.

5. Click **Next**.
  6. The **Edit Forwarder** page appears.
  7. Within the **Query** field, create a query to filter the events sent to NNMi, or leave the default, **NONE**, to send all events.
  8. Continue to fill in the remaining parameters, ensuring that the **Ip/Host** field contains the correct Logger Forwarding Connector IP address and that the **Port** number matches that of the connector.
  9. Click **Save**. The following page appears.
10. New forwarders are initially disabled, so click the disabled icon (🔴) to enable the new forwarder.

The forwarder is now enabled.

**Note:** To create a specific filter for NNMi, refer to the Micro Focus NNMi documentation.

**Tip:** Wait a few minutes after enabling a forwarder before disabling it. Likewise, wait before enabling a forwarder that has just been disabled. Background tasks initiated by enabling or disabling a forwarder can produce unexpected results if they are interrupted.

# Appendix A: Supported Cisco Router, Micro Focus H3C, and Micro Focus ProCurve Sub-Messages

This appendix lists Cisco Router, Micro Focus H3C, and Micro Focus ProCurve sub-messages, for which additional mappings were provided in this release.

## Cisco Router Sub-messages

The following Cisco Router sub-messages are provided:

- BGP-5-ADJCHANGE
- CDP-4-DUPLEX\_MISMATCH
- DTP-3-NONTRUNKPORTFAIL
- DTP-3-TRUNKPORTFAIL
- DTP-5-NONTRUNKPORTON
- DTP-5-TRUNKPORTCHG
- DTP-5-TRUNKPORTON
- FR-5-DLCICHANGE
- LINEPROTO-5-UPDOWN
- LINK-3-UPDOWN
- STANDBY-3-DUPADDR
- LINK-4-ERROR
- PAGP-5-PORTFROMSTP
- PAGP-5-PORTTOSTP
- PORT\_SECURITY-2-PSECURE\_VIOLATION\_VLAN
- SNMP-5-MODULETRAP
- SPANTREE-5-PORTLISTEN



- SPANTREE-5-ROOTCHANGE
- SPANTREE-6-PORTFWD
- SPANTREE-6-PORTLISTEN
- STACKMGR-6-MASTER\_ELECTED
- STACKMGR-6-MASTER\_READY
- STACKMGR-6-STACK\_LINK\_CHANGE
- STANDBY-6-STATECHANGE
- SYS-3-MOD\_CFGMISMATCH1
- SYS-3-MOD\_CFGMISMATCH2
- SYS-3-MOD\_CFGMISMATCH3
- SYS-3-MOD\_CFGMISMATCH4
- SYS-3-PKTBUFBAD
- SYS-3-PORT\_COLL
- SYS-3-PORT\_COLLDIS
- SYS-3-PORT\_IN\_ERRORS
- SYS-3-PORT\_RUNTS
- SYS-4-SYS\_LCPERR4
- SYS-5-MOD\_INSERT
- SYS-5-MOD\_OK
- SYS-5-MOD\_REMOVE
- SYS-5-MOD\_RESET
- SYS-5-RELOAD
- SYS-5-RESTART
- SYS-5-SYS\_LCPERR5

## Micro Focus H3C Sub-messages

The following Micro Focus H3C sub-messages are provided:

- CFM/5/CFM\_SAVECONFIG\_SUCCESSFULLY
- NTP/5/NTP\_SOURCE\_LOST
- DEV/4/FAN\_FAILED
- OSPF/5/OSPF\_NBR\_CHG
- DEVM/3/BOARD\_REMOVED
- DEV/4/FAN\_RECOVERED
- DEVM/2/BOARD\_STATE\_FAULT
- VRRP/6/VRRP\_STATUS\_CHANGE
- DEV/4/POWER\_FAILED
- DEV/4/POWER\_RECOVERED
- MSTP/5/MSTP\_BPDU\_RECEIVE\_EXPIRY
- OPTMOD/4/MODULE\_IN
- OSPF/6/OSPF\_LAST\_NBR\_DOWN
- ARP/5/ARP\_DUPVRRPIP
- ARP/3/ROUTECONFLICT
- BFD/5/BFD\_CHANGE\_FSM
- BGP/5/BGP\_RECHED\_THRESHOLD
- DEV/4/BOARD\_LOADING
- DEV/4/LOAD\_FINISHED
- DEVM/2/POWER\_FAILED
- DEVM/5/POWER\_RECOVERED
- DEVM/3/RPS\_ABSENT
- DEVM/5/RPS\_NORMAL
- DEVM/5/SYSTEM\_REBOOT

- DEV/4/POWER\_ABSENT
- DEV/4/SYSTEM\_REBOOT
- LDP/5/LDP\_SESSION\_DOWN
- OPTMOD/5/CHKSUM\_ERR
- OPTMOD/5/IO\_ERR
- OPTMOD/5/MOD\_ALM\_OFF
- OPTMOD/5/MOD\_ALM\_ON
- OPTMOD/4/MODULE\_OUT
- OPTMOD/3/TYPE\_ERR
- PIM/5/PIM\_NBR\_DOWN
- STM/4/LINK\_STATUS\_CHANGE
- STM/3/STM\_LINK\_STATUS\_DOWN
- STM/6/STM\_LINK\_STATUS\_UP

# Micro Focus ProCurve Sub-messages

The following Micro Focus ProCurve sub-messages are provided:

- RMON\_PMGR\_PORT\_UP
- RMON\_CHASSIS\_FAN\_STATUS
- RMON\_STP\_NEW\_ROOT
- RMON\_LACP\_DYNAMIC\_TRUNK\_OFF\_LINE
- RMON\_LACP\_DYNAMIC\_TRUNK\_ON\_LINE
- RMON\_LACP\_ERROR\_CONDITION\_BLOCK
- RMON\_POEMGR\_PD\_DENIED\_POWER
- RMON\_POEMGR\_PD\_OVERCURRENT
- RMON\_POEMGR\_INTERNAL\_50V\_FAULT
- RMON\_BOOT\_CRASH\_RECORD0
- RMON\_BOOT\_CRASH\_RECORD1
- RMON\_BOOT\_NO\_CRASH\_RECORD
- RMON\_BOOT\_SELFTEST\_FAILURE
- RMON\_SSH\_DISABLED
- RMON\_SSH\_ENABLED
- RMON\_CHASSIS\_POWER\_STATUS
- RMON\_CHASSIS\_HEARTBEAT\_FAILURE

# Send Documentation Feedback

If you have comments about this document, you can [contact the documentation team](#) by email. If an email client is configured on this computer, click the link above and an email window opens with the following information in the subject line:

## **Feedback on Release Notes (Logger Forwarding Connector for NNMi 8.3.0)**

Just add your feedback to the email and click send.

If no email client is available, copy the information above to a new message in a web mail client, and send your feedback to [Documentation-Feedback@microfocus.com](mailto:Documentation-Feedback@microfocus.com).

We appreciate your feedback!