

---

# **Micro Focus Fortify ScanCentral DAST**

Software Version: 21.2.0  
Windows®

## **Configuration and Usage Guide**

Document Release Date: November 2021  
Software Release Date: November 2021



## Legal Notices

Micro Focus  
The Lawn  
22-30 Old Bath Road  
Newbury, Berkshire RG14 1QN  
UK

<https://www.microfocus.com>

## Warranty

The only warranties for products and services of Micro Focus and its affiliates and licensors (“Micro Focus”) are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Micro Focus shall not be liable for technical or editorial errors or omissions contained herein. The information contained herein is subject to change without notice.

## Restricted Rights Legend

Confidential computer software. Except as specifically indicated otherwise, a valid license from Micro Focus is required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

## Copyright Notice

© Copyright 2020-2021 Micro Focus or one of its affiliates

## Trademark Notices

All trademarks, service marks, product names, and logos included in this document are the property of their respective owners.

## Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number
- Document Release Date, which changes each time the document is updated
- Software Release Date, which indicates the release date of this version of the software

This document was produced on November 10, 2021. To check for recent updates or to verify that you are using the most recent edition of a document, go to:

<https://www.microfocus.com/support/documentation>

# Contents

|                                                               |    |
|---------------------------------------------------------------|----|
| Preface .....                                                 | 17 |
| Contacting Micro Focus Fortify Customer Support .....         | 17 |
| For More Information .....                                    | 17 |
| About the Documentation Set .....                             | 17 |
| Fortify Product Feature Videos .....                          | 17 |
| Change Log .....                                              | 18 |
| Chapter 1: Introduction .....                                 | 25 |
| What is ScanCentral DAST? .....                               | 25 |
| Software Security Center .....                                | 25 |
| LIM .....                                                     | 25 |
| DAST API .....                                                | 26 |
| DAST Utility Service .....                                    | 26 |
| DAST Global Service .....                                     | 26 |
| ScanCentral DAST Database .....                               | 26 |
| WebInspect Sensor .....                                       | 27 |
| Permissions in Fortify Software Security Center .....         | 27 |
| Tasks Requiring Admin Permissions .....                       | 28 |
| Related Documents .....                                       | 28 |
| All Products .....                                            | 29 |
| Micro Focus Fortify ScanCentral DAST .....                    | 29 |
| Micro Focus Fortify Software Security Center .....            | 30 |
| Micro Focus Fortify WebInspect .....                          | 30 |
| Chapter 2: Configuring the ScanCentral DAST Environment ..... | 32 |
| Important Information about SSL .....                         | 32 |
| Requesting Access to Fortify Docker Repository .....          | 32 |
| Before You Begin .....                                        | 33 |
| Understanding the Installation Process .....                  | 33 |
| Upgrading and Managing ScanCentral DAST .....                 | 35 |

|                                                                    |    |
|--------------------------------------------------------------------|----|
| Upgrading ScanCentral DAST .....                                   | 35 |
| Requirements for Upgrading .....                                   | 35 |
| Recommendation for Upgrading .....                                 | 36 |
| Effect of Upgrades on Scheduled Scans .....                        | 36 |
| Managing ScanCentral DAST .....                                    | 36 |
| Setting Up Docker .....                                            | 36 |
| Configuring the Database and Core Containers .....                 | 37 |
| About the ScanCentral DAST Configuration Tool .....                | 37 |
| Installing and Launching the Configuration Tool .....              | 38 |
| What's Next? .....                                                 | 38 |
| Configuring the Database Connection .....                          | 38 |
| Configuring the DBO-level Account .....                            | 38 |
| Configuring the Standard Account .....                             | 39 |
| What's Next? .....                                                 | 40 |
| Initializing the Database .....                                    | 40 |
| Updating SecureBase .....                                          | 40 |
| Using the Default SecureBase .....                                 | 40 |
| Using a Local SecureBase .....                                     | 41 |
| What's Next? .....                                                 | 41 |
| Configuring DAST SSL .....                                         | 41 |
| About the Certificate Path .....                                   | 41 |
| Generating an API SSL Certificate .....                            | 41 |
| Using an Existing Certificate .....                                | 42 |
| Not Using SSL .....                                                | 42 |
| What's Next? .....                                                 | 43 |
| Configuring Utility Service SSL .....                              | 43 |
| About the Certificate Path .....                                   | 43 |
| Generating a Utility Service SSL Certificate .....                 | 43 |
| Using an Existing Certificate .....                                | 44 |
| Not Using SSL .....                                                | 44 |
| What's Next? .....                                                 | 45 |
| Configuring Environment Settings .....                             | 45 |
| Configuring Proxy Settings .....                                   | 45 |
| Known Issue with Host Name, Machine Name, and Container Name ..... | 46 |
| Allowing Untrusted Certificates .....                              | 46 |
| What's Next? .....                                                 | 46 |
| Configuring ScanCentral DAST Settings .....                        | 46 |
| Configuring SSC Settings .....                                     | 46 |

|                                                          |    |
|----------------------------------------------------------|----|
| Configuring API Settings .....                           | 47 |
| Configuring Utility Service Settings .....               | 48 |
| Configuring LIM Settings .....                           | 48 |
| Creating a Sensor Service Token .....                    | 48 |
| Retaining Completed Scans on Sensor .....                | 49 |
| Disabling Advanced Scan Prioritization .....             | 49 |
| Changing the SmartUpdate URL .....                       | 49 |
| Changing the Licensing URL .....                         | 49 |
| What's Next? .....                                       | 50 |
| Applying the Settings .....                              | 50 |
| What's Next? .....                                       | 50 |
| Generating Launch Artifacts .....                        | 50 |
| Understanding the Launch Artifacts .....                 | 51 |
| Generating the Launch Artifacts .....                    | 52 |
| What's Next? .....                                       | 52 |
| Using the Compose File .....                             | 52 |
| Using PowerShell Scripts .....                           | 53 |
| Using One Script .....                                   | 53 |
| Using Two Scripts .....                                  | 54 |
| Using Fortify WebInspect on Docker .....                 | 55 |
| Using Fortify WebInspect with the Sensor Service .....   | 55 |
| Before You Begin .....                                   | 55 |
| Important Information About Licenses .....               | 55 |
| Important Prerequisite for Windows Server 2016 .....     | 56 |
| Configuring the Fortify WebInspect REST API .....        | 56 |
| Installing and Configuring the DAST Sensor Service ..... | 58 |
| Integrating with Kubernetes .....                        | 59 |
| DNS Requirement .....                                    | 60 |
| Sensor Installation Requirement .....                    | 61 |
| Implementing Scan Scaling with Kubernetes .....          | 61 |
| Downloading kubectl and Helm .....                       | 62 |
| Downloading in Windows PowerShell .....                  | 62 |
| Downloading in Linux .....                               | 63 |
| Deploying HAProxy in Kubernetes .....                    | 63 |
| Before You Begin .....                                   | 63 |
| Guideline for Configuring HAProxy in Azure .....         | 64 |
| Deploying HAProxy Ingress Controller .....               | 64 |

|                                                           |        |
|-----------------------------------------------------------|--------|
| Deploying the Kubernetes Metrics Server .....             | 65     |
| Before You Begin .....                                    | 65     |
| Deploying the Metrics Server .....                        | 65     |
| Confirming the Metrics Server Installation .....          | 65     |
| Deploying WISE in Kubernetes .....                        | 66     |
| Before You Begin .....                                    | 66     |
| Using the Default Parameters .....                        | 66     |
| Viewing the Default Parameters .....                      | 66     |
| Overriding the Default Parameters .....                   | 67     |
| Installing WISE Into a Kubernetes Namespace .....         | 68     |
| Understanding the Parameters for WISE Deployment .....    | 69     |
| Uninstalling WISE .....                                   | 70     |
| Installing the Sensor into the Kubernetes Cluster .....   | 70     |
| Before You Begin .....                                    | 70     |
| Installing the Sensor .....                               | 71     |
| Understanding the Helm Parameters .....                   | 72     |
| Uninstalling the Sensor from the Kubernetes Cluster ..... | 73     |
| <br>Chapter 3: Understanding the User Interface .....     | <br>74 |
| ScanCentral DAST User Interface .....                     | 74     |
| Scan Visualization .....                                  | 75     |
| Resizing the Display Areas .....                          | 76     |
| Hiding and Showing a Display Area .....                   | 76     |
| Working with Tables .....                                 | 77     |
| Customizing Table Views .....                             | 77     |
| Updating or Creating a View .....                         | 78     |
| Selecting a Different View .....                          | 78     |
| Managing Columns in Tables .....                          | 78     |
| Rearranging the Columns .....                             | 78     |
| Adding and Removing Columns .....                         | 79     |
| Understanding Basic Filters in Tables .....               | 79     |
| Guidelines .....                                          | 80     |
| Using Basic Filters in Tables .....                       | 80     |
| Accessing the Basic Filter Feature .....                  | 80     |
| Filtering by Application, Version, Name, or URL .....     | 80     |
| Filtering by Date, Scan Status, or Scan Type .....        | 81     |
| Clearing the Filter .....                                 | 82     |

|                                                                             |        |
|-----------------------------------------------------------------------------|--------|
| Understanding Advanced Filters in Tables .....                              | 83     |
| Understanding the Operators .....                                           | 83     |
| Understanding Conditions and Field Filters .....                            | 84     |
| Using Advanced Filters in Tables .....                                      | 84     |
| Accessing the Advance Filter Feature .....                                  | 84     |
| Creating an Advanced Filter .....                                           | 84     |
| Editing an Advanced Filter Condition .....                                  | 85     |
| Removing an Advanced Filter Condition .....                                 | 85     |
| Clearing Filters .....                                                      | 85     |
| Sorting Data in Columns .....                                               | 86     |
| Known Issue with Sorting .....                                              | 87     |
| Sorting Directly in the Table .....                                         | 87     |
| Sorting in the Table Preferences Panel .....                                | 87     |
| Clearing Data from Input Boxes .....                                        | 88     |
| Viewing Content on Multiple Pages .....                                     | 88     |
| Changing the Number of Items Displayed .....                                | 88     |
| Navigating Multiple Pages .....                                             | 88     |
| Changing the Number of Items Displayed in the Table Preferences Panel ..... | 89     |
| <br>Chapter 4: Configuring a Scan .....                                     | <br>90 |
| What is a Scan? .....                                                       | 90     |
| Preparing Your System for Audit .....                                       | 90     |
| Sensitive Data .....                                                        | 90     |
| Firewalls, Anti-virus Software, and Intrusion Detection Systems .....       | 91     |
| Effects to Consider .....                                                   | 91     |
| Helpful Hints .....                                                         | 92     |
| Accessing Settings Configuration from Software Security Center .....        | 93     |
| Accessing from the DAST Scans List .....                                    | 93     |
| Accessing from the Settings List .....                                      | 93     |
| What's Next? .....                                                          | 93     |
| Getting Started .....                                                       | 93     |
| What's Next? .....                                                          | 94     |
| Configuring a Standard Scan .....                                           | 95     |
| What's Next? .....                                                          | 96     |
| Configuring a Workflow-driven Scan .....                                    | 96     |
| Types of Macros Supported .....                                             | 96     |

|                                                       |     |
|-------------------------------------------------------|-----|
| Configuring a Workflow-driven Scan .....              | 97  |
| What's Next? .....                                    | 98  |
| Configuring an API Scan .....                         | 98  |
| What's Next? .....                                    | 102 |
| Configuring Proxy Settings .....                      | 102 |
| What's Next? .....                                    | 103 |
| Configuring Authentication .....                      | 103 |
| Configuring Site Authentication .....                 | 104 |
| Downloading the Macro Recorder Tool .....             | 104 |
| Using a Client Certificate .....                      | 104 |
| Configuring Network Authentication .....              | 105 |
| What's Next? .....                                    | 105 |
| Configuring Scan Details .....                        | 106 |
| What's Next? .....                                    | 106 |
| Adding and Managing Allowed Hosts .....               | 106 |
| Adding Allowed Hosts .....                            | 107 |
| Editing or Removing Hosts .....                       | 107 |
| Configuring Scan Priority .....                       | 107 |
| Changing the Priority .....                           | 108 |
| Understanding Advanced Scan Prioritization .....      | 108 |
| Priority and Sensor Pools .....                       | 108 |
| Priority and Scan Status .....                        | 108 |
| Priority and Sensors .....                            | 109 |
| When Advanced Scan Prioritization is Disabled .....   | 109 |
| Configuring Data Retention .....                      | 110 |
| Scanning Single-page Applications .....               | 110 |
| Technology Preview .....                              | 110 |
| The Challenge of Single-page Applications .....       | 110 |
| Configuring SPA Support .....                         | 111 |
| Using Traffic Viewer (Traffic Monitor) .....          | 111 |
| Proxy Server Included .....                           | 111 |
| Option Must be Enabled .....                          | 111 |
| Enabling Traffic Viewer (or Traffic Monitor) .....    | 111 |
| Creating and Managing Exclusions .....                | 112 |
| Creating Exclusions .....                             | 112 |
| Exclusion Examples .....                              | 113 |
| Editing or Removing Exclusions .....                  | 113 |
| Understanding and Creating Inclusive Exclusions ..... | 114 |



|                                                             |     |
|-------------------------------------------------------------|-----|
| Understanding Inclusive Exclusion Regular Expressions ..... | 114 |
| Example One .....                                           | 114 |
| Example Two .....                                           | 115 |
| Configuring Redundant Page Detection .....                  | 116 |
| Enabling SAST Correlation .....                             | 117 |
| Enabling Scan Scaling .....                                 | 117 |
| Reviewing Scan Settings .....                               | 118 |
| Saving the Settings to Software Security Center .....       | 118 |
| Scheduling a Scan .....                                     | 118 |
| Running a Scan .....                                        | 120 |
| Using the Scan Settings in the DAST API .....               | 120 |
| Accessing the DAST API Swagger UI .....                     | 121 |
| Using the Swagger UI .....                                  | 121 |
| Conducting an Automated Scan with FAST .....                | 121 |
| Installation Recommendation .....                           | 121 |
| Before You Begin .....                                      | 122 |
| Process Overview .....                                      | 122 |
| Downloading the FAST Installer .....                        | 123 |
| Understanding the FAST Options .....                        | 123 |
| Chapter 5: Working with Scans .....                         | 126 |
| Accessing DAST Scans in Software Security Center .....      | 126 |
| User Role Determines Capabilities .....                     | 126 |
| Understanding the Scans List .....                          | 126 |
| Understanding the Scan Detail Panel .....                   | 130 |
| Findings by Severity .....                                  | 130 |
| Additional Scan Details .....                               | 130 |
| Working with Active Scans .....                             | 132 |
| Pausing a Scan .....                                        | 132 |
| Stopping a Scan .....                                       | 132 |
| Resuming a Scan .....                                       | 133 |
| Re-importing a Scan .....                                   | 133 |
| Working with Alerts .....                                   | 133 |
| Technology Preview .....                                    | 133 |
| Accessing Alerts .....                                      | 134 |
| Understanding the ALERTS Tab .....                          | 134 |
| Acknowledging New Alerts .....                              | 135 |

|                                                          |     |
|----------------------------------------------------------|-----|
| Managing the DAST Scans List .....                       | 135 |
| Starting a New Scan .....                                | 135 |
| Refreshing the Scans List .....                          | 135 |
| Publishing to Fortify Software Security Center .....     | 136 |
| Deleting a Scan .....                                    | 136 |
| Using the Force Delete Option .....                      | 136 |
| Downloading DAST Scans, Settings, and Logs .....         | 137 |
| Paused Scans .....                                       | 137 |
| License Unavailable Scan Status .....                    | 137 |
| File Types Available .....                               | 137 |
| Downloading a File .....                                 | 139 |
| Viewing Scan Results .....                               | 139 |
| Working with the Site Tree .....                         | 140 |
| Site Tree Icons .....                                    | 140 |
| Using Breadcrumbs .....                                  | 140 |
| Understanding the Findings Table .....                   | 141 |
| Available Columns .....                                  | 141 |
| Working with Findings .....                              | 142 |
| Viewing the Vulnerability Description .....              | 142 |
| Viewing the Request and Response .....                   | 142 |
| Viewing Steps .....                                      | 142 |
| Understanding the Traffic Table .....                    | 143 |
| Available Columns .....                                  | 143 |
| Working with Traffic .....                               | 145 |
| Viewing the Request and Response .....                   | 145 |
| Viewing Parameters .....                                 | 145 |
| Viewing Steps .....                                      | 146 |
| Understanding SPA Coverage .....                         | 146 |
| Chapter 6: Working with Sensors .....                    | 148 |
| Accessing DAST Sensors in Software Security Center ..... | 148 |
| User Role Determines Capabilities .....                  | 148 |
| Understanding the Sensor List .....                      | 148 |
| Understanding the Sensor Detail Panel .....              | 149 |
| Enabling or Disabling Sensors .....                      | 150 |
| Facts About Disabled Sensors .....                       | 150 |
| Enabling or Disabling a Sensor .....                     | 150 |

|                                                                 |     |
|-----------------------------------------------------------------|-----|
| Chapter 7: Working with Sensor Pools .....                      | 152 |
| Accessing DAST Sensor Pools in Software Security Center .....   | 152 |
| User Role Determines Capabilities .....                         | 152 |
| Understanding the Sensor Pools List .....                       | 152 |
| Understanding the Pool Detail Panel .....                       | 153 |
| Creating a DAST Sensor Pool .....                               | 153 |
| Managing Sensor Pools .....                                     | 155 |
| Facts About Managing Sensor Pools .....                         | 155 |
| Editing a Sensor Pool .....                                     | 155 |
| Refreshing the Pools List .....                                 | 155 |
| Deleting a Sensor Pool .....                                    | 156 |
| Changing the Default Sensor Pool .....                          | 156 |
| Chapter 8: Working with Scan Settings .....                     | 157 |
| Accessing DAST Scan Settings in Software Security Center .....  | 157 |
| User Role Determines Capabilities .....                         | 157 |
| Understanding the Scan Settings List .....                      | 157 |
| Understanding the Scan Settings Detail Panel .....              | 158 |
| Managing Scan Settings .....                                    | 159 |
| Creating New Settings .....                                     | 159 |
| Editing Settings .....                                          | 160 |
| Downloading Settings .....                                      | 160 |
| Deleting Settings .....                                         | 160 |
| Copying the Settings ID for Use in the API .....                | 161 |
| Chapter 9: Working with Scan Schedules .....                    | 162 |
| Accessing DAST Scan Schedules in Software Security Center ..... | 162 |
| User Role Determines Capabilities .....                         | 162 |
| Understanding the Scan Schedules List .....                     | 162 |
| Understanding the Schedule Detail Panel .....                   | 163 |
| Managing Schedules .....                                        | 163 |
| Creating a New Schedule .....                                   | 163 |
| Editing a Schedule .....                                        | 164 |
| Enabling or Disabling Schedules .....                           | 164 |
| Deleting a Schedule .....                                       | 165 |

|                                                            |     |
|------------------------------------------------------------|-----|
| Chapter 10: Working with Deny Intervals .....              | 166 |
| Deny Intervals Apply to Applications .....                 | 166 |
| Deny Intervals are Global Settings .....                   | 166 |
| Accessing Deny Intervals in Software Security Center ..... | 166 |
| User Role Determines Capabilities .....                    | 167 |
| Understanding the Deny Intervals List .....                | 167 |
| Understanding the Deny Intervals Detail Panel .....        | 167 |
| Creating a Deny Interval .....                             | 168 |
| Managing Deny Intervals .....                              | 171 |
| Facts About Editing a Deny Interval .....                  | 171 |
| Editing a Deny Interval .....                              | 171 |
| Deleting a Deny Interval .....                             | 172 |
| Refreshing the Deny Intervals List .....                   | 172 |
| Chapter 11: Working with Policies .....                    | 173 |
| Accessing Policies in Software Security Center .....       | 173 |
| User Role Determines Capabilities .....                    | 173 |
| Understanding the Policies List .....                      | 173 |
| Understanding the Policy Detail Panel .....                | 174 |
| Importing a Custom Policy .....                            | 174 |
| Managing Policies .....                                    | 175 |
| Editing a Policy .....                                     | 175 |
| Deleting a Policy .....                                    | 175 |
| Refreshing the Policies List .....                         | 176 |
| Chapter 12: Working with Base Settings .....               | 177 |
| Differences Between Base Settings and Templates .....      | 177 |
| Base Settings are Global Settings .....                    | 177 |
| Accessing Base Settings in Software Security Center .....  | 177 |
| User Role Determines Capabilities .....                    | 177 |
| Understanding the Base Settings List .....                 | 178 |
| Understanding the Base Settings Detail Panel .....         | 178 |
| Creating Base Settings .....                               | 179 |
| What's Next? .....                                         | 180 |

|                                                               |     |
|---------------------------------------------------------------|-----|
| Configuring Base Settings for a Standard Scan .....           | 180 |
| What's Next? .....                                            | 181 |
| Configuring Base Settings for a Workflow-driven Scan .....    | 182 |
| Types of Macros Supported .....                               | 182 |
| Configuring Base Settings for a Workflow-driven Scan .....    | 182 |
| What's Next? .....                                            | 183 |
| Configuring Base Settings for an API Scan .....               | 183 |
| What's Next? .....                                            | 187 |
| Configuring Proxy Settings in Base Settings .....             | 187 |
| What's Next? .....                                            | 188 |
| Configuring Authentication in Base Settings .....             | 188 |
| Configuring Site Authentication .....                         | 189 |
| Downloading the Macro Recorder Tool .....                     | 189 |
| Configuring Network Authentication .....                      | 189 |
| What's Next? .....                                            | 190 |
| Configuring Base Settings Details .....                       | 190 |
| What's Next? .....                                            | 190 |
| Adding and Managing Allowed Hosts in Base Settings .....      | 190 |
| Adding Allowed Hosts .....                                    | 191 |
| Editing or Removing Hosts .....                               | 191 |
| Configuring Scan Priority in Base Settings .....              | 192 |
| Changing the Priority .....                                   | 192 |
| Configuring Data Retention in Base Settings .....             | 192 |
| Scanning Single-page Applications in Base Settings .....      | 192 |
| Technology Preview .....                                      | 193 |
| The Challenge of Single-page Applications .....               | 193 |
| Configuring SPA Support .....                                 | 193 |
| Using Traffic Viewer (Traffic Monitor) in Base Settings ..... | 193 |
| Proxy Server Included .....                                   | 194 |
| Option Must be Enabled .....                                  | 194 |
| Enabling Traffic Viewer (or Traffic Monitor) .....            | 194 |
| Creating and Managing Exclusions in Base Settings .....       | 194 |
| Creating Exclusions .....                                     | 194 |
| Exclusion Examples .....                                      | 195 |
| Editing or Removing Exclusions .....                          | 196 |
| Configuring Redundant Page Detection in Base Settings .....   | 196 |
| Enabling SAST Correlation in Base Settings .....              | 197 |
| Applying Base Settings to Applications .....                  | 197 |
| What's Next? .....                                            | 197 |

|                                                                                                       |     |
|-------------------------------------------------------------------------------------------------------|-----|
| Reviewing and Saving Base Settings .....                                                              | 197 |
| Chapter 13: Working with Application Settings .....                                                   | 198 |
| Application Settings are Global Settings .....                                                        | 198 |
| Priority .....                                                                                        | 198 |
| Data Retention .....                                                                                  | 198 |
| Accessing the Application Settings .....                                                              | 198 |
| User Role Determines Capabilities .....                                                               | 199 |
| Understanding the Application Settings List .....                                                     | 199 |
| Managing Application Settings .....                                                                   | 199 |
| Editing Application Settings .....                                                                    | 200 |
| Refreshing the Application Settings List .....                                                        | 201 |
| Appendix A: Troubleshooting ScanCentral DAST .....                                                    | 202 |
| Locating Log Files .....                                                                              | 202 |
| Log File Names .....                                                                                  | 202 |
| Extracting Log Files .....                                                                            | 202 |
| API Logs .....                                                                                        | 202 |
| DAST Configuration Tool Logs .....                                                                    | 203 |
| Global Service Logs .....                                                                             | 203 |
| Scanner Service Logs .....                                                                            | 203 |
| Utility Service Logs .....                                                                            | 204 |
| Troubleshooting the Configuration Tool .....                                                          | 204 |
| Troubleshooting Upgrade Issues .....                                                                  | 206 |
| Troubleshooting the DAST API .....                                                                    | 209 |
| Troubleshooting DAST Scans .....                                                                      | 210 |
| Troubleshooting Alerts .....                                                                          | 212 |
| Technology Preview .....                                                                              | 212 |
| Disabling Alerts .....                                                                                | 212 |
| Alerts Troubleshooting Table .....                                                                    | 212 |
| Checking and Restarting the WebInspect REST API Service .....                                         | 213 |
| Checking the WebInspect REST API Service Status in a Classic Fortify WebInspect<br>Installation ..... | 213 |
| Restarting the Service in a Classic Fortify WebInspect installation .....                             | 213 |
| Checking the WebInspect REST API Service Status in Fortify WebInspect on Docker .....                 | 214 |

|                                                                                       |     |
|---------------------------------------------------------------------------------------|-----|
| Restarting the Service for Fortify WebInspect on Docker .....                         | 214 |
| Troubleshooting the Sensor Service .....                                              | 214 |
| Checking the Sensor Service Status in a Classic Fortify WebInspect Installation ..... | 215 |
| Restarting the Sensor Service in a Classic Fortify WebInspect Installation .....      | 215 |
| Checking the Sensor Service Status in Fortify WebInspect on Docker .....              | 215 |
| Restarting the Sensor Service in Fortify WebInspect on Docker .....                   | 216 |
| Appendix B: Scanning with a Postman Collection .....                                  | 217 |
| What is Postman? .....                                                                | 217 |
| Benefits of a Postman Collection .....                                                | 217 |
| Known Limitations with Postman Variables .....                                        | 217 |
| Postman Prerequisites .....                                                           | 217 |
| Tips for Preparing a Postman Collection .....                                         | 218 |
| Ensure Valid Responses .....                                                          | 218 |
| Order of Requests .....                                                               | 218 |
| Handling Authentication .....                                                         | 218 |
| Using Static Authentication .....                                                     | 219 |
| Using Dynamic Authentication .....                                                    | 219 |
| Using a Postman Login Macro .....                                                     | 219 |
| Postman Auto-configuration .....                                                      | 219 |
| Sample Postman Scripts .....                                                          | 220 |
| Manually Configuring Postman Login for Dynamic Tokens .....                           | 220 |
| What are Dynamic Tokens? .....                                                        | 220 |
| Before You Begin .....                                                                | 220 |
| Process Overview .....                                                                | 220 |
| Identifying and Isolating the Login Request .....                                     | 221 |
| Creating a Logout Condition with Regular Expressions .....                            | 221 |
| Creating a Response State Rule for a Bearer Token .....                               | 222 |
| Creating a Response State Rule for an API Key .....                                   | 222 |
| Appendix C: Reference Lists .....                                                     | 224 |
| Policies .....                                                                        | 224 |
| Best Practices .....                                                                  | 224 |
| By Type .....                                                                         | 226 |
| Custom .....                                                                          | 227 |
| Hazardous .....                                                                       | 227 |

|                                      |     |
|--------------------------------------|-----|
| Deprecated Checks and Policies ..... | 228 |
| HTTP Status Codes .....              | 229 |
| Send Documentation Feedback .....    | 233 |



# Preface

## Contacting Micro Focus Fortify Customer Support

Visit the Support website to:

- Manage licenses and entitlements
- Create and manage technical assistance requests
- Browse documentation and knowledge articles
- Download software
- Explore the Community

<https://www.microfocus.com/support>

## For More Information

For more information about Fortify software products:

<https://www.microfocus.com/cyberres/application-security>

## About the Documentation Set

The Fortify Software documentation set contains installation, user, and deployment guides for all Fortify Software products and components. In addition, you will find technical notes and release notes that describe new features, known issues, and last-minute updates. You can access the latest versions of these documents from the following Micro Focus Product Documentation website:

<https://www.microfocus.com/support/documentation>

To be notified of documentation updates between releases, subscribe to Fortify Product Announcements on the Micro Focus Community:

<https://community.microfocus.com/cyberres/fortify/w/fortify-product-announcements>

## Fortify Product Feature Videos

You can find videos that highlight Fortify products and features on the Fortify Unplugged YouTube channel:

<https://www.youtube.com/c/FortifyUnplugged>

# Change Log

The following table lists changes made to this document. Revisions to this document are published between software releases only if the changes made affect product functionality.

| Software Release / Document Version | Changes                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|-------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 21.2.0                              | <p>Added:</p> <ul style="list-style-type: none"><li>• Content describing tables and table preferences. See <a href="#">"Working with Tables" on page 77</a>.</li><li>• Content describing advanced filtering. See <a href="#">"Understanding Advanced Filters in Tables" on page 83</a> and <a href="#">"Using Advanced Filters in Tables" on page 84</a>.</li><li>• Content for redundant page detection in scan settings. See <a href="#">"Configuring Redundant Page Detection" on page 116</a> and <a href="#">"Configuring Redundant Page Detection in Base Settings" on page 196</a>.</li><li>• Content for SAST correlation in scan settings. See <a href="#">"Enabling SAST Correlation" on page 117</a> and <a href="#">"Enabling SAST Correlation in Base Settings" on page 197</a>.</li><li>• Content related to scan visualization. See the following topics:<ul style="list-style-type: none"><li>• <a href="#">"Scan Visualization" on page 75</a></li><li>• <a href="#">"Viewing Scan Results" on page 139</a></li><li>• <a href="#">"Working with the Site Tree" on page 140</a></li><li>• <a href="#">"Understanding the Findings Table" on page 141</a></li><li>• <a href="#">"Working with Findings" on page 142</a></li><li>• <a href="#">"Understanding the Traffic Table" on page 143</a></li><li>• <a href="#">"Working with Traffic" on page 145</a></li><li>• <a href="#">"Understanding SPA Coverage" on page 146</a></li></ul></li><li>• Content describing advanced scan prioritization. See <a href="#">"Understanding Advanced Scan Prioritization" on page 108</a>.</li><li>• Procedure for using a client certificate in a scan. See <a href="#">"Configuring Authentication" on page 103</a>.</li></ul> |

| Software Release /<br>Document Version | Changes                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|----------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                        | <ul style="list-style-type: none"> <li>• HTTP status codes for reference. See <a href="#">"HTTP Status Codes" on page 229</a>.</li> </ul> <p>Updated:</p> <ul style="list-style-type: none"> <li>• Configuration tool content with new upgrade and manage options. See the following topics: <ul style="list-style-type: none"> <li>• <a href="#">"Configuring the ScanCentral DAST Environment" on page 32</a></li> <li>• <a href="#">"Upgrading and Managing ScanCentral DAST" on page 35</a></li> <li>• <a href="#">"Configuring the Database and Core Containers" on page 37</a></li> <li>• <a href="#">"Configuring the Database Connection" on page 38</a></li> <li>• <a href="#">"Initializing the Database" on page 40</a></li> <li>• <a href="#">"Configuring DAST SSL" on page 41</a></li> <li>• <a href="#">"Configuring Utility Service SSL" on page 43</a></li> <li>• <a href="#">"Configuring Environment Settings" on page 45</a></li> <li>• <a href="#">"Configuring ScanCentral DAST Settings" on page 46</a></li> <li>• <a href="#">"Applying the Settings" on page 50</a></li> <li>• <a href="#">"Generating Launch Artifacts" on page 50</a></li> </ul> </li> <li>• Database connection configuration with important information about when to specify the server port. See <a href="#">"Configuring the Database Connection" on page 38</a>.</li> <li>• Miscellaneous content with procedures for using the table preferences panel. See the following: <ul style="list-style-type: none"> <li>• <a href="#">"Understanding Basic Filters in Tables" on page 79</a></li> <li>• <a href="#">"Using Basic Filters in Tables" on page 80</a></li> <li>• <a href="#">"Sorting Data in Columns" on page 86</a></li> <li>• <a href="#">"Viewing Content on Multiple Pages" on page 88</a></li> </ul> </li> <li>• Postman scanning information with known limitations for Postman variables. See <a href="#">"Scanning with a Postman Collection" on page 217</a>.</li> <li>• FAST proxy content with important statement regarding where <i>not</i> to</li> </ul> |

| Software Release / Document Version | Changes                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|-------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                     | <p>install the proxy. See <a href="#">"Conducting an Automated Scan with FAST" on page 121</a>.</p> <ul style="list-style-type: none"> <li>• Scans list table description with Scan Id and new statuses related to scan priority. See <a href="#">"Understanding the Scans List" on page 126</a>.</li> <li>• Scan detail panel description with Scan Id. See <a href="#">"Understanding the Scan Detail Panel" on page 130</a>.</li> <li>• Application settings with SAST correlation. See <a href="#">"Managing Application Settings" on page 199</a>.</li> <li>• Content related to managing the scans list with the force delete option. See <a href="#">"Managing the DAST Scans List" on page 135</a>.</li> <li>• File types that can be downloaded with new scan statuses. See <a href="#">"Downloading DAST Scans, Settings, and Logs" on page 137</a>.</li> <li>• Proxy settings content with note regarding Utility Service being automatically added to the proxy bypass list, and a known issue with using host name, machine name, and container name for proxy bypass. See <a href="#">"Configuring Environment Settings" on page 45</a>.</li> <li>• Configuration tool content with important information about not retaining traffic files on sensor containers and option to disable advanced scan prioritization. See <a href="#">"Configuring ScanCentral DAST Settings" on page 46</a>.</li> <li>• Procedures for generating certificates to indicate that certificate passwords are required. See <a href="#">"Configuring DAST SSL" on page 41</a> and <a href="#">"Configuring Utility Service SSL" on page 43</a>.</li> <li>• Target list and Type list with new options for exclusions. See <a href="#">"Creating and Managing Exclusions" on page 112</a>.</li> <li>• Troubleshooting for proxy issue during configuration. See <a href="#">"Troubleshooting the Configuration Tool" on page 204</a>.</li> <li>• Troubleshooting for redundant content alert. See <a href="#">"Troubleshooting Alerts" on page 212</a>.</li> <li>• Troubleshooting for client certificates. See <a href="#">"Troubleshooting DAST Scans" on page 210</a>.</li> <li>• DAST sensor service content with information regarding encrypted communication for the DAST API service. See <a href="#">"Using Fortify WebInspect with the Sensor Service" on page 55</a> and <a href="#">"Troubleshooting</a></li> </ul> |

| Software Release / Document Version   | Changes                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|---------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                       | <p><a href="#">the Sensor Service</a> on page 214.</p> <ul style="list-style-type: none"> <li>Summary page content to include the error messages dialog box in the Configuration Tool. See <a href="#">"Applying the Settings"</a> on page 50.</li> </ul>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| 21.1.0 / Revision 1:<br>July 23, 2021 | <p>Updated:</p> <ul style="list-style-type: none"> <li>The location of the DAST Configuration Tool uninstaller. See <a href="#">"Troubleshooting the Configuration Tool"</a> on page 204.</li> </ul>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| 21.1.0                                | <p>Added:</p> <ul style="list-style-type: none"> <li>Content for preparing the website for audit. See <a href="#">"Preparing Your System for Audit"</a> on page 90.</li> <li>Content related to deny intervals. See <a href="#">"Working with Deny Intervals"</a> on page 166.</li> <li>Content related to base settings. See <a href="#">"Working with Base Settings"</a> on page 177.</li> <li>Content related to application settings. See <a href="#">"Working with Application Settings"</a> on page 198.</li> <li>Content related to scan priority. See <a href="#">"Configuring Scan Priority"</a> on page 107 and <a href="#">"Configuring Scan Priority in Base Settings"</a> on page 192.</li> <li>Process and procedures for using Site Explorer to view scan results. See <a href="#">"Viewing Scan Results"</a> on page 139.</li> <li>Content related to scan Alerts. See <a href="#">"Working with Alerts"</a> on page 133 and <a href="#">"Troubleshooting Alerts"</a> on page 212.</li> <li>Content related to Scan Scaling. See the following topics: <ul style="list-style-type: none"> <li><a href="#">"Integrating with Kubernetes"</a> on page 59</li> <li><a href="#">"Creating a DAST Sensor Pool"</a> on page 153</li> <li><a href="#">"Enabling Scan Scaling"</a> on page 117 (Scan Details)</li> </ul> </li> <li>Content related to custom policies. See the following topics: <ul style="list-style-type: none"> <li><a href="#">"Working with Policies"</a> on page 173</li> <li><a href="#">"Configuring a Standard Scan"</a> on page 95</li> <li><a href="#">"Configuring a Workflow-driven Scan"</a> on page 96</li> </ul> </li> </ul> |

| Software Release / Document Version | Changes                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|-------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                     | <ul style="list-style-type: none"> <li>• <a href="#">"Configuring an API Scan" on page 98</a></li> <li>• Information about using Postman collection files. See <a href="#">"Scanning with a Postman Collection" on page 217</a>.</li> <li>• Description of Functional Application Security Testing (FAST) and process for conducting scans using FAST. See <a href="#">"Conducting an Automated Scan with FAST" on page 121</a>.</li> <li>• Location of the utility service log files. See <a href="#">"Locating Log Files" on page 202</a>.</li> <li>• Troubleshooting content related to upgrades. See <a href="#">"Troubleshooting Upgrade Issues" on page 206</a>.</li> </ul> <p>Updated:</p> <ul style="list-style-type: none"> <li>• Descriptions of scans and procedures for configuring scans to include scan priority. See the following topics: <ul style="list-style-type: none"> <li>• <a href="#">"Configuring a Standard Scan" on page 95</a></li> <li>• <a href="#">"Configuring a Workflow-driven Scan" on page 96</a></li> <li>• <a href="#">"Configuring an API Scan" on page 98</a></li> <li>• <a href="#">"Understanding the Scans List" on page 126</a></li> <li>• <a href="#">"Understanding the Scan Detail Panel" on page 130</a></li> </ul> </li> <li>• Content related to Postman scanning with scan configuration improvements. See <a href="#">"Configuring an API Scan" on page 98</a>.</li> <li>• Permissions table to include deny interval-related tasks. See <a href="#">"Permissions in Fortify Software Security Center" on page 27</a>.</li> <li>• Scan statuses to include statuses related to deny intervals. See <a href="#">"Understanding the Scans List" on page 126</a>.</li> <li>• Procedure for configuring a scan with base settings option. See <a href="#">"Getting Started" on page 93</a>.</li> <li>• Procedures for configuring a scan with Scan Scaling. See <a href="#">"Enabling Scan Scaling" on page 117</a>.</li> <li>• Content related to scans with data retention setting. See the following topics: <ul style="list-style-type: none"> <li>• <a href="#">"Configuring Data Retention" on page 110</a> (Scan Details)</li> </ul> </li> </ul> |

| Software Release / Document Version      | Changes                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                          | <ul style="list-style-type: none"> <li>• <a href="#">"Understanding the Scans List" on page 126</a></li> <li>• <a href="#">"Understanding the Scan Detail Panel" on page 130</a></li> <li>• Deleting scan settings procedure with delete error for dependencies. See <a href="#">"Managing Scan Settings" on page 159</a>.</li> <li>• Fortify ScanCentral DAST architecture overview to include new utility service container. See <a href="#">"What is ScanCentral DAST?" on page 25</a></li> <li>• List of policies with description of the NIST-SP80053R5 policy. See <a href="#">"Policies" on page 224</a>.</li> <li>• Procedures for DAST Configuration Tool to include the DAST Utility service and environment settings. See the following topics: <ul style="list-style-type: none"> <li>• <a href="#">"Configuring the Database and Core Containers" on page 37</a></li> <li>• <a href="#">"Configuring Utility Service SSL" on page 43</a></li> <li>• <a href="#">"Configuring Environment Settings" on page 45</a></li> <li>• <a href="#">"Generating Launch Artifacts" on page 50</a></li> </ul> </li> <li>• Setup overview with information, requirements, and recommendations for upgrades and using SSL. See <a href="#">"Configuring the ScanCentral DAST Environment" on page 32</a>.</li> <li>• Examples of inclusive exclusions with content about including the port in regular expressions. See <a href="#">"Understanding Inclusive Exclusion Regular Expressions" on page 114</a>.</li> </ul> <p>Removed:</p> <ul style="list-style-type: none"> <li>• Time zone setting from scheduling a scan.</li> </ul> |
| 20.2.0 / Revision 1:<br>December 4, 2020 | <p>Updated:</p> <ul style="list-style-type: none"> <li>• Permissions for Application Security Tester and Security Lead to include running scans from existing settings templates. See <a href="#">"Permissions in Fortify Software Security Center" on page 27</a>.</li> <li>• Installation process to include the trailing slash "/" after "/api" in the ScanCentral DAST URL in the ADMINISTRATION view in Fortify Software Security Center. See <a href="#">"Understanding the Installation Process" on page 33</a>.</li> </ul>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |

| Software Release /<br>Document Version | Changes                                                                                                                                                                                    |
|----------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                        | <ul style="list-style-type: none"><li>• Configuring ScanCentral DAST settings to remove reference of trailing "/api". See <a href="#">"Configuring API Settings" on page 47</a>.</li></ul> |
| 20.2.0                                 | Initial release of product.                                                                                                                                                                |




# Chapter 1: Introduction

Fortify ScanCentral DAST allows you to download and run a set of Docker containers, configure a connection with your instance of Fortify Software Security Center, and then configure and conduct dynamic scans of your web applications from Fortify Software Security Center.

## What is ScanCentral DAST?

Fortify ScanCentral DAST is a dynamic application security testing tool that is comprised of the Fortify WebInspect sensor service and other supporting technologies that you can use in conjunction with Fortify Software Security Center.

The following diagram illustrates the Fortify ScanCentral DAST architecture.



The following paragraphs describe these components in more detail.

## Software Security Center

The Fortify Software Security Center user interface (UI) provides a way to view the DAST scans list, sensors list, sensor pools, settings, and scan schedules. You can also access the DAST Settings Configuration wizard from the UI.

ScanCentral DAST communicates with Fortify Software Security Center by way of the Software Security Center Rest API.

ScanCentral DAST retrieves Application and Version information and user permissions from the Fortify Software Security Center database. ScanCentral DAST uploads scans for triage to the database as FPR files.

## LIM

The License and Infrastructure Manager (LIM) Docker image provides the licensing service for the ScanCentral DAST components. For more information about the LIM, see the *Micro Focus Fortify License and Infrastructure Manager Installation and Usage Guide*.

## DAST API

The ScanCentral DAST REST API Docker image provides communication between the sensor and the ScanCentral DAST database. It also communicates with the LIM for licensing, and Fortify Software Security Center.

The image name is `scancentral-dast-api`.

## DAST Utility Service

The ScanCentral DAST Utility Service is the Fortify WebInspect image. However, it runs in a restricted mode and handles lightweight executable utilities without regard to whether a sensor is running and available. It provides support for Postman scans.

The image name is `webinspect` and the container name is `scancentral-dast-utilityservice`.

**Important!** Before you can run the DAST utility service container, you must install Microsoft update KB4561608 on the host machine. For more information, see <https://support.microsoft.com/en-us/topic/june-9-2020-kb4561608-os-build-17763-1282-437af506-e3ef-a8a1-09e7-26cc94e509c7>.

## DAST Global Service

The ScanCentral DAST Global Service Docker image does the following:

- Starts scans (including scheduled scans), manages scan prioritization, and builds the site tree for completed scans
- Communicates messages to and from the ScanCentral DAST Sensor Service
- Imports scan results to the Fortify Software Security Center database
- Performs additional background tasks

**Note:** The ScanCentral DAST Global Service uses SmartUpdate to obtain the most recent SecureBase updates.

The image name is `scancentral-dast-globalservice`.

## ScanCentral DAST Database

Configuration settings for ScanCentral DAST are stored in the ScanCentral DAST database. The ScanCentral DAST REST API and ScanCentral DAST Global Service connect to the database on start up to retrieve configuration settings.

## WebInspect Sensor

The Fortify WebInspect sensor is either a Docker image or a Windows computer that runs the ScanCentral DAST Sensor Service and a Fortify WebInspect sensor. The sensor does the following:

- Starts and runs scans
- Reports scan statistics to the ScanCentral DAST Global Service
- Uploads the scan to the ScanCentral DAST Rest API

**Note:** The ScanCentral DAST Sensor uses SmartUpdate to obtain the most recent SecureBase updates.

## Permissions in Fortify Software Security Center

The permissions designated by your user role in Fortify Software Security Center determine the types of tasks that you can perform on ScanCentral DAST scans, sensors, sensor pools, settings, scan schedules, and global features such as deny windows and base settings. The following table describes the predefined roles in Fortify Software Security Center that allow dynamic-related tasks.

| <b>ScanCentral DAST Tasks</b>                                  | <b>Application Security Tester</b> | <b>Developer</b> | <b>Manager</b> | <b>Security Lead</b> | <b>View-only</b> |
|----------------------------------------------------------------|------------------------------------|------------------|----------------|----------------------|------------------|
| Manage pools and sensors                                       |                                    |                  | x              | x                    |                  |
| View data                                                      | x                                  | x                | x              | x                    | x                |
| Create, run, change, and delete scans, schedules, and settings | x                                  |                  |                | x                    |                  |
| Run scans from existing templates and base settings            | x                                  | x                |                | x                    |                  |
| Download artifacts (settings,                                  | x                                  | x                |                | x                    |                  |

| ScanCentral<br>DAST Tasks                                                              | Application<br>Security<br>Tester | Developer | Manager | Security<br>Lead | View-only |
|----------------------------------------------------------------------------------------|-----------------------------------|-----------|---------|------------------|-----------|
| scans, and<br>logs)                                                                    |                                   |           |         |                  |           |
| Manage deny<br>intervals,<br>application<br>priority level,<br>and retention<br>policy |                                   |           |         | x                |           |

For information about creating custom user roles, see the *Micro Focus Fortify Software Security Center User Guide*.

## Tasks Requiring Admin Permissions

The following ScanCentral DAST tasks require Fortify Software Security Center administrator-level privileges (with the **Universal access** option):

- Creating and maintaining custom policies
- Creating and maintaining base settings
- Force deleting scans from the ScanCentral DAST database

## Related Documents

This topic describes documents that provide information about Micro Focus Fortify software products.

**Note:** You can find the Micro Focus Fortify Product Documentation at <https://www.microfocus.com/support/documentation>. Most guides are available in both PDF and HTML formats. Product help is available within the Fortify LIM product and the Fortify WebInspect products.

## All Products

The following documents provide general information for all products. Unless otherwise noted, these documents are available on the [Micro Focus Product Documentation](#) website.

| Document / File Name                                                                                                      | Description                                                                                                                                                                                                                     |
|---------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>About Micro Focus Fortify Product Software Documentation</i><br><br>About_Fortify_Docs_<version>.pdf                   | This paper provides information about how to access Micro Focus Fortify product documentation.<br><br><b>Note:</b> This document is included only with the product download.                                                    |
| <i>Micro Focus Fortify License and Infrastructure Manager Installation and Usage Guide</i><br><br>LIM_Guide_<version>.pdf | This document describes how to install, configure, and use the Fortify License and Infrastructure Manager (LIM), which is available for installation on a local Windows server and as a container image on the Docker platform. |
| <i>Micro Focus Fortify Software System Requirements</i><br><br>Fortify_Sys_Reqs_<version>.pdf                             | This document provides the details about the environments and products supported for this version of Fortify Software.                                                                                                          |
| <i>Micro Focus Fortify Software Release Notes</i><br><br>FortifySW_RN_<version>.pdf                                       | This document provides an overview of the changes made to Fortify Software for this release and important information not included elsewhere in the product documentation.                                                      |
| <i>What's New in Micro Focus Fortify Software &lt;version&gt;</i><br><br>Fortify_Whats_New_<version>.pdf                  | This document describes the new features in Fortify Software products.                                                                                                                                                          |

## Micro Focus Fortify ScanCentral DAST

The following document provides information about Fortify ScanCentral DAST. Unless otherwise noted, these documents are available on the Micro Focus Product Documentation website at <https://www.microfocus.com/documentation/fortify-ScanCentral-DAST>.

| Document / File Name                   | Description                                     |
|----------------------------------------|-------------------------------------------------|
| <i>Micro Focus Fortify ScanCentral</i> | This document provides information about how to |

| Document / File Name                                                     | Description                                                                              |
|--------------------------------------------------------------------------|------------------------------------------------------------------------------------------|
| <i>DAST Configuration and Usage Guide</i><br>SC_DAST_Guide_<version>.pdf | configure and use Fortify ScanCentral DAST to conduct dynamic scans of Web applications. |

## Micro Focus Fortify Software Security Center

The following document provides information about Fortify Software Security Center. Unless otherwise noted, these documents are available on the Micro Focus Product Documentation website at <https://www.microfocus.com/documentation/fortify-software-security-center>.

| Document / File Name                                                                      | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|-------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Micro Focus Fortify Software Security Center User Guide</i><br>SSC_Guide_<version>.pdf | <p>This document provides Fortify Software Security Center users with detailed information about how to deploy and use Software Security Center. It provides all of the information you need to acquire, install, configure, and use Software Security Center.</p> <p>It is intended for use by system and instance administrators, database administrators (DBAs), enterprise security leads, development team managers, and developers. Software Security Center provides security team leads with a high-level overview of the history and current status of a project.</p> |

## Micro Focus Fortify WebInspect

The following documents provide information about Fortify WebInspect. Unless otherwise noted, these documents are available on the Micro Focus Product Documentation website at <https://www.microfocus.com/documentation/fortify-webinspect>.

| Document / File Name                                                                 | Description                                                                                                                                     |
|--------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Micro Focus Fortify WebInspect Installation Guide</i><br>WI_Install_<version>.pdf | This document provides an overview of Fortify WebInspect and instructions for installing Fortify WebInspect and activating the product license. |
| <i>Micro Focus Fortify WebInspect User Guide</i><br>WI_Guide_<version>.pdf           | This document describes how to configure and use Fortify WebInspect to scan and analyze Web applications and Web services.                      |

| Document / File Name                                                                                                     | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|--------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                                                                                                          | <p><b>Note:</b> This document is a PDF version of the Fortify WebInspect help. This PDF file is provided so you can easily print multiple topics from the help information or read the help in PDF format. Because this content was originally created to be viewed as help in a web browser, some topics may not be formatted properly. Additionally, some interactive topics and linked content may not be present in this PDF version.</p>                                         |
| <p><i>Micro Focus Fortify WebInspect on Docker User Guide</i></p> <p>WI_Docker_Guide_&lt;version&gt;.pdf</p>             | <p>This document describes how to download, configure, and use Fortify WebInspect that is available as a container image on the Docker platform. This full version of the product is intended to be used in automated processes as a headless sensor configured by way of the command line interface (CLI) or the application programming interface (API). It can also be run as a Fortify ScanCentral DAST sensor and used in conjunction with Fortify Software Security Center.</p> |
| <p><i>Micro Focus Fortify WebInspect Tools Guide</i></p> <p>WI_Tools_Guide_&lt;version&gt;.pdf</p>                       | <p>This document describes how to use the Fortify WebInspect diagnostic and penetration testing tools and configuration utilities packaged with Fortify WebInspect and Fortify WebInspect Enterprise.</p>                                                                                                                                                                                                                                                                             |
| <p><i>Micro Focus Fortify WebInspect Agent Installation Guide</i></p> <p>WI_Agent_Install_&lt;version&gt;.pdf</p>        | <p>This document describes how to install the Fortify WebInspect Agent for applications running under a supported Java Runtime Environment (JRE) on a supported application server or service and applications running under a supported .NET Framework on a supported version of IIS.</p>                                                                                                                                                                                            |
| <p><i>Micro Focus Fortify WebInspect Agent Rulepack Kit Guide</i></p> <p>WI_Agent_Rulepack_Guide_&lt;version&gt;.pdf</p> | <p>This document describes the detection capabilities of Fortify WebInspect Agent Rulepack Kit. Fortify WebInspect Agent Rulepack Kit runs atop the Fortify WebInspect Agent, allowing it to monitor your code for software security vulnerabilities as it runs. Fortify WebInspect Agent Rulepack Kit provides the runtime technology to help connect your dynamic results to your static ones.</p>                                                                                  |

# Chapter 2: Configuring the ScanCentral DAST Environment

You must install and manage the DAST API, DAST Global Service, and DAST Utility Service containers on a VM, and each Fortify WebInspect sensor service on its own, separate VM. To assist you in setting up and maintaining the Fortify ScanCentral DAST components, Fortify engineers have created a configuration tool, or wizard, that guides you through the process and prompts you for the information needed for a successful implementation.

The ScanCentral DAST Configuration Tool provides the following three options:

- Creating and configuring a new ScanCentral DAST environment
- Upgrading all ScanCentral DAST components from one version to another
- Changing ScanCentral DAST settings, such as a proxy or database account information, or uploading new SecureBase content, without upgrading the version

## Important Information about SSL

You can deploy both Fortify Software Security Center and ScanCentral DAST without SSL. However, Fortify recommends that you deploy both Fortify Software Security Center and ScanCentral DAST with SSL.

You cannot deploy Fortify Software Security Center with a certificate authority (CA) certificate and ScanCentral DAST without a certificate and vice versa. Mixing secure and non-secure content is not supported.

You cannot use a CA certificate for Fortify Software Security Center and a self-signed certificate for ScanCentral DAST. Mixing self-signed and trusted CA certificates is not supported.

## Requesting Access to Fortify Docker Repository

Access to the Fortify Docker repository requires credentials and is granted through your Docker ID. To access the Fortify Docker repository, email your Docker ID to [fortifydocker@microfocus.com](mailto:fortifydocker@microfocus.com).



## Before You Begin

Ensure that you have met the following prerequisites before you begin configuring your Fortify ScanCentral DAST components:

- You must have a Fortify License and Infrastructure Manager (LIM) container downloaded, configured, and running in your environment.
  - The LIM must be accessible to the network where your VMs will be running Fortify ScanCentral DAST components.
- You must know the LIM URL and LIM user credentials to configure licensing for Fortify ScanCentral DAST.
- You must know the Fortify Software Security Center URL and user credentials to connect Fortify ScanCentral DAST to Fortify Software Security Center.
- You must have a database installed and accessible to the VMs on which you install your Fortify ScanCentral DAST environment and to your instance of Fortify Software Security Center.

## Understanding the Installation Process

The following table describes the process you must use to install and configure the Fortify ScanCentral DAST environment.

| Stage | Description                                                                                                                                                                                                                                                                                                                                                                                            |
|-------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1.    | Receive the following licenses from Micro Focus: <ul style="list-style-type: none"><li>• Fortify ScanCentral DAST Server License (server-type license)</li><li>• Fortify WebInspect Concurrent License</li></ul>                                                                                                                                                                                       |
| 2.    | Do the following: <ol style="list-style-type: none"><li>1. Install a License and Infrastructure Manager (LIM) from the Docker Hub or by using the MSI.</li><li>2. Add the licenses received in Stage 1 to the LIM.</li></ol> <p>For information about how to install the LIM and add licenses, see the <i>Micro Focus Fortify License and Infrastructure Manager Installation and Usage Guide</i>.</p> |
| 3.    | Do the following: <ol style="list-style-type: none"><li>1. Download and deploy Fortify Software Security Center 21.2.0 from the Micro Focus Software License and Downloads (SLD) portal.</li></ol>                                                                                                                                                                                                     |

| Stage | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|-------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|       | <p>2. Create user accounts for users who will access Fortify ScanCentral DAST.</p> <p>For information about how to install and configure Fortify Software Security Center, see the <i>Micro Focus Fortify Software Security Center User Guide</i>.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| 4.    | <p>Set up Docker on the host that will run the core ScanCentral DAST containers (DAST API, DAST Global Service, and DAST Utility Service). For more information, see <a href="#">"Setting Up Docker" on page 36</a>.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| 5.    | <p>Download the ScanCentral DAST 21.2.0 package from the Micro Focus SLD portal.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| 6.    | <p>Use the ScanCentral DAST Configuration Tool 21.2.0 to do the following:</p> <ul style="list-style-type: none"> <li>• Configure and initialize the ScanCentral DAST database</li> <li>• Configure the settings that are used by the ScanCentral DAST API, DAST Global Service, and DAST Utility Service, and then generate a compose file or PowerShell script</li> </ul> <p>For more information, see <a href="#">"Configuring the Database and Core Containers" on page 37</a>.</p>                                                                                                                                                                                                                                                                                   |
| 7.    | <p>Use the compose file or PowerShell script to pull and launch the core ScanCentral DAST 21.2.0 containers (DAST API, DAST Global Service, and DAST Utility Service).</p> <p>For more information, see <a href="#">"Generating Launch Artifacts" on page 50</a>.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| 8.    | <p>Log in to Fortify Software Security Center and enable ScanCentral DAST in the ADMINISTRATION view.</p> <div style="background-color: #f0f0f0; padding: 10px; margin: 10px 0;"> <p><b>Important!</b> You must provide the ScanCentral DAST server URL to the Fortify Software Security Center administrator. The URL should be similar to the following:</p> <p><code>https://&lt;DAST_API_Hostname&gt;:&lt;Port&gt;/api/</code></p> <p><code>https://&lt;DAST_API_IP_Address&gt;:&lt;Port&gt;/api/</code></p> <p>Make sure that you include the trailing <code>/api/</code> in the URL.</p> <p>The URL can use the <code>http</code> protocol instead.</p> </div> <p>For more information, see the <i>Micro Focus Fortify Software Security Center User Guide</i>.</p> |
| 9.    | <p>Deploy the Fortify WebInspect on Docker container or deploy classic Fortify WebInspect with the sensor service.</p> <p>For more information, see <a href="#">"Using Fortify WebInspect on Docker" on page 55</a> or <a href="#">"Using Fortify WebInspect with the Sensor Service" on page 55</a>.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |

# Upgrading and Managing ScanCentral DAST

After initial installation and configuration of the Fortify ScanCentral DAST environment, you may need to upgrade or manage the environment.

## Upgrading ScanCentral DAST

The upgrade process is similar to the installation process. As part of the installation process, however, you will already have received licenses and setup LIM, Fortify Software Security Center, and Docker.

The following table describes the upgrade process.

| Stage | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|-------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1.    | Download the ScanCentral DAST 21.2.0 package from the Micro Focus Software License and Downloads (SLD) portal.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| 2.    | <p>Use the ScanCentral DAST Configuration Tool 21.2.0 to do the following:</p> <ul style="list-style-type: none"><li>• Configure the ScanCentral DAST database with the latest database schema, if applicable</li><li>• Configure the settings that are used by the ScanCentral DAST API, DAST Global Service, and DAST Utility Service, and then generate a compose file or PowerShell script</li></ul> <p><b>Note:</b> During the upgrade, all settings from your current environment are loaded into the ScanCentral DAST Configuration Tool. You progress through the tool accessing each page of the wizard just as you did when installing the ScanCentral DAST environment.</p> |
| 3.    | Use the compose file or PowerShell script(s) to pull and launch the 21.2.0 version of the core ScanCentral DAST containers (DAST API, DAST Global Service, and DAST Utility Service).                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |

## Requirements for Upgrading

When upgrading your ScanCentral DAST environment, follow these requirements:

- Use the ScanCentral DAST Configuration Tool that is packaged with the version of ScanCentral DAST software that you downloaded. Do *not* use a previous version of the tool.
- Upgrade your Fortify Software Security Center to the current compatible version. For version compatibility, see "Software Integrations for Fortify ScanCentral DAST" in the *Micro Focus Fortify*

#### *Software System Requirements.*

- Upgrade all ScanCentral DAST components, including the DAST database, DAST API container, DAST Global Service container, DAST Utility Service container, and the Fortify WebInspect on Docker image or the classic Fortify WebInspect installation with the Fortify ScanCentral DAST sensor service.

## Recommendation for Upgrading

Fortify recommends that you stop all ScanCentral DAST containers and services before upgrading your environment. Many settings that you configure in the ScanCentral DAST Configuration Tool are applied immediately to the database after clicking Apply Settings. These changes, however, are not recognized by containers that have not been upgraded. If stopping containers and services is not possible because scans are running, then you must upgrade those containers later for any database changes to be recognized.

## Effect of Upgrades on Scheduled Scans

When upgrading your DAST environment, you cannot upgrade existing containers. You can only create new containers based on updated images.

When you create a new Fortify WebInspect sensor container with an updated Fortify WebInspect on Docker image, any scheduled scans that were assigned to the sensor and configured with the **Use this sensor only** option will not start on the new container. You must edit the scheduled scan settings to use the new sensor container.

## Managing ScanCentral DAST

When you use the ScanCentral DAST Configuration Tool 21.2.0 to make changes to one or more of the components, all settings from your current environment are loaded into the tool. You can click any page in the left navigation menu to access the page and make changes to the settings.

## Setting Up Docker

Before you can run Docker containers, you must set up Docker on the host that will run the containers. Set up Docker according to the process described in the following table.

| Stage | Description                                                                                                                                                                                        |
|-------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1.    | Download and install Docker for Windows.                                                                                                                                                           |
| 2.    | Optionally, if you plan to use a compose file to pull and run the core ScanCentral DAST containers (DAST API, DAST Global Service, and DAST Utility Service), download and install Docker Compose. |

| Stage | Description                                   |
|-------|-----------------------------------------------|
| 3.    | Configure your machine for Docker containers. |
| 4.    | Register and start the Docker service.        |

For information about Docker Engine Enterprise, see <https://docs.mirantis.com/docker-enterprise/v3.0/docker-ee-products/docker-ee/windows.html>.

For additional Docker documentation, see <http://docs.docker.oeynet.com/>.

## Configuring the Database and Core Containers

Use the Fortify ScanCentral DAST Configuration Tool to configure the settings that are used by the ScanCentral DAST components.

### About the ScanCentral DAST Configuration Tool

The ScanCentral DAST Configuration Tool helps you to configure the following components of the ScanCentral DAST environment:

- Connection settings and initialization of the ScanCentral DAST database
- SSL for DAST API and DAST Utility Service
- Proxy settings (if needed)
- Connection settings for Fortify Software Security Center and the License and Infrastructure Manager (LIM)
- Settings for SmartUpdate and DAST API

With these settings, the ScanCentral DAST Configuration Tool generates a compose file or a PowerShell script that you can run to pull the core containers (DAST API, DAST Global Service, and DAST Utility Service) from Docker Hub and run them on a host.

The ScanCentral DAST Configuration Tool is provided in the Fortify ScanCentral DAST software download package, which is a ZIP file that you download after purchase. The application and any required data are included in the ZIP file. You can extract the ZIP file and store its contents on your local machine.

You can run the Configuration Tool on one machine, and you can run the compose file or PowerShell script(s) that it generates on another. However, the Configuration Tool must have access to the database.

## Installing and Launching the Configuration Tool

To install and launch the Configuration Tool:

1. Extract the files from the Fortify ScanCentral DAST software download package (a ZIP file).
2. To install the Configuration Tool, locate and double-click the file named `DAST Config Tool Setup <version>.exe`.  
The installer launches, installs the application, and adds a shortcut to the desktop.
3. To launch the Configuration Tool, double-click the **DAST Config Tool** shortcut.  
The Configuration Tool opens to the Getting Started page.
4. Select one of the following options:
  - To install a new environment, select **Configure a new DAST environment**.
  - To upgrade all components from one version to another, select **Upgrade an existing DAST environment**.
  - To change one or more components without upgrading the version, select **Manage an existing DAST environment**.

## What's Next?

Proceed with ["Configuring the Database Connection" below](#).

## Configuring the Database Connection

You can configure connections to an existing database or have the Configuration Tool create a new database with the information you provide on the **Database connection** page.

### Configuring the DBO-level Account

You must configure a connection to the database using an existing database owner (DBO) server-level account that has full access to the database. DBO access is required to create the schema on the database server.

To configure a database connection for the DBO-level account:

1. In the **DBO-LEVEL ACCOUNT** area, type the database server name or the server IP address in the **Server** field.

**Important!** If SQL Server Browser is not running and you are using a port other than 1433, then you must also specify the port. Use the following format:

`<server_name>,<port>`

`<ip_address>,<port>`

Note that a comma separates the values.

2. For authentication to the server, do one of the following:
  - To use the credentials of the user who is currently logged into Windows, select **Use Windows authentication**.
  - To use the credentials for another account, then type the user name in the **User name** field and the password in the **Password** field.

**Important!** The user account must be a database owner (DBO) server-level account that has full access to the database.

3. Do one of the following:
  - If you selected **Configure a new DAST environment** on the **Getting Started** page, then you must create a new database. Type a name for the new database in the **Database** field.
  - If you selected **Upgrade an existing DAST environment** or **Manage an existing DAST environment** on the **Getting Started** page, then you must use an existing database. Select the database from the **Database** list.

**Caution!** An existing database might be upgraded during this process. Be sure to create a backup of the existing database before proceeding.

**Important!** If you selected **Manage an existing DAST environment** on the **Getting Started** page, the Configuration Tool checks to see if a new database schema is available. If one is available, you will be prompted to update it. The update is required for any other changes to occur.

4. To verify that you can access the database with the credentials provided, click **Validate**.

## Configuring the Standard Account

You must configure a second connection to the database for a standard user for everyday use, preferably with non-DBO credentials. This account should have select, insert, update, and delete functions, but should not be able to create tables and so forth.

**Tip:** You may use the same credentials as the DBO-level account. However, it is generally considered a safer option to provide limited access for general use after the schema has been created.

To configure a database connection for the standard user account:

1. In the **STANDARD ACCOUNT** area, type the user name in the **User name** field and the password in the **Password** field.
2. Type the password in the **Confirm Password** field.
3. Does this user account exist?
  - If yes, proceed to Step 4.
  - If no, select **Create a new user** and then proceed to Step 4.
4. To verify that you can access the database with the credentials provided, click **Validate**.

**Note:** If you are creating a new user, then clicking **Validate** verifies that the DBO user can create the standard user account on the database server. The account is created at the end of the configuration process.

## What's Next?

Do one of the following:

- If you selected **Configure a new DAST environment** or **Upgrade an existing DAST environment** on the **Getting Started** page, then click **Next** and proceed with ["Initializing the Database" below](#).
- If you selected **Manage an existing DAST environment** on the **Getting Started** page, then select any page in the left navigation and locate the corresponding topic in this document for instructions. If no other changes are needed, select **Summary** in the left navigation and proceed with ["Applying the Settings" on page 50](#).

## Initializing the Database

When initializing the database, you can use the default SecureBase ZIP file that is packaged with the ScanCentral DAST Configuration Tool or you can use a local version of SecureBase content to seed the database on the **Database initializer** page.

### Updating SecureBase

If you selected **Upgrade an existing DAST environment** on the **Getting Started** page, then you must update your SecureBase. If you selected **Manage an existing DAST environment** on the **Getting Started** page, then the **Update SecureBase** option is available, but not required.

To update SecureBase:

- Select **Update SecureBase**.

**Note:** This option is selected by default when upgrading an existing environment. It is not available if you selected **Configure a new DAST environment** on the **Getting Started** page.

When you click **Apply Settings** on the **Summary** page, any schema changes to the database are applied.

### Using the Default SecureBase

To initialize the database using the zipped SecureBase that is included in the ScanCentral DAST Configuration Tool:

1. Ensure that **Use default SecureBase zip** is selected.
2. Click **Next**.



## Using a Local SecureBase

To use a version of SecureBase that you have locally:

1. Click **select**, and then locate and select the SecureBase file.
2. Click **Next**.

## What's Next?

Do one of the following:

- If you selected **Configure a new DAST environment** or **Upgrade an existing DAST environment** on the **Getting Started** page, then proceed with ["Configuring DAST SSL" below](#).
- If you selected **Manage an existing DAST environment** on the **Getting Started** page, then select any page in the left navigation and locate the corresponding topic in this document for instructions. If no other changes are needed, select **Summary** in the left navigation and proceed with ["Applying the Settings" on page 50](#).

## Configuring DAST SSL

You can configure whether to use encrypted communication for the DAST API service on the **Configure SSL details** page. If you use encrypted communication, you can generate a certificate or use an existing certificate for this service.

### About the Certificate Path

Generating a certificate or using an existing certificate requires you to specify a certificate path. It is not necessary to install the certificate on your local machine, but the certificate path must be accessible from the computer where you run the Docker compose file or PowerShell scripts to pull and start the ScanCentral DAST containers. The certificate is passed to the Docker container when you run the compose file or the PowerShell scripts.

### Generating an API SSL Certificate

You can provide the information needed to generate a certificate on the Generate Certificate tab. The certificate is generated when the Configuration Tool creates and downloads launch artifacts.

To generate a self-signed API SSL certificate:

1. Select the **Generate Certificate** tab.
2. In the **Certificate path** field, type the directory path where you will place the certificate on the host computer that will run the API container.

**Note:** Alternatively, click **select** and navigate to the location.

3. In the **Generate Self-Signed Certificate** area, continue according to the following table.

| For this field...       | Do this...                                                                                                   |
|-------------------------|--------------------------------------------------------------------------------------------------------------|
| <b>Host</b>             | Type the IP address of the machine running the DAST API service container.                                   |
| <b>Email</b>            | Optionally, enter your email address.                                                                        |
| <b>Location</b>         | Optionally, enter your city.                                                                                 |
| <b>Password</b>         | Type the password for the private key.<br><b>Note:</b> The password is encrypted and stored in the database. |
| <b>Confirm Password</b> | Retype the password for the private key.                                                                     |
| <b>Validity</b>         | Enter the number of days the certificate will be valid.                                                      |

## Using an Existing Certificate

You can use an existing certificate by specifying the directory path to the certificate on the Use Existing Certificate tab.

To use an existing certificate:

1. Select the **Use Existing Certificate** tab.
2. In the **Certificate file** field, type the directory path to the existing certificate.

**Note:** Alternatively, click **select** and navigate to the certificate.

3. Optionally, in the **Certificate password** field, type the password for the private key.
4. Optionally, in the **Certificate confirm password** field, retype the password for the private key.

**Important!** Ensure that you enter the correct password for the certificate. The Configuration Tool does not validate certificate passwords

## Not Using SSL

**Important!** Encrypted communication for the DAST API service is not required, but Fortify highly recommends it.

To not use encrypted communication for the DAST API service:

1. Select the **Do Not Use SSL** tab.
2. Select the **Run the ScanCentral DAST API without SSL** check box.

## What's Next?

Do one of the following:

- If you selected **Configure a new DAST environment** or **Upgrade an existing DAST environment** on the **Getting Started** page, then click **Next** and proceed with "[Configuring Utility Service SSL](#)" below.
- If you selected **Manage an existing DAST environment** on the **Getting Started** page, then select any page in the left navigation and locate the corresponding topic in this document for instructions. If no other changes are needed, select **Summary** in the left navigation and proceed with "[Applying the Settings](#)" on page 50.

## Configuring Utility Service SSL

You can configure whether to use encrypted communication for the DAST Utility service on the **Configure utility SSL details** page. If you use encrypted communication, you can generate a certificate or use an existing certificate for this service.

### About the Certificate Path

Generating a certificate or using an existing certificate requires you to specify a certificate path. It is not necessary to install the certificate on your local machine, but the certificate path must be accessible from the computer where you run the Docker compose file or PowerShell scripts to pull and start the ScanCentral DAST containers. The certificate is passed to the Docker container when you run the compose file or the PowerShell scripts.

### Generating a Utility Service SSL Certificate

You can provide the information needed to generate a certificate on the Generate Certificate tab. The certificate is generated when the Configuration Tool creates and downloads launch artifacts.

To generate a self-signed Utility service SSL certificate:

1. Select the **Generate Certificate** tab.
2. In the **Certificate path** field, type the directory path where you will place the certificate on the host computer that will run the Utility Service container.

**Note:** Alternatively, click **select** and navigate to the location.

3. In the **Generate Self-Signed Certificate** area, continue according to the following table.

| For this field... | Do this...                                                                     |
|-------------------|--------------------------------------------------------------------------------|
| <b>Host</b>       | Type the IP address of the machine running the DAST Utility service container. |

| For this field...       | Do this...                                                                                                   |
|-------------------------|--------------------------------------------------------------------------------------------------------------|
| <b>Email</b>            | Optionally, enter your email address.                                                                        |
| <b>Location</b>         | Optionally, enter your city.                                                                                 |
| <b>Password</b>         | Type the password for the private key.<br><b>Note:</b> The password is encrypted and stored in the database. |
| <b>Confirm Password</b> | Retype the password for the private key.                                                                     |
| <b>Validity</b>         | Enter the number of days the certificate will be valid.                                                      |

## Using an Existing Certificate

You can use an existing certificate by specifying the directory path to the certificate on the Use Existing Certificate tab.

To use an existing certificate:

1. Select the **Use Existing Certificate** tab.
2. In the **Certificate file** field, type the directory path to the existing certificate.

**Note:** Alternatively, click **select** and navigate to the certificate.

3. Optionally, in the **Certificate password** field, type the password for the private key.
4. Optionally, in the **Certificate confirm password** field, retype the password for the private key.

**Important!** Ensure that you enter the correct password for the certificate. The Configuration Tool does not validate certificate passwords

## Not Using SSL

**Important!** Encrypted communication for the DAST Utility service is not required, but Fortify highly recommends it.

To not use encrypted communication for the DAST Utility service:

1. Select the **Do Not Use SSL** tab.
2. Select the **Run the ScanCentral DAST Utility without SSL** check box.

## What's Next?

Do one of the following:

- If you selected **Configure a new DAST environment** or **Upgrade an existing DAST environment** on the **Getting Started** page, then click **Next** and proceed with ["Configuring Environment Settings"](#) below.
- If you selected **Manage an existing DAST environment** on the **Getting Started** page, then select any page in the left navigation and locate the corresponding topic in this document for instructions. If no other changes are needed, select **Summary** in the left navigation and proceed with ["Applying the Settings"](#) on page 50.

## Configuring Environment Settings

You can configure proxy settings and allow untrusted certificates on the **Environment configuration** page.

### Configuring Proxy Settings

If you need to use a proxy in your Fortify ScanCentral DAST environment, you can configure it in the **PROXY SETTINGS** area. The proxy settings configured here, including the exclusions, are used for internal communications between ScanCentral DAST components. The settings also apply when communicating with Fortify Software Security Center, LIM, SmartUpdate, DAST API, DAST Utility service, and OpenAPI and OData definition URLs.

To configure proxy settings:

1. To enable proxy settings, select **Use proxy**.
2. In the **Proxy address** field, type the URL or IP address and port number of your proxy server.
3. If you do not need to use a proxy server to access certain IP addresses (such as internal testing sites), type the addresses or URLs in the **Proxy bypass list** field.

**Tip:** This field accepts a comma separated list of regular expressions. For example:

```
localhost,[a-z]+\.\myestore\.net$
```

**Important!** If you want to bypass the proxy when connecting to the LIM, enter the LIM IP address. You cannot enter the host name, machine name, or container name for the LIM.

4. If your proxy server requires authentication, type the qualifying user name in the **Proxy username** field.
5. If your proxy server requires authentication, type the qualifying password in the **Proxy password** and **Confirm password** fields.

**Note:** The DAST Configuration Tool automatically adds the DAST Utility Service to the proxy bypass list.

## Known Issue with Host Name, Machine Name, and Container Name

Configuring a proxy in the Configuration Tool and then bypassing the proxy for communications with Fortify Software Security Center and the LIM may cause issues when using the host name, machine name, or container name for these products.

If you want to use the host name, machine name, or container name for Fortify Software Security Center and the LIM without a proxy, then clear the **Use proxy** option and configure HTTP\_PROXY and NO\_PROXY environment variables instead. Additionally, add the host names, machine names, or container names for Fortify Software Security Center and the LIM to the NO\_PROXY variable as a comma-separated list.

Refer to your OS documentation and change these environment variables.

You must also add these variables to the Docker containers' run commands as shown in the following example:

```
-e "HTTP_PROXY=http://<proxy_address>" -e "NO_PROXY=localhost,<ssc_machine>,<lim_machine>"
```

## Allowing Untrusted Certificates

To allow Fortify ScanCentral DAST components to accept self-signed (untrusted) certificates when communicating with other Fortify products:

- In the **OTHER SETTINGS** area, select **Allow untrusted server certificates**.

## What's Next?

Do one of the following:

- If you selected **Configure a new DAST environment** or **Upgrade an existing DAST environment** on the **Getting Started** page, then click **Next** and proceed with ["Configuring ScanCentral DAST Settings"](#) below.
- If you selected **Manage an existing DAST environment** on the **Getting Started** page, then select any page in the left navigation and locate the corresponding topic in this document for instructions. If no other changes are needed, select **Summary** in the left navigation and proceed with ["Applying the Settings"](#) on page 50.

## Configuring ScanCentral DAST Settings

You can configure the various settings needed to deploy your Fortify ScanCentral DAST environment on the **Settings configuration** page.

### Configuring SSC Settings

You must configure the connection between Fortify ScanCentral DAST and Fortify Software Security Center in the **SSC SETTINGS** area.

To configure your Fortify Software Security Center settings:

1. In the **SSC URL** field, type the URL for your Fortify Software Security Center application.

**Important!** You cannot use `localhost` for the SSC URL. You must use a routable IP address or hostname. The URL must use the following format:

```
https://<ip_address>:<port>/ssc
```

```
https://<hostname>:<port>/ssc
```

2. In the **Service account username** field, type the user name under which Fortify ScanCentral DAST will communicate with Fortify Software Security Center.

**Important!** This account must be an Admin account that can perform service-level functions. Individual users who log into Fortify Software Security Center in a browser to use Fortify ScanCentral DAST are restricted based on the permissions designated by their user role in Fortify Software Security Center. For more information, see ["Permissions in Fortify Software Security Center" on page 27](#).

3. In the **Service account password** field, type the password for the account.
4. To verify that you can access Fortify Software Security Center with the credentials provided, click **Validate**.

**Important!** If you selected **Upgrade an existing DAST environment** on the **Getting Started** page and you made changes to these settings, then you must validate the new settings.

## Configuring API Settings

You must configure the URL for the DAST API in the **API Settings** area. You can also configure cross-origin resource sharing (CORS) settings in this area.

To configure API settings:

1. In the **DAST API URL** field, type the URL and port where the DAST API service will run.

**Important!** You cannot use `localhost` in the URL. You must use a routable IP address or hostname as shown in the following examples:

```
https://<DAST_API_hostname>:<port>
```

```
https://<DAST_API_ip_address>:<port>
```

The URL can use the `http` protocol instead.

Make note of this URL. It is required to enable Fortify ScanCentral DAST in Fortify Software Security Center.

2. By default, **Allow all origins for CORS policy** is not selected. The Fortify Software Security Center URL is the only one that is automatically allowed. To change this behavior, do one of the following:

- To add an allowed URL, type the URL in the **URL** field, and then click **Add**.

The URL is added to the Allowed CORS origins list.

**Note:** The Fortify Software Security Center URL is not visible in the list, but is allowed by default.

- To allow traffic from all URLs, select the **Allow all origins for CORS policy** option.

## Configuring Utility Service Settings

You must configure the URL for the DAST Utility service in the **Utility Settings** area.

To configure Utility service settings:

- In the **Utility Service URL** field, type the URL and port where the DAST Utility service will run.

**Important!** You cannot use `localhost` in the URL. You must use a routable IP address or hostname as shown in the following examples:

`https://<DAST_Utility_hostname>:<port>`

`https://<DAST_Utility_ip_address>:<port>`

The URL can use the `http` protocol instead.

## Configuring LIM Settings

During the database initialization, a sensor pool named "default" is created in the database. You must configure a LIM and LIM pool to associate with the default sensor pool for licensing. You configure these details in the **LIM SETTINGS** area.

To configure the LIM settings:

1. In the **LIM URL** field, type the LIM service URL, which uses the following format:  
`https://<server_url>/<service-directory>`  
where `server_url` is the root web site and `service-directory` is the service virtual directory name.  
The default virtual directory name is `LIM.Service`.
2. In the **Service account username** field, type a LIM account username.
3. In the **Service account password** field, type the password for the account.
4. In the **Default LIM Pool Name** field, type the LIM pool name to associate with the default sensor pool for licensing.
5. In the **Default LIM Pool Password** field, type the password for the LIM pool.
6. To verify that you can access the LIM with the credentials provided, click **Validate**.

**Important!** If you selected **Upgrade an existing DAST environment** on the **Getting Started** page and you made changes to these settings, then you must validate the new settings.

## Creating a Sensor Service Token

You must create a sensor service token, which is a shared secret for all of your sensors to use to authenticate with the ScanCentral DAST API.



To create a sensor service token:

- In the **Sensor Service Token** field in the **Sensor Settings** area, type a string with a minimum of 10 characters.

The value is encrypted.

## Retaining Completed Scans on Sensor

By default, scans are not saved in the sensor container after the sensor completes the scan and uploads the data to the DAST database.

To save completed scans in the sensor container:

- In the **OTHER SETTINGS** area, select **Retain completed Scans**.

**Important!** If you plan to enable the Traffic Viewer (Traffic Monitor) regularly in scan settings, do *not* retain completed scans on the sensor. Traffic files consume large amounts of storage on the sensor container.

## Disabling Advanced Scan Prioritization

Advanced scan prioritization allows the Global Service to move a scan to a different sensor, depending on the scan priority and other settings. For more information, see ["Understanding Advanced Scan Prioritization" on page 108](#).

Advanced scan prioritization is enabled by default.

To disable advanced scan prioritization for all scans:

- In the **OTHER SETTINGS** area, select **Disable Advanced Scan Prioritization**.

## Changing the SmartUpdate URL

To change the URL for the SmartUpdate service:

- In the **SmartUpdate URL** field in the **OTHER SETTINGS** area, type the URL for the SmartUpdate service.

The default URL is `https://smartupdate.fortify.microfocus.com/`.

## Changing the Licensing URL

To change the URL for the licensing service:

- In the **Licensing URL** field in the **OTHER SETTINGS** area, type the URL for the licensing service.

The default URL is `https://licenseservice.fortify.microfocus.com/`.

## What's Next?

Do one of the following:

- If you selected **Configure a new DAST environment** or **Upgrade an existing DAST environment** on the **Getting Started** page, then click **Next** and proceed with ["Applying the Settings" below](#).
- If you selected **Manage an existing DAST environment** on the **Getting Started** page, then select any page in the left navigation and locate the corresponding topic in this document for instructions. If no other changes are needed, select **Summary** in the left navigation and proceed with ["Applying the Settings" below](#).

## Applying the Settings

On the Summary page, you can review the settings that you have configured before applying them to your environment.

**Important!** When upgrading, any changes will be applied immediately to the database when you click **Apply Settings**. However, these changes will not be recognized by containers until those containers have been upgraded.

To apply the settings and initialize and seed the database (if applicable):

1. On the **Summary** page, click **Apply Settings**.

A dialog box displays the progress.

**Note:** Depending on your network configuration, it might take several minutes to apply the settings and initialize the database. When the process is complete, a message indicates success.

**Important!** If settings are not valid or contain errors, then a dialog box displays error messages and the Configuration Tool pages that contain the errors appear in red text in the left navigation menu. You must correct all errors before you can apply the settings.

2. Click **OK**.

The Configuration complete page appears.

## What's Next?

Proceed with ["Generating Launch Artifacts" below](#).

## Generating Launch Artifacts

Using the settings you configured in the Fortify ScanCentral DAST Configuration Tool, you can generate the files needed to launch your Fortify ScanCentral DAST environment.

**Tip:** If you selected **Manage an existing DAST environment** on the **Getting Started** page and do not need updated scripts, click **Close**.

## Understanding the Launch Artifacts

The Configuration Tool creates a file named `DAST-start.zip` and downloads it to your local machine. The ZIP file includes the following files:

- `appsettings.json` - This file configures the sensor service. Use this file to run the Fortify ScanCentral DAST Sensor Service and a Fortify WebInspect sensor.
- `docker-compose.yml` - This file pulls images and starts containers for the DAST API, DAST Global Service, and DAST Utility Service.
- `DAST-api.pfx` - If you generated a certificate for the DAST API service using the Configuration Tool, this certificate file must be on the host computer where the DAST API container will be running.

**Note:** This file is not downloaded if you use a certificate provided by a certificate authority (CA) or use an existing certificate.

- `DAST-utilityservice.pfx` - If you generated a certificate for the DAST Utility service using the Configuration Tool, this certificate file must be on the host computer where the DAST Utility service container will be running.

**Note:** This file is not downloaded if you use a certificate provided by a certificate authority (CA) or use an existing certificate.

- `pull-and-start-containers.ps1` - This PowerShell script pulls the DAST API, DAST Global Service, and DAST Utility Service images from Docker Hub, and then starts the containers.
- `pull-and-start-sensor-container.ps1` - This PowerShell script pulls the Fortify WebInspect image from Docker Hub, and then starts the container.
- `pull-images.ps1` - This PowerShell script pulls the DAST API, DAST Global Service, and DAST Utility Service images from Docker Hub, but does not start the containers.
- `pull-sensor-image.ps1` - This PowerShell script pulls the Fortify WebInspect image from Docker Hub, but does not start the container.
- `service-token.txt` - This text file contains the shared secret that all your DAST sensors must use to authenticate with the DAST API.
- `start-containers.ps1` - This PowerShell script starts the DAST API, DAST Global Service, and DAST Utility Service containers, but does not pull the images.
- `start-sensor-container.ps1` - This PowerShell script starts the Fortify WebInspect container, but does not pull the image.

For more information about the DAST components mentioned here, ["What is ScanCentral DAST?" on page 25](#).

## Generating the Launch Artifacts

To generate and download the launch artifacts:

1. On the **Configuration complete** page, click **Download launch artifacts**.

The Configuration Tool prompts you for the location to save the `DAST-start.zip` file containing the launch files.

2. After the ZIP file is downloaded, click **Close**.

## What's Next?

After you have downloaded the launch artifacts, you can use them to pull the DAST API, DAST Global Service, DAST Utility Service, and Fortify WebInspect images from Docker Hub and start the containers. You can accomplish this task in one of the following ways:

- ["Using the Compose File" below](#)
- ["Using PowerShell Scripts" on the next page](#)

## Using the Compose File

**Important!** To use the compose file, you must first download and install Docker Compose on the host machine. For more information, see ["Setting Up Docker" on page 36](#).

The `docker-compose.yml` file contains the various service settings required to pull images of the DAST API, DAST Global Service, and DAST Utility Service, and then start the containers. You use the compose file on the host where you want to run these containers.

Use the following process to use the compose file.

| Stage | Description                                                                                                                                                                                                                                                                                                                                                                                                           |
|-------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1.    | Copy the following files to the host where you want to run the DAST API, DAST Global Service, and DAST Utility Service containers: <ul style="list-style-type: none"><li>• <code>DAST-api.pfx</code> (Required only if generated by the Configuration Tool)</li><li>• <code>DAST-utilityservice.pfx</code> (Required only if generated by the Configuration Tool)</li><li>• <code>docker-compose.yml</code></li></ul> |
| 2.    | On this same host, start Windows PowerShell as Administrator. For more information about PowerShell, refer to your Windows documentation.                                                                                                                                                                                                                                                                             |
| 3.    | At the prompt, type <code>docker-compose up</code> , and press <b>Enter</b> .<br><br>The DAST API, DAST Global Service, and DAST Utility Service images are pulled and the containers are started.                                                                                                                                                                                                                    |

## Using PowerShell Scripts

The Configuration Tool creates and downloads three PowerShell scripts. These scripts offer the following options:

- Use one script to pull images of the DAST API, DAST Global Service, and DAST Utility Service, and then start the containers.
- Use two scripts: one to pull the images, and then another to start the containers.

You use the script or scripts on the host where you want to run the DAST API, DAST Global Service, and DAST Utility Service containers.

### Using One Script

Use the following process to use a single PowerShell script to pull images and start the containers.

| Stage | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|-------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1.    | <p>Copy the following files to the host where you want to run the DAST API, DAST Global Service, and DAST Utility Service containers:</p> <ul style="list-style-type: none"><li>• <code>DAST-api.pfx</code> (Required only if generated by the Configuration Tool)</li><li>• <code>DAST-utilityservice.pfx</code> (Required only if generated by the Configuration Tool)</li><li>• <code>pull-and-start-containers.ps1</code></li></ul>                                                                                                                                                                                                                                                                                         |
| 2.    | <p>On this same host, start Windows PowerShell ISE as Administrator. For more information about using PowerShell, refer to your Windows PowerShell documentation.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| 3.    | <p>To avoid errors regarding non-digitally signed scripts, run the contents of the <code>pull-and-start-containers.ps1</code> script:</p> <ol style="list-style-type: none"><li>1. Copy the contents from the <code>pull-and-start-containers.ps1</code> script.</li><li>2. Paste the contents in the PowerShell ISE script pane.</li><li>3. Click the <b>Run Selection</b> icon.</li></ol> <p><b>Note:</b> Alternatively, you can set the execution policy to allow all scripts, and then run the script as follows:</p> <pre>&amp; "&lt;drive&gt;:&lt;path_to_script&gt;\pull-and-start-containers.ps1"</pre> <p>For more information about setting the execution policy, refer to your Windows PowerShell documentation.</p> |

| Stage | Description                                                                                                   |
|-------|---------------------------------------------------------------------------------------------------------------|
|       | The DAST API, DAST Global Service, and DAST Utility Service images are pulled and the containers are started. |

## Using Two Scripts

Use the following process to use separate pull and start PowerShell scripts.

| Stage | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|-------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1.    | <p>Copy the following files to the host where you want to run the DAST API, DAST Global Service, and DAST Utility Service containers:</p> <ul style="list-style-type: none"><li>• <code>DAST-api.pfx</code> (Required only if generated by the Configuration Tool)</li><li>• <code>DAST-utilityservice.pfx</code> (Required only if generated by the Configuration Tool)</li><li>• <code>pull-images.ps1</code></li><li>• <code>start-containers.ps1</code></li></ul>                                                                                                                                                                                                                                                                                                                                        |
| 2.    | <p>On this same host, start Windows PowerShell ISE as Administrator. For more information about using PowerShell, refer to your Windows PowerShell documentation.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| 3.    | <p>Pull the images.</p> <p>To avoid errors regarding non-digitally signed scripts, run the contents of the <code>pull-images.ps1</code> script:</p> <ol style="list-style-type: none"><li>1. Copy the contents from the <code>pull-images.ps1</code> script.</li><li>2. Paste the contents in the PowerShell ISE script pane.</li><li>3. Click the <b>Run Selection</b> icon.</li></ol> <div><p><b>Note:</b> Alternatively, you can set the execution policy to allow all scripts, and then run the script as follows:</p><pre>&amp; "&lt;drive&gt;:&lt;path_to_script&gt;\pull-images.ps1"</pre><p>For more information about setting the execution policy, refer to your Windows PowerShell documentation.</p></div> <p>The DAST API, DAST Global Service, and DAST Utility Service images are pulled.</p> |
| 4.    | <p>Start the containers.</p> <p>To avoid errors regarding non-digitally signed scripts, run the contents of the <code>start-</code></p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |

| Stage | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|-------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|       | <p>containers.ps1 script:</p> <ol style="list-style-type: none"><li>1. Copy the contents from the start-containers.ps1 script.</li><li>2. Paste the contents in the PowerShell ISE script pane.</li><li>3. Click the <b>Run Selection</b> icon.</li></ol> <p><b>Note:</b> Alternatively, if you set the execution policy to allow all scripts as described in Stage 3, you can run the script as follows:</p> <pre>&amp; "&lt;drive&gt;:&lt;path_to_script&gt;\start-containers.ps1"</pre> <p>The DAST API, DAST Global Service, and DAST Utility Service containers are started.</p> |

## Using Fortify WebInspect on Docker

The Fortify WebInspect on Docker image is available for download on the Docker container platform. The image includes the full version of Fortify WebInspect software, and is packaged with a running mode that enables it to run as a Fortify ScanCentral DAST sensor. For information on how to pull and run the image as a DAST sensor, see the *Micro Focus Fortify WebInspect on Docker User Guide*.

## Using Fortify WebInspect with the Sensor Service

You can use a classic Fortify WebInspect installation with the Fortify ScanCentral DAST sensor service. To do so, you must first configure and start the WebInspect REST API, and then install and configure the DAST sensor service.

### Before You Begin

If you use encrypted communication for the DAST API service, then you must copy the API SSL certificate from the Configuration Tool artifacts and add it to the Trusted Store on the machine where the DAST sensor service will run.

### Important Information About Licenses

When running a scan using ScanCentral DAST with the sensor service and a Fortify WebInspect installation, the license that is configured in the Fortify WebInspect user interface is overridden to use a LIM license. When the ScanCentral DAST scan is complete, the LIM license is released. The next time you open the Fortify WebInspect user interface, it will be unlicensed.

As a workaround, reactivate the installed version of Fortify WebInspect using the previous license in the Fortify WebInspect UI.

## Important Prerequisite for Windows Server 2016

You can install Fortify WebInspect on Windows Server 2016. However, if you install the DAST sensor service on Windows Server 2016, you must first install the full .NET SDK or ASP.NET Core Runtime 5.0.3. Otherwise, the following error occurs:

```
A fatal error occurred. The required library hostfxr.dll could not be found.  
If this is a self-contained application, that library should exist in  
[C:\ScannerService\].  
If this is a framework-dependent application, install the runtime in  
the global location [C:\Program Files\dotnet] or use the DOTNET_ROOT  
environment variable to specify the runtime location or register the  
runtime location in [HKLM\SOFTWARE\dotnet\Setup\InstalledVersions\  
x64\InstallLocation].
```

## Configuring the Fortify WebInspect REST API

On the machine where Fortify WebInspect is installed, configure the Fortify WebInspect REST API as follows:

1. From the Windows Start menu, click **All Programs > Fortify > Fortify WebInspect > Micro Focus Fortify Monitor**.  
The Micro Focus Fortify Monitor icon appears in the system tray.
2. Right-click the **Micro Focus Fortify Monitor** icon, and select **Configure WebInspect API**.  
The Configure WebInspect API dialog box appears.
3. Configure the API Server settings as described in the following table.

| Setting        | Value                                                                                                                                                                                                                                                                                                                                                                                              |
|----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Host           | Both Fortify WebInspect and the Fortify WebInspect REST API must reside on the same machine. The default setting, +, is a wild card that tells the Fortify WebInspect REST API to intercept all request on the port identified in the Port field. If you have another service running on the same port and want to define a specific hostname just for the API service, this value can be changed. |
| Port           | Use the provided value or change it using the up/down arrows to an available port number.                                                                                                                                                                                                                                                                                                          |
| Authentication | Choose <b>None</b> , <b>Windows</b> , <b>Basic</b> , or <b>Client Certificate</b> from the                                                                                                                                                                                                                                                                                                         |



| Setting   | Value                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|-----------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|           | <p>Authentication drop-down list.</p> <p>If you choose <b>Basic</b> for authentication, you must provide user name(s) and password(s). To do this:</p> <ol style="list-style-type: none"> <li>Click the <b>Edit passwords</b> button and select a text editor.</li> </ol> <p>The <code>wircserver.keys</code> file opens in the text editor. The file includes sample user name and password entries:</p> <pre>username1:password1 username2:password2</pre> <ol style="list-style-type: none"> <li>Replace the samples with user credentials for access to your server. If additional credentials are needed, add a user name and password, separated by a colon, for each user to be authenticated. There should be only one user name and password per line.</li> <li>Save the file.</li> </ol> <p>If you choose <b>Client Certificate</b> for authentication, you must first generate a client certificate based on your root SSL certificate issued by a trusted certificate authority (CA), and then install it on the client machine.</p> <p><b>Tip:</b> You can use a tool, such as the MakeCert utility in the Windows Software Development Kit (SDK), to create your client certificate.</p> |
| Use HTTPS | <p>Select this check box to access the server over an HTTPS connection.</p> <p>To run the server over HTTPS, you must create a server certificate and bind it to the API service. To quickly create a self-signed certificate to test the API over HTTPS, run the following script in an Administrator PowerShell console:</p> <pre>\$rootcertID = (New-SelfSignedCertificate -DnsName "DO NOT TRUST - WIRC Test Root CA", "localhost", "\$((\$env:computername)" -CertStoreLocation "cert:\LocalMachine\My").Thumbprint \$rootcert = (Get-Item -Path "cert:\LocalMachine\My\\${\$rootcertID}")  \$trustedRootStore = (Get-Item -Path "cert:\LocalMachine\Root") \$trustedRootStore.open("ReadWrite") \$trustedRootStore.add(\$rootcert) \$trustedRootStore.close()</pre>                                                                                                                                                                                                                                                                                                                                                                                                                              |

| Setting   | Value                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|-----------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|           | <pre>netsh http add sslcert iport=0.0.0.0:8443 certhash=(\$rootcertID) appid="{160e1003-0b46-47c2-a2bc-01ea1e49b9dc}"</pre> <p>The preceding script creates a certificate for the local host and the computer name, puts the certificate in the Personal Store and Trusted Root, and binds the certificate to port 8443. If you use a different port, specify the port you use in the script.</p> <div> <p><b>Important!</b> Use the self-signed certificate created by the preceding script for testing only. The certificate works only on your local machine and does not provide the security of a certificate from a certificate authority. For production, use a certificate that is generated by a certificate authority.</p> </div> |
| Log Level | Choose the level of log information you want to collect.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |

4. Do one of the following:

- To start the Fortify WebInspect REST API service and test the API configuration, click **Test API**.  
The service starts, and a browser opens and navigates to the Fortify WebInspect REST API Swagger UI page.
- To start the Fortify WebInspect REST API service without testing the API configuration, click **Start**.

## Installing and Configuring the DAST Sensor Service

**Important!** To install and run the DAST sensor service, you must run the service with the `appsettings.json` file that the ScanCentral DAST Configuration Tool created. Make sure you have access to this file. For more information, see ["Generating Launch Artifacts" on page 50](#).

On the machine where Fortify WebInspect is installed, install and run the DAST sensor service as follows:

1. Download the `ScannerService<version>.zip` file from the Fortify ScanCentral DAST software download package.

**Tip:** The software download package is the file that you downloaded after your purchase .

2. Extract the `ScannerService<version>.zip` file to any directory, such as the following:  
`c:\ScannerService`

3. Place the `appsettings.json` file that the ScanCentral DAST Configuration Tool created in the same directory, replacing the existing file.

**Important!** If Fortify WebInspect is not installed in the default location or the datapath has changed, you must update entries in the `appsettings.json` file accordingly.

4. Run the Command Prompt as Administrator, and then enter the following command:

```
sc create ScannerWorkerService binpath= "<PathToScannerService>  
  \DAST.ScannerWorkerService.exe" start= auto depend= "WebInspect API"  
  displayname= "WebInspect DAST Scanner Worker Service"
```

The following sample uses the `c:\ScannerService` directory in the path:

```
sc create ScannerWorkerService binpath= "C:\ScannerService  
  \DAST.ScannerWorkerService.exe" start= auto depend= "WebInspect API"  
  displayname= "WebInspect DAST Scanner Worker Service"
```

The `ScannerWorkerService` is created and automatically starts each time the computer is restarted. Additional options provide the following benefits:

- `depend= "WebInspect API"` – Starts the Fortify WebInspect API service if it has stopped. It also stops the `ScannerWorkerService` if the Fortify WebInspect API service is stopped for any reason.
  - `displayname= "WebInspect DAST Scanner Worker Service"` - Groups the services together in Windows Service Manager, which may help with troubleshooting.
5. Open Windows Services Manager (`services.msc`). For more information, refer to your Windows documentation.
  6. In Windows Services Manager, configure the scanner worker service as follows:
    - a. Right-click the newly created **ScannerWorkerService**.
    - b. Configure the user account and password under which the service should run.

**Note:** You can use credentials for any user account that has access to log in to the Windows OS.

- c. Apply the changes.

**Note:** You might need to manually start the service the first time.

The service starts and polls the Fortify WebInspect API for instructions.


## Integrating with Kubernetes

You can integrate Fortify ScanCentral DAST with Kubernetes to create a scalable cloud architecture that provides scan scaling functionality, resulting in faster scans of your applications.

During a scan, script engines replay TruClient macros and run scripts to reveal the Document Object Model (DOM) of the application and events on the page. Scan scaling involves automatically creating multiple pools of these script engines in Kubernetes. In essence, it distributes the work of performing the scan across multiple script engines, thereby reducing the amount of time it takes to conduct the scan.

Scan scaling might be beneficial for applications that generally have long-running scans.

The following diagram illustrates the integration of ScanCentral DAST with Kubernetes.



## DNS Requirement

Your Domain Name System (DNS) can use Azure Private DNS zones. However, you must add a record into the DNS for the WebInspect script engine (WISE) ingress host name and the Kubernetes ingress controller IP address.

## Sensor Installation Requirement

You must use one of the following options to install the Fortify WebInspect sensor for integration with Kubernetes:

- Install the Fortify WebInspect sensor on a machine that is located in the same subnet that is used by the Kubernetes cluster.
- If the Kubernetes cluster supports both Windows and Linux nodes on the same subnet, then you can install the Fortify WebInspect sensor into the Kubernetes cluster using the WebInspect Helm Charts. For more information, see ["Installing the Sensor into the Kubernetes Cluster" on page 70](#).

**Tip:** Make note of the sensors that you install for integration with Kubernetes. You will need to add one or more of these sensors to the sensor pool(s) that you create for scan scaling.

## Implementing Scan Scaling with Kubernetes

You must configure the machine(s) where the remote script engines will run and the Kubernetes node that will manage them. You must also configure at least one sensor pool for scan scaling and then enable scaling in your scan. The following table describes this process.

| Stage | Description                                                                                                                                                                                                                                                                                                                 |
|-------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1.    | Download and configure kubectl and Helm software. For more information, see <a href="#">"Downloading kubectl and Helm" on the next page</a> .                                                                                                                                                                               |
| 2.    | Deploy the HAProxy ingress Kubernetes controller. For more information, see <a href="#">"Deploying HAProxy in Kubernetes" on page 63</a> .                                                                                                                                                                                  |
| 3.    | Deploy the Kubernetes Metrics Server to handle horizontal auto scaling for the Kubernetes WISE pods. For more information, <a href="#">"Deploying the Kubernetes Metrics Server" on page 65</a> .                                                                                                                           |
| 4.    | Deploy the WebInspect Script Engine (WISE) cluster in Kubernetes. For more information, see <a href="#">"Deploying WISE in Kubernetes" on page 66</a> .                                                                                                                                                                     |
| 5.    | Optionally, install the Fortify WebInspect sensor into the Kubernetes cluster. For more information, see <a href="#">"Installing the Sensor into the Kubernetes Cluster" on page 70</a> .                                                                                                                                   |
| 6.    | Configure one or more sensor pools for scan scaling. For more information, see <a href="#">"Creating a DAST Sensor Pool" on page 153</a> .<br><br><b>Note:</b> Not all pools need to use scan scaling. You may only need one or two pools configured for scan scaling. You can then add your applications with long-running |

| Stage | Description                                                                                                              |
|-------|--------------------------------------------------------------------------------------------------------------------------|
|       | scans to the sensor pools that are configured for scan scaling.                                                          |
| 7.    | Configure scan scaling in scan settings. For more information, see <a href="#">"Enabling Scan Scaling" on page 117</a> . |

## Downloading kubectl and Helm

Integrating ScanCentral DAST with Kubernetes requires use of the following software:

- kubectl - the command line tool used to control Kubernetes clusters. For more information about kubectl, refer to your Kubernetes documentation.
- Helm - the package manager for Kubernetes. For more information about Helm, refer to the Helm documentation at <https://helm.sh/docs/>.

The Helm CLI tool uses kubectl for all its interactions with Kubernetes clusters, so download and install these two software packages on the same machine.

### Downloading in Windows PowerShell

To download kubectl and Helm in Windows:

1. In PowerShell, enter the following to download kubectl for Windows and add it to \$PATH:

```
mkdir C:\docker\tools
cd C:\docker\tools Invoke-WebRequest `
  -Uri https://dl.k8s.io/release/v1.20.0/bin/windows/amd64/kubectl.exe `
  -OutFile .\kubectl.exe;
$env:Path += ";C:\docker\tools"
[Environment]::SetEnvironmentVariable("Path", $env:Path,
[EnvironmentVariableTarget]::Machine)
[Environment]::SetEnvironmentVariable("Path", $env:Path,
[EnvironmentVariableTarget]::User)
```

2. Enter the following to download and install Helm for windows:

```
Invoke-WebRequest `
  -Uri https://get.helm.sh/helm-v3.5.1-windows-amd64.zip `
  -OutFile .\helm-v3.5.1-windows-amd64.zip;
Unzip and copy helm.exe into: C:\docker\tools
rm .\helm-v3.5.1-windows-amd64.zip;
```

3. Enter the following to determine if the kubeconfig file points to the correct cluster:

```
kubectl cluster-info
```

**Tip:** You can change the default cluster by way of the `kubectl config set-context` command.

If you are using the Azure command-line interface (CLI), then you can use the following command:

```
az aks get-credentials --resource-group <resource-group-name>  
--name <Kubernetes-cluster-name>
```

## Downloading in Linux

To download kubectl and Helm in Linux:

1. Enter the following to download and install kubectl in Linux:

```
curl -LO "https://dl.k8s.io/release/$(curl -L -s  
https://dl.k8s.io/release/stable.txt)/bin/linux/amd64/kubectl"  
sudo install -o root -g root -m 0755 kubectl /usr/local/bin/kubectl
```

2. Enter the following to download and install Helm in Linux:

```
wget https://get.helm.sh/helm-v3.5.0-linux-amd64.tar.gz  
tar -xzf helm-v3.5.0-linux-amd64.tar.gz  
cd ./<helm-tar-dir>  
sudo install -o root -g root -m 0755 helm /usr/local/bin/helm
```

## Deploying HAProxy in Kubernetes

The HAProxy Kubernetes ingress controller provides a way to route traffic into your Kubernetes cluster while providing load balancing and other features.

**Important!** Fortify recommends that the HAProxy ingress controller be deployed only by users who have experience configuring and managing Kubernetes clusters.

For more information, refer to your Kubernetes documentation.

### Before You Begin

Ensure that you have downloaded and configured the prerequisite software. For more information, see ["Downloading kubectl and Helm" on the previous page](#).

## Guideline for Configuring HAProxy in Azure

ScanCentral DAST integration with Kubernetes does not require an external or public IP address. Use caution with your ingress controller configuration to ensure that you do not expose the ingress controller into the Internet. This exposure will not happen in local Kubernetes clusters. However, an Azure ingress controller could be exposed to the Internet using a public IP address.

To prevent using a public IP address in Azure, use the following command for HAProxy Helm install:

```
--set-string  
controller.service.annotations.'service\.beta\.kubernetes\.io/azure-load-  
balancer-internal'=true"
```

For details about using an ingress controller with restricted public access in Azure, refer to Microsoft documentation.

## Deploying HAProxy Ingress Controller

To deploy the HAProxy ingress controller:

- On the machine where the kubectl client and Helm are installed, enter the following in PowerShell:

```
kubectl label node <node-name> role=ingress-controller  
helm repo add haproxy-ingress https://haproxy-ingress.github.io/charts  
helm install haproxy-ingress haproxy-ingress/haproxy-ingress `   
  --create-namespace --namespace=ingress-controller `   
  --set controller.hostNetwork=true `   
  --set controller.nodeSelector.role=ingress-controller `   
  --set controller.service.type=LoadBalancer `   
  --set-string controller.service.annotations.'service\.beta\.  
    kubernetes\.io/azure-load-balancer-internal'=true
```

To confirm that the HAProxy ingress has started:

- Enter the following in PowerShell:

```
kubectl --namespace ingress-controller get services haproxy-ingress -o  
wide
```

You should see a response similar to the following:

| NAME                       | TYPE         | CLUSTER-IP   | EXTERNAL-IP |
|----------------------------|--------------|--------------|-------------|
| PORT(S)                    |              | AGE          |             |
| haproxy-ingress            | LoadBalancer | <ip_address> | <Pending>   |
| 80:31255/TCP,443:30766/TCP |              | 34s          |             |



## Deploying the Kubernetes Metrics Server

Before you can deploy the WebInspect script engine (WISE) Docker container, you must deploy the Kubernetes Metrics Server to handle horizontal auto scaling for the Kubernetes WISE pods. The Metrics Server measures resource allocations, such as CPU and RAM, for nodes and pods. It provides information for Kubernetes Wise pods horizontal auto scaling to increase the number of pods during loading or decrease the number to the `wise.replicas.min` setting when there is no loading. For more information, see ["Understanding the Parameters for WISE Deployment" on page 69](#).

### Before You Begin

Ensure that you have downloaded and configured the prerequisite software. For more information, see ["Downloading kubectl and Helm" on page 62](#).

### Deploying the Metrics Server

For Azure Kubernetes, the Metrics Server is installed by default. For local Kubernetes cluster installation, however, this component may need to be installed manually.

To deploy the Metrics Server to Kubernetes:

- On the machine where the kubectl client and Helm are installed, enter the following in PowerShell:

```
kubectl apply -f https://github.com/kubernetes-sigs/metrics-server/  
releases/latest/download/components.yaml
```

### Confirming the Metrics Server Installation

To confirm that the Metrics Server exists and is working:

1. Enter the following in PowerShell:

```
kubectl top nodes
```

You should see a response similar to the following:

| NAME      | CPU(cores) | CPU% | MEMORY(bytes) | MEMORY% |
|-----------|------------|------|---------------|---------|
| rbp-main  | 141m       | 3%   | 1550Mi        | 19%     |
| rbp-node1 | 45m        | 0%   | 1476Mi        | 9%      |
| rbp-node2 | 47m        | 0%   | 1519Mi        | 9%      |

2. Enter the following:

```
kubectl top po
```

You should see a response similar to the following:

| NAME                                     | CPU(cores) | MEMORY(bytes) |
|------------------------------------------|------------|---------------|
| wise-cluster-deployment-7747bb68b5-7q8m7 | 2m         | 96Mi          |
| wise-cluster-deployment-7747bb68b5-w179m | 2m         | 99Mi          |

**Note:** You can use the `kubectl top po` command to return the CPU and memory metrics for the WISE pods after WISE has been installed as described in ["Deploying WISE in Kubernetes"](#) below.

## Deploying WISE in Kubernetes

The WebInspect script engine (WISE) is a Docker container that provides a remote script server client for the Fortify WebInspect sensor.

**Important!** Fortify recommends that the WISE cluster be deployed only by users who have experience configuring and managing Kubernetes clusters.

### Before You Begin

Ensure that you have downloaded and configured the prerequisite software. For more information, see ["Downloading kubectl and Helm" on page 62](#).

The `wise-cluster-21.2.tgz` file that you use to install WISE is included in the Fortify Software Security Center download package. It is packaged in a ZIP file named `Dynamic_Addons.zip`. You can find this ZIP file in the directory where you downloaded the Fortify Software Security Center installation package.

Additionally, ensure that you have deployed the Kubernetes Metrics Server to handle horizontal auto scaling for the Kubernetes WISE pods. For more information, see ["Deploying the Kubernetes Metrics Server" on the previous page](#).

### Using the Default Parameters

To deploy the WISE cluster in Kubernetes using the default parameters:

- On the machine where the `kubectl` client and Helm are installed, enter the following in PowerShell:

```
helm install wi-script-engine wise-cluster-21.2.tgz
```

### Viewing the Default Parameters

To view the default parameters in the TGZ file:

- Enter the following in PowerShell:

```
helm show values wise-cluster-21.2.tgz
```

You should see a response similar to the following:

```
# Default values for wise-cluster.
# This is a YAML-formatted file.
# Declare variables to be passed into wise-cluster templates.

wise:
  authtoken: ""
  nodeSelector: ""
  replicas:
    min: 2
    max: 10
    autoscale: true
  cpu:
    cores: "4"

ingress:
  host: "wise-cluster"

image:
  repository: "fortifydocker/wise"
  tag: "21.2.ubuntu.1804"
  pull:
    policy: IfNotPresent
    secret: wise-regcred
    registry: "https://index.docker.io/v1/"
    username: ""
    password: ""
```

## Overriding the Default Parameters

To override any of the default values, use the `--set` command with the parameter name and desired value for each parameter to override as shown in the following example:

```
helm install wi-script-engine wise-cluster-21.2.tgz `
  --set wise.image.pull.registry=<container_registry> `
  --set wise.image.repository=fortifydocker/wise `
  --set wise.image.pull.username=<username> `
  --set wise.image.pull.password=<password> `
  --set wise.image.tag=<tagname> `
  --set wise.replicas.min=2 `
  --set wise.ingress.host=<hostname> `
  --set wise.authtoken=<token>
```

**Tip:** For Helm in PowerShell, the backtick character (```) at the end of each line is the new line character. For Helm in Linux, the backslash character (`\`) is the new line character.

## Installing WISE Into a Kubernetes Namespace

By default, the `helm install wi-script-engine...` command installs WISE into the Kubernetes default namespace. If your organization uses Kubernetes namespaces, you can create a new namespace and install WISE into it, or install WISE into an existing namespace.

**Important!** If you install WISE into a specific namespace, then all `kubectl` and Helm commands for managing the WISE installation must contain `--namespace=<wise_namespace>`. For example:

```
helm ls --namespace=<wise_namespace>
kubectl get po --namespace=<wise_namespace>
```

To create a namespace and install WISE:

- Add the following command to the `helm install...` command, either before or after the `--set` commands:

```
--create-namespace --namespace=<wise_namespace> `
```

The namespace is created and WISE is installed into it.

You can also view a list of your existing namespaces and choose a namespace for your WISE installation.

To view existing namespaces:

- Enter the following in PowerShell:

```
kubectl get ns
```

You should see a response similar to the following:

| NAME               | STATUS | AGE |
|--------------------|--------|-----|
| default            | Active | 54d |
| ingress-controller | Active | 54d |
| kube-node-lease    | Active | 54d |
| kube-public        | Active | 54d |
| kube-system        | Active | 54d |

To install WISE into an existing namespace:

- Add the following command to the `helm install...` command, either before or after the `--set` commands:

```
--namespace=<wise_namespace> `
```

## Understanding the Parameters for WISE Deployment

The following table describes the parameters that are used to deploy the WISE cluster.

| Parameter                             | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
|---------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>wise.image.pull.registry</code> | Optionally, specifies the Docker registry for a private repository. For example, if you use Azure and have created an Azure container registry to keep images that will be used in your Azure Kubernetes installation, you might specify something similar to <code>myreg.azurecr.io</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| <code>wise.image.pull.username</code> | Identifies the Docker repository username used to pull the WISE image.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| <code>wise.image.pull.password</code> | Identifies the Docker repository password used to pull the WISE image.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| <code>wise.image.repository</code>    | Specifies the Fortify Docker repository from which to pull the WISE image. This is <code>fortifydocker/wise</code> .<br><br><b>Note:</b> If you use a private repository, you might specify something similar to <code>myreg.azurecr.io/wise</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| <code>wise.image.tag</code>           | Specifies the WISE Docker image build and the operating system on which it was built.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| <code>wise.replicas.min</code>        | <p>Indicates the minimal number of WISE Kubernetes pods that will be started.</p> <p>Consider the following facts when configuring this parameter:</p> <ul style="list-style-type: none"><li>• If the <code>wise.replicas.min</code> setting is higher than Kubernetes cluster hardware resources can handle, then Kubernetes will not start all pods and their state will be set to "Pending." Kubernetes horizontal pods auto-scaler <i>will not</i> reduce the number of WISE pods lower than the configured <code>wise.replicas.min</code> setting.</li><li>• If the <code>wise.replicas.min</code> setting is too low and Kubernetes cluster still has free resources during WISE cluster loading, then Kubernetes horizontal pods auto-scaler <i>will</i> increase the number of replicas.</li></ul> |

| Parameter                      | Description                                                                                                                                                                                                                                                                                                        |
|--------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>wise.ingress.host</code> | <p>Specifies the ingress virtual wise cluster hostname.</p> <p><b>Important!</b> You can use any hostname value, but you must configure your DNS server or the hostfile on your Fortify WebInspect sensor client box to associate it with the IP address of the Kubernetes node that runs the HAProxy ingress.</p> |
| <code>wise.authtoken</code>    | <p>Optionally, specifies authentication for the WISE cluster. If the authtoken is configured, then Fortify WebInspect sensor clients will be required to provide an authtoken.</p> <p><b>Tip:</b> Make note of this token. You must enter it when configuring your sensor pools for scan scaling.</p>              |

## Uninstalling WISE

To uninstall WISE:

- Enter the following in PowerShell:

```
helm uninstall wi-script-engine
```

## Installing the Sensor into the Kubernetes Cluster

If you are integrating ScanCentral DAST with Kubernetes, and the Kubernetes cluster supports both Windows and Linux nodes on the same subnet, then you can install the Fortify WebInspect sensor into the Kubernetes cluster using WebInspect Helm Charts. For more information, see ["Integrating with Kubernetes" on page 59](#).

### Before You Begin

Ensure that you have downloaded and configured the prerequisite software. For more information, see ["Downloading kubectl and Helm" on page 62](#).

The `wi-21.2.0.tgz` file that you use to install the sensor is included in the Fortify Software Security Center download package. It is packaged in a ZIP file named `Dynamic_Addons.zip`. You can find this ZIP file in the directory where you downloaded the Fortify Software Security Center installation package.

## Installing the Sensor

To install the Fortify WebInspect sensor into the Kubernetes cluster:

1. On the machine where the kubectl client and Helm are installed, enter the following in PowerShell:

```
helm install webinspect wi-21.2.0.tgz `
  --set wi.mode=3 `
  --set wi.image.pull.registry=<container-registry> `
  --set wi.image.pull.username=<username> `
  --set wi.image.pull.password=<password> `
  --set wi.image.repository=fortifydocker/webinspect `
  --set wi.image.tag=<tagname> `
  --set wi.lim.url=http://<server-url>/<service-directory>/ `
  --set wi.lim.pool=<PoolName> `
  --set wi.lim.pswd=<PoolPassword> `
  --set wi.ingress.host=wi-api `
  --set dast.api.url="http://<dast_api_url>/api"
  --set dast.api.token="<dast_api_service_token>"
  --set dast.api.cert.validation="false"
```

**Tip:** For Helm in PowerShell, the backtick character (`) at the end of each line is the new line character. For Helm in Linux, the backslash character (\) is the new line character.

For descriptions of the parameters used in this Step, see ["Understanding the Helm Parameters" on the next page](#).

2. To verify that Helm installed WebInspect correctly, enter the following:

```
helm ls
```

You should see a response similar to the following:

| NAME       | NAMESPACE | STATUS   | CHART   | APP VERSION |
|------------|-----------|----------|---------|-------------|
| webinspect | default   | deployed | wi-2x.x | 2x.x.x      |

3. To verify that Kubernetes was able to pull the WebInspect image and start the pod, enter the following:

```
kubectl get po
```

You should see a response similar to the following:

| NAME                         | READY | STATUS  | RESTARTS | AGE |
|------------------------------|-------|---------|----------|-----|
| wi-deployment-b78f55f7-5n284 | 1/1   | Running | 0        | 31s |

**Tip:** To troubleshoot a response that shows the deployment is not running, enter the following:

```
kubectl describe po <Pod_Name>
```

You should see error details regarding why the pod failed to start in the event logs that are returned.

## Understanding the Helm Parameters

The following table describes the parameters that are used to install the sensor.

**Tip:** To view all configurable parameters and their default values, use the `helm show values .\` command.

| Parameter              | Description                                                                                                                                                                                                                                                                                                                                                                                                                 |
|------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| wi.mode                | Specifies the operation mode for the Docker image. Supported modes for ScanCentral DAST are: <ul style="list-style-type: none"><li>• 2 - WebInspect API mode</li><li>• 3 - ScanCentral DAST mode</li></ul>                                                                                                                                                                                                                  |
| wi.image.pull.registry | Optionally, specifies the Docker registry for a private repository. For example, if you use Azure and have created an Azure container registry to keep images that will be used in your Azure Kubernetes installation, you might specify something similar to <code>myreg.azurecr.io</code> .<br><br><b>Note:</b> This is not needed if you use the default <code>fortifydocker/webinspect</code> repository on Docker Hub. |
| wi.image.pull.username | Identifies the Docker repository username used to pull the WebInspect image.                                                                                                                                                                                                                                                                                                                                                |
| wi.image.pull.password | Identifies the Docker repository password used to pull the WebInspect image.                                                                                                                                                                                                                                                                                                                                                |
| wi.image.repository    | Specifies the Fortify Docker repository from which to pull the WebInspect image. This is <code>fortifydocker/webinspect</code> .<br><br><b>Note:</b> If you use a private repository, you might specify something similar to <code>myreg.azurecr.io/webinspect</code> .                                                                                                                                                     |
| wi.image.tag           | Specifies the WebInspect Docker image tag.                                                                                                                                                                                                                                                                                                                                                                                  |



| Parameter                             | Description                                                                                                                                                                                                  |
|---------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>wi.lim.url</code>               | Specifies the site from which Fortify WebInspect will get a license. The default <i>&lt;service-directory&gt;</i> is LimService.                                                                             |
| <code>wi.lim.pool</code>              | Specifies the LIM pool name.                                                                                                                                                                                 |
| <code>wi.lim.pswd</code>              | Specifies the LIM Pool password.                                                                                                                                                                             |
| <code>wi.ingress.host</code>          | Allows the WebInspect sensor to be exposed by way of the Kubernetes ingress using any host name that can be resolved to the Kubernetes ingress node IP.                                                      |
| <code>wi.nodeSelector</code>          | Allows Kubernetes to restrict deployment of the WebInspect pod to specific nodes. Example:<br><pre>--set wi.nodeSelector="agentpool: wipool"</pre>                                                           |
| <code>dast.api.url</code>             | Specifies the DAST API URL. This is required for mode 3.                                                                                                                                                     |
| <code>dast.api.token</code>           | Specifies the required DAST API service token.<br><br><b>Important!</b> This is the <b>Authorization Token</b> you will use to authenticate to the DAST API when configuring Scan Scaling for a sensor pool. |
| <code>dast.api.cert.validation</code> | Optionally, indicates if the DAST API uses a self-signed certificate for testing. Values are <b>true</b> or <b>false</b> .                                                                                   |

## Uninstalling the Sensor from the Kubernetes Cluster

To uninstall the sensor:

- Enter the following in PowerShell:

```
helm uninstall webinspect
```


# Chapter 3: Understanding the User Interface

After you configure your Fortify ScanCentral DAST environment and enable DAST in the ADMINISTRATION view in Fortify Software Security Center, you can work with DAST scans, sensors, sensor pools, settings, and scan schedules directly in Fortify Software Security Center.

Depending on your permissions in Fortify Software Security Center, you may also be able to work with deny intervals, custom policies, base settings, and application settings. These features are considered global settings. Global settings are those that apply or may apply to all of your applications, scans, scan schedules, sensors, or sensor pools.

## ScanCentral DAST User Interface

The following image shows the Fortify ScanCentral DAST user interface in Fortify Software Security Center.




The following table describes the areas called out in the previous image.

| Item | Description                                                                                                                         |
|------|-------------------------------------------------------------------------------------------------------------------------------------|
| 1    | The left panel allows you to navigate to the Fortify ScanCentral DAST pages that are available in Fortify Software Security Center. |
| 2    | The detail panel displays additional information about the item selected in the list.                                               |

## Scan Visualization

When you open a scan, the scan appears on a new tab in your browser. The following image shows the default view for an open scan.



The following table describes the display areas of the default view for an open scan.


| Item | Description                                                                                                                                                                                                                                                 |
|------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1    | Site Tree (see <a href="#">"Working with the Site Tree" on page 140</a> )                                                                                                                                                                                   |
| 2    | Findings, Traffic, and SPA Coverage tabs<br><br><b>Note:</b> The SPA Coverage tab is available only for scans that include SPA events.                                                                                                                      |
| 3    | Findings, Traffic, and SPA Coverage table views<br><br>(See <a href="#">"Understanding the Findings Table" on page 141</a> , <a href="#">"Understanding the Traffic Table" on page 143</a> , and <a href="#">"Understanding SPA Coverage" on page 146</a> ) |
| 4    | Steps tab<br><br>(See <a href="#">"Working with Findings" on page 142</a> and <a href="#">"Working with Traffic" on page 145</a> )                                                                                                                          |
| 5    | Vulnerability Description, HTTP, and Parameter tabs                                                                                                                                                                                                         |
| 6    | Vulnerability Description, HTTP, and Parameter detail views<br><br>(See <a href="#">"Working with Findings" on page 142</a> and <a href="#">"Working with Traffic" on page 145</a> )                                                                        |

## Resizing the Display Areas

You can resize the Site Tree, the Findings, Traffic, and SPA Coverage view, and the Vulnerability Description, HTTP, and Parameter view.

To resize an area:

- Drag the display area border either right or left to the width you want.



## Hiding and Showing a Display Area

By default, the Site Tree and the Vulnerability Description, HTTP, and Parameter view are visible when you open a scan. You can hide the Site Tree and the Vulnerability Description, HTTP, and Parameter view.

To hide an area:

- To hide the Site Tree, click the collapse icon (◀).
- To hide the Vulnerability Description, HTTP, and Parameter view, click the collapse icon (◀).

To show an area:

- To show the Site Tree, click the expand icon (▶).
- To show the Vulnerability Description, HTTP, and Parameter view, click the expand icon (▶).

## Working with Tables

Much of the data available in ScanCentral DAST is presented in tables. You can customize those tables and then save the customized views. Table preferences are saved per user.

The factory default view is named DEFAULT. You can edit the default view or use the default view to create custom views.

## Customizing Table Views

You can edit existing views or create new views in the table preferences panel.

The screenshot shows the 'Table Preferences' panel for the 'DEFAULT' view. It is divided into four main sections:   
1. **FILTER**: Includes a text input for 'Filter' (placeholder: 'Application, Version, Name, or URL'), a 'Date Range' dropdown (placeholder: 'Select date'), 'Start date' and 'End date' date pickers, and a 'Scan Status' dropdown (placeholder: 'Scan Status').   
2. **CURRENT SORT**: Includes a 'default sort' dropdown (placeholder: 'Select default sort') and a 'default sort direction' dropdown (placeholder: 'Select default sort di...').   
3. **ITEMS PER PAGE**: Includes a 'default items per page' dropdown set to '100'.   
4. **COLUMNS TO DISPLAY**: A list of checkboxes for columns: Application, Version, Name, Url, Critical, High, Medium, Low, Started On, and Status. All are checked.   
5. **VIEWS**: A section with a 'DEFAULT' button (highlighted in blue) and a 'default' button. At the bottom is a 'CREATE VIEW' button.   
At the bottom right of the panel are 'CANCEL' and 'OK' buttons.

The table preferences panel allows you to customize the following:

- Filtering (see ["Understanding Basic Filters in Tables" on page 79](#) and ["Understanding Advanced Filters in Tables" on page 83](#))
- Sorting (see ["Sorting Data in Columns" on page 86](#))
- Items Per Page (see ["Viewing Content on Multiple Pages" on page 88](#))
- Columns to Display (see ["Managing Columns in Tables" on the next page](#))

**Note:** Not all preference options are available for all tables. Some tables include only a subset of the preferences.

## Updating or Creating a View

After making changes to an existing view, you can either update the existing view or create a new view.

To update the original view with the new settings:

- In the table preferences panel, click **UPDATE <VIEW NAME>**.

To create a new view using the new settings:

1. In the table preferences panel, click **CREATE VIEW**.  
The CREATE VIEW dialog box opens.
2. In the **View name** box, type a name for the new view.
3. (Optional) To make the new view the default view, select **Make default**.
4. Click **OK**.

## Selecting a Different View

To select an existing view:

1. Click the table preferences icon (⚙️).  
The table preferences panel opens.
2. In the **VIEWS** list, select a view.

**Note:** If you have unsaved changes in the current view and attempt to switch views, you will be prompted that the changes will be lost.

3. Click **OK**.

## Managing Columns in Tables


You can customize the order in which columns appear in tables, as well as change the columns to display in tables.

### Rearranging the Columns

You can rearrange the order in which the columns appear in the table.

To move a column:

1. Click the column heading that you want to move.
2. Drag the column right or left and drop it into its new position.



**Note:** You cannot move the column of check boxes or columns containing icons, such as the download (⬇) and publish (⬆) icons.

## Adding and Removing Columns

You can use the table preferences panel to select which columns of data you want visible in the table.

To add or remove displayed columns:

1. Click the table preferences icon (⚙️).  
The table preferences panel opens.
2. In the **COLUMNS TO DISPLAY** area, do the following:
  - Select the column checkbox to display the column.
  - Clear the column checkbox to hide the column.
3. Click **OK**.

## Understanding Basic Filters in Tables

Basic filtering allows you to filter on certain columns of data in the Scans and Settings List tables.

You can filter data in the Scans table by application, version, name, or URL. You can also filter by scan start date, end date, date range, scan status, or a combination thereof.

You can filter data in the Settings List table by name, application, or version. You can also filter by scan start date, end date, date range, scan type, or a combination thereof.

Additionally, you can combine filtering by Application, Version, Name, or URL with Date, Scan Status, or Scan Type.

## Guidelines

The following guidelines apply to basic filtering:

- You can use partial words for filtering. For example, using the filter criteria "che" includes the application named "OnlineParcheesi" and scans named "Allchecks" in the filter results.
- You cannot use wildcard characters, such as the asterisk (\*), as placeholders.
- You cannot use regular expressions.

## Using Basic Filters in Tables

This topic describes how to access the basic filter user interface, specify filter criteria, and clear filters.

### Accessing the Basic Filter Feature

You can access the basic filter feature in the table preferences panel for the Scans table and the Settings List table.

To access the basic filter feature:

- In the **Scans** or **Settings List** table view, click the table preferences icon (⚙️).  
The table preferences panel opens.

Specify the filter criteria in the **FILTER** area as described in ["Filtering by Application, Version, Name, or URL" below](#) and ["Filtering by Date, Scan Status, or Scan Type" on the next page](#).

### Filtering by Application, Version, Name, or URL

You can use filter criteria to filter across the Application, Version, Name, and URL columns of data in the Scans table. For example, if you use the filter criteria "OurEstore," then all applications named "OurEstore" and all scans named "OurEstore" will be included in the filtered data. Similarly, you can filter across the Name, Application, and Version columns in the Settings List table. This procedure illustrates filtering in the Scans table, but it also works in the Settings List table.



To filter by application, version, name, or URL:

1. In the **FILTER** area, type the filter criteria into the **Filter** box.

Filter

Application, Version, Name, or URL

**Note:** Type only one application, one version, one name, or one URL. Do not combine filter criteria in the Filter box.

2. Click **OK**.

The table displays the data matching the filter criteria in any of the four columns.


**Tip:** To combine filtering by Application, Version, Name, or URL with Date, Scan Status, or Scan Type, proceed to ["Filtering by Date, Scan Status, or Scan Type" below](#) before you click **OK**.

## Filtering by Date, Scan Status, or Scan Type

You can filter by date range, specific date, scan status, or a combination of date and scan status in the Scans table. Similarly, you can filter by date range, specific date, scan type, or a combination of date and scan type in the Settings List table. However, when you filter on a date in the Settings List table, you are filtering on the Modified date column. This procedure describes filtering in either the Scans table or the Settings List table.

To filter by date or Scan Status or Scan Type:


1. In the **FILTER** area, continue according to the following table.

| To filter by...                                 | Then...                                                                                                                                                                                                                                                                                                                                                                                                                         |
|-------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| A date range                                    | Select a range from the <b>Date Range</b> list. Options are <b>This week</b> , <b>This month</b> , <b>Last year</b> , and <b>Custom Range</b> .<br>If you select Custom Range, type dates for the range in the <b>Start date</b> and <b>End date</b> fields.<br><br><b>Tip:</b> Click the calendar icon (  ) to select dates from a calendar. |
| Scan status in the Scans list                   | Select a scan status from the <b>Scan Status</b> list.                                                                                                                                                                                                                                                                                                                                                                          |
| A date range and scan status in the Scans list  | Select a range from the <b>Date Range</b> list and a scan status from the <b>Scan Status</b> list.                                                                                                                                                                                                                                                                                                                              |
| Scan type in the Settings List                  | Select a scan type from the <b>Scan Type</b> list.                                                                                                                                                                                                                                                                                                                                                                              |
| A date range and scan type in the Settings List | Select a range from the <b>Date Range</b> list and a scan status from the <b>Scan Status</b> list.                                                                                                                                                                                                                                                                                                                              |


2. Click **OK**.

## Clearing the Filter

Active filters appear as tiles at the top of the table. For basic filters, the filter value is listed in each filter tile.



To clear a filter:

- Click the remove filter icon (  ) on the filter tile.

To clear all filters:

- Click the clear filters icon ().

**Important!** Making changes outside of the table preferences panel adds a save table preferences icon (💾) to the left of the table preferences icon. Clicking the save table preferences icon saves the changes to the current view.

## Understanding Advanced Filters in Tables

Advanced filtering allows you to construct filters using fields, operators, and conditions. The Findings and Traffic tables of a completed scan offer advanced filtering.

**Important!** Bear in mind that selecting a resource in the Site Tree filters data to that resource in the Findings and Traffic tables. Advanced filters are then applied to the data that is already filtered.

## Understanding the Operators

The following table describes the operators that are available for each type of data in advanced filtering.

| Operator              | Data Type |         |           |                   |
|-----------------------|-----------|---------|-----------|-------------------|
|                       | String    | Numeric | Date/Time | Enum <sup>1</sup> |
| Equal                 | x         | x       | x         | x                 |
| Not Equal             | x         | x       | x         | x                 |
| Less Than             |           | x       | x         |                   |
| Less Than or Equal    |           | x       | x         |                   |
| Greater Than          |           | x       | x         |                   |
| Greater Than or Equal |           | x       | x         |                   |
| Between               |           | x       | x         |                   |
| Contains              | x         | x       |           |                   |
| Starts With           | x         | x       |           |                   |
| Ends With             | x         | x       |           |                   |

<sup>1</sup>Enumerator data consists of a key-value pair and is always presented as a list for filtering.

## Understanding Conditions and Field Filters

Field filters are treated as AND filters. For example, creating a field filter for a Severity of "High" and a field filter for a Method of "GET" filters in all records with a Severity of High AND a Method of GET.

For each field filter, you can add conditions. These conditions are treated as OR. For example, creating a field filter for a Severity of "High" and adding a condition for a Severity of "Medium" filters in all records with a either a Severity of High or of Medium.

## Using Advanced Filters in Tables

This topic describes how to access the advanced filter user interface, construct filters, and clear filters.

### Accessing the Advance Filter Feature

You can access the advanced filter feature in the table preferences panel for the Findings table and the Traffic table.

To access the advance filter feature:

1. In the **Findings** or **Traffic** table of an open scan, click the table preferences (⚙️) icon.  
The table preferences panel opens.
2. In the **FILTER** area, click **ADD FILTER**.  
The ADVANCED FILTER dialog box opens.

### Creating an Advanced Filter

You can create an advanced filter by specifying a field, an operator, and one or more values.

To create an advanced filter in the ADVANCED FILTER dialog box:

1. In the **Field** list, select a field to filter.
2. In the **Operator** box, select an operator. For more information, see the ["Understanding the Operators" on the previous page](#).
3. In the box to the right of the operator, select a value from the list or type a text string.
4. Do you want to add another condition to the current filter?
  - If yes, click **ADD CONDITION**, and repeat Steps 2 and 3.

**Note:** Each condition is treated as an "OR" condition. For more information, see ["Understanding Conditions and Field Filters" above](#).


- If no, go to Step 5.
5. Click **OK**.

## Editing an Advanced Filter Condition

You can edit the conditions for an advanced filter.

To edit a condition:

1. Click the table preferences icon (⚙️).  
The table preferences panel opens.
2. In the **FIELD FILTERS** area, click the edit filter icon for the condition you want to edit.



The ADVANCED FILTER dialog box opens.

3. Make edits as needed.
4. Click **OK**.

## Removing an Advanced Filter Condition


You can remove a condition for an advanced filter.

To remove a condition:

1. Click the table preferences icon (⚙️).  
The table preferences panel opens.
2. In the **FIELD FILTERS** area, click the edit filter icon.  
The ADVANCED FILTER dialog box opens.
3. In the **ADVANCED FILTER** dialog box, click the remove condition icon (✕) next to condition to delete.  
The condition is removed.
4. Click **OK**.

## Clearing Filters

Active filters appear as tiles at the top of the table. For advanced filters, the field name is listed in each filter tile.



To clear a filter:

- Click the remove filter icon ( **x** ) on the filter tile.

To clear all filters:


- Click the clear filters icon ( **Yx** ).

**Important!** Making changes outside of the table preferences panel adds a save table preferences icon ( **💾** ) to the left of the table preferences icon. Clicking the save table preferences icon saves the changes to the current view.

To clear a filter from the table preferences:

1. Click the table preferences icon ( **⚙** ).  
The table preferences panel opens.
2. In the **FIELD FILTERS** area, click the delete filter icon.

#### FIELD FILTERS



The filter is deleted.

3. Click **OK**.

## Sorting Data in Columns

By default, columns of text in tables are listed in alphabetical order, columns of dates are in chronological order, and columns of numerical data are in numerical order. You can change the sorting directly in the table or in the table preferences panel.

**Important!** Making changes outside of the table preferences panel adds a save table preferences icon ( **💾** ) to the left of the table preferences icon. Clicking the save table preferences icon saves the changes to the current view.

## Known Issue with Sorting

In some columns, ascending and descending sorting sorts on a numeric value in the database, rather than on the alphabetical order of the text displayed. Therefore, sorting order may not appear as expected. For example, when sorting the sensor Status column in ascending order, one would expect to see the following alphabetical order:

- Offline
- Online

However, the sort order is based on the numeric values of 1 and 2 in the DAST database, rendering the following sort order:

- Online (represented by 1 in the database)
- Offline (represented by 2 in the database)

## Sorting Directly in the Table

To change the sort order on any column of data:

- Click the column name.

The arrow next to the column name indicates the new sort order.

| Version | Name ↑ | URL |
|---------|--------|-----|
|---------|--------|-----|

To reverse the current sort order:

- Click the column name again.

The arrow next to the column name indicates the reverse sort order.

| Version | Name ↓ | URL |
|---------|--------|-----|
|---------|--------|-----|

To clear the sorting:

- Click the column name a third time.

The arrow next to the column name disappears.

| Version | Name | URL |
|---------|------|-----|
|---------|------|-----|

## Sorting in the Table Preferences Panel

To sort table data in the table preferences panel:

1. Click the table preferences icon (⚙️).

The table preferences panel opens.

2. In the **default sort** list of the **CURRENT SORT** area, select a column to sort.

**Note:** If a column is hidden in the current view, you cannot select the column for sorting.

3. In the **default sort direction** list, do one of the following:
  - Select **asc** for ascending sort order.
  - Select **desc** for descending sort order.
4. Click **OK**.

## Clearing Data from Input Boxes


For any input box in the user interface for which you select recently used data, such as recently used options from a drop-down list box, you can clear the selected data without manually deleting it.

To clear selected data from an input box:

- Click the **Clear** (X) icon.

## Viewing Content on Multiple Pages

If you have multiple pages of content, you can use the page navigation options to change the number of items displayed per page and navigate through the pages.



## Changing the Number of Items Displayed

The default number of items displayed per page is 100. You can change the number to 5, 10, 25, or 50.

To change the number of items displayed:

- Select a number from the **Items per page** drop-down list.

**Important!** Making changes outside of the table preferences panel adds a save table preferences icon (💾) to the left of the table preferences icon. Clicking the save table preferences icon saves the changes to the current view.

## Navigating Multiple Pages

When the number of items you are viewing spans multiple pages, you can navigate through the pages using the page navigation icons.



To view the next page of items:

- Click the **Next page** (>>) icon.

To view the previous page of items:

- Click the **Previous page** (<<) icon.

## Changing the Number of Items Displayed in the Table Preferences Panel

To change the number of items listed per page in the table preferences panel:

1. Click the table preferences icon (⚙️).  
The table preferences panel opens.
2. In the **default items per page** list in the **ITEMS PER PAGE** area, select the number of items to view.
3. Click **OK**.

# Chapter 4: Configuring a Scan

Use the Settings Configuration wizard to configure a Fortify ScanCentral DAST scan of your Web application to assess potential security flaws. A ScanCentral DAST scan is an automated scan of your Web application, rather than a scan of your code. It is designed to apply attack algorithms to locate vulnerabilities, determine their severity, and provide the information you need to fix them.

## What is a Scan?

The ScanCentral DAST sensor, which is a Fortify WebInspect sensor, uses two basic modes for determining the security weaknesses of your Web application:

- Crawl - The process by which the sensor identifies the structure of the target Web site. In essence, a crawl runs until no more links on the URL can be followed.
- Audit - The actual vulnerability assessment.

A scan can combine the application crawl and audit phases into a single fluid process, or it can be a crawl-only or an audit-only scan. The scan is refined based on real-time audit findings, resulting in a comprehensive view of an entire Web application's attack surface.

## Preparing Your System for Audit

The Fortify WebInspect sensor is an aggressive web application analyzer that rigorously inspects your entire website for real and potential security vulnerabilities. This procedure is intrusive to varying degrees. Depending on which Fortify ScanCentral DAST policy you apply and the options you select, it can affect server and application throughput and efficiency. When using the most aggressive policies, Fortify recommends that you perform this analysis in a controlled environment while monitoring your servers.

## Sensitive Data

The WebInspect sensor captures and displays all application data sent between the application and server. It might even discover sensitive data in your application that you are not aware of. Fortify recommends that you follow one of these best practices regarding sensitive data:

- Do not use potentially sensitive data, such as real user names and passwords, while testing with the WebInspect sensor.
- Do not allow ScanCentral DAST scans, related artifacts, and data stores to be accessed by anyone unauthorized to access potentially sensitive data.

Network authentication credentials are not displayed in ScanCentral DAST and are encrypted when stored in settings.

## Firewalls, Anti-virus Software, and Intrusion Detection Systems

The WebInspect sensor sends attacks to servers, and then analyzes and stores the results. Web application firewalls (WAF), anti-virus software, firewalls, and intrusion detection/prevention systems (IDS/IPS) are in place to prevent these activities. Therefore, these tools can be problematic when conducting a scan for vulnerabilities.

First, these tools can interfere with the WebInspect sensor's scanning of a server. An attack that the WebInspect sensor sends to the server can be intercepted, resulting in a failed request to the server. If the server is vulnerable to that attack, then a false negative is possible.

Second, results or attacks that are in the ScanCentral DAST product, cached on disk locally, or in the database can be identified and quarantined by these tools. When working files used by the WebInspect sensor or data in the database are quarantined, the sensor can produce inconsistent results. Such quarantined files and data can also cause unexpected behavior.

These types of issues are environmentally specific, though McAfee IPS is known to cause both types of problems, and any WAF will cause the first problem. Fortify has seen other issues related to these tools as well.

If such issues arise while conducting a scan, Fortify recommends that you disable WAF, anti-virus software, firewall, and IDS/IPS tools for the duration of the scan. Doing so is the only way to be sure you are getting reliable scan results.

## Effects to Consider

During an audit of any type, the WebInspect sensor submits a large number of HTTP requests, many of which have "invalid" parameters. On slower systems, the volume of requests may degrade or deny access to the system by other users. Additionally, if you are using an intrusion detection system, it will identify numerous illegal access attempts.

To conduct a thorough scan, the WebInspect sensor attempts to identify every page, form, file, and folder in your application. If the option to submit forms during a crawl of your site is selected, the sensor will complete and submit all forms it encounters. Although this enables the sensor to navigate seamlessly through your application, it may also produce the following consequences:

- If, when a user normally submits a form, the application creates and sends e-mails or bulletin board postings (to a product support or sales group, for example), the WebInspect sensor will also generate these messages as part of its probe.
- If normal form submission causes records to be added to a database, then the forms that the WebInspect sensor submits will create spurious records.

During the audit phase of a scan, the WebInspect sensor resubmits forms many times, manipulating every possible parameter to reveal problems in the applications. This greatly increases the number of messages and database records created.

## Helpful Hints

- For systems that write records to a back-end server (database, LDAP, and so on) based on forms submitted by clients, some ScanCentral DAST users, before auditing their production system, backup their database, and then reinstall it after the audit is complete. If this is not feasible, you can query your servers after the audit to search for and delete records that contain one or more of the form values submitted by the WebInspect sensor. You can determine these values by opening the Web Form Editor.
- If your system generates e-mail messages in response to user-submitted forms, consider disabling your mail server. Alternatively, you could redirect all e-mails to a queue and then, following the audit, manually review and delete those e-mails that were generated in response to forms submitted by the WebInspect sensor.
- The WebInspect sensor can be configured to send up to 75 concurrent HTTP requests before it waits for an HTTP response to the first request. The default thread count setting is 5 for a crawl and 10 for an audit (if using separate requestors). In some environments, you may need to specify a lower number to avoid application or server failure. For more information, see Scan Settings: Requestor in the *Micro Focus Fortify WebInspect User Guide*.
- If, for any reason, you do not want the WebInspect sensor to crawl and attack certain directories, you must specify those directories in the Basic Exclusions list when configuring your scan. For more information, see ["Creating and Managing Exclusions" on page 112](#) or ["Creating and Managing Exclusions in Base Settings" on page 194](#).
- By default, the WebInspect sensor is configured to ignore many binary files (images, documents, and so on) that are commonly found in web applications. These documents cannot be crawled or attacked, so there is no value in auditing them. Bypassing these documents greatly increases the audit speed. If proprietary documents are in use, determine the file extensions of the documents and exclude them within the sensor's default settings. For more information, see Scan Settings: Session Exclusions and Crawl Settings: Session Exclusions in the *Micro Focus Fortify WebInspect User Guide*. If, during a crawl, the sensor becomes extremely slow or stops, it may be because it attempted to download a binary document.
- For form submission, the WebInspect sensor submits data extracted from a prepackaged file. If you require specific values (such as user names and passwords), you must create a file with Fortify's Web Form Editor and identify that file to the WebInspect sensor. For more information, see the *Micro Focus Fortify WebInspect Tools Guide*.
- The WebInspect sensor tests for certain vulnerabilities by attempting to upload files to your server. If your server allows this, the sensor will record this susceptibility in its scan report and attempt to delete the file. Sometimes, however, the server prevents file deletion. For this reason, search for and delete files with names that start with "CreatedByHP" as a routine part of your post-scan maintenance.

# Accessing Settings Configuration from Software Security Center

You can access the Settings Configuration wizard and configure a ScanCentral DAST scan from Fortify Software Security Center.

## Accessing from the DAST Scans List

To access the Settings Configuration wizard from the ScanCentral DAST Scans list:

1. Select **SCANCENTRAL > DAST**.  
The scans list appears.
2. On the **Scans** list, click **+ NEW SCAN**.  
The Settings Configuration wizard opens to the Getting Started page.

## Accessing from the Settings List

To access the Settings Configuration wizard from the ScanCentral DAST Settings List page:

1. Select **SCANCENTRAL > DAST**.  
The scans list appears.
2. In the left panel, select **Settings List**.
3. Click **+ NEW SETTINGS**.  
The Settings Configuration wizard opens to the Getting Started page.

## What's Next?

Proceed with ["Getting Started" below](#).

## Getting Started

To configure a ScanCentral DAST scan:

1. On the Getting Started page, select an application from the **Application Name** list.
2. From the **Application Version** list, select a version.  
The START list appears, providing options for creating new settings or editing existing settings. A RECENT list also appears, displaying recently-opened scan settings for the specified application and version.

3. Continue according to the following table.

| If you want to...                                                                                                                                | Then...                                                                                                                                                                                                                                         |
|--------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Configure scan settings for a new scan                                                                                                           | Select <b>New settings</b> from the <b>START</b> list.                                                                                                                                                                                          |
| View and edit existing scan settings from a template in Fortify Software Security Center                                                         | <ol style="list-style-type: none"> <li>Select <b>Open from SSC</b> from the <b>START</b> list.<br/>A Template list appears.</li> <li>Select the existing settings from the <b>Template</b> list.</li> </ol>                                     |
| View and edit existing scan settings from your local machine                                                                                     | <ol style="list-style-type: none"> <li>Select <b>Open file</b> from the <b>START</b> list.<br/>An OPEN button appears.</li> <li>Click <b>OPEN</b> and use the standard Windows Open dialog box to locate and open the settings file.</li> </ol> |
| <p>View and edit scan settings from base settings</p> <p>For more information, see <a href="#">"Working with Base Settings" on page 177</a>.</p> | <ol style="list-style-type: none"> <li>Select <b>Base Settings</b> from the <b>START</b> list.<br/>A Base Settings list appears.</li> <li>Select the existing settings from the <b>Base Settings</b> list.</li> </ol>                           |
| View and edit recently-opened scan settings for the specified application and version                                                            | Select the settings from the <b>RECENT</b> list.                                                                                                                                                                                                |

4. Click **NEXT**.

## What's Next?

Do one of the following:

- To configure a standard scan, proceed with ["Configuring a Standard Scan" on the next page](#).
- To configure a workflow-driven scan, proceed with ["Configuring a Workflow-driven Scan" on page 96](#).
- To configure an API scan, proceed with ["Configuring an API Scan" on page 98](#).

## Configuring a Standard Scan

A standard scan performs an automated analysis, beginning from the start URL.

To configure a standard scan:

1. On the Target page, click **STANDARD SCAN**.
2. Select one of the following scan modes:
  - **Crawl Only:** Maps the hierarchical data structure of the site.
  - **Crawl and Audit:** Maps the hierarchical data structure of the site and audits each resource (page).
  - **Audit Only:** Applies the methodologies of the selected policy to determine vulnerability risks, but does not crawl the website. This scan mode does not follow or assess links on the site.
3. Type the complete URL or IP address in the **Url** field.

If you enter a URL, it must be precise. For example, if you enter MYCOMPANY.COM, the sensor will not scan WWW.MYCOMPANY.COM or any other variation unless you specify alternatives in the **Allowed Hosts** setting. For more information, see ["Adding and Managing Allowed Hosts" on page 106](#).

An invalid URL or IP address will result in an error. If you want to scan from a certain point in your hierarchical tree, append a starting point for the scan, such as `http://www.myserver.com/myapplication/`.

Scans by IP address will not follow links that use fully qualified URLs (as opposed to relative paths).

**Note:** The sensor supports both Internet Protocol version 4 (IPV4) and Internet Protocol version 6 (IPV6). You must enclose IPV6 addresses in brackets.

4. (Optional) To limit the scope of the scan to a specified area, select **Restrict to folder**, and from the list, select one of the following options:
  - **Directory only** – The sensor crawls and/or audits only the URL that you specify. For example, if you select this option and specify the URL `www.mycompany/one/two/`, the sensor will assess only the "two" directory.
  - **Directory and subdirectories** – The sensor begins crawling and/or auditing at the URL you specify, but does not access any directory that is higher in the directory tree.
  - **Directory and parent directories** – The sensor begins crawling and/or auditing at the URL you specify, but does not access any directory that is lower in the directory tree.
5. (Optional) To submit the completed scan for triage in Fortify Software Security Center, select **Submit for triage**.

**Note:** Submitting for triage allows you to perform audit analysis of the findings so that you can assign a user and an analysis value to the issue.

6. Under **Audit Depth (Policy)**, do one of the following:
  - Select a policy from the **Policy** list.
  - Begin typing the policy name in the **Policy** list box to filter the list of policy names that begin with the text that you enter.

**Note:** The default policies are stored in SecureBase tables in the ScanCentral DAST database. For more information about the list of default policies, see ["Policies" on page 224](#). Custom policies are assigned to specific applications and are stored in the ScanCentral DAST database. Only those custom policies that are assigned to the selected application appear in the Policy list.

7. Do one of the following:
    - To use a standard user agent, select it from the **User Agent** list.
- Note:** Default uses the user agent that is defined in Fortify WebInspect.
- To use a custom user agent, select **Custom** from the **User Agent** list, and then type the user-agent string in the **Custom User Agent** box.

**Tip:** User-agent strings generally use the following format:

*<browser>/<version> (<system and browser information>) <platform> (<platform details>) <extensions>*

## What's Next?

Do one of the following:

- To configure proxy settings for the scan, proceed with ["Configuring Proxy Settings" on page 102](#).
- To configure authentication for the scan, click **NEXT** and proceed with ["Configuring Authentication" on page 103](#).

## Configuring a Workflow-driven Scan

A workflow-driven scan audits only those URLs included in a macro that you previously recorded. It does not follow any hyperlinks encountered during the audit. A logout signature is not required. This type of macro is used most often to focus on a particular subsection of the application. If you select multiple macros, all of them will be included in the same scan.

## Types of Macros Supported

You can use .webmacro files or Burp Proxy captures.

**Important!** If you use a login macro in conjunction with a workflow macro or startup macro or both, all macros must be of the same type: all .webmacro files or all Burp Proxy captures. You



cannot use different types of macros in the same scan. Likewise, .webmacro login and workflow files must have been created using the same version of Web Macro Recorder. You cannot use a login file that was recorded in the Web Macro Recorder with Macro Engine 6.1 and a workflow file that was recorded in the Session-based Web Macro Recorder.

## Configuring a Workflow-driven Scan

To configure a workflow-driven scan:

1. On the Target page, click **WORKFLOW-DRIVEN SCAN**.
2. Select one of the following scan modes:
  - **Crawl Only:** Maps the hierarchical data structure of the site.
  - **Crawl and Audit:** Maps the hierarchical data structure of the site and audits each resource (page).
  - **Audit Only:** Applies the methodologies of the selected policy to determine vulnerability risks, but does not crawl the website. This scan mode does not follow or assess links on the site.
3. Continue according to the following table.

| To...                                  | Then...                                                                                                                                                                                                                                                                                                                                         |
|----------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Record a workflow macro                | <p>Click <b>Open Workflow Macro Recorder 6.1</b>.</p> <p><b>Tip:</b> If you have not already downloaded and installed the Macro Recorder tool, the Open Workflow Macro Recorder 6.1 link will not open the tool. You must first download the tool and install it on your local machine.</p>                                                     |
| Add a macro to the scan settings       | <ol style="list-style-type: none"><li>a. Click <b>MANAGE</b>.</li><li>b. Type a name for the macro in the <b>Name</b> field.</li><li>c. Click <b>IMPORT</b> and browse to locate the workflow to add to the scan settings.</li><li>d. Click <b>OK</b>.</li><li>e. Repeat steps a through d to add another macro to the scan settings.</li></ol> |
| Remove a macro from the list of macros | <ol style="list-style-type: none"><li>a. Select the macro in the macro list.</li><li>b. Click <b>REMOVE</b>.</li></ol>                                                                                                                                                                                                                          |

4. (Optional) To submit the completed scan for triage in Fortify Software Security Center, select **Submit for triage**.

**Note:** Submitting for triage allows you to perform audit analysis of the findings so that you can assign a user and an analysis value to the issue.

5. Under **Audit Depth (Policy)**, do one of the following:
  - Select a policy from the **Policy** list.
  - Begin typing the policy name in the **Policy** list box to filter the list of policy names that begin with the text that you enter.

**Note:** The default policies are stored in SecureBase tables in the ScanCentral DAST database. For more information about the list of default policies, see ["Policies" on page 224](#). Custom policies are assigned to specific applications and are stored in the ScanCentral DAST database. Only those custom policies that are assigned to the selected application appear in the Policy list.

6. Do one of the following:
  - To use a standard user agent, select it from the **User Agent** list.

**Note:** Default uses the user agent that is defined in Fortify WebInspect.

- To use a custom user agent, select **Custom** from the **User Agent** list, and then type the user-agent string in the **Custom User Agent** box.

**Tip:** User-agent strings generally use the following format:

`<browser>/<version> (<system and browser information>) <platform> (<platform details>) <extensions>`

## What's Next?

Do one of the following:

- To configure proxy settings for the scan, proceed with ["Configuring Proxy Settings" on page 102](#).
- To configure authentication for the scan, click **NEXT** and proceed with ["Configuring Authentication" on page 103](#).

## Configuring an API Scan

An API scan creates a macro from a REST API definition and performs an automated analysis.

**Important!** The DAST Utility Service container must be up and running to configure and run a Postman scan. Also, if the Postman scan requires a proxy, you must configure the proxy settings before you validate the Postman collection file(s). For more information, see ["Configuring Proxy Settings" on page 102](#).

To configure an API scan:

1. On the **Target** page, click **API SCAN**.
2. In the **Type** list, select the API type to be scanned. The options are **Open API** (also known as Swagger), **Postman**, and **OData**.

**Important!** If you are configuring a Postman scan while using a classic Fortify WebInspect installation with the Fortify ScanCentral DAST sensor service, you must install prerequisite software on the sensor machine. For more information about this and other aspects of using Postman collection files, including configuring dynamic authentication using dynamic tokens, see ["Scanning with a Postman Collection" on page 217](#).

3. Continue according to the following table.

| For this API type... | Do this...                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Open API</b>      | <ol style="list-style-type: none"><li>a. In the <b>Definition</b> list, select <b>File</b> or <b>URL</b>, and continue as follows:<ul style="list-style-type: none"><li>◦ If you selected File, click <b>IMPORT</b> and import the definition file.</li><li>◦ If you selected URL, provide the URL to the API definition file, as shown in the following example:<br/><code>http://172.16.81.36/v1</code><br/><b>Tip:</b> Alternatively, you can paste in the full path to a definition file that is saved on your local machine.</li></ul></li><li>b. If HTTP authorization credentials, such as a bearer token, are needed to access the API definition, enter them in the <b>Authentication Header</b> box, as shown in the following example:<br/><code>Basic YWxhZGRpbjpvGVuc2VzYW11</code></li></ol> |
| <b>Postman</b>       | <ol style="list-style-type: none"><li>a. Do one of the following:<ul style="list-style-type: none"><li>◦ To import a workflow collection, select <b>IMPORT</b> and then import the Postman collection file.</li><li>◦ To import an authentication collection, select <b>Authentication</b> from the <b>IMPORT</b> drop-down list, and then import the Postman collection file.</li><li>◦ To import an environment file, select <b>Environment</b> from the <b>IMPORT</b> drop-down list, and then import the Postman environment file.</li></ul>The file is added to the list of collection files. Repeat this Step to import additional files.</li></ol>                                                                                                                                                  |

| For this API type... | Do this...                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|----------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                      | <div data-bbox="548 352 1401 455" style="background-color: #f0f0f0; padding: 10px; margin-bottom: 10px;"> <p><b>Important!</b> You can import only one authentication collection and one environment file.</p> </div> <p>b. Click <b>VALIDATE</b> to validate the collection file(s).</p> <p>Upon successful validation, the POSTMAN VALIDATION dialog box opens, displaying a list of sessions contained in the collection file(s). If authentication sessions are identified, they are preselected as <b>Auth</b> sessions. All other sessions are preselected as <b>Audit</b> sessions. Additionally, the Postman Authentication Results area displays the type of authentication detected as <b>None</b>, <b>Static</b>, or <b>Dynamic</b>.</p> <div data-bbox="548 787 1401 890" style="background-color: #f0f0f0; padding: 10px; margin-bottom: 10px;"> <p><b>Note:</b> <b>Auth</b> sessions will be used for authentication for the scan. <b>Audit</b> sessions will be audited in the scan.</p> </div> <p>c. (Optional) Select the <b>Auth</b> or <b>Audit</b> check box for a session to change its type as needed.</p> <p>d. (Optional) Make changes to the <b>Postman Authentication Results</b> as follows:</p> <ul style="list-style-type: none"> <li>◦ For <b>Static</b> authentication, enter a token in the <b>Custom Header Token</b> box.</li> <li>◦ For <b>Dynamic</b> authentication, do the following: <ul style="list-style-type: none"> <li>• Select the <b>Regex (Custom)</b> option to the right of the <b>Response Token Name</b> box, and then enter a custom regular expression in the <b>Response Token Name</b> box.</li> <li>• Select the <b>Regex (Custom)</b> option to the right of the <b>Request Token Name</b> box, and then enter a custom regular expression in the <b>Request Token Name</b> box.</li> <li>• Clear the <b>Use Auto Detect</b> option to the right of the <b>Logout Condition</b> box, and then enter a new logout condition string in the <b>Logout Condition</b> box.</li> </ul> </li> </ul> <p>e. Did you make changes to the Postman Authentication Results?</p> <ul style="list-style-type: none"> <li>◦ If yes, click <b>VALIDATE</b> to validate the new authentication settings, and then click <b>OK</b>.</li> <li>◦ If no, click <b>OK</b>.</li> </ul> |

| For this API type... | Do this...                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>OData</b>         | <p>In the <b>Definition</b> list, select <b>File</b> or <b>URL</b>, and continue as follows:</p> <ul style="list-style-type: none"> <li>If you selected File, click <b>IMPORT</b> and import the definition file.</li> <li>If you selected URL, provide the URL to the API definition file, as shown in the following example:</li> </ul> <p><code>http://172.16.81.36/v1</code></p> <p><b>Tip:</b> Alternatively, you can paste in the full path to a definition file that is saved on your local machine.</p> |

4. (Optional) To submit the completed scan for triage in Fortify Software Security Center, select **Submit for triage**.

**Note:** Submitting for triage allows you to perform audit analysis of the findings so that you can assign a user and an analysis value to the issue.

5. Under **Audit Depth (Policy)**, do one of the following:
  - Select a policy from the **Policy** list.
  - Begin typing the policy name in the **Policy** list box to filter the list of policy names that begin with the text that you enter.

**Note:** The default policies are stored in SecureBase tables in the ScanCentral DAST database. For more information about the list of default policies, see ["Policies" on page 224](#). Custom policies are assigned to specific applications and are stored in the ScanCentral DAST database. Only those custom policies that are assigned to the selected application appear in the Policy list.

**Tip:** The **API** policy is the default policy for API scan settings in the Settings Configuration wizard. However, you can choose another policy if needed.

6. Do one of the following:
  - To use a standard user agent, select it from the **User Agent** list.

**Note:** Default uses the user agent that is defined in Fortify WebInspect.

- To use a custom user agent, select **Custom** from the **User Agent** list, and then type the user-agent string in the **Custom User Agent** box.

**Tip:** User-agent strings generally use the following format:

`<browser>/<version> (<system and browser information>) <platform> (<platform details>) <extensions>`

## What's Next?

Do one of the following:

- To configure proxy settings for the scan, proceed with ["Configuring Proxy Settings" below](#).
- To configure authentication for the scan, click **NEXT** and proceed with ["Configuring Authentication" on the next page](#).

## Configuring Proxy Settings

To configure proxy settings:

1. On the Target page, click **PROXY SETTINGS**.  
The PROXY CONFIGURATION dialog box opens.
2. Select the **Use Proxy Server** option.  
The settings become available for you to configure.
3. Configure the settings according to the following table.

| To...                                                                                                                         | Then...                                                                                                                                                                                                                                                                          |
|-------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Use the Web Proxy Autodiscovery Protocol (WPAD) to locate and use a proxy autoconfig file to configure the web proxy settings | Select <b>Auto detect proxy settings</b> .                                                                                                                                                                                                                                       |
| Import your proxy server information from Firefox                                                                             | Select <b>Use Firefox proxy settings</b> .<br><br><b>Note:</b> Using browser proxy settings does not guarantee that you can access the Internet through a proxy server. If the Firefox browser connection settings are configured for "No proxy," then a proxy will not be used. |
| Load proxy settings from a Proxy Automatic Configuration (PAC) file                                                           | a. Select <b>Configure proxy settings using a PAC file</b> .<br><br>b. In the <b>URL</b> box, type the URL location for the PAC file.                                                                                                                                            |
| Access the Internet through a proxy server                                                                                    | a. Select <b>Explicitly configure proxy settings</b> .                                                                                                                                                                                                                           |

| To... | Then...                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|-------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|       | <ul style="list-style-type: none"><li>b. In the <b>Server</b> box, enter the URL or IP address of your proxy server.</li><li>c. In the <b>Port</b> box, enter the port number (for example, 8080).</li><li>d. From the <b>Type</b> list, select the protocol type for handling TCP traffic through the proxy server. The options are: <b>Standard</b>, <b>SOCKS4</b>, or <b>SOCKS5</b>.</li><li>e. If authentication is required, select a type from the <b>Authentication</b> list. The options are: <b>None</b>, <b>Basic</b>, <b>NTLM</b>, <b>Digest</b>, <b>Automatic</b>, <b>Kerberos</b>, or <b>Negotiate</b>.</li><li>f. If your proxy server requires authentication, enter the qualifying user name in the <b>User Name</b> field and the qualifying password in the <b>Password</b> field.</li><li>g. If you do not need to use a proxy server to access certain IP addresses (such as internal testing sites), enter the addresses or URLs in the <b>Bypass</b> field. Use commas to separate entries.</li></ul> |

4. Click **OK**.

The proxy settings are saved and the PROXY CONFIGURATION dialog box closes.

## What's Next?

To configure authentication for the scan, click **NEXT** and proceed with ["Configuring Authentication" below](#).

## Configuring Authentication

If your site or network or both require authentication, you can configure it on the Authentication page.

## Configuring Site Authentication

You can use a recorded login macro containing one or more usernames and passwords that allow you to log in to the target site. The macro must also contain a "logout condition," which indicates when an inadvertent logout has occurred so that the sensor can rerun the macro to log in again.

To configure site authentication:

1. Select **Site Authentication**.
2. Do one of the following:
  - To import an existing login macro, click **IMPORT**, and then locate and select the file to import.
  - To record a login macro, click **Open Macro Recorder 6.1**.

**Tip:** If you have not already downloaded and installed the Macro Recorder tool, the Open Macro Recorder 6.1 link will not open the tool. You must first download the tool and install it on your local machine as described in ["Downloading the Macro Recorder Tool" below](#).

## Downloading the Macro Recorder Tool

You can download the Macro Recorder with Macro Engine 6.1 tool from the ScanCentral DAST REST API container.

To download the Macro Recorder tool:

- Under **Site Authentication**, click **Download Macro Recorder 6.1**.

The MacroRecorder64Setup.exe file is downloaded to the default download directory that is specified in your browser settings. Navigate to the download directory and install the EXE file as usual.

**Tip:** After installation, you can launch the Macro Recorder tool from the Windows Start menu under **Fortify ScanCentral DAST**.

## Using a Client Certificate

Client certificate authentication allows users to present client certificates rather than entering a user name and password. You can enable the use of a certificate and then import the certificate to the scan settings.

To use a client certificate:

1. Select **Enable client certificate**.
2. Click **IMPORT**.  
A standard Windows file selection dialog box opens.
3. Locate and select the certificate file, and then click **Open**.  
The certificate file is added to the Client certificate box.



4. If the certificate requires a password, do the following:
  - a. Select **Requires password**.
  - b. Enter the password in the **Client certificate password** box.
5. Optionally, click **VALIDATE** to perform basic validation of the certificate.

**Note:** Basic validation only confirms that the file is a certificate, verifies the password if applicable, and checks for a private key. If the certificate is not valid, the scan will fail upon startup.

## Configuring Network Authentication

If server authentication is required, you can configure authentication using network credentials.

To configure network authentication:

1. Select **Network Authentication**.
2. Select an **Authentication Type**. Options are as follows:
  - **ADFS CBT**
  - **Automatic**
  - **Basic**
  - **Digest**
  - **Kerberos**
  - **NT LAN Manager (NTLM)**
3. Type the authentication username in the **Username** box.
4. Type the authentication password in the **Password** box.

**Caution!** The sensor crawls all servers granted access by this password (if the sites/servers are included in the Allowed Hosts setting). To avoid potential damage to your administrative systems, do not use credentials that have administrative rights. If you are unsure about your access rights, contact your System Administrator or internal security professional.

## What's Next?

To configure details for the scan, click **NEXT** and proceed with ["Configuring Scan Details" on the next page](#).

## Configuring Scan Details

You can configure the following settings on the Details page:

- Allowed hosts (For more information, see ["Adding and Managing Allowed Hosts" below.](#))
- Scan priority (For more information, see ["Configuring Scan Priority" on the next page.](#))
- Data retention (For more information, see ["Configuring Data Retention" on page 110.](#))
- Single-page application (SPA) support (For more information, see ["Scanning Single-page Applications" on page 110.](#))
- Traffic Monitor (For more information, see ["Using Traffic Viewer \(Traffic Monitor\)" on page 111.](#))
- Exclusions (For more information, see ["Creating and Managing Exclusions" on page 112.](#))
- Redundant page detection (For more information, see ["Configuring Redundant Page Detection" on page 116.](#))
- Scan scaling (For more information, see ["Enabling Scan Scaling" on page 117.](#))

## What's Next?

After you configure the scan details, click **NEXT** and proceed with ["Reviewing Scan Settings" on page 118.](#)

## Adding and Managing Allowed Hosts

Use the **Allowed Hosts** setting to add and manage domains to crawl and audit. If your Web application uses multiple domains, add those domains here. For example, if you were scanning "Wlexample.com," you would need to add "Wlexample2.com" and "Wlexample3.com" here if those domains were part of your Web presence and you wanted to include them in the scan.

You can also use this feature to scan any domain whose name contains the text you specify. For example, suppose you specify www.myco.com as the scan target and you enter "myco" as an allowed host. As the sensor scans the target site, if it encounters a link to any URL containing "myco," it will pursue that link and scan that site's server, repeating the process until all linked sites are scanned. For this hypothetical example, the sensor would scan the following domains:

- www.myco.com:80
- contact.myco.com:80
- www1.myco.com
- ethics.myco.com:80
- contact.myco.com:443
- wow.myco.com:80
- mycocorp.com:80
- www.interconnection.myco.com:80

## Adding Allowed Hosts

To add allowed hosts:

1. Click **MANAGE**.
2. In the SPECIFY ALLOWED HOST dialog box, type a URL in the **Name** box.

**Important!** When you specify the URL, do not include the protocol designator (such as http:// or https://).

3. (Optional) To use a regular expression to represent a URL, select **Use Regular Expression**.
4. Do one of the following:
  - To save the allowed host to the list, click the check mark icon (✓).  
The URL is added to the allowed hosts list. To add another allowed host, return to Step 2.
  - To clear the fields and start over, click the retry icon (↺) and return to Step 2.
5. When the list of allowed hosts is complete, click **OK**.

## Editing or Removing Hosts

To edit or remove an allowed host:

1. Select a host from the **Allowed Hosts** list.
2. Do one of the following:
  - To edit the host name or regular expression, click **MANAGE**.  
The SPECIFY ALLOWED HOST dialog box opens. For more information about using this dialog box, see ["Adding Allowed Hosts" above](#).
  - To remove the host from the allowed hosts list, click **REMOVE**.

## Configuring Scan Priority

Scans are run using a priority ranking from 0 to 10, where 0 is the lowest priority and 10 is the highest. Before starting a scan, the Global Service determines if there is a higher-priority scan that needs to be started. If there is, the lower-priority scan will remain in the queue. Additionally, a lower-priority scan that is running will be paused for a higher-priority scan if no other sensor is available.

If Advanced Scan Prioritization is enabled, the Global Service may move scans to other sensors, depending on scan priority and other settings. For more information about Advanced Scan Prioritization, see ["Understanding Advanced Scan Prioritization" on the next page](#).

**Note:** Applications are configured with a default priority level in the application settings. For more information, see ["Understanding the Application Settings List" on page 199](#).

## Changing the Priority

To select a priority other than the default setting for the scan:

- Select a priority from 0 to 10 in the **Priority** list.

**Note:** If you set a priority that differs from the Application Settings, the lower of the two settings will be used.

**Tip:** You cannot disable scan priority. However, you can set all applications and scans to the same priority to accomplish something similar.

## Understanding Advanced Scan Prioritization

Advanced scan prioritization allows the Global Service to move a scan to a different sensor, depending on the scan priority and other settings as described in the following paragraphs.

### Priority and Sensor Pools

For prioritization, scans are grouped by the sensor pool to which the scan belongs. Grouping scans by pool ensures that a higher-priority scan in sensor pool 1 will not pause a lower priority scan in sensor pool 2.

### Priority and Scan Status

Scans with the following statuses are processed first from the highest to lowest scan priority and then from the oldest to newest:

- Queued
- Resume Scan Queued
- Resume Scan Queued Scan Priority
- License Unavailable
- Paused Scan Priority

The following table provides examples using five scans with various statuses, priorities, and creation times.

| Scan Status                      | Priority | Created On Date/Time | When Started or Resumed |
|----------------------------------|----------|----------------------|-------------------------|
| Paused Scan Priority             | 0        | 10/26/2021 08:00 AM  | Fifth                   |
| Resume Scan Queued               | 5        | 10/26/2021 08:15 AM  | Second                  |
| Resume Scan Queued Scan Priority | 5        | 10/26/2021 09:00 AM  | Third                   |

| Scan Status | Priority | Created On Date/Time | When Started or Resumed |
|-------------|----------|----------------------|-------------------------|
| Queued      | 5        | 10/26/2021 11:26 AM  | Fourth                  |
| Queued      | 10       | 10/26/2021 12:01 PM  | First                   |

## Priority and Sensors

When configuring a scan, you can select a specific sensor in the Run Scan or Schedule Scan dialog boxes. You can also select the **Use this sensor only** option. The following table describes how these options affect advanced scan prioritization.

| Selected Sensor Options                                                             | What Happens                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
|-------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| A specific sensor is selected with the <b>Use this sensor only</b> option           | <p>If the sensor is available, then the scan starts on the sensor.</p> <p>If the sensor is not available and there is a lower-priority scan that is running on that sensor, then the lower-priority scan is paused and the higher-priority scan is started on the sensor.</p>                                                                                                                                                                                                                        |
| A specific sensor is selected <i>without</i> the <b>Use this sensor only</b> option | <p>If the sensor is available, then the scan starts on the sensor.</p> <p>If the sensor is not available, the Global Service attempts to find any other available sensor in the sensor pool. If an available sensor is found, the scan starts on that sensor. If no sensor is available, the Global Service checks whether a lower-priority scan is running. If a lower-priority scan is running, then the lower-priority scan is paused and the higher-priority scan is started on that sensor.</p> |
| <b>Any Available</b> sensor is selected                                             | <p>If a sensor is available in the sensor pool, then the scan is started on the sensor.</p> <p>If no sensor is available in the sensor pool, the Global Service checks whether a lower-priority scan is running. If a lower-priority scan is running, then the lower-priority scan is paused and the higher-priority scan is started on that sensor.</p>                                                                                                                                             |

## When Advanced Scan Prioritization is Disabled

If the **Disable Advanced Scan Prioritization** option was selected in the ScanCentral DAST Configuration Tool, then when a lower-priority scan is paused for a higher-priority scan to run, the lower-priority scan resumes only on the sensor on which it was originally running, regardless to whether another sensor is available in the sensor pool. Partial scan results are uploaded to the

ScanCentral DAST database, but the paused scan remains on the sensor. If the scan is resumed, but the scan no longer exists on the sensor for any reason, the Global Service downloads and imports the partial results prior to resuming the scan.

For more information, see ["Configuring Scan Priority" on page 107](#).

## Configuring Data Retention

If data retention is enabled for the application being scanned, then a default number of days for scan retention is configured in the application settings. In such cases, the default number of days for scan retention is displayed in the Details page. For more information, see ["Working with Application Settings" on page 198](#).

To set a number of days other than the default setting for the scan:

- Enter the number of days in the **Data Retention** box.

**Note:** If you set a number of days that differs from the Application Settings, the lower of the two settings will be used.

## Scanning Single-page Applications

This topic describes single-page application (SPA) support for crawling and auditing the Document Object Model (DOM) of an application.

**Important!** This version of SPA support is provided as a technology preview.

### Technology Preview

Technology preview features are currently unsupported, may not be functionally complete, and are not suitable for deployment in production. These features are provided as a courtesy and the primary objective is to gain wider exposure for the feature with the goal of full support in the future.

### The Challenge of Single-page Applications

Developers use JavaScript frameworks such as Angular, Ext JS, and Ember.js to build SPAs. These frameworks make it easier for developers to build applications, but more difficult for security testers to scan those applications for security vulnerabilities.

Traditional sites use simple back-end server rendering, which involves constructing the complete HTML web page on the server side. SPAs and other Web 2.0 sites use front-end DOM rendering, or a mix of front-end and back-end DOM rendering. With SPAs, if the user selects a menu item, the entire page can be erased and recreated with new content. However, the event of selecting the menu item does not generate a request for a new page from the server. The content update occurs without reloading the page from the server.

With traditional vulnerability testing, the event that triggered the new content might destroy other events that were previously collected on the SPA for audit. Through its SPA support, the dynamic sensor offers a solution to the challenge of vulnerability testing on SPAs.

## Configuring SPA Support

When SPA support is enabled, the DOM script engine finds JavaScript includes, frame and iframe includes, CSS file includes, and AJAX calls during the crawl, and then audits all traffic generated by those events.

To configure SPA support:

- Under **Single-Page Applications** on the Details page, select one of the following options:
  - **Automatic** - If the sensor detects a SPA framework, it automatically switches to SPA-support mode.
  - **Disabled** - Indicates that SPA frameworks are not used in the target application.
  - **Enabled** - Indicates that SPA frameworks are used in the target application.

**Caution!** Enable SPA support for single-page applications only. Enabling SPA support to scan a non-SPA website results in a slow scan.

## Using Traffic Viewer (Traffic Monitor)

The site tree of a scan normally displays only the hierarchical structure of the website or web service, plus those sessions in which a vulnerability was discovered. The Traffic Viewer (or Traffic Monitor) allows you to display and review every HTTP request sent by the sensor and the associated HTTP response received from the web server.

### Proxy Server Included

The Traffic Viewer includes a self-contained proxy server that you can configure and run on your desktop. With it, you can monitor traffic from your browser as it submits HTTP requests and receives responses from a web server. The Traffic Viewer proxy is a tool for debugging and penetration assessment; you can see every request and server response while browsing a site.

### Option Must be Enabled

To use the Traffic Viewer, you must enable Traffic Monitor logging in the scan settings. Otherwise, the Traffic Viewer is not available for a scan.

### Enabling Traffic Viewer (or Traffic Monitor)

To enable the Traffic Viewer (or Traffic Monitor):

- Under **Traffic Analysis** on the Details page, select **Enable Traffic Monitor**.

## Creating and Managing Exclusions

You can exclude URLs and sessions—based on criteria in their requests or responses—from being crawled and audited. Excluding URLs means that the sensor will not examine the specified URL or host for links to other resources. Excluding sessions means that sensor will not process the sessions that meet the exclusion criteria.

To exclude these items from your scan, you must create a list of Basic Exclusions. Each exclusion in the list identifies one or more targets in which the criteria for exclusion is found.

**Note:** You can add multiple targets to each entry in the Basic Exclusions list.

### Creating Exclusions

To create one or more exclusions:

1. Under **Basic Exclusions** on the Details page, click **CREATE**.  
The MANAGE EXCLUSIONS dialog box opens.
2. Type a name for the exclusion in the **Name** box.
3. From the **Target** list, select one of the following target types to configure for exclusion:
  - **Extension** - Excludes file extensions that match the exclusion criteria
  - **Host** - Excludes hosts that match the exclusion criteria
  - **Post parameter** - Excludes sessions with a POST request parameter that matches the exclusion criteria
  - **Query parameter** - Excludes sessions with a query parameter in the URL that matches the exclusion criteria
  - **Request** – Excludes sessions with a request that matches the exclusion criteria
  - **Response** – Excludes sessions with a response that matches the exclusion criteria
  - **Response header** - Excludes sessions with a response header that matches the exclusion criteria
  - **Status code** - Excludes sessions with a response status code that match the exclusion criteria
  - **URL** – Excludes URLs that match the exclusion criteria
4. Type a name for the target in the **Name** box.
5. Select one of the following types of exclusion for the target from the **Type** list:
  - **Matches Regex** – Matches the regular expression you specify in the **String** box
  - **Matches Regex extension** – Matches the regular expression extension you specify in the **String** box



- **Matches** - Matches the specified criteria in the **String** box
  - **Contains** – Contains the text string you specify in the **String** box
6. Type the string to match in the **String** box.  
For examples of Target, Type, and String settings, see ["Exclusion Examples" below](#).
  7. Do one of the following:
    - To save the exclusion to the list, click the check mark icon (✓).  
The exclusion is added to the list. To create another exclusion, return to Step 2.
    - To clear the fields and start over, click the retry icon (↺) and return to Step 2.
  8. When the list of exclusions is complete, click **OK**.

## Exclusion Examples

The following table provides examples of exclusions.

| To...                                                                                                                                  | Create the following exclusion... |
|----------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------|
| Ensure that you never send requests to any resource at Microsoft.com                                                                   | URL contains Microsoft.com        |
| Exclude the following directories:<br><br>http://www.test.com/W3SVC55/<br>http://www.test.com/W3SVC5/<br>http://www.test.com/W3SVC550/ | URL matches regex /W3SVC[0-9]*/   |
| Ensure that you never process session responses with 404 Not Found                                                                     | Response contains Not Found       |

For more information about creating exclusions, see ["Understanding and Creating Inclusive Exclusions" on the next page](#).

## Editing or Removing Exclusions

To edit or remove an entry in the **Basic Exclusions** list:

1. Select an entry from the **Basic Exclusions** list.
2. Do one of the following:
  - To edit the exclusion settings, click **MANAGE**.  
The MANAGE EXCLUSIONS dialog box opens. For more information about using this dialog box, see ["Creating Exclusions" on the previous page](#).
  - To remove the host from the allowed hosts list, click **REMOVE**.

## Understanding and Creating Inclusive Exclusions

When a site contains many pages that are essentially redundant, it makes sense to scan only a selection of such pages and exclude the rest. To accomplish this, we need to specify what to include by excluding everything else. Such exclusions are called "inclusive exclusions."

You can create regular expressions that exclude everything including the sessions you want to scan, and then add the inclusion regular expression within the negative look ahead construct.

### Understanding Inclusive Exclusion Regular Expressions

Suppose you have the following URLs:

```
http://site.tld/sub/sub1
http://site.tld/sub/sub2
http://site.tld/sub/sub3
http://site.tld/sub/sub4
http://site.tld/sub/sub5
...
http://site.tld/sub/sub9999
```

And you want to include sub1 in the scan but not sub2 through sub9999.

A regular expression to match and exclude everything is:

```
\sub/sub[0-9]+
```

Adding the negative look ahead to include sub1 results in this regular expression:

```
\sub/sub(?!1)[0-9]+
```

This regular expression matches and excludes everything in the previous list of URLs that does not include sub1.

**Important!** If the regular expression includes the host name, then it must also include the port as shown here:

```
site\.tld:80/sub/sub[0-9]+
site\.tld:80/sub/sub(?!1)[0-9]+
```

The following paragraphs provide additional examples of various inclusive exclusions.

### Example One

Suppose you want to scan only the contents of folders where the folder name starts with the combination "N13" and omit the others in the following list:

```
http://10.0.6.124:22000/cssbundle/1666793387/bundles/service.css
http://10.0.6.124:22000/cssbundle/N1375383199/bundles/service.css
```

```
http://10.0.6.124:22000/jsbundle/1337374041/bundles/catalogs.js
http://10.0.6.124:22000/jsbundle/1337374041/bundles/general.js
http://10.0.6.124:22000/jsbundle/335652056/bundles/search.js
http://10.0.6.124:22000/jsbundle/N1222120407/bundles/
http://10.0.6.124:22000/jsbundle/N1408948977/bundles/
http://10.0.6.124:22000/jsbundle/N1982198842/bundles/
http://10.0.6.124:22000/jsbundle/N273479010/bundles/
```

A regular expression to match and exclude all folder names that begin with letter "N" is:

```
\N[\d]+\
```

Adding the negative look ahead to include (?!13) results in this regular expression:

```
\N(?!13)[\d]+\
```

Using this regular expression as a session exclusion causes Fortify WebInspect to omit all of the paths except for those where the folder name starts with the combination "N13":

```
http://10.0.6.124:22000/cssbundle/N1375383199/bundles/service.css
```

**Note:** The number "13" is arbitrary. You could easily replace the "13" character set in the regular expression with your desired character set.

## Example Two

Suppose you want to omit most of My Awesome Store's catalog while still permitting URLs that include keywords "awesome" or "core" in the following list:

```
http://my.awesome.store.com/dotcom/14k-gold-plated-ring/cat.jump
http://my.awesome.store.com/dotcom/2-panel-jewelry-box/prod.jump
http://my.awesome.store.com/dotcom/core-short-sleeve-top/prod.jump
http://my.awesome.store.com/dotcom/core-graphic-tee/prod.jump
http://my.awesome.store.com/dotcom/core-pro-striped-shorts/prod.jump
http://my.awesome.store.com/dotcom/awesome-brand-pro-striped-shorts/prod.jump
http://my.awesome.store.com/dotcom/core-pro-striped-shorts/prod.jump
http://my.awesome.store.com/dotcom/shoes/sandals-flip-flops/low-mid-heel/cat.jump
http://my.awesome.store.com/dotcom/shoes/sandals-flip-flops/wedge-sandals/cat.jump
http://my.awesome.store.com/dotcom/shoes/sandals-flip-flops/flat-sandals/cat.jump
http://my.awesome.store.com/dotcom/shows/all-mens-shoes/slippers/cat.jump
http://my.awesome.store.com/dotcom/men/shorts/bermuda-core-beige/prod.jump
http://my.awesome.store.com/dotcom/men/shorts/pleated-core-beige/prod.jump
http://my.awesome.store.com/dotcom/men/shorts/bermuda-awesome-brand-beige/prod.jump
```

```
http://my.awesome.store.com/dotcom/core-proportioned-pants/prod.jump
http://my.awesome.store.com/dotcom/awesome-brand-slender-jean---plus/prod.jump
http://my.awesome.store.com/dotcom/awesome-brand/half-zip-jacket/prod.jump
http://my.awesome.store.com/dotcom/toys/categories/costumes-dress-
up/boys/cat.jump
http://my.awesome.store.com/dotcom/shoes/kids-shoes/boys-shoes/cat.jump
http://my.awesome.store.com/dotcom/toys/gender/boys/cat.jump
http://my.awesome.store.com/dotcom/shoes/boots/ankle-boots-booties/cat.jump
http://my.awesome.store.com/dotcom/shoes/all-womens-shoes/view-all/cat.jump
http://my.awesome.store.com/dotcom/women/awesome-brand/tops-sweaters/cat.jump
http://my.awesome.store.com/dotcom/men/wallets-accessories/backpacks-
bags/cat.jump
http://my.awesome.store.com/dotcom/women/wear-to-work/skirts/cat.jump
```

A regular expression to include "awesome" or "core" keywords is:

```
\.dotcom\/((?!awesome|core)[\w-%\/])+(?:cat|prod)\.jump
```

## Configuring Redundant Page Detection

Highly dynamic sites could create an infinite number of resources (pages) that are virtually identical. If allowed to pursue each resource, the sensor would never be able to finish the scan. The **Perform redundant page detection** option compares page structure to determine the level of similarity, allowing the sensor to identify and exclude processing of redundant resources.

**Important!** Redundant page detection works in the crawl portion of the scan. If the audit introduces a session that would be redundant, the session will not be excluded from the scan.

To configure redundant page detection:

1. Select the **Perform redundant page detection** check box.
2. Configure settings as described in the following table.

| Setting                              | Description                                                                                                                                                                                                                                                                                                                                                     |
|--------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Page Similarity Threshold (%)</b> | Indicates how similar two pages must be to be considered redundant. Enter a percentage from 1 to 100, where 100 is an exact match. The default setting is 95 percent.                                                                                                                                                                                           |
| <b>Tag attributes to include</b>     | Identifies the tag attributes to include in the page structure. Typically, tag attributes and their values are dropped when determining structure. Identifying tag attributes in this list adds those attributes and their values in the page structure. By default, <code>id</code> and <code>class</code> tag attributes are included. To add tag attributes: |

| Setting | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
|---------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|         | <ol style="list-style-type: none"><li>Type the attribute name in the <b>Tag item</b> box. Do not include tag brackets (&lt; and &gt;).</li><li>Click <b>ADD</b>.<br/>The tag attribute is added to the <b>Tag attributes to include</b> list.</li></ol> <div><b>Tip:</b> Certain sites may be primarily composed of one type of tag, such as &lt;div&gt;. Including these attributes creates a more rigid page match. Excluding these attributes creates a less strict match.</div> |

## Enabling SAST Correlation

SAST correlation correlates the static and dynamic findings for your web application in Fortify Software Security Center. Correlation allows you to see the static findings that were also found in a dynamic scan. It can help you to prioritize which issues to fix and help verify that those issues are not false positives.

To enable SAST correlation:

- Select **Enable SAST Correlation**.

## Enabling Scan Scaling

If the application is configured in a sensor pool that has scan scaling enabled, then the Scan Scaling check box is available on the Details page.

During a scan, script engines replay TruClient macros and run scripts to reveal the Document Object Model (DOM) of the application and events on the page. Scan scaling involves automatically creating multiple pools of these script engines in Kubernetes. In essence, it distributes the work of performing the scan across multiple script engines, thereby reducing the amount of time it takes to conduct the scan.

Scan scaling might be beneficial for applications that generally have long-running scans.

For more information, see ["Integrating with Kubernetes" on page 59](#).

If you enable scan scaling, then the scan inherits the scan scaling settings that are configured in the sensor pool. Scan scaling adjusts the number of script engine pools to equal the number of crawl and audit threads in the scan or to the maximum number specified in the sensor pool settings, whichever is lower. For more information, see ["Creating a DAST Sensor Pool" on page 153](#).

To enable scan scaling:

- In the **Scan Scaling** area, select **Use scan scaling**.

## Reviewing Scan Settings

You can review the settings you configured for the scan on the Review page.

After you review the settings, do one of the following:

- If the settings are correct, type a name for the settings in the **Name** box.
- If changes are needed, click the page name in the navigation pane, and then make corrections.

**Tip:** The names of pages that contain missing information or errors are displayed in red text in the navigation pane.

When the settings are correct, do one of the following:

- Save the settings to Fortify Software Security Center (For instructions, see ["Saving the Settings to Software Security Center" below](#).)
- Schedule a scan (For instructions, see ["Scheduling a Scan" below](#).)
- Run a scan (For instructions, see ["Running a Scan" on page 120](#).)
- Use the settings in the API (For instructions, see ["Using the Scan Settings in the DAST API" on page 120](#).)

## Saving the Settings to Software Security Center

You can save the settings as a template to Fortify Software Security Center. The settings are stored in XML format along with a JSON object with setting overrides.

To save as a template:

- Click **SAVE**.  
The file is saved to Fortify Software Security Center.

## Scheduling a Scan

You can use the settings for a scheduled scan to be run later.

To schedule a scan:

1. Click **SCHEDULE**.  
The SCHEDULE SCAN dialog box opens.
2. Type a name for the scheduled scan in the **Name** box.
3. Enter a date for the scan to run in the **Start Date** box.

**Tip:** To select a date from the calendar, click the calendar icon (📅).

4. Enter a time for the scan to start in the **Start Time** box.

**Note:** The schedule uses the time zone from your browser.

5. To schedule a recurring scan, in the **Pattern** section specify how often to run the scan according to the following table.

| To run... | Then...                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
|-----------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Daily     | a. Select <b>DAILY</b> .<br>b. Select a recurrence in the <b>Occur every ___ day</b> box.                                                                                                                                                                                                                                                                                                                                                                                              |
| Weekly    | a. Select <b>WEEKLY</b> .<br>b. Select a recurrence in the <b>Occur every ___ week</b> box.<br>c. Select the days to run each week.                                                                                                                                                                                                                                                                                                                                                    |
| Monthly   | a. Select <b>MONTHLY</b> .<br>b. Select a recurrence in the <b>Occur every ___ month</b> box.<br>c. Do one of the following: <ul style="list-style-type: none"> <li>Select <b>Occur on day</b> and enter a date in the box.</li> <li>Select <b>Occur on the</b>, and then select an interval from the <b>Interval</b> list and a day from the <b>Day</b> list.</li> </ul> <p><b>Note:</b> Interval options are First, Second, Third, Fourth, and Last.</p>                             |
| Yearly    | a. Select <b>YEARLY</b> .<br>b. Do one of the following: <ul style="list-style-type: none"> <li>Select <b>Occur on</b>, and then select a month from the <b>Month</b> list and enter a date in the <b>Day</b> box.</li> <li>Select <b>Occur on the</b>, and then select an interval from the <b>Interval</b> list, a day from the <b>Day</b> list, and a month from the <b>Month</b> list.</li> </ul> <p><b>Note:</b> Interval options are First, Second, Third, Fourth, and Last.</p> |

6. Under **Range**, do one of the following:
- To leave the recurrence open ended, select **Never ends**.
  - To set an end date, select **Ends by**, and then enter an end date in the **End Date** box or enter the number of occurrences after which to end in the **occurrence** box.

**Note:** Entering data into the **End Date** box automatically updates the **occurrence** box, and conversely.

7. Select a dynamic sensor from the **Sensor** list.

The list of sensors comes from the Fortify Software Security Center sensor pools. **Any Available** is the default.

8. (Optional) If you select a sensor that is currently unavailable, another sensor may conduct the scan instead. To ensure that the selected sensor conducts the scan, select **Use this sensor only**.
9. Click **OK**.

The scan schedule is added to the ScanCentral DAST database.

## Running a Scan

You can use the settings to run a scan immediately. To run a scan:

1. Click **RUN**.

The RUN SCAN dialog box opens.

**Note:** The name you gave to the settings appears in the **Name** field. You can type a different name in the field if needed.

2. Select a ScanCentral DAST sensor from the **Sensor** list.

The list of sensors comes from the Fortify Software Security Center sensor pools. **Any Available** is the default.

3. (Optional) If you select a sensor, but it is currently unavailable, another sensor may conduct the scan instead. To ensure that the selected sensor conducts the scan, select **Use this sensor only**.
4. Click **RUN**.

The scan is queued to run.

## Using the Scan Settings in the DAST API

You can use the scan settings to conduct a scan from the DAST API.

**Settings Identifier:** 8c27261d-8f0a-4ebe-897e-0538bf988c77

The above Settings Identifier can be used to run this scan template from any automation platform by performing a POST request against `http://[base-url]/api/scans/start-scan-cicd`. The request should include the Settings Identifier as the `cicdToken` in the JSON payload, and should include an Authorization header using an encoded `CIToken` from SSC | Administration | Users | Token Management. For more information, see `http://[base-url]/api/swagger`.

Copy CURL example to clipboard 

After saving the settings, the GUID in the **Settings Identifier** field provides a unique identifier for the settings. You can copy a cURL sample that includes this GUID to use in the API.

**Note:** This GUID is also known as the CICD Identifier.



If you copy the settings before saving, a placeholder is used for the settings ID. You must manually update the sample with the settings ID.

To copy the cURL sample:

- Click the copy to clipboard (📋) icon.

## Accessing the DAST API Swagger UI

Complete documentation—including detailed schema, parameter information, sample code, and functionality for testing endpoints—is included in the DAST API Swagger UI.

To access this information:

- In your browser, navigate to the DAST API URL using the following format:  
`http://<ScanCentral_DAST_API_URL>:<Port>/swagger/index.html`

## Using the Swagger UI

To use the Swagger UI:

1. On the Swagger UI page, click an endpoint category.
2. Click the endpoint method to use.  
Detailed schema, parameter information, sample code, and functionality for testing the endpoint appear.
3. (Optionally) To view a previous version of the DAST API, select the version from the **Select a definition** list.

**Important!** The latest version of the DAST API includes newer functionality than older versions. For this reason, Fortify recommends that you use the most recent version of the DAST API.

# Conducting an Automated Scan with FAST

Functional Application Security Testing (FAST) is a lightweight proxy that integrates with Fortify ScanCentral DAST. FAST provides a way to capture traffic from functional test scripts, such as those of Selenium, Cucumber, Curl, Postman, Unified Functional Test (UFT), and others. FAST turns the captured traffic into a workflow macro and sends it to ScanCentral DAST, which uses the macro and an existing scan settings identifier to conduct a scan.

## Installation Recommendation

**Important!** Do not install the Functional Application Security Testing (FAST) proxy on the same machine as Fortify WebInspect, a Fortify WebInspect installation running the sensor service in a DAST environment, or a Fortify WebInspect sensor being used with Fortify WebInspect Enterprise.

Fortify recommends that you install the FAST proxy on the machine that runs your functional tests, and then control the FAST proxy using the command line interface (CLI). This installation method allows you to integrate FAST CLI scripts into your functional testing automation pipeline.

The automation scenario involves three stages:

1. Start the FAST proxy using a CLI command.
2. Run functional tests through the FAST proxy.
3. Stop the FAST proxy using a CLI command.

## Before You Begin

You will need the following items to conduct an automated scan with FAST:

- The WIRCServerSetup64-ProxyOnly.msi installer
- An authentication token from Fortify Software Security Center
- A settings identifier, or GUID, for scan settings in ScanCentral DAST
- The ScanCentral DAST API URL

## Process Overview

The following table describes the process for conducting an automated scan with FAST.

| Stage | Description                                                                                                                                                                                                                                                                           |
|-------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1.    | Download and install the WIRCServerSetup64-ProxyOnly.msi. For more information, see <a href="#">"Downloading the FAST Installer" on the next page</a> .                                                                                                                               |
| 2.    | Obtain an authentication token of type <b>CIToken</b> from Fortify Software Security Center. For more information, see the <i>Micro Focus Fortify Software Security Center User Guide</i> .<br><br><b>Tip:</b> This token is passed as the value for the CIToken in the FAST command. |
| 3.    | Obtain a settings identifier from a scan settings file in ScanCentral DAST. For more information, see <a href="#">"Understanding the Scan Settings Detail Panel" on page 158</a> .<br><br><b>Tip:</b> This token is passed as the value for the CICDTOKEN in the FAST command.        |
| 4.    | On the machine where you installed the FAST proxy, open the command prompt and start the FAST proxy.<br><br><b>Tip:</b> The default installation directory for the FAST proxy is C:\Program Files\Micro Focus WIRC Server\Fast.exe.                                                   |

| Stage | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|-------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|       | <p>The following is an example of the command to start the proxy:</p> <pre>Fast.exe -p &lt;ListeningPort&gt; -u https://&lt;DAST_API_HOST IP&gt;:<br/>:&lt;port&gt;/api/ -CIToken &lt;Base64_encoded_token&gt; -CICDTOKEN<br/>&lt;Guid&gt;</pre> <p>You should see a response similar to the following:</p> <pre>0.0.0.0:&lt;ListeningPort&gt;<br/>Listening</pre> <p>For descriptions of these and other FAST command options, see <a href="#">"Understanding the FAST Options" below</a>.</p> |
| 5.    | <p>Run the traffic from your functional tests through the FAST proxy IP address and port specified in the start command.</p> <p><b>Note:</b> If your functional tests run on the same machine where you installed the FAST proxy, then you can use 127.0.0.1 for proxy address.</p>                                                                                                                                                                                                             |
| 6.    | <p>After traffic has been captured, stop the FAST proxy. The following is an example of the command to stop the proxy:</p> <pre>Fast.exe -p &lt;ListeningPort&gt; -s</pre>                                                                                                                                                                                                                                                                                                                      |
| 7.    | <p>The ScanCentral DAST instance specified in the &lt;DAST_API_HOST IP&gt;/api/ option automatically runs the scan with workflow overrides applied to the settings.</p>                                                                                                                                                                                                                                                                                                                         |

## Downloading the FAST Installer

The FAST installer, named `WIRCServerSetup64-ProxyOnly.msi`, is included in the Fortify Software Security Center download package. It is packaged in a ZIP file named `Dynamic_Addons.zip`. You can find this ZIP file in the directory where you downloaded the Fortify Software Security Center installation package.

## Understanding the FAST Options

The following table describes the FAST options.

| Option | Description                                                                                                                                                                                                                                                                                               |
|--------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| -h     | Displays the help.                                                                                                                                                                                                                                                                                        |
| -p     | <p>Specifies the listening port for the FAST proxy.</p> <p>Example:</p> <pre>-p &lt;port&gt;</pre>                                                                                                                                                                                                        |
| -n     | <p>Identifies the scan name that will appear in ScanCentral DAST.</p> <p>Example:</p> <pre>-n &lt;FAST_scan_name&gt;</pre>                                                                                                                                                                                |
| -u     | <p>Specifies the ScanCentral DAST URL.</p> <p>Example:</p> <pre>-u http://&lt;host ip&gt;:&lt;port&gt;/api/</pre>                                                                                                                                                                                         |
| -c     | <p>Optionally, exports the FAST proxy root CA certificate. If your https application performs certificate validation, you can use this option alone to install the certificate on your client application to avoid an untrusted certificate error.</p> <p>Example:</p> <pre>-c c:\fast_proxy_ca.crt</pre> |
| -f     | <p>Optionally when starting the proxy, specifies a regular expression for the allowed hosts for proxy capture.</p> <p>Example:</p> <pre>-f ".*\.&lt;hostname&gt;\.com"</pre>                                                                                                                              |
| -ps    | <p>Optionally when starting the proxy, configures an external proxy server when the target application does not have direct access from the machine where the FAST proxy is installed.</p> <p>Example:</p> <pre>-ps &lt;host ip&gt;:&lt;port&gt;</pre>                                                    |
| -s     | Stops listening.                                                                                                                                                                                                                                                                                          |

| Option     | Description                                                                              |
|------------|------------------------------------------------------------------------------------------|
|            | Example:<br><pre>-s -p &lt;port&gt;</pre>                                                |
| -q         | Runs the FAST proxy in quiet mode. This mode does not display messages.                  |
| -k         | Keeps local traffic files after capture.                                                 |
| -CICDToken | Specifies the Guid for the scan settings in ScanCentral DAST.                            |
| -CIToken   | Specifies the Base64-encoded authentication token from Fortify Software Security Center. |

# Chapter 5: Working with Scans

You can view the scans that are available in the ScanCentral DAST database in the Scans list. You can also start a new scan, refresh the scan list, delete scans, and download scans, settings, and logs. You can pause, stop, and resume scans that are currently running, and re-import completed scans that failed to import. You can view details about each scan in the scan detail panel.

## Accessing DAST Scans in Software Security Center

After you configure your Fortify ScanCentral DAST environment and enable DAST in the ADMINISTRATION view in Fortify Software Security Center, you can work with DAST scans directly in Fortify Software Security Center.

To access DAST scans in Fortify Software Security Center:

- Select **SCANCENTRAL** > **DAST**.

The scans list appears.

## User Role Determines Capabilities

Your user role and permissions in Fortify Software Security Center determine which tasks you can perform on applications and DAST scans, sensors, sensor pools, settings, and scan schedules. For more information, see ["Permissions in Fortify Software Security Center" on page 27](#).

## Understanding the Scans List

The Scans list table displays the scans that are available in the ScanCentral DAST database.

You can select the information you want to display, as well as customize other aspects of the table. For more information, see ["Working with Tables" on page 77](#).

The following table describes the columns of information provided for each scan.

| Column      | Description                                                                                                                                                                        |
|-------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Scan Id     | Indicates the integer ID in the ScanCentral DAST database for the scan.<br><br><b>Note:</b> Each scan is assigned an integer ID when it is added to the ScanCentral DAST database. |
| Application | Indicates the application that was selected when the scan was configured for                                                                                                       |

| Column                                                        | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|---------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                                               | the target URL.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| <b>Version</b>                                                | Indicates the version that was selected when the scan was configured for the target URL.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| <b>Name</b>                                                   | Indicates the name of the scan. This is the name that was assigned in the scan settings.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| <b>URL</b>                                                    | Identifies the target URL for the scan.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| <b>Critical</b><br><b>High</b><br><b>Medium</b><br><b>Low</b> | Indicates the number of findings for each severity category in the scan.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| <b>Started On</b>                                             | Indicates the date and time that the scan started. The start time is stored in the dynamic scan database as UTC time and is converted to the local machine's system time when displayed in the user interface.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| <b>Status</b>                                                 | <p>Indicates the current status of the scan. Possible statuses are as follows:</p> <ul style="list-style-type: none"> <li>• <b>Queued</b> – The scan has been submitted and is waiting for an available sensor.</li> <li>• <b>Pending</b> – The scan has been accepted by a sensor but is waiting for the sensor to acknowledge that it has accepted and started the scan.</li> <li>• <b>License Unavailable</b> – No license is available for a sensor to start the scan. The scan remains in the queue until a license is available for use.</li> </ul> <div style="background-color: #f0f0f0; padding: 10px; margin: 10px 0;"> <p><b>Note:</b> If the <b>Use this sensor only</b> option was not selected when the scan was submitted, the scan will use any available sensor in the assigned pool.</p> </div> <ul style="list-style-type: none"> <li>• <b>Paused</b> – The sensor might have accepted the scan but not yet started it, or the user might have paused the scan so that it is not in a running state.</li> <li>• <b>Paused Deny Interval</b> – The scan was running when a deny interval started. The scan is now paused until the deny interval ends. For more information, see <a href="#">"Working with Deny Intervals" on page 166</a>.</li> <li>• <b>Paused Scan Priority</b> – The scan was running when a higher-priority scan started. The scan is now paused until the higher-priority scan completes or another sensor accepts the scan. For more information, see <a href="#">"Understanding Advanced Scan Prioritization" on page 108</a> and <a href="#">"Configuring Scan Priority"</a></li> </ul> |

| Column | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
|--------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|        | <p><a href="#">on page 107.</a></p> <ul style="list-style-type: none"> <li>• <b>Running</b> – The sensor is actively conducting the scan.</li> <li>• <b>Running Deny Interval</b> – The scan was paused for a deny interval. The deny interval has ended and the sensor is actively conducting the scan. For more information, see <a href="#">"Working with Deny Intervals" on page 166.</a></li> <li>• <b>Running Scan Priority</b> – The scan was paused for a higher-priority scan. The higher-priority scan has completed or another sensor has accepted the scan and is actively conducting it. For more information, see <a href="#">"Understanding Advanced Scan Prioritization" on page 108</a> and <a href="#">"Configuring Scan Priority" on page 107.</a></li> <li>• <b>Complete</b> – The sensor has finished the scan and results are available. If the <b>Submit for triage</b> option was selected during scan configuration, then the scan has been published to Fortify Software Security Center, where you can perform audit analysis of the findings.</li> <li>• <b>Interrupted</b> – Something went wrong with the sensor that was conducting the scan. For example, the sensor heartbeat has expired.</li> <li>• <b>Unknown</b> – The scan failed to complete for an unknown reason.</li> <li>• <b>Importing</b> – The scan is being imported from the ScanCentral DAST database into Fortify Software Security Center.</li> <li>• <b>Import Failed</b> – Something went wrong during the import process.</li> <li>• <b>Failed to Start</b> – A sensor accepted the scan, but the scan failed to start. Possible reasons include: <ul style="list-style-type: none"> <li>• The Fortify Software Security Center DAST API is not running.</li> <li>• The connection to the ScanCentral DAST database has been lost.</li> <li>• Communication with the sensor has been lost.</li> <li>• The sensor failed to start.</li> <li>• The scan settings contain errors or invalid settings.</li> </ul> </li> <li>• <b>Pausing</b> – The user has paused the scan, which now displays this transitional state before changing to Not Running.</li> <li>• <b>Pausing Deny Interval</b> – The scan was running when a deny interval started. The scan now displays this transitional state before changing to Paused Deny Interval. For more information, see <a href="#">"Working with Deny Intervals" on page 166.</a></li> </ul> |



| Column          | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                 | <ul style="list-style-type: none"> <li>• <b>Pausing Scan Priority</b> – The scan was running when a higher-priority scan started. The scan now displays this transitional state before changing to Paused Scan Priority. For more information, see <a href="#">"Understanding Advanced Scan Prioritization" on page 108</a> and <a href="#">"Configuring Scan Priority" on page 107</a>.</li> <li>• <b>Resuming</b> – The user has resumed the scan, which now displays this transitional state before changing to Running.</li> <li>• <b>Resuming Deny Interval</b> – The scan was paused for a deny interval, but the deny interval has ended. The scan now displays this transitional state before changing to Running. For more information, see <a href="#">"Working with Deny Intervals" on page 166</a>.</li> <li>• <b>Resuming Scan Priority</b> – The scan was paused for a higher-priority scan. The scan now displays this transitional state before changing to <b>Running Scan Priority</b>. For more information, see <a href="#">"Understanding Advanced Scan Prioritization" on page 108</a> and <a href="#">"Configuring Scan Priority" on page 107</a>.</li> <li>• <b>Completing Scan</b> – The user has paused the scan and subsequently clicked <b>Complete</b>, which stops the scan at that point and processes it as an incomplete scan.</li> </ul> <div data-bbox="487 1081 1404 1182"> <p><b>Tip:</b> You can perform the same analysis and operations on an incomplete scan as you can a completed scan.</p> </div> <ul style="list-style-type: none"> <li>• <b>Resume Scan Queued</b> – The user resumed a paused scan and the scan is waiting for the sensor to become available.</li> <li>• <b>Resume Scan Queued Deny Interval</b> – The scan was paused due to a deny interval which has ended, so the scan is queued to be resumed.</li> <li>• <b>Resume Scan Queued Scan Priority</b> – The scan was paused for a higher-priority scan which has completed, so the scan is queued to be resumed. For more information, see <a href="#">"Understanding Advanced Scan Prioritization" on page 108</a> and <a href="#">"Configuring Scan Priority" on page 107</a>.</li> <li>• <b>Forced Complete</b> – The user paused a scan and subsequently clicked <b>Complete</b>. The scan completed with partial results.</li> <li>• <b>Forced Complete Deny Interval</b> – The scan was running when a deny interval started. The scan stopped and completed with partial results. For more information, see <a href="#">"Working with Deny Intervals" on page 166</a>.</li> </ul> |
| <b>Duration</b> | Indicates how long the scan ran before completion. For scans that are not                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |

| Column                 | Description                                                                                                                                                                   |
|------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                        | completed, the column displays the last known duration that was received from the sensor.                                                                                     |
| <b>Requests</b>        | Indicates the total number of requests sent during the scan.                                                                                                                  |
| <b>Macro Playbacks</b> | Indicates the number of times that macros have been played during the scan.                                                                                                   |
| <b>Priority</b>        | Indicates the scan priority from 0 through 10. For more information, see <a href="#">"Configuring Scan Priority" on page 107</a> .                                            |
| <b>Purge date</b>      | If data retention is enabled, indicates the date when the scan will be purged from the database. The number in parentheses indicates the number of days until the purge date. |

## Understanding the Scan Detail Panel

When you click a scan in the Scans list, the scan detail panel appears to the right. The scan detail panel provides options to view, download, and publish completed scans. For more information, see the following:

- ["Viewing Scan Results" on page 139](#)
- ["Downloading a File" on page 139](#)
- ["Publishing to Fortify Software Security Center" on page 136](#)

In addition to these options, the scan detail panel provides information about the scan, as described in the following paragraphs.

### Findings by Severity

The number of findings for each severity category in the scan appears at the top of the panel. From left to right, the severity categories are: Critical, High, Medium, and Low.



### Additional Scan Details

The following table describes the additional information that is provided in this panel.

| Item                              | Description                                                                                                                                                                                                    |
|-----------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Scan Id</b>                    | Indicates the integer ID in the ScanCentral DAST database for the scan.<br><br><b>Note:</b> Each scan is assigned an integer ID when it is added to the ScanCentral DAST database.                             |
| <b>Created On</b>                 | Indicates the date and time that the scan was created in the dynamic scan database and queued to be run.                                                                                                       |
| <b>Started On</b>                 | Indicates the date and time that the scan started. The start time is stored in the dynamic scan database as UTC time and is converted to the local machine's system time when displayed in the user interface. |
| <b>Scan Type</b>                  | Indicates the type of scan selected during scan configuration: <b>Standard Scan</b> , <b>Workflow-Driven Scan</b> , or <b>API Scan</b> .                                                                       |
| <b>Status</b>                     | Indicates the current status of the scan. For more information, see <a href="#">"Understanding the Scans List" on page 126</a> .                                                                               |
| <b>Status Update</b>              | Indicates the date and time that the sensor last reported its status.                                                                                                                                          |
| <b>Duration</b>                   | Indicates how long the scan ran before completion. For more information, see <a href="#">"Understanding the Scans List" on page 126</a> .                                                                      |
| <b>Has Site Authentication</b>    | Indicates whether site authentication was used to conduct the scan. Possible values are <b>true</b> and <b>false</b> .                                                                                         |
| <b>Has Network Authentication</b> | Indicates whether network authentication was used to conduct the scan. Possible values are <b>true</b> and <b>false</b> .                                                                                      |
| <b>Has API Auth Credentials</b>   | For API scans, indicates whether authentication was used to conduct the scan. Possible values are <b>true</b> and <b>false</b> .                                                                               |
| <b>Requests</b>                   | Shows the total number of requests that were sent during the scan.                                                                                                                                             |
| <b>Failed Requests</b>            | Shows the number of failed requests that occurred during the scan.                                                                                                                                             |
| <b>KB Sent / KB Received</b>      | Shows the total number of kilobytes sent and received during the scan.                                                                                                                                         |
| <b>Macro Playbacks</b>            | Indicates the number of times that macros have been played during the scan.                                                                                                                                    |
| <b>Priority</b>                   | Indicates the scan priority from 0 through 10. For more information, see <a href="#">"Configuring Scan Priority" on page 107</a> .                                                                             |

| Item                         | Description                                                                                                                                                                                   |
|------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Pool</b>                  | Identifies the pool to which the sensor belongs in Fortify Software Security Center.                                                                                                          |
| <b>Policy</b>                | Identifies the dynamic policy that was used to conduct the scan.                                                                                                                              |
| <b>Completed Date</b>        | Indicates the date and time that the scan finished. Available only for scans with a "Complete" status. For more information, see <a href="#">"Understanding the Scans List" on page 126</a> . |
| <b>Sensor</b>                | Indicates the name of the dynamic sensor that conducted the scan.                                                                                                                             |
| <b>Publish Status</b>        | Indicates whether the scan has been published to Fortify Software Security Center, where you can perform audit analysis of the findings.                                                      |
| <b>Publish Status Update</b> | Indicates the date and time that the scan was published to Fortify Software Security Center.                                                                                                  |
| <b>Scan Schedule</b>         | If the scan is the result of a schedule, indicates the name of the schedule.                                                                                                                  |
| <b>Purge date</b>            | If data retention is enabled, indicates the date when the scan will be purged from the database. The number in parentheses indicates the number of days until the purge date.                 |

## Working with Active Scans

You can pause, stop, resume, and re-import active scans in the Scans list. The actions that you can take depend on the current status of the scan. Active scans are those that do not show a status of Complete.

### Pausing a Scan

You can pause a scan that has a status of Running.

To pause a scan, do one of the following:

- In the scans list, click the pause icon (||) for the scan you want to pause.
- In the scan detail panel for a selected scan, click the pause icon (||).

The scan is paused.

### Stopping a Scan

You can stop a scan that has a status of Not Running, Interrupted, Unknown, or Queued.

To stop a scan, do one of the following:

- In the scans list, click the stop icon (■) for the scan you want to stop.
- In the scan detail panel for a selected scan, click the stop icon (■).

The scan is stopped.

## Resuming a Scan

You can resume a scan that has a status of Not Running or Interrupted.

To resume a scan, do one of the following:

- In the scans list, click the start icon (▶) for the scan you want to resume.
- In the scan detail panel for a selected scan, click the start icon (▶).

The scan is resumed.

## Re-importing a Scan

If the "Submit for triage" option was selected during scan configuration, the scan is imported to Fortify Software Security Center upon completion. Importing a scan could take some time, during which the status in the scans list is "Importing." The status changes to "Import Failed" if unsuccessful. You can attempt to re-import a scan with the "Import Failed" status.

To re-import a scan, do one of the following:

- In the scans list, click the retry icon (↺) for the scan you want to re-import.
- In the scan detail panel for a selected scan, click the retry icon (↺).

Another attempt is made to import the scan.

## Working with Alerts

Alerts occur when situations arise that *could* adversely affect scan performance or results. Alerts dealing with scan settings may provide you with suggested settings changes to improve performance of future scans. Other alerts may provide actionable information to help with a scan that is currently running.

**Important!** The alerts feature is provided as a technology preview.

## Technology Preview

Technology preview features are currently unsupported, may not be functionally complete, and are not suitable for deployment in production. However, these features are provided as a courtesy and

the primary objective is for the feature to gain wider exposure with the goal of full support in the future.

**Tip:** The alerts feature includes sample intervals and active intervals. Sample interval alerts may occur as often as once per minute on the ALERTS tab. Although these alerts may not indicate a functional issue with the scan, if the number of alerts received becomes problematic, contact Fortify Customer Support for assistance in disabling the alerts feature. For more information, see ["Preface" on page 17](#).

## Accessing Alerts


If a scan has an active and unacknowledged alert, it will be highlighted in orange in the Scans list. When you click the scan, the detail panel appears to the right with an ALERTS tab. The number of unacknowledged alerts appears in a red circle next to the ALERTS tab.

**Note:** Alerts are written to the scan log in near real time. However, you must refresh the page to view updates to the ALERTS tab.

To access the alerts:

1. Click the highlighted scan in the Scans list.

The scan detail panel, now with an ALERTS tab, appears to the right.



2. Click the **ALERTS** tab.

The alerts that the scan triggered are listed.

## Understanding the ALERTS Tab

The ALERTS tab displays the following categories of alerts:

- **NEW** – Lists the alerts that are active and have not yet been acknowledged. The number of alerts listed in this category should match the number displayed in the red circle.

- **ACTIVE** – Lists the alerts that are active and have been acknowledged. These alerts are still affecting the scan.
- **HISTORY** – Lists alerts that are no longer active, but that occurred during the scan. These alerts are no longer affecting the scan.

**Note:** After the scan has completed or been forced to complete, all alerts become historical alerts.

## Acknowledging New Alerts

To acknowledge an alert in the NEW category:

1. On the **ALERTS** tab, click the alert.  
A check mark appears next to the alert, indicating that the alert is selected.
2. Click **MARK AS ACKNOWLEDGED**.  
The alert is moved to the ACTIVE category.

**Important!** Acknowledging an alert does not resolve the issue that caused the alert. You must perform troubleshooting to determine the cause and resolve it. For more information, see ["Troubleshooting Alerts" on page 212](#).

## Managing the DAST Scans List

You can configure and submit a new scan, refresh the scans list, publish scans to Fortify Software Security Center, and delete scans from the scans list on the Scans page.

### Starting a New Scan

You can configure new settings or use existing settings, and then run a scan, which queues the scan in the scans list.

To configure settings or use existing settings for a new scan:

- Click **+ NEW SCAN**.  
The SETTINGS CONFIGURATION wizard opens.

### Refreshing the Scans List

You must manually refresh the scans list to see new scans that have been queued or scan statuses that have changed.

To view an updated list of scans:

- Click **REFRESH**.

## Publishing to Fortify Software Security Center

You can publish FPR artifacts to Fortify Software Security Center.

**Note:** If a scan does not have FPR artifacts, the publish icon is not available.

To publish FPR artifacts for a scan:

- Do one of the following:
  - In the scans list, click the publish icon (📤) for the scan whose FPR artifacts you want to publish.
  - In the scan detail panel for a selected scan, click the publish icon (📤).

The FPR artifacts are published to the Fortify Software Security Center database.

## Deleting a Scan

The scans displayed in the scans list come from the ScanCentral DAST database. You can delete scans from the database that you no longer need, depending on the scan status. Deleting scans from the database has no effect on scans that have already been published to Fortify Software Security Center.

You can delete scans that have a status of Complete, Queued, Pending, Failed to Start, Import Failed, Interrupted, Not Running, and Unknown.

To delete a scan, do one of the following:

- Select one or more check boxes for scans in the scans list, and then click **DELETE** at the bottom of the list.
- Select a scan to view the scan details, and then click **DELETE** at the bottom of the scan details panel.

## Using the Force Delete Option

In some cases, scans may not be deleted from the ScanCentral DAST database after you click the delete button. When this occurs, a user with administrator-level privileges can force the deletion of the scan. For more information, see ["Permissions in Fortify Software Security Center" on page 27](#).

To force delete a scan:

1. Select one or more check boxes for scans in the scans list, and then click **DELETE** at the bottom of the list.  
The Delete Scans dialog opens.
2. Select **Force delete**, and then click **OK**.

**Note:** The Force delete option is available only for users with administrator-level privileges.



## Downloading DAST Scans, Settings, and Logs

You can download a scan settings file (.xml format) from the ScanCentral DAST database to your local machine for any scan in the Scans list, except certain scans with the License Unavailable status. (For more information, see ["License Unavailable Scan Status" below](#).) Depending on the status of the associated scan, you can also download a log file, the site tree (.csv format), or the scan results (.scan or .fpr format).

**Note:** You must have Fortify WebInspect, Log Viewer, Site Explorer, Traffic Viewer, or another Fortify WebInspect tool on your local machine to work with the log file or scan results.

### Paused Scans

Anytime a scan is paused—by a user, due to scan priority, or due to deny interval—the partial scan results are uploaded to the ScanCentral DAST database and are available for download. After the partial results have been uploaded, the scan is deleted from the sensor.

ScanCentral DAST does not send the results to Fortify Software Security Center until the scan is complete or forced complete.

### License Unavailable Scan Status

If a scan has not started because a license is unavailable, then scan settings are not created. Therefore, no file types are available for download for these scans with the License Unavailable status.

However, if a scan is paused and then resumed, but no license is available, then scan settings, scan results, site tree, and scan log files are available for download for these scans with the License Unavailable status.

### File Types Available

The following table describes the file types that are available for download for each scan status.

| Scan Status     | File Types Available for Download |                                     |           |
|-----------------|-----------------------------------|-------------------------------------|-----------|
|                 | Scan Settings                     | Scan Result /<br>Site Tree /<br>FPR | Scan Logs |
| Complete        | x                                 | x                                   | x         |
| Completing Scan | x                                 |                                     |           |

| Scan Status                                                                                | File Types Available for Download |                                     |           |
|--------------------------------------------------------------------------------------------|-----------------------------------|-------------------------------------|-----------|
|                                                                                            | Scan Settings                     | Scan Result /<br>Site Tree /<br>FPR | Scan Logs |
| Failed to Start                                                                            | x                                 |                                     |           |
| Forced Complete<br>Forced Complete Deny Interval                                           | x                                 | x <sup>1</sup>                      | x         |
| Import Failed                                                                              | x                                 |                                     |           |
| Importing                                                                                  | x                                 |                                     |           |
| Interrupted                                                                                | x                                 |                                     | x         |
| Not Running                                                                                | x                                 |                                     |           |
| Paused<br>Paused Deny Interval<br>Paused Scan Priority                                     | x                                 | x <sup>2</sup>                      |           |
| Pausing<br>Pausing Deny Interval<br>Pausing Scan Priority                                  | x                                 |                                     |           |
| Pending                                                                                    | x                                 |                                     |           |
| Queued                                                                                     | x                                 |                                     |           |
| Resume Scan Queued<br>Resume Scan Queued Deny Interval<br>Resume Scan Queued Scan Priority | x                                 |                                     |           |
| Resuming<br>Resuming Deny Interval<br>Resuming Scan Priority                               | x                                 |                                     |           |

<sup>1</sup>Scans with a Forced Complete status might not have scan results or a site tree, depending on when the scan was stopped. For this reason, Scan Result and Site Tree might not be available file types to download.

<sup>2</sup>Scans with a Paused status do not include an FPR and cannot be published to Fortify Software Security Center.

| Scan Status                                               | File Types Available for Download |                                     |           |
|-----------------------------------------------------------|-----------------------------------|-------------------------------------|-----------|
|                                                           | Scan Settings                     | Scan Result /<br>Site Tree /<br>FPR | Scan Logs |
| Running<br>Running Deny Interval<br>Running Scan Priority | x                                 |                                     |           |
| Unknown                                                   | x                                 |                                     |           |

For more information about the scan statuses, see ["Understanding the Scans List" on page 126](#).

## Downloading a File

To download a file for a scan:

1. Do one of the following:
  - In the scans list, click the download icon (📄) for the scan whose file you want to download.
  - In the scan detail panel for a selected scan, click the download icon (📄).

The DOWNLOAD dialog box opens.

2. Select the file type to download from the list.

**Tip:** To view the scan results in Site Explorer, you must select **Scan Result**.

**Note:** The available file types to download depend on the scan status. For details, see ["File Types Available" on page 137](#).

3. Click **DOWNLOAD**.

By default, the file is downloaded to the folder on your local machine that is specified in your browser settings for downloads.

## Viewing Scan Results

You can examine the scan results for scans with a status of Complete or Forced Complete. For more information about scan statuses, see ["Understanding the Scans List" on page 126](#).

To view scan results:

1. In the Scans list, click the scan that you want to view.  
The scan detail panel appears to the right.
2. Click **VIEW SCAN**.

The scan opens in a new tab with the scan name displayed.




**Tip:** If you run a scan in ScanCentral DAST, the findings are automatically imported. If the completed scan fails to import or if the completed scan was not conducted in ScanCentral DAST, the button will be labeled **IMPORT FINDINGS**. When this occurs, you must import the findings before you can view the scan.

## Working with the Site Tree

By default, the Site Tree displays an unfiltered tree view of all traffic that was generated during the scan. The tree includes a list of hosts and all sub-directories within those hosts. In this view, you can select a top-level host and expand the sub-directories to examine the requests and responses that occurred at each level. To display the requests that were made to a resource, select the resource in the Site Tree.


### Site Tree Icons

The following table identifies the icons that appear in the Site Tree.

| Icon                                                                                | Name        | Represents                                                                                                                                                          |
|-------------------------------------------------------------------------------------|-------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|   | Server/host | The top level of your site's tree structure<br><b>Note:</b> You might have multiple server/host icons in your site tree representing different protocols and ports. |
|  | Folder      | A directory                                                                                                                                                         |
|  | Page        | A file                                                                                                                                                              |

### Using Breadcrumbs

When you select a resource in the Site Tree, breadcrumbs appear at the top of the Findings and Traffic tables, similar to the sample shown here.



Breadcrumbs provide a visual aid that indicates the location of the resource within the website's hierarchy. You can click a breadcrumb in the path to view findings or traffic for that resource.

To filter the findings or traffic for a specific resource listed in the breadcrumbs:

- Click the resource in the breadcrumbs.

For example, if you want to view all findings or traffic for the `extjs` folder shown in the previous image, click **extjs**.

The selected resource becomes the final breadcrumb and the Findings and Traffic tables are updated to show only data for the selected resource.

To remove the filter completely:

- Click the clear breadcrumbs icon (✕) at the end of the breadcrumbs.

The breadcrumbs are removed and the findings and traffic data are no longer filtered.

## Understanding the Findings Table

The Findings table lists information about each vulnerability discovered during an audit of your web presence. Each row (or session) in the Findings table represents a single finding.

You can select the information you want to display, as well as customize other aspects of the table. For more information, see ["Working with Tables" on page 77](#).

### Available Columns

The following table describes the available columns.

| Column                 | Description                                                                                                                                                                            |
|------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Severity</b>        | A relative assessment of the vulnerability, ranging from low to critical.                                                                                                              |
| <b>Check ID</b>        | The identification number of a Fortify WebInspect probe that checks for the existence of a specific vulnerability. For example, Check ID 742 tests for database server error messages. |
| <b>Name</b>            | A Fortify WebInspect probe for a specific vulnerability, such as Cross-site Scripting, Unencrypted Log-in Form, and so on.                                                             |
| <b>URL</b>             | The hierarchical path to the resource along with parameters.                                                                                                                           |
| <b>Parameter Name</b>  | The name of the vulnerable parameter.                                                                                                                                                  |
| <b>Parameter Value</b> | The value assigned to the vulnerable parameter.                                                                                                                                        |
| <b>CWE</b>             | The Common Weakness Enumeration identifier(s) associated with the vulnerability.                                                                                                       |

| Column     | Description                                                                                                                                                                                                             |
|------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Method     | The HTTP request method used for the attack.                                                                                                                                                                            |
| Kingdom    | The vulnerability category from the Seven Pernicious Kingdoms taxonomy for ordering and organizing vulnerabilities. For more information, see <a href="https://vulncat.fortify.com/">https://vulncat.fortify.com/</a> . |
| Session ID | The unique session ID for the request and response in the DAST database.                                                                                                                                                |

## Working with Findings

You can view the vulnerabilities discovered during the scan on the Findings tab, which includes the Findings table and the Vulnerability Description, HTTP, and Steps tabs.

**Tip:** Remember that selecting a resource in the Site Tree filters the data to that resource in the Findings table. For more information, see ["Working with the Site Tree" on page 140](#).

### Viewing the Vulnerability Description

The Vulnerability Description tab displays content from SecureBase related to the selected vulnerability. In addition to a detailed description of the vulnerability, the SecureBase content might include information on how to verify the issue, possible implications if the issue is not fixed, remediation information, and links to additional references.

To view the Vulnerability Description:

- Select a finding in the **FINDINGS** table.  
The VULNERABILITY DESCRIPTION tab displays information about the vulnerability.

### Viewing the Request and Response

The HTTP tab includes the request and response session details for the selected vulnerability.

To view the request and response:

1. Select a finding in the **FINDINGS** table.
2. Click the **HTTP** tab.

### Viewing Steps

The Steps tab displays the route taken by the sensor to arrive at the session selected in the Findings table. Beginning with the parent session (at the top of the list), the sequence reveals the subsequent URLs visited and provides details about the scan methodology.

To view the steps:

1. Select a finding in the **FINDINGS** table.
2. Click the **Steps** tab.

The STEPS table displays the route taken by the sensor to arrive at the session selected.

To close the Steps tab, do one of the following:

- Press the **ESC** key.
- Click the **Steps** tab again.

## Understanding the Traffic Table

The Traffic table displays all traffic generated during the scan, enabling you to explore the traffic for the entire scan.

You can select the information you want to display, as well as customize other aspects of the table. For more information, see ["Working with Tables" on page 77](#).

### Available Columns

The following table describes the available columns.

| Column               | Description                                                                                                                      |
|----------------------|----------------------------------------------------------------------------------------------------------------------------------|
| <b>Request Start</b> | The date and time the sensor started sending the request.                                                                        |
| <b>Request End</b>   | The date and time the sensor finished sending the request.                                                                       |
| <b>Host</b>          | The top-level URL of the target web site.                                                                                        |
| <b>Port</b>          | The port number over which the requests were sent.                                                                               |
| <b>Path</b>          | The hierarchical path to the resource on the web server.                                                                         |
| <b>Method</b>        | The HTTP request method used, such as GET, POST, and PUT.                                                                        |
| <b>Status</b>        | The HTTP status code returned from the host. For more information, see <a href="#">"HTTP Status Codes" on page 229</a> .         |
| <b>Category</b>      | Broadly defines the source of the request, such as audit, crawl, and so forth. This information might be useful for diagnostics. |
| <b>Sequence</b>      | The order in which the request appeared in the traffic.                                                                          |
| <b>Scheme</b>        | The protocol used to make the request, such as <code>http://</code> or <code>https://</code> .                                   |

| Column                          | Description                                                                                                                                                                                                                                                                                                                                                             |
|---------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Error Code</b>               | An error code that indicates the request failed at the TCP/IP level, such as the connection closed or a time out occurred.                                                                                                                                                                                                                                              |
| <b>Request Length</b>           | The request length, expressed in bytes.                                                                                                                                                                                                                                                                                                                                 |
| <b>Response Length</b>          | The response length, expressed in bytes.                                                                                                                                                                                                                                                                                                                                |
| <b>Scan.Sid</b>                 | The unique session ID for the request and response in the DAST database.                                                                                                                                                                                                                                                                                                |
| <b>Scan.Psid</b>                | The unique parent session ID for the request and response in the DAST database.                                                                                                                                                                                                                                                                                         |
| <b>Scan.Sessiontype</b>         | Identifies why there is a session in the database, such as crawl, attack, triggered macro, and so on.                                                                                                                                                                                                                                                                   |
| <b>Scan.Attacktype</b>          | Identifies what the sensor did in the request, such as cookie injection, query injection, and so on.                                                                                                                                                                                                                                                                    |
| <b>Scan.Checkid</b>             | The identification number of a Fortify WebInspect probe that checks for the existence of a specific vulnerability.                                                                                                                                                                                                                                                      |
| <b>Scan.Attacksequence</b>      | Shows the order of requests sent by the audit engine. This information might be useful for debugging a specific engine.                                                                                                                                                                                                                                                 |
| <b>Scan.Engine</b>              | Name of the audit engine that sent the request.                                                                                                                                                                                                                                                                                                                         |
| <b>Scan.Attackparamdesc</b>     | Name of the parameter being attacked in the request.                                                                                                                                                                                                                                                                                                                    |
| <b>Scan.Attackparamindex</b>    | <p>Identifies a parameter by index instead of by name. This might be useful because not all parameters have names and in some applications names are duplicated.</p> <p>Index of the parameter. The index count starts at 0, so if your site has 10 cookies and the audit engine attacked the third one, then the parameter index of the attacked cookie will be 2.</p> |
| <b>Scan.Attackparamsubindex</b> | When we break up something smaller than Post and Query and cookie, such as a JSON document.                                                                                                                                                                                                                                                                             |
| <b>Scan.Crawltype</b>           | Identifies the type of crawl, such as from script execution, forms submission, dynamically generated URLs, HREF, and so forth.                                                                                                                                                                                                                                          |



| Column                    | Description                                               |
|---------------------------|-----------------------------------------------------------|
| <b>Scan.Attributename</b> | Used for diagnostics to help identify the request source. |
| <b>Scan.Format</b>        | Used for diagnostics to help identify the request source. |
| <b>Scan.Linkkind</b>      | Used for diagnostics to help identify the request source. |
| <b>Scan.Locations</b>     | Used for diagnostics to help identify the request source. |
| <b>Scan.Source</b>        | Used for diagnostics to help identify the request source. |
| <b>Scan.Nodename</b>      | Used for diagnostics to help identify the request source. |

## Working with Traffic

You can view the traffic generated during the scan on the Traffic tab, which includes the Traffic table and the HTTP, Parameters, and Steps tabs.

**Tip:** Remember that selecting a resource in the Site Tree filters the data to that resource in the Traffic table. For more information, see ["Working with the Site Tree" on page 140](#).

### Viewing the Request and Response

The HTTP tab includes the request and response session details for the selected vulnerability.

To view the request and response:

1. Select a session in the **TRAFFIC** table.
2. Click the **HTTP** tab.

In the REQUEST area, the attack is highlighted. In the RESPONSE area, the vulnerability is highlighted.

### Viewing Parameters

You can view the Type, Name, and Value for parameters used in a traffic session. The Parameters detail view displays a table with one record for each cookie or query string used in the traffic session.

A parameter can be one of the following:

- Cookie data
- A query string submitted as part of the URL in the HTTP request (or contained in another header)
- Data submitted using the Post method (such as `set_<parametername>`)

To view the parameter details for a session:

1. Select a session in the **TRAFFIC** table.
2. Click the **PARAMETERS** tab.

The PARAMETERS table displays the parameters used in the selected session.

## Viewing Steps

The Steps tab displays the route taken by the sensor to arrive at the session selected in the Traffic table. Beginning with the parent session (at the top of the list), the sequence reveals the subsequent URLs visited and provides details about the scan methodology.

To view the steps:

1. Select a session in the **TRAFFIC** table.
2. Click the **Steps** tab.


The STEPS table displays the route taken by the sensor to arrive at the session selected.

To close the Steps tab, do one of the following:

- Press the **ESC** key.
- Click the **Steps** tab again.

## Understanding SPA Coverage

The single-page application (SPA) Coverage view is available only if the scan includes SPA events. This view displays the elements in the page that the crawler interacted with during the crawl. The SPA events are filtered based on what you select in the Site Tree.



| Url                                                     | Name         | Selector                                              |
|---------------------------------------------------------|--------------|-------------------------------------------------------|
| http://zero.webappsecurity.com:80/admin/currencies.html | Users        | /html/body/div[1]/div[2]/div/div[2]/div[1]/ul/li[3]/a |
| http://zero.webappsecurity.com:80/admin/currencies.html | Add Currency | //a[@id="add_currency"]                               |
| http://zero.webappsecurity.com:80/admin/currencies.html | Currencies   | /html/body/div[1]/div[2]/div/div[2]/div[1]/ul/li[4]/a |
| http://zero.webappsecurity.com:80/admin/currencies.html | Signin       | //button[@id="signin_button"]                         |
| http://zero.webappsecurity.com:80/admin/currencies.html | Home         | /html/body/div[1]/div[2]/div/div[2]/div[1]/ul/li[1]/a |

The SPA Coverage view lists the URLs where the elements were discovered, along with the following additional information:

- **Name** – The visible text, symbol, link, HTML tag name, or other UI information related to the element.
- **Selector** – The XPath location of the element in the page. This is used to find and perform operations on the element.

For more information, see ["Scanning Single-page Applications" on page 110](#).

# Chapter 6: Working with Sensors

You can view all of the sensors that are stored in the ScanCentral DAST database in the Sensors list. You can view a sensor's status and whether it is enabled, as well as other details, in the sensor detail panel. From the sensor detail panel, you can also enable or disable sensors.

## Accessing DAST Sensors in Software Security Center

After you configure your Fortify ScanCentral DAST environment and enable DAST in the ADMINISTRATION view in Fortify Software Security Center, you can work with DAST sensors directly in Fortify Software Security Center.

To access DAST sensors in Fortify Software Security Center:

1. Select **SCANCENTRAL > DAST**.

The scans list appears.

2. In the left panel, select **Sensors**.

The Sensors list appears.

## User Role Determines Capabilities

Your user role and permissions in Fortify Software Security Center determine which tasks you can perform on applications and DAST scans, sensors, sensor pools, settings, and scan schedules. For more information, see ["Permissions in Fortify Software Security Center" on page 27](#).

## Understanding the Sensor List

The Sensors list table shows all sensors that are stored in the ScanCentral DAST database.

You can select the information you want to display, as well as customize other aspects of the table. For more information, see ["Working with Tables" on page 77](#).

The following table describes the columns of information provided for each sensor.

| Column                 | Description                                                                 |
|------------------------|-----------------------------------------------------------------------------|
| <b>Name</b>            | Identifies the sensor name.                                                 |
| <b>Pool</b>            | Identifies the pool to which the sensor belongs.                            |
| <b>Current Scan ID</b> | Indicates the integer ID in the ScanCentral DAST database for the scan that |

| Column         | Description                                                                                                                                          |
|----------------|------------------------------------------------------------------------------------------------------------------------------------------------------|
|                | <p>the sensor is actively conducting.</p> <p><b>Note:</b> Each scan is assigned an integer ID when it is added to the ScanCentral DAST database.</p> |
| <b>Enabled</b> | Indicates whether the sensor is enabled to perform scans. Possible values are <b>true</b> and <b>false</b> .                                         |
| <b>Status</b>  | Indicates the current status of the sensor. Possible values are <b>Online</b> and <b>Offline</b> .                                                   |

## Understanding the Sensor Detail Panel

When you select a sensor in the Sensors list, the sensor detail panel appears. The sensor details show the sensor's status and whether it is enabled. The following table describes the additional information that is provided for the selected sensor.

| Item                       | Description                                                                                                                                                                                                                      |
|----------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>IP Address</b>          | Identifies the IP address assigned to the sensor when the image was started.                                                                                                                                                     |
| <b>Pool</b>                | Identifies the pool to which the sensor belongs.                                                                                                                                                                                 |
| <b>Current Scan ID</b>     | <p>Indicates the integer ID in the ScanCentral DAST database for the scan that the sensor is actively conducting.</p> <p><b>Note:</b> Each scan is assigned an integer ID when it is added to the ScanCentral DAST database.</p> |
| <b>Last Connect</b>        | Indicates the last time the sensor sent an update on its status to the scanner service.                                                                                                                                          |
| <b>Operating System</b>    | Indicates the operating system of the VM or machine that is running the Docker container. Currently, Microsoft Windows is the only supported operating system.                                                                   |
| <b>Version</b>             | Indicates the operating system version of the VM or machine that is running the Docker container.                                                                                                                                |
| <b>Application Version</b> | Indicates the version of ScanCentral DAST Sensor Service, whether running as a container or as a service with a classic Fortify WebInspect installation.                                                                         |

| Item                      | Description                                                              |
|---------------------------|--------------------------------------------------------------------------|
| <b>WebInspect Version</b> | Indicates the version of Fortify WebInspect being used to conduct scans. |

## Enabling or Disabling Sensors

The Sensors list shows all sensors that are stored in the ScanCentral DAST database. Depending on your permissions in Fortify Software Security Center, you can enable and disable the sensors in the list.

### Facts About Disabled Sensors

You should understand the following facts that apply to disabling a sensor:


- If a sensor is disabled, it is still online but cannot process any new scans.
- If a sensor is currently running a scan and you disable the sensor, the scan that is running will finish and then the sensor will not process any more scans until it is enabled again.

### Enabling or Disabling a Sensor

To enable or disable a sensor:

1. Select the sensor in the list.

The sensor details panel appears.



2. Do one of the following:
  - To enable the sensor, toggle the switch to **Enabled**.
  - To disable the sensor, toggle the switch to **Disabled**.

# Chapter 7: Working with Sensor Pools

A sensor pool provides a way for you to license your ScanCentral DAST sensors with a specific license pool in the License and Infrastructure Manager (LIM) and designate which applications each sensor can scan.

## Accessing DAST Sensor Pools in Software Security Center

After you configure your Fortify ScanCentral DAST environment and enable DAST in the ADMINISTRATION view in Fortify Software Security Center, you can work with DAST sensor pools directly in Fortify Software Security Center.

To access DAST sensor pools in Fortify Software Security Center:

1. Select **SCANCENTRAL > DAST**.  
The scans list appears.
2. In the left panel, select **Sensor Pools**.  
The Sensors Pools list appears.

## User Role Determines Capabilities

Your user role and permissions in Fortify Software Security Center determine which tasks you can perform on applications and DAST scans, sensors, sensor pools, settings, and scan schedules. For more information, see ["Permissions in Fortify Software Security Center" on page 27](#).

## Understanding the Sensor Pools List

The Sensor Pools list table displays the ScanCentral DAST sensor pools that are configured in the ScanCentral DAST database.

You can select the information you want to display, as well as customize other aspects of the table. For more information, see ["Working with Tables" on page 77](#).

The following table describes the columns of information provided for each pool.

| Column | Description                             |
|--------|-----------------------------------------|
| Name   | Identifies the name of the sensor pool. |



| Column             | Description                                                                                                                                                                                                                                             |
|--------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Description</b> | Provides a description of the pool.                                                                                                                                                                                                                     |
| <b>LIM Pool</b>    | Identifies the license pool that is configured in the License and Infrastructure Manager (LIM).                                                                                                                                                         |
| <b>Default</b>     | <p>Indicates whether the pool is designated as the default pool. Possible values are <b>true</b> or <b>false</b>.</p> <p>If you spin up a new sensor and do not assign it to a pool, the sensor will be assigned to the default pool automatically.</p> |

## Understanding the Pool Detail Panel

When you select a pool in the Sensor Pools list, the pool detail panel appears. If the pool you select is the default pool, it will be identified as DEFAULT at the top of the pool detail panel. Otherwise, an option is available to make the pool the default pool. For more information, see ["Managing Sensor Pools" on page 155](#).

The following table describes the additional information provided for each pool.

| Item                         | Description                                               |
|------------------------------|-----------------------------------------------------------|
| <b>ASSIGNED APPLICATIONS</b> | Lists the applications that sensors in the pool can scan. |
| <b>ASSIGNED SENSORS</b>      | Lists the sensors that are assigned to the pool.          |

## Creating a DAST Sensor Pool

When you create a ScanCentral DAST sensor pool, you can assign a single sensor or group of sensors to specific applications. These assignments determine which sensors can scan each application in your environment.

To create a new sensor pool:

1. On the **Sensor Pools** page, click **+ NEW POOL**.

The SENSOR POOL - CREATE dialog box opens with the Getting Started page in view.

2. In the **Name** box, type a name for the pool.
3. In the **Description** box, type a description for the pool.

4. In the **Pool** list, select the License and Infrastructure Manager (LIM) license pool for licensing the sensors in the pool.
5. In the **Password** box, type the password associated with the LIM license pool.
6. To verify that you can connect to the LIM with the license pool and password, click **VALIDATE**.
7. Click **Sensors** in the menu or click **NEXT**.  
The SENSORS list appears.
8. Select one or more sensors to add to the pool.

**Important!** If you are creating a pool to allow scan scaling, make sure that you select sensors that have been configured for integration with Kubernetes. For more information, see ["Integrating with Kubernetes" on page 59](#).

The sensors are added to the SENSORS SELECTED list.

9. Click **Applications** in the menu or click **NEXT**.  
The APPLICATIONS list appears.
10. Select one or more applications to add to the pool.  
The applications are added to the APPLICATIONS SELECTED list.
11. Click **Scan Scaling** in the menu or click **NEXT**.

**Important!** Scan Scaling is optional. However, to configure Scan Scaling, you must first configure a WebInspect Script Engine (WISE) cluster in Kubernetes. For more information, see ["Integrating with Kubernetes" on page 59](#).

12. To configure Scan Scaling, continue as follows:
  - a. Slide the Disabled-Enabled toggle to **Enabled**.
  - b. In the **Host** box, enter the Kubernetes ingress host URL that was configured when the WISE cluster was deployed in Kubernetes. It uses the WebSocket protocol such as `ws://<wise-cluster-ingress-hostname>/`.
  - c. In the **Authorization Token** box, enter the token used to authenticate the sensor to use the WISE Kubernetes cluster.

**Tip:** This user-specified token was generated by the `--set wise.authtoken` command during the WISE Helm installation.

- d. Do one of the following:
  - To allow ScanCentral DAST to scale the number of script engine pools to equal the number of crawl and audit threads in the scan, select **Automatically set script engines per scan** check box.
  - To specify a maximum number of script engine pools per scan, clear the **Automatically set script engines per scan** check box, and then enter a number in the **Maximum script engines per scan** box.

**Tip:** If your Kubernetes cluster has limited resources, setting the **Maximum script engines per scan** limits the amount of resources used in scan scaling and avoids having one or two scans consume all of your resources.

13. Click **Review** in the menu or click **NEXT**.  
Review your sensor pool settings.
14. Click **SAVE**.  
The pool is added to the Sensor Pools list.

## Managing Sensor Pools

You can edit and delete pools, refresh the pools list, and change the default pool on the Sensor Pools page.

### Facts About Managing Sensor Pools

You should understand the following facts about managing sensor pools:

- You cannot delete the default sensor pool.
- If you delete a sensor pool, all sensors and applications assigned to that pool will be reassigned to the default pool.

### Editing a Sensor Pool

To edit a sensor pool:

1. In the Sensor Pools list, select the pool to edit.  
The pool detail panel appears.
2. Click **EDIT**.  
The pool settings appear in a dialog box that is similar to the CREATE NEW POOL dialog box.
3. To make edits, follow the procedure listed in ["Creating a DAST Sensor Pool" on page 153](#).

### Refreshing the Pools List

Generally, the changes that you make to the sensor pools appear right away on the Sensor Pools page. However, if other users have access to the same sensor pools, any changes they make will not be updated in your view. To see such changes, you can manually refresh the pools list.

To view an updated pools list:

- Click **REFRESH**.

## Deleting a Sensor Pool

To delete a sensor pool, do one of the following:

- Select one or more check boxes for pools in the Sensor Pools list, and then click **DELETE** at the bottom of the list.
- Select a pool to view the pool details, and then click **DELETE** at the bottom of the pool details panel.

**Tip:** You cannot delete the default sensor pool.

## Changing the Default Sensor Pool

The first pool you configure becomes the default pool. If you have only one pool configured, it will always be the default pool. If you have multiple pools configured, however, you can change the default pool at any time.

To change the default pool:

- Select a pool to view the pool details, and then select **Make default** in the pool details panel.

# Chapter 8: Working with Scan Settings

You can view the scan settings that are available in the ScanCentral DAST database in the settings list. You can view the application, version, and URL that are configured for each settings file, as well as other details, in the settings detail panel. From the settings list, you can also configure new scan settings, edit existing settings, download settings, and delete settings.

## Accessing DAST Scan Settings in Software Security Center

After you configure your Fortify ScanCentral DAST environment and enable DAST in the ADMINISTRATION view in Fortify Software Security Center, you can work with DAST scan settings directly in Fortify Software Security Center.

To access DAST scan settings in Fortify Software Security Center:

1. Select **SCANCENTRAL > DAST**.  
The scans list appears.
2. In the left panel, select **Settings List**.  
The settings list appears.

## User Role Determines Capabilities

Your user role and permissions in Fortify Software Security Center determine which tasks you can perform on applications and DAST scans, sensors, sensor pools, settings, and scan schedules. For more information, see ["Permissions in Fortify Software Security Center" on page 27](#).

## Understanding the Scan Settings List

The settings list table displays the scan settings that are available in the ScanCentral DAST database.

You can select the information you want to display, as well as customize other aspects of the table. For more information, see ["Working with Tables" on page 77](#).

The following table describes the columns of information provided for each settings file in the list.

| Column      | Description                                                                                                                     |
|-------------|---------------------------------------------------------------------------------------------------------------------------------|
| <b>Name</b> | Indicates the name of the settings file. This is the name that was assigned at the time the settings were configured and saved. |

| Column                 | Description                                                                                                                                                                                                      |
|------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Application</b>     | Indicates the application for which the settings apply.                                                                                                                                                          |
| <b>Version</b>         | Indicates the version for which the settings apply.                                                                                                                                                              |
| <b>Scan Type</b>       | Indicates the type of scan to be conducted using the settings. Types are: <ul style="list-style-type: none"><li>• <b>Standard Scan</b></li><li>• <b>Workflow-driven Scan</b></li><li>• <b>API Scan</b></li></ul> |
| <b>Modified</b>        | Indicates the date and time that the settings were created, or if edited, the last date and time that the settings were changed.                                                                                 |
| <b>CICD identifier</b> | Identifies the settings identifier GUID that was assigned to the settings.                                                                                                                                       |

## Understanding the Scan Settings Detail Panel

When you click a settings file in the settings list, the settings detail panel appears to the right. The application, version, and URL that are configured in the scan settings are listed at the top of the panel. The following table describes the additional information that is provided in this panel.

| Item              | Description                                                                                                                                                                                                      |
|-------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Created</b>    | Indicates the date and time that the settings were saved.                                                                                                                                                        |
| <b>Modified</b>   | Indicates the date and time that the settings were created, or if edited, the last date and time that the settings were changed.                                                                                 |
| <b>Type</b>       | Indicates the type of scan to be conducted using the settings. Types are: <ul style="list-style-type: none"><li>• <b>Standard Scan</b></li><li>• <b>Workflow-driven Scan</b></li><li>• <b>API Scan</b></li></ul> |
| <b>Policy</b>     | Identifies the dynamic policy to be used to conduct the scan.                                                                                                                                                    |
| <b>User Agent</b> | Indicates the user agent one or more of the following: <ul style="list-style-type: none"><li>• <b>Chrome</b></li><li>• <b>Chrome (Mobile Android)</b></li><li>• <b>Custom</b></li></ul>                          |

| Item                          | Description                                                                                                                                                                                                                                                                           |
|-------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                               | <ul style="list-style-type: none"><li>• <b>Default</b></li><li>• <b>Edge</b></li><li>• <b>Safari</b></li><li>• <b>Safari (Mobile IOS)</b></li></ul> <p><b>Note:</b> Default uses the user agent that is defined in Fortify WebInspect.</p>                                            |
| <b>Login Macro</b>            | If applicable, indicates the file name of the login macro specified in the settings.                                                                                                                                                                                                  |
| <b>Network Auth</b>           | Indicates whether network authentication is specified in the settings.                                                                                                                                                                                                                |
| <b>Allowed Hosts</b>          | If applicable, lists the first (or only) allowed host from the settings file. If the settings include more than one allowed host, a plus sign and number indicate the number of additional allowed hosts. <p><b>Tip:</b> To view the additional allowed hosts, click <b>EDIT</b>.</p> |
| <b>SPA Option</b>             | Indicates how SPA support is configured in the settings.                                                                                                                                                                                                                              |
| <b>Enable Traffic Monitor</b> | Indicates whether Traffic Monitor is enabled in the settings.                                                                                                                                                                                                                         |
| <b>Submit for Triage</b>      | Indicates whether a scan run from these settings is uploaded to Fortify Software Security Center upon completion.                                                                                                                                                                     |
| <b>SETTINGS IDENTIFIER</b>    | Indicates the settings identifier GUID that was assigned to the settings.                                                                                                                                                                                                             |

## Managing Scan Settings

You can configure new scan settings, edit existing settings, download settings, and delete settings from the settings list.

### Creating New Settings

You can access the Settings Configuration wizard from the settings list and create new settings.

To create new settings:

- Click **+ NEW SETTINGS**.

The Settings Configuration wizard opens.

## Editing Settings

You can access the Settings Configuration wizard from the settings detail panel and edit settings.

To edit settings:

1. In the **SETTINGS List**, select the settings to edit.

The settings detail panel appears.

2. In the settings detail panel, click **EDIT**.

The Settings Configuration wizard opens pre-populated with the selected scan settings.

## Downloading Settings

You can download settings from the ScanCentral DAST database to your local machine.

**Note:** The download option may not be immediately available for newly created settings. The Settings Configuration wizard uses the Fortify WebInspect API to create the settings file. In some environments and situations, it might take several seconds to several minutes for the API to complete the process.

To download settings:

- Click the download icon (↓).

By default, the file is downloaded to the folder on your local machine that is specified in your browser settings for downloads.

**Caution!** Fortify WebInspect supports only Standard scan settings that are downloaded from ScanCentral DAST. Other types of scan settings may cause undesirable results in Fortify WebInspect.

## Deleting Settings

To delete settings:

1. Do one of the following:
  - Select one or more check boxes for settings in the **Settings List**, and then click **DELETE** at the bottom of the list.
  - Select the settings in the **Settings List** to view the details, and then click **DELETE** at the bottom of the settings detail panel.



If the settings have dependencies, such as scheduled scans, a **DELETE ERROR** dialog box opens. In this case, you must resolve the dependencies before you can delete the settings.

2. To aid in resolving dependencies, in the **DELETE ERROR** dialog box, click **Copy list of dependencies**.

A JSON string of the error summary is copied to the clipboard.

## Copying the Settings ID for Use in the API

You can copy the settings identifier and use it to conduct a scan by way of the Fortify Software Security Center API.

To copy the settings identifier:

1. In the **Settings List**, select the settings to copy.  
The settings detail panel appears.
2. In the settings detail panel, click the copy icon as shown below.

ZEROSQL



Version Project01  
<http://zero.webappsecurity.com>

|                        |                     |
|------------------------|---------------------|
| Created                | 07/24/2020 05:34 PM |
| Modified               | 07/24/2020 05:34 PM |
| Type                   | Standard Scan       |
| Policy                 | Passive Scan        |
| User Agent             | Default             |
| Login Macro            | none                |
| Network Auth           | false               |
| Allowed Hosts          | none                |
| Enable SPA Support     | off                 |
| Enable Traffic Monitor | off                 |
| Submit for Triage      | no                  |

SETTINGS IDENTIFIER

697AD7D3-2231-4468-99A4-0F8013517602



The scan settings identifier is copied to the clipboard.

# Chapter 9: Working with Scan Schedules

You can view all of the scan schedules that are available in the ScanCentral DAST database in the Scan Schedules list. You can also configure a new scan schedule, edit an existing schedule, enable or disable schedules, and delete schedules. You can view whether a schedule is enabled, as well as other details, in the schedule detail panel. From the schedule detail panel, you can also enable or disable schedules.

## Accessing DAST Scan Schedules in Software Security Center

After you configure your Fortify ScanCentral DAST environment and enable DAST in the ADMINISTRATION view in Fortify Software Security Center, you can work with DAST scan schedules directly in Fortify Software Security Center.

To access DAST scan schedules in Fortify Software Security Center:

1. Select **SCANCENTRAL > DAST**.  
The scans list appears.
2. In the left panel, select **Scan Schedules**.  
The Scan Schedules list appears.

## User Role Determines Capabilities

Your user role and permissions in Fortify Software Security Center determine which tasks you can perform on applications and DAST scans, sensors, sensor pools, settings, and scan schedules. For more information, see ["Permissions in Fortify Software Security Center" on page 27](#).

## Understanding the Scan Schedules List

The Scan Schedules list displays the scan schedules that are available in the ScanCentral DAST database.

You can select the information you want to display, as well as customize other aspects of the table. For more information, see ["Working with Tables" on page 77](#).

The following table describes the columns of information provided for each schedule.

| Column                 | Description                                                                                                       |
|------------------------|-------------------------------------------------------------------------------------------------------------------|
| <b>Application</b>     | Indicates the application for the scheduled scan.                                                                 |
| <b>Version</b>         | Indicates the version for the scheduled scan.                                                                     |
| <b>Name</b>            | Indicates the name of the schedule as assigned in the SETTINGS CONFIGURATION wizard.                              |
| <b>Scan Settings</b>   | Indicates the name of the settings file that is used to conduct the scan.                                         |
| <b>Recurrence Type</b> | Indicates how often the scheduled scan is run: <b>Daily</b> , <b>Weekly</b> , <b>Monthly</b> , or <b>Yearly</b> . |
| <b>Last Occurrence</b> | Indicates the last date and time that the scheduled scan ran.                                                     |
| <b>Next Occurrence</b> | Indicates the next date and time that the scheduled scan will be run.                                             |
| <b>Enabled</b>         | Indicates whether the schedule is enabled. Possible values are <b>true</b> and <b>false</b> .                     |

## Understanding the Schedule Detail Panel

When you click a scan schedule in the Scan Schedules list, the schedule detail panel appears to the right. The following table describes the additional information that is provided for the selected schedule.

| Item              | Description                                                                                                                                                                     |
|-------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Start Date</b> | Indicates the initial date and time that the schedule ran a scan.                                                                                                               |
| <b>End Date</b>   | Indicates the last date and time that the schedule will run a scan, based on the number of occurrences or actual date that was configured in the Settings Configuration wizard. |

## Managing Schedules

You can configure a new scan schedule, edit an existing schedule, enable or disable schedules, and delete schedules from the Scan Schedules list.

### Creating a New Schedule

You can configure a new schedule from an existing template saved in Fortify Software Security Center or in a file.

To configure a new schedule:

1. On the **Scan Schedules** page, click **+ NEW SCHEDULE**.  
The SCAN SETTINGS TEMPLATE dialog box opens.
2. Select an application from the **Application Name** list.
3. Select a version from the **Application Version** list.  
A START list and a list of recently opened settings templates, if applicable, appear at the bottom of the dialog box.
4. Do one of the following:
  - To use a template from Fortify Software Security Center, select **Open from SSC** in the **START** list, and then click **+ NEW SCHEDULE**.
  - To use a template saved to a file, select **Open file** in the **START** list, and then click **+ NEW SCHEDULE**.
  - To use a recently opened template, select a template under **RECENT**.The SCHEDULE SCAN dialog box opens.
5. Follow the procedure described in ["Scheduling a Scan" on page 118](#).

## Editing a Schedule

To edit a schedule:

1. Select the schedule in the list.  
The schedule detail panel appears.
2. In the settings detail panel, click **EDIT**.  
The SCHEDULE SCAN dialog box opens pre-populated with the selected schedule settings.
3. Follow the procedure described in ["Scheduling a Scan" on page 118](#).

## Enabling or Disabling Schedules

You can enable or disable schedules in the schedule detail pane. If a schedule is enabled, the scan runs as scheduled. If it is disabled, no additional scans are run.

To enable or disable a schedule:

1. Select the schedule in the list.  
The schedule detail panel appears.
2. Do one of the following:
  - To enable the schedule, toggle the switch to **Enabled**.
  - To disable the schedule, toggle the switch to **Disabled**.

## Deleting a Schedule

To delete a schedule, do one of the following:

- Select one or more check boxes for schedules in the schedules list, and then click **DELETE** at the bottom of the list.
- Select a schedule to view the schedule details, and then click **DELETE** at the bottom of the schedule detail panel.

# Chapter 10: Working with Deny Intervals

A deny interval is a block of time during which scans are not permitted. ScanCentral DAST will not prevent you from scheduling a scan or attempting to start a scan manually during a blackout period. It will, however, place the job in the pending job queue and will start the scan when the deny interval ends.

Similarly, if a scan is running when a deny interval begins, the ScanCentral DAST will do one of the following:

- Pause the scan and finish it when the deny interval ends
- Force the scan to complete

## Deny Intervals Apply to Applications

Deny intervals are applied to one or more applications. However, an application can have only one deny interval. If you create and apply a deny interval to an application with an existing deny interval, the existing deny interval is overwritten with the new one.

## Deny Intervals are Global Settings

Global settings are those that apply or may apply to all of your applications, scans, scan schedules, sensors, or sensor pools. For example, all scans that are running when a deny interval starts may be paused or forced to complete, depending on the deny interval settings.

## Accessing Deny Intervals in Software Security Center

After you configure your Fortify ScanCentral DAST environment and enable DAST in the ADMINISTRATION view in Fortify Software Security Center, you can work with DAST deny intervals directly in Fortify Software Security Center.

To access DAST deny intervals in Fortify Software Security Center:

1. Select **SCANCENTRAL > DAST**.  
The scans list appears.
2. In the left panel, select **Deny Intervals**.  
The deny intervals list appears.

## User Role Determines Capabilities

Your user role and permissions in Fortify Software Security Center determine which tasks you can perform on applications and DAST scans, sensors, sensor pools, settings, and scan schedules. For more information, see ["Permissions in Fortify Software Security Center" on page 27](#).

## Understanding the Deny Intervals List

Deny intervals are applied to applications. If you create a deny interval and apply it to 100 applications, you will have 100 entries in the deny intervals list table.

You can select the information you want to display, as well as customize other aspects of the table. For more information, see ["Working with Tables" on page 77](#).

The following table describes the columns of information provided for each application that is configured with a deny interval.

| Column                 | Description                                                                                                                                                                                                                                                                                                  |
|------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Application</b>     | Identifies the application to which the deny interval applies.                                                                                                                                                                                                                                               |
| <b>Recurrence Type</b> | Indicates how often the deny interval occurs: <b>Daily</b> , <b>Weekly</b> , <b>Monthly</b> , or <b>Yearly</b> .<br><br>Sorting by the Recurrence Type column is not alphabetical. This column sorts by the length of the deny interval—either shortest to longest interval or longest to shortest interval. |
| <b>Last Occurrence</b> | Indicates the last date and time that the deny interval occurred.                                                                                                                                                                                                                                            |
| <b>Next Occurrence</b> | Indicates the next date and time that the deny interval will occur.                                                                                                                                                                                                                                          |
| <b>Modified</b>        | Indicates the date and time that the deny interval was created, or if edited, the last date and time that the deny interval was changed.                                                                                                                                                                     |

## Understanding the Deny Intervals Detail Panel

When you select an entry in the deny intervals list, the deny interval detail panel appears. The following table describes the information that is provided for the selected deny interval.

| Item                   | Description                                                                                                                                                    |
|------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Created Date</b>    | Indicates the date and time that the deny interval was saved.                                                                                                  |
| <b>Modified Date</b>   | Indicates the date and time that the deny interval was created, or if edited, the last date and time that the deny interval was changed.                       |
| <b>Recurrence Type</b> | Indicates how often the deny interval occurs: <b>Daily</b> , <b>Weekly</b> , <b>Monthly</b> , or <b>Yearly</b> .                                               |
| <b>Action Type</b>     | Indicates the action to take for a scan that is running when the deny interval begins. Possible actions are <b>Pause scan</b> and <b>Force complete scan</b> . |

## Creating a Deny Interval

When you create a ScanCentral DAST deny interval, you must assign it to one or more applications. You create the deny interval and assign applications to it in the DENY INTERVAL wizard.

To create a deny interval:

1. On the **Deny Intervals** page, click **+ NEW DENY INTERVAL**.  
The DENY INTERVAL wizard opens.
2. On the **General** page, continue according to the following table.

| To configure a...                                                                                      | Then...                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|--------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Recurring</b> deny interval<br><br><b>Note:</b> The <b>Recurring</b> option is selected by default. | <ol style="list-style-type: none"> <li>a. Enter a date and time for the deny interval to start in the <b>Start Date</b> and <b>Start Time</b> boxes.</li> <li>b. In the <b>Duration</b> area, specify a duration in the <b>Days</b>, <b>Hours</b>, and <b>Minutes</b> boxes.<br/><br/> <b>Tip:</b> To calculate the duration, click <b>CALCULATE DURATION</b>, enter a date and time for the deny interval to end in the <b>End Date</b> and <b>End Time</b> boxes, and then click <b>OK</b>. The duration is automatically calculated and added to the <b>Days</b>, <b>Hours</b>, and <b>Minutes</b> boxes.           </li> </ol> |
| <b>Non-recurring</b> deny interval                                                                     | <ol style="list-style-type: none"> <li>a. Clear the <b>Recurring</b> option.</li> <li>b. Enter a date and time for the deny interval to start in the <b>Start Date</b> and <b>Start Time</b> boxes.</li> </ol>                                                                                                                                                                                                                                                                                                                                                                                                                     |



| To configure a... | Then...                                                                                                                                                                                            |
|-------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                   | <p>c. Enter a date and time for the deny interval to end in the <b>End Date</b> and <b>End Time</b> boxes.</p> <p><b>Tip:</b> To select a date from the calendar, click the calendar icon (📅).</p> |

- In the **Scan action** area, select an action. Options are:
  - **Pause scan** – the running scan is paused until the deny interval has ended.
  - **Force complete scan** – the running scan is forced to complete. If the **Submit for triage** option was selected in the scan settings, the scan results will be published to Fortify Software Security Center when the action is completed.
- Click **NEXT**.  
The Recurrence page appears. If you did not select the Recurring option on the General page, you cannot configure settings on the Recurrence page. Proceed to Step 7.
- To schedule a recurring deny interval, in the **Pattern** section specify how often to apply the deny interval according to the following table.

| To apply... | Then...                                                                                                                                                                                                                                                                                                                                               |
|-------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Daily       | <p>a. Select <b>DAILY</b>.</p> <p><b>Note:</b> If you selected a Duration longer than 24 hours from the Start Date and Start Time on the General page, then the Daily option is not visible on the Recurrence page.</p> <p>b. Select a recurrence in the <b>Occur every ___ day</b> box.</p>                                                          |
| Weekly      | <p>a. Select <b>WEEKLY</b>.</p> <p><b>Note:</b> If you selected a Duration longer than a week from the Start Date and Start Time on the General page, then the Daily and Weekly options are not visible on the Recurrence page.</p> <p>b. Select a recurrence in the <b>Occur every ___ week</b> box.</p> <p>c. Select the days to run each week.</p> |
| Monthly     | <p>a. Select <b>MONTHLY</b>.</p> <p><b>Note:</b> If you selected a Duration longer than a month from the Start Date and Start Time on the General page, then the Daily, Weekly, and</p>                                                                                                                                                               |

| To apply... | Then...                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|-------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|             | <p>Monthly options are not visible on the Recurrence page.</p> <p>b. Select a recurrence in the <b>Occur every ___ month</b> box.</p> <p>c. Do one of the following:</p> <ul style="list-style-type: none"> <li>◦ Select <b>Occur on day</b> and enter a date in the box.</li> <li>◦ Select <b>Occur on the</b>, and then select an interval from the <b>Interval</b> list and a day from the <b>Day</b> list.</li> </ul> <p><b>Note:</b> Interval options are First, Second, Third, Fourth, and Last.</p>                                                                                                                                                                                                                                                                     |
| Yearly      | <p>a. Select <b>YEARLY</b>.</p> <p><b>Note:</b> If you selected a Duration longer than a year from the Start Date and Start Time on the General page, then the Yearly option is visible on the Recurrence page. However, you cannot configure a duration that is longer than the recurrence interval.</p> <p>b. Do one of the following:</p> <ul style="list-style-type: none"> <li>◦ Select <b>Occur on</b>, and then select a month from the <b>Month</b> list and enter a date in the <b>Day</b> box.</li> <li>◦ Select <b>Occur on the</b>, and then select an interval from the <b>Interval</b> list, a day from the <b>Day</b> list, and a month from the <b>Month</b> list.</li> </ul> <p><b>Note:</b> Interval options are First, Second, Third, Fourth, and Last.</p> |

- Under **Range**, do one of the following:
  - To leave the recurrence open ended, select **Never ends**.
  - To set an end date, select **Ends by**, and then enter an end date in the **End Date** box or enter the number of occurrences after which to end in the **occurrence** box.

**Note:** Entering data into the **End Date** box automatically updates the **occurrence** box, and conversely.

- Click **NEXT**.  
The Application Select page appears, listing all available applications.
- In the **APPLICATIONS** list, select one or more applications to which you want the deny interval to apply.  
The selected applications are added to the APPLICATIONS SELECTED area.
- Click **NEXT**.

The Review page appears.

10. Click **SAVE**.

The deny interval is added to the ScanCentral DAST database for the applications selected.

## Managing Deny Intervals

You can edit and delete deny intervals, and refresh the list on the Deny Intervals page.

### Facts About Editing a Deny Interval

Because each entry in the deny interval list is for a specific application, be aware of the following facts when editing a deny interval:

- When you select a deny interval from the deny interval list to edit, by default the changes apply only to the selected application. You can, however, apply changes to other applications while editing.
- Applications can have only one deny interval. When you edit a deny interval and apply it to an application, it replaces any existing deny interval already applied to that application.
- If you edit the start date and start time of an existing deny interval so that the current time is included in the deny interval, any scan that is currently running for the specified application will be paused or forced to complete.

### Editing a Deny Interval

To edit a deny interval:

1. In the deny interval list, select the deny interval to edit.

The deny interval detail panel appears.

2. Click **EDIT**.

The DENY INTERVAL wizard opens with the deny interval settings visible for the selected application.

**Important!** You are editing the settings for the selected application only. To apply your changes to multiple applications, you must select them in the **APPLICATIONS** list in the DENY INTERVAL wizard.

3. To make edits, follow the procedure in ["Creating a Deny Interval" on page 168](#).

## Deleting a Deny Interval

To delete a deny interval, do one of the following:

- Select one or more check boxes for deny intervals in the list, and then click **DELETE** at the bottom of the list.
- Select a deny interval to view the deny interval details, and then click **DELETE** at the bottom of the deny interval detail panel.

## Refreshing the Deny Intervals List

Generally, the changes that you make to deny intervals appear right away on the deny intervals list. However, if other users have access to the same list, any changes they make will not be updated in your view. To see such changes, you can manually refresh the list.

To view an updated deny intervals list:

- Click **REFRESH**.

# Chapter 11: Working with Policies

You can import into the ScanCentral DAST database policies that have been customized using the Fortify WebInspect Policy Manager tool. Afterward, you can view the custom policies that are available in the ScanCentral DAST database in the policies list. You can view the policy description, the applications to which the policy is assigned, and other details in the policy detail panel. From the policy detail panel, you can also edit and delete policies.

## Accessing Policies in Software Security Center

After you configure your Fortify ScanCentral DAST environment and enable DAST in the ADMINISTRATION view in Fortify Software Security Center, you can work with DAST policies directly in Fortify Software Security Center.

To access DAST policies in Fortify Software Security Center:

1. Select **SCANCENTRAL > DAST**.  
The scans list appears.
2. In the left panel, select **Policies**.  
The policies list appears.

## User Role Determines Capabilities

Your user role and permissions in Fortify Software Security Center determine which tasks you can perform on applications and DAST scans, sensors, sensor pools, settings, and scan schedules. For more information, see ["Permissions in Fortify Software Security Center" on page 27](#).

## Understanding the Policies List

The policies list table displays the custom policies that have been imported into Fortify ScanCentral DAST from Fortify WebInspect.

You can select the information you want to display, as well as customize other aspects of the table. For more information, see ["Working with Tables" on page 77](#).

The following table describes the columns of information provided for each policy.

| Column | Description                                 |
|--------|---------------------------------------------|
| Name   | Identifies the name of the imported policy. |

| Column          | Description                                                                                                                                                                     |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Modified</b> | Indicates the last date and time that the policy was edited.<br><br><b>Note:</b> You can only edit the name, description, and the applications to which the policy is assigned. |

## Understanding the Policy Detail Panel

When you select a policy in the policies list, the policy detail panel appears. The policy name and description are displayed at the top. following table describes the information that is provided for the selected policy.

| Item                         | Description                                                                     |
|------------------------------|---------------------------------------------------------------------------------|
| <b>ASSIGNED APPLICATIONS</b> | Lists the applications to which the policy has been assigned.                   |
| <b>Created</b>               | Indicates the date and time that the policy was imported into ScanCentral DAST. |
| <b>Modified</b>              | Indicates the last date and time that the policy was changed.                   |

## Importing a Custom Policy

When you import a custom policy into ScanCentral DAST, you must assign it to one or more applications. You import the policy and assign applications to it in the CUSTOM POLICY wizard.

To import a policy:

1. On the **Policies** page, click **+ CUSTOM POLICY**.  
The CUSTOM POLICY wizard opens.
2. On the **General** page, click **IMPORT**.
3. Using the standard file-selection window, locate the .policy file and click **Open**.  
The **File** name, policy **Name**, and **Description** fields in the General page are populated.
4. Edit the **Name** and **Description** fields as needed.
5. Click **NEXT**.  
The Application Select page appears.
6. In the **APPLICATIONS** list, select one or more applications to which you want the policy to apply.  
The selected applications are added to the APPLICATIONS SELECTED area.
7. Click **NEXT**.

The Review page appears.

8. Click **SAVE**.

The policy is added to the ScanCentral DAST database for the applications selected.

## Managing Policies

You can edit and delete policies, and refresh the list on the Policies page.

### Editing a Policy

To edit a policy:

1. In the policies list, select the policy to edit.  
The policy detail panel appears.
2. Click **EDIT**.  
The CUSTOM POLICY wizard opens.
3. Edit the **Name** and **Description** fields as needed.
4. Click **NEXT**.  
The Application Select page appears.
5. In the **APPLICATIONS** list, select one or more applications to which you want the policy to apply.  
The selected applications are added to the APPLICATIONS SELECTED area.
6. Click **NEXT**.  
The Review page appears.
7. Click **SAVE**.  
The changes are saved in the ScanCentral DAST database.

### Deleting a Policy

To delete a custom policy:

1. Do one of the following:
  - Select one or more check boxes for policies in the list, and then click **DELETE** at the bottom of the list.
  - Select a policy to view the policy details, and then click **DELETE** at the bottom of the policy detail panel.

A confirmation message appears with a prompt to select a replacement policy.
2. In the **Replacement policy** drop-down list, select a replacement policy to be used in all scan settings that contain the policy or policies being deleted.

**Important!** If you are deleting multiple policies, then the replacement policy you choose will be used for all deleted policies.

## Refreshing the Policies List

Generally, the changes that you make to policies appear right away on the policies list. However, if other users have access to the same list, any changes they make will not be updated in your view. To see such changes, you can manually refresh the list.

To view an updated policies list:

- Click **REFRESH**.



# Chapter 12: Working with Base Settings

If you have Admin Role privileges in Fortify Software Security Center, you can create and edit base settings and apply them to applications. All users who have access to the selected applications can use these base settings as templates to create new settings or conduct a scan.

## Differences Between Base Settings and Templates

A template from Fortify Software Security Center:

- Is a complete set of settings with all fields containing data
- Applies to one application and version

Base settings may:

- Be an incomplete set of settings with some fields missing data
- Apply to multiple applications and versions

## Base Settings are Global Settings

Global settings are those that apply or may apply to all of your applications, scans, scan schedules, sensors, or sensor pools. For example, base settings may apply to multiple applications and versions.

## Accessing Base Settings in Software Security Center

After you configure your Fortify ScanCentral DAST environment and enable DAST in the ADMINISTRATION view in Fortify Software Security Center, you can work with DAST base settings directly in Fortify Software Security Center.

To access DAST base settings in Fortify Software Security Center:

1. Select **SCANCENTRAL > DAST**.  
The scans list appears.
2. In the left panel, select **Base Settings**.  
The base settings list appears.

## User Role Determines Capabilities

Your user role and permissions in Fortify Software Security Center determine which tasks you can perform on applications and DAST scans, sensors, sensor pools, settings, and scan schedules. For

more information, see ["Permissions in Fortify Software Security Center" on page 27](#).

## Understanding the Base Settings List

The base settings list table displays the base settings that are available in the ScanCentral DAST database.

You can select the information you want to display, as well as customize other aspects of the table. For more information, see ["Working with Tables" on page 77](#).

The following table describes the columns of information provided for each base settings file in the list.

| Column           | Description                                                                                                                                                                                                           |
|------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Name</b>      | Indicates the name of the base settings file.                                                                                                                                                                         |
| <b>Scan Type</b> | Indicates the type of scan to be conducted using the base settings. Types are: <ul style="list-style-type: none"><li>• <b>Standard Scan</b></li><li>• <b>Workflow-driven Scan</b></li><li>• <b>API Scan</b></li></ul> |
| <b>Modified</b>  | Indicates the date and time that the settings were created, or if edited, the last date and time that the settings were changed.                                                                                      |

## Understanding the Base Settings Detail Panel

When you click a settings file in the base settings list, the base settings detail panel appears to the right. The assigned applications that are configured in the base settings are listed at the top of the panel. The following table describes the additional information that is provided in this panel.

| Item            | Description                                                                                                                                                                            |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Created</b>  | Indicates the date and time that the settings were saved.                                                                                                                              |
| <b>Modified</b> | Indicates the date and time that the settings were created, or if edited, the last date and time that the settings were changed.                                                       |
| <b>Type</b>     | Indicates the type of scan to be conducted using the settings. Types are: <ul style="list-style-type: none"><li>• <b>Standard Scan</b></li><li>• <b>Workflow-driven Scan</b></li></ul> |

| Item                          | Description                                                                                                                                                                                                                                                                                                                                                                                       |
|-------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                               | <ul style="list-style-type: none"><li>• <b>API Scan</b></li></ul>                                                                                                                                                                                                                                                                                                                                 |
| <b>Policy</b>                 | Identifies the dynamic policy to be used to conduct the scan.                                                                                                                                                                                                                                                                                                                                     |
| <b>User Agent</b>             | <p>Indicates the user agent one or more of the following:</p> <ul style="list-style-type: none"><li>• <b>Chrome</b></li><li>• <b>Chrome (Mobile Android)</b></li><li>• <b>Custom</b></li><li>• <b>Default</b></li><li>• <b>Edge</b></li><li>• <b>Safari</b></li><li>• <b>Safari (Mobile IOS)</b></li></ul> <p><b>Note:</b> Default uses the user agent that is defined in Fortify WebInspect.</p> |
| <b>Login Macro</b>            | If applicable, indicates the file name of the login macro specified in the settings.                                                                                                                                                                                                                                                                                                              |
| <b>Network Auth</b>           | Indicates whether network authentication is specified in the settings.                                                                                                                                                                                                                                                                                                                            |
| <b>Allowed Hosts</b>          | If applicable, indicates the number of allowed hosts configured in the settings.                                                                                                                                                                                                                                                                                                                  |
| <b>SPA Option</b>             | Indicates how SPA support is configured in the settings.                                                                                                                                                                                                                                                                                                                                          |
| <b>Enable Traffic Monitor</b> | Indicates whether Traffic Monitor is enabled in the settings.                                                                                                                                                                                                                                                                                                                                     |
| <b>Submit for Triage</b>      | Indicates whether a scan run from these settings is uploaded to Fortify Software Security Center upon completion.                                                                                                                                                                                                                                                                                 |

## Creating Base Settings

You create base settings in the Base Settings configuration wizard. To access this wizard from the ScanCentral DAST Base Settings list page:

- Click **+ BASE SETTINGS**.

The Base Settings configuration wizard opens to the Target page.

## What's Next?

Do one of the following:

- To configure base settings for a standard scan, proceed with ["Configuring Base Settings for a Standard Scan" below](#).
- To configure base settings for a workflow-driven scan, proceed with ["Configuring Base Settings for a Workflow-driven Scan" on page 182](#).
- To configure base settings for an API scan, proceed with ["Configuring Base Settings for an API Scan" on page 183](#).

## Configuring Base Settings for a Standard Scan

A standard scan performs an automated analysis, beginning from the start URL.

To configure base settings for a standard scan:

1. On the Target page, click **STANDARD SCAN**.
2. Select one of the following scan modes:
  - **Crawl Only:** Maps the hierarchical data structure of the site.
  - **Crawl and Audit:** Maps the hierarchical data structure of the site and audits each resource (page).
  - **Audit Only:** Applies the methodologies of the selected policy to determine vulnerability risks, but does not crawl the website. This scan mode does not follow or assess links on the site.
3. Type the complete URL or IP address in the **Url** field.

If you enter a URL, it must be precise. For example, if you enter MYCOMPANY.COM, the sensor will not scan WWW.MYCOMPANY.COM or any other variation unless you specify alternatives in the **Allowed Hosts** setting. For more information, see ["Adding and Managing Allowed Hosts in Base Settings" on page 190](#).

An invalid URL or IP address will result in an error. If you want to scan from a certain point in your hierarchical tree, append a starting point for the scan, such as `http://www.myserver.com/myapplication/`.

Scans by IP address will not follow links that use fully qualified URLs (as opposed to relative paths).

**Note:** The sensor supports both Internet Protocol version 4 (IPV4) and Internet Protocol version 6 (IPV6). You must enclose IPV6 addresses in brackets.

4. (Optional) To limit the scope of the scan to a specified area, select **Restrict to folder**, and from the list, select one of the following options:
  - **Directory only** – The sensor crawls and/or audits only the URL that you specify. For example, if you select this option and specify the URL `www.mycompany/one/two/`, the sensor will assess only the "two" directory.

- **Directory and subdirectories** – The sensor begins crawling and/or auditing at the URL you specify, but does not access any directory that is higher in the directory tree.
  - **Directory and parent directories** – The sensor begins crawling and/or auditing at the URL you specify, but does not access any directory that is lower in the directory tree.
5. (Optional) To submit the completed scan for triage in Fortify Software Security Center, select **Submit for triage**.

**Note:** Submitting for triage allows you to perform audit analysis of the findings so that you can assign a user and an analysis value to the issue.

6. Under **Audit Depth (Policy)**, do one of the following:
- Select a policy from the **Policy** list.
  - Begin typing the policy name in the **Policy** list box to filter the list of policy names that begin with the text that you enter.

**Note:** The default policies are stored in SecureBase tables in the ScanCentral DAST database. For more information about the list of default policies, see ["Policies" on page 224](#). Custom policies are assigned to specific applications and are stored in the ScanCentral DAST database. Only those custom policies that are assigned to the selected application appear in the Policy list.

7. Do one of the following:
- To use a standard user agent, select it from the **User Agent** list.

**Note:** Default uses the user agent that is defined in Fortify WebInspect.

- To use a custom user agent, select **Custom** from the **User Agent** list, and then type the user-agent string in the **Custom User Agent** box.

**Tip:** User-agent strings generally use the following format:

```
<browser>/<version> (<system and browser information>) <platform> (<platform details>) <extensions>
```

## What's Next?

Do one of the following:

- To configure proxy settings in the base settings, proceed with ["Configuring Proxy Settings in Base Settings" on page 187](#).
- To configure authentication in the base settings, click **NEXT** and proceed with ["Configuring Authentication in Base Settings" on page 188](#).

## Configuring Base Settings for a Workflow-driven Scan

A workflow-driven scan audits only those URLs included in a macro that you previously recorded. It does not follow any hyperlinks encountered during the audit. A logout signature is not required. This type of macro is used most often to focus on a particular subsection of the application. If you select multiple macros, all of them will be included in the same scan.

### Types of Macros Supported

You can use .webmacro files or Burp Proxy captures.

**Important!** If you use a login macro in conjunction with a workflow macro or startup macro or both, all macros must be of the same type: all .webmacro files or all Burp Proxy captures. You cannot use different types of macros in the same scan. Likewise, .webmacro login and workflow files must have been created using the same version of Web Macro Recorder. You cannot use a login file that was recorded in the Web Macro Recorder with Macro Engine 6.1 and a workflow file that was recorded in the Session-based Web Macro Recorder.

## Configuring Base Settings for a Workflow-driven Scan

To configure base settings for a workflow-driven scan:

1. On the Target page, click **WORKFLOW-DRIVEN SCAN**.
2. Select one of the following scan modes:
  - **Crawl Only:** Maps the hierarchical data structure of the site.
  - **Crawl and Audit:** Maps the hierarchical data structure of the site and audits each resource (page).
  - **Audit Only:** Applies the methodologies of the selected policy to determine vulnerability risks, but does not crawl the website. This scan mode does not follow or assess links on the site.
3. Continue according to the following table.

| To...                            | Then...                                                                                                                                                                                                                                                                                                                                         |
|----------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Add a macro to the scan settings | <ol style="list-style-type: none"><li>a. Click <b>MANAGE</b>.</li><li>b. Type a name for the macro in the <b>Name</b> field.</li><li>c. Click <b>IMPORT</b> and browse to locate the workflow to add to the scan settings.</li><li>d. Click <b>OK</b>.</li><li>e. Repeat steps a through d to add another macro to the scan settings.</li></ol> |

| To...                                  | Then...                                                                                                          |
|----------------------------------------|------------------------------------------------------------------------------------------------------------------|
| Remove a macro from the list of macros | <ol style="list-style-type: none"><li>Select the macro in the macro list.</li><li>Click <b>REMOVE</b>.</li></ol> |

- (Optional) To submit the completed scan for triage in Fortify Software Security Center, select **Submit for triage**.

**Note:** Submitting for triage allows you to perform audit analysis of the findings so that you can assign a user and an analysis value to the issue.

- Under **Audit Depth (Policy)**, do one of the following:
  - Select a policy from the **Policy** list.
  - Begin typing the policy name in the **Policy** list box to filter the list of policy names that begin with the text that you enter.

**Note:** The default policies are stored in SecureBase tables in the ScanCentral DAST database. For more information about the list of default policies, see ["Policies" on page 224](#). Custom policies are assigned to specific applications and are stored in the ScanCentral DAST database. Only those custom policies that are assigned to the selected application appear in the Policy list.

- Do one of the following:
  - To use a standard user agent, select it from the **User Agent** list.
- To use a custom user agent, select **Custom** from the **User Agent** list, and then type the user-agent string in the **Custom User Agent** box.

**Tip:** User-agent strings generally use the following format:

`<browser>/<version> (<system and browser information>) <platform> (<platform details>) <extensions>`

## What's Next?

Do one of the following:

- To configure proxy settings in the base settings, proceed with ["Configuring Proxy Settings in Base Settings" on page 187](#).
- To configure authentication in the base settings, click **NEXT** and proceed with ["Configuring Authentication in Base Settings" on page 188](#).

## Configuring Base Settings for an API Scan

An API scan creates a macro from a REST API definition and performs an automated analysis.

**Important!** The DAST Utility Worker Service container must be up and running to configure and run a Postman scan.

To configure base settings for an API scan:

1. On the **Target** page, click **API SCAN**.
2. In the **Type** list, select the API type to be scanned. The options are **Open API** (also known as Swagger), **Postman**, and **OData**.

**Important!** If you are configuring a Postman scan while using a classic Fortify WebInspect installation with the Fortify ScanCentral DAST sensor service, you must install prerequisite software on the sensor machine. For more information about this and other aspects of using Postman collection files, including configuring dynamic authentication using dynamic tokens, see ["Scanning with a Postman Collection" on page 217](#).

3. Continue according to the following table.

| For this API type... | Do this...                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
|----------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Open API</b>      | <ol style="list-style-type: none"><li>a. In the <b>Definition</b> list, select <b>File</b> or <b>URL</b>, and continue as follows:<ul style="list-style-type: none"><li>◦ If you selected File, click <b>IMPORT</b> and import the definition file.</li><li>◦ If you selected URL, provide the URL to the API definition file, as shown in the following example:<br/><br/><code>http://172.16.81.36/v1</code><br/><br/><b>Tip:</b> Alternatively, you can paste in the full path to a definition file that is saved on your local machine.</li></ul></li><li>b. If HTTP authorization credentials, such as a bearer token, are needed to access the API definition, enter them in the <b>Authentication Header</b> box, as shown in the following example:<br/><br/><code>Basic YWxhZGRpbjpvGVuc2VzYW11</code></li></ol> |
| <b>Postman</b>       | <ol style="list-style-type: none"><li>a. Do one of the following:<ul style="list-style-type: none"><li>◦ To import a workflow collection, select <b>IMPORT</b> and then import the Postman collection file.</li><li>◦ To import an authentication collection, select <b>Authentication</b> from the <b>IMPORT</b> drop-down list, and then import the Postman collection file.</li><li>◦ To import an environment file, select <b>Environment</b> from the <b>IMPORT</b> drop-down list, and then import the Postman environment file.</li></ul></li></ol>                                                                                                                                                                                                                                                                |



| For this<br>API type... | Do this...                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|-------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                         | <p>The file is added to the list of collection files. Repeat this Step to import additional files.</p> <p><b>Important!</b> You can import only one authentication collection and one environment file.</p> <p>b. Click <b>VALIDATE</b> to validate the collection file(s).</p> <p>Upon successful validation, the POSTMAN VALIDATION dialog box opens, displaying a list of sessions contained in the collection file(s). If authentication sessions are identified, they are preselected as <b>Auth</b> sessions. All other sessions are preselected as <b>Audit</b> sessions. Additionally, the Postman Authentication Results area displays the type of authentication detected as <b>None</b>, <b>Static</b>, or <b>Dynamic</b>.</p> <p><b>Note:</b> <b>Auth</b> sessions will be used for authentication for the scan. <b>Audit</b> sessions will be audited in the scan.</p> <p>c. (Optional) Select the <b>Auth</b> or <b>Audit</b> check box for a session to change its type as needed.</p> <p>d. (Optional) Make changes to the <b>Postman Authentication Results</b> as follows:</p> <ul style="list-style-type: none"> <li>◦ For <b>Static</b> authentication, enter a token in the <b>Custom Header Token</b> box.</li> <li>◦ For <b>Dynamic</b> authentication, do the following: <ul style="list-style-type: none"> <li>• Select the <b>Regex (Custom)</b> option to the right of the <b>Response Token Name</b> box, and then enter a custom regular expression in the <b>Response Token Name</b> box.</li> <li>• Select the <b>Regex (Custom)</b> option to the right of the <b>Request Token Name</b> box, and then enter a custom regular expression in the <b>Request Token Name</b> box.</li> <li>• Clear the <b>Use Auto Detect</b> option to the right of the <b>Logout Condition</b> box, and then enter a new logout condition string in the <b>Logout Condition</b> box.</li> </ul> </li> </ul> <p>e. Did you make changes to the Postman Authentication Results?</p> <ul style="list-style-type: none"> <li>◦ If yes, click <b>VALIDATE</b> to validate the new authentication settings,</li> </ul> |

| For this API type... | Do this...                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                      | <p>and then click <b>OK</b>.</p> <ul style="list-style-type: none"> <li>◦ If no, click <b>OK</b>.</li> </ul>                                                                                                                                                                                                                                                                                                                                                                                           |
| <b>OData</b>         | <p>In the <b>Definition</b> list, select <b>File</b> or <b>URL</b>, and continue as follows:</p> <ul style="list-style-type: none"> <li>• If you selected File, click <b>IMPORT</b> and import the definition file.</li> <li>• If you selected URL, provide the URL to the API definition file, as shown in the following example:</li> </ul> <p>http://172.16.81.36/v1</p> <p><b>Tip:</b> Alternatively, you can paste in the full path to a definition file that is saved on your local machine.</p> |

4. (Optional) To submit the completed scan for triage in Fortify Software Security Center, select **Submit for triage**.

**Note:** Submitting for triage allows you to perform audit analysis of the findings so that you can assign a user and an analysis value to the issue.

5. Under **Audit Depth (Policy)**, do one of the following:
  - Select a policy from the **Policy** list.
  - Begin typing the policy name in the **Policy** list box to filter the list of policy names that begin with the text that you enter.

**Note:** The default policies are stored in SecureBase tables in the ScanCentral DAST database. For more information about the list of default policies, see "[Policies](#)" on page 224. Custom policies are assigned to specific applications and are stored in the ScanCentral DAST database. Only those custom policies that are assigned to the selected application appear in the Policy list.

**Tip:** The **API** policy is the default policy for API scan settings in the Settings Configuration wizard. However, you can choose another policy if needed.

6. Do one of the following:
  - To use a standard user agent, select it from the **User Agent** list.

**Note:** Default uses the user agent that is defined in Fortify WebInspect.

  - To use a custom user agent, select **Custom** from the **User Agent** list, and then type the user-agent string in the **Custom User Agent** box.

**Tip:** User-agent strings generally use the following format:

<browser>/<version> (<system and browser information>) <platform> (<platform details>) <extensions>

## What's Next?

Do one of the following:

- To configure proxy settings in the base settings, proceed with ["Configuring Proxy Settings in Base Settings" below](#).
- To configure authentication in the base settings, click **NEXT** and proceed with ["Configuring Authentication in Base Settings" on the next page](#).

## Configuring Proxy Settings in Base Settings

To configure proxy settings in the base settings:

1. On the Target page, click **PROXY SETTINGS**.  
The PROXY CONFIGURATION dialog box opens.
2. Select the **Use Proxy Server** option.  
The settings become available for you to configure.
3. Configure the settings according to the following table.

| To...                                                                                                                         | Then...                                                                                                                                                                                                                                                                          |
|-------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Use the Web Proxy Autodiscovery Protocol (WPAD) to locate and use a proxy autoconfig file to configure the web proxy settings | Select <b>Auto detect proxy settings</b> .                                                                                                                                                                                                                                       |
| Import your proxy server information from Firefox                                                                             | Select <b>Use Firefox proxy settings</b> .<br><br><b>Note:</b> Using browser proxy settings does not guarantee that you can access the Internet through a proxy server. If the Firefox browser connection settings are configured for "No proxy," then a proxy will not be used. |
| Load proxy settings from a Proxy Automatic Configuration (PAC) file                                                           | a. Select <b>Configure proxy settings using a PAC file</b> .<br><br>b. In the <b>URL</b> box, type the URL location for the PAC file.                                                                                                                                            |

| To...                                      | Then...                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
|--------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Access the Internet through a proxy server | <ul style="list-style-type: none"><li>a. Select <b>Explicitly configure proxy</b> settings.</li><li>b. In the <b>Server</b> box, enter the URL or IP address of your proxy server.</li><li>c. In the <b>Port</b> box, enter the port number (for example, 8080).</li><li>d. From the <b>Type</b> list, select the protocol type for handling TCP traffic through the proxy server. The options are: <b>Standard</b>, <b>SOCKS4</b>, or <b>SOCKS5</b>.</li><li>e. If authentication is required, select a type from the <b>Authentication</b> list. The options are: <b>None</b>, <b>Basic</b>, <b>NTLM</b>, <b>Digest</b>, <b>Automatic</b>, <b>Kerberos</b>, or <b>Negotiate</b>.</li><li>f. If your proxy server requires authentication, enter the qualifying user name in the <b>User Name</b> field and the qualifying password in the <b>Password</b> field.</li><li>g. If you do not need to use a proxy server to access certain IP addresses (such as internal testing sites), enter the addresses or URLs in the <b>Bypass</b> field. Use commas to separate entries.</li></ul> |

4. Click **OK**.

The proxy settings are saved and the PROXY CONFIGURATION dialog box closes.

## What's Next?

To configure authentication for the scan, click **NEXT** and proceed with ["Configuring Authentication in Base Settings" below](#).

## Configuring Authentication in Base Settings

If your site or network or both require authentication, you can configure it on the Authentication page.

## Configuring Site Authentication

You can use a recorded login macro containing one or more usernames and passwords that allow you to log in to the target site. The macro must also contain a "logout condition," which indicates when an inadvertent logout has occurred so that the sensor can rerun the macro to log in again.

To configure site authentication:

1. Select **Site Authentication**.
2. Do one of the following:
  - To import an existing login macro, click **IMPORT**, and then locate and select the file to import.
  - To record a login macro, click **Open Macro Recorder 6.1**.

**Tip:** If you have not already downloaded and installed the Macro Recorder tool, the Open Macro Recorder 6.1 link will not open the tool. You must first download the tool and install it on your local machine as described in ["Downloading the Macro Recorder Tool" below](#).

## Downloading the Macro Recorder Tool

You can download the Macro Recorder with Macro Engine 6.1 tool from the ScanCentral DAST REST API container.

To download the Macro Recorder tool:

- Under **Site Authentication**, click **Download Macro Recorder 6.1**.

The MacroRecorder64Setup.exe file is downloaded to the default download directory that is specified in your browser settings. Navigate to the download directory and install the EXE file as usual.

**Tip:** After installation, you can launch the Macro Recorder tool from the Windows Start menu under **Fortify ScanCentral DAST**.

## Configuring Network Authentication

If server authentication is required, you can configure authentication using network credentials.

To configure network authentication:

1. Select **Network Authentication**.
2. Select an **Authentication Type**. Options are as follows:
  - **ADFS CBT**
  - **Automatic**
  - **Basic**
  - **Digest**

- **Kerberos**
- **NT LAN Manager (NTLM)**

3. Type the authentication username in the **Username** box.
4. Type the authentication password in the **Password** box.

**Caution!** The sensor crawls all servers granted access by this password (if the sites/servers are included in the Allowed Hosts setting). To avoid potential damage to your administrative systems, do not use credentials that have administrative rights. If you are unsure about your access rights, contact your System Administrator or internal security professional.

## What's Next?

To configure details for the scan, click **NEXT** and proceed with ["Configuring Base Settings Details" below](#).

## Configuring Base Settings Details

You can configure the following settings on the Base Settings Details page:

- Allowed hosts (For more information, see ["Adding and Managing Allowed Hosts in Base Settings" below](#).)
- Scan priority (For more information, see ["Configuring Scan Priority in Base Settings" on page 192](#).)
- Data retention (For more information, see ["Configuring Data Retention in Base Settings" on page 192](#).)
- Single-page application (SPA) support (For more information, see ["Scanning Single-page Applications in Base Settings" on page 192](#).)
- Traffic Monitor (For more information, see ["Using Traffic Viewer \(Traffic Monitor\) in Base Settings" on page 193](#).)
- Exclusions (For more information, see ["Creating and Managing Exclusions in Base Settings" on page 194](#).)
- Redundant page detection (For more information, see ["Configuring Redundant Page Detection in Base Settings" on page 196](#).)

## What's Next?

After you configure the scan details, click **NEXT** and proceed with ["Applying Base Settings to Applications" on page 197](#).

## Adding and Managing Allowed Hosts in Base Settings

Use the **Allowed Hosts** setting to add and manage domains to crawl and audit. If your Web application uses multiple domains, add those domains here. For example, if you were scanning "Wlexample.com," you would need to add "Wlexample2.com" and "Wlexample3.com" here if those domains were part of your Web presence and you wanted to include them in the scan.

You can also use this feature to scan any domain whose name contains the text you specify. For example, suppose you specify `www.myco.com` as the scan target and you enter "myco" as an allowed host. As the sensor scans the target site, if it encounters a link to any URL containing "myco," it will pursue that link and scan that site's server, repeating the process until all linked sites are scanned. For this hypothetical example, the sensor would scan the following domains:

- `www.myco.com:80`
- `contact.myco.com:80`
- `www1.myco.com`
- `ethics.myco.com:80`
- `contact.myco.com:443`
- `wow.myco.com:80`
- `mycocorp.com:80`
- `www.interconnection.myco.com:80`

### Adding Allowed Hosts

To add allowed hosts:

1. Click **MANAGE**.
2. In the SPECIFY ALLOWED HOST dialog box, type a URL in the **Name** box.

**Important!** When you specify the URL, do not include the protocol designator (such as `http://` or `https://`).

3. (Optional) To use a regular expression to represent a URL, select **Use Regular Expression**.
4. Do one of the following:
  - To save the allowed host to the list, click the check mark icon (✓).  
The URL is added to the allowed hosts list. To add another allowed host, return to Step 2.
  - To clear the fields and start over, click the retry icon (↺) and return to Step 2.
5. When the list of allowed hosts is complete, click **OK**.

### Editing or Removing Hosts

To edit or remove an allowed host:

1. Select a host from the **Allowed Hosts** list.
2. Do one of the following:
  - To edit the host name or regular expression, click **MANAGE**.  
The SPECIFY ALLOWED HOST dialog box opens. For more information about using this dialog box, see ["Adding Allowed Hosts" above](#).
  - To remove the host from the allowed hosts list, click **REMOVE**.

## Configuring Scan Priority in Base Settings

Scans are run using a priority ranking from 0 to 10, where 0 is the lowest priority and 10 is the highest. Before starting a scan, the Global Service determines if there is a higher-priority scan that needs to be started. If there is, the lower-priority scan will remain in the queue. Additionally, a lower-priority scan that is running will be paused for a higher-priority scan if no other sensor is available.

If Advanced Scan Prioritization is enabled, the Global Service may move scans to other sensors, depending on scan priority and other settings. For more information about Advanced Scan Prioritization, see ["Understanding Advanced Scan Prioritization" on page 108](#).

**Note:** Applications are configured with a default priority level in the application settings. For more information, see ["Understanding the Application Settings List" on page 199](#).

### Changing the Priority

To select a priority other than the default setting for the scan:

- Select a priority from 0 to 10 in the **Priority** list.

**Note:** If you set a priority that differs from the Application Settings, the lower of the two settings will be used.

**Tip:** You cannot disable scan priority. However, you can set all applications and scans to the same priority to accomplish something similar.

## Configuring Data Retention in Base Settings

If data retention is enabled for the application being scanned, then a default number of days for scan retention is configured in the application settings. In such cases, the default number of days for scan retention is displayed in the Details page. For more information, see ["Working with Application Settings" on page 198](#).

To set a number of days other than the default setting for the scan:

- Enter the number of days in the **Data Retention** box.

**Note:** If you set a number of days that differs from the Application Settings, the lower of the two settings will be used.

## Scanning Single-page Applications in Base Settings

This topic describes single-page application (SPA) support for crawling and auditing the Document Object Model (DOM) of an application.

**Important!** This version of SPA support is provided as a technology preview.



## Technology Preview

Technology preview features are currently unsupported, may not be functionally complete, and are not suitable for deployment in production. These features are provided as a courtesy and the primary objective is to gain wider exposure for the feature with the goal of full support in the future.

## The Challenge of Single-page Applications

Developers use JavaScript frameworks such as Angular, Ext JS, and Ember.js to build SPAs. These frameworks make it easier for developers to build applications, but more difficult for security testers to scan those applications for security vulnerabilities.

Traditional sites use simple back-end server rendering, which involves constructing the complete HTML web page on the server side. SPAs and other Web 2.0 sites use front-end DOM rendering, or a mix of front-end and back-end DOM rendering. With SPAs, if the user selects a menu item, the entire page can be erased and recreated with new content. However, the event of selecting the menu item does not generate a request for a new page from the server. The content update occurs without reloading the page from the server.

With traditional vulnerability testing, the event that triggered the new content might destroy other events that were previously collected on the SPA for audit. Through its SPA support, the dynamic sensor offers a solution to the challenge of vulnerability testing on SPAs.

## Configuring SPA Support

When SPA support is enabled, the DOM script engine finds JavaScript includes, frame and iframe includes, CSS file includes, and AJAX calls during the crawl, and then audits all traffic generated by those events.

To configure SPA support:

- Under **Single-Page Applications** on the Details page, select one of the following options:
  - **Automatic** - If the sensor detects a SPA framework, it automatically switches to SPA-support mode.
  - **Disabled** - Indicates that SPA frameworks are not used in the target application.
  - **Enabled** - Indicates that SPA frameworks are used in the target application.

**Caution!** Enable SPA support for single-page applications only. Enabling SPA support to scan a non-SPA website results in a slow scan.

## Using Traffic Viewer (Traffic Monitor) in Base Settings

The site tree of a scan normally displays only the hierarchical structure of the website or web service, plus those sessions in which a vulnerability was discovered. The Traffic Viewer (or Traffic Monitor) allows you to display and review every HTTP request sent by the sensor and the associated HTTP response received from the web server.

### Proxy Server Included

The Traffic Viewer includes a self-contained proxy server that you can configure and run on your desktop. With it, you can monitor traffic from your browser as it submits HTTP requests and receives responses from a web server. The Traffic Viewer proxy is a tool for debugging and penetration assessment; you can see every request and server response while browsing a site.

### Option Must be Enabled

To use the Traffic Viewer, you must enable Traffic Monitor logging in the scan settings. Otherwise, the Traffic Viewer is not available for a scan.

### Enabling Traffic Viewer (or Traffic Monitor)

To enable the Traffic Viewer (or Traffic Monitor):

- Under **Traffic Analysis** on the Details page, select **Enable Traffic Monitor**.

### Creating and Managing Exclusions in Base Settings

You can exclude URLs and sessions—based on criteria in their requests or responses—from being crawled and audited. Excluding URLs means that the sensor will not examine the specified URL or host for links to other resources. Excluding sessions means that sensor will not process the sessions that meet the exclusion criteria.

To exclude these items from your scan, you must create a list of Basic Exclusions. Each exclusion in the list identifies one or more targets in which the criteria for exclusion is found.

**Note:** You can add multiple targets to each entry in the Basic Exclusions list.

### Creating Exclusions

To create one or more exclusions:

1. Under **Basic Exclusions** on the Details page, click **CREATE**.  
The MANAGE EXCLUSIONS dialog box opens.
2. Type a name for the exclusion in the **Name** box.
3. From the **Target** list, select one of the following target types to configure for exclusion:
  - **Extension** - Excludes file extensions that match the exclusion criteria
  - **Host** - Excludes hosts that match the exclusion criteria
  - **Post parameter** - Excludes sessions with a POST request parameter that matches the exclusion criteria
  - **Query parameter** - Excludes sessions with a query parameter in the URL that matches the exclusion criteria
  - **Request** - Excludes sessions with a request that matches the exclusion criteria

- **Response** – Excludes sessions with a response that matches the exclusion criteria
  - **Response header** - Excludes sessions with a response header that matches the exclusion criteria
  - **Status code** - Excludes sessions with a response status code that match the exclusion criteria
  - **URL** – Excludes URLs that match the exclusion criteria
4. Type a name for the target in the **Name** box.
  5. Select one of the following types of exclusion for the target from the **Type** list:
    - **Matches Regex** – Matches the regular expression you specify in the **String** box
    - **Matches Regex extension** – Matches the regular expression extension you specify in the **String** box
    - **Matches** - Matches the specified criteria in the **String** box
    - **Contains** – Contains the text string you specify in the **String** box
  6. Type the string to match in the **String** box.  
For examples of Target, Type, and String settings, see ["Exclusion Examples" below](#).
  7. Do one of the following:
    - To save the exclusion to the list, click the check mark icon (✓).  
The exclusion is added to the list. To create another exclusion, return to Step 2.
    - To clear the fields and start over, click the retry icon (↺) and return to Step 2.
  8. When the list of exclusions is complete, click **OK**.

### Exclusion Examples

The following table provides examples of exclusions.

| To...                                                                                                                                  | Create the following exclusion... |
|----------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------|
| Ensure that you never send requests to any resource at Microsoft.com                                                                   | URL contains Microsoft.com        |
| Exclude the following directories:<br><br>http://www.test.com/W3SVC55/<br>http://www.test.com/W3SVC5/<br>http://www.test.com/W3SVC550/ | URL matches regex /W3SVC[0-9]*/   |
| Ensure that you never process session responses with 404 Not Found                                                                     | Response contains Not Found       |

For more information about creating exclusions, see ["Understanding and Creating Inclusive Exclusions" on page 114](#).

## Editing or Removing Exclusions

To edit or remove an entry in the **Basic Exclusions** list:

1. Select an entry from the **Basic Exclusions** list.
2. Do one of the following:
  - To edit the exclusion settings, click **MANAGE**.  
The MANAGE EXCLUSIONS dialog box opens. For more information about using this dialog box, see ["Creating Exclusions" on page 194](#).
  - To remove the host from the allowed hosts list, click **REMOVE**.

## Configuring Redundant Page Detection in Base Settings

Highly dynamic sites could create an infinite number of resources (pages) that are virtually identical. If allowed to pursue each resource, the sensor would never be able to finish the scan. The **Perform redundant page detection** option compares page structure to determine the level of similarity, allowing the sensor to identify and exclude processing of redundant resources.

**Important!** Redundant page detection works in the crawl portion of the scan. If the audit introduces a session that would be redundant, the session will not be excluded from the scan.

To configure redundant page detection:

1. Select the **Perform redundant page detection** check box.
2. Configure settings as described in the following table.

| Setting                              | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|--------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Page Similarity Threshold (%)</b> | Indicates how similar two pages must be to be considered redundant. Enter a percentage from 1 to 100, where 100 is an exact match. The default setting is 95 percent.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| <b>Tag attributes to include</b>     | <p>Identifies the tag attributes to include in the page structure. Typically, tag attributes and their values are dropped when determining structure. Identifying tag attributes in this list adds those attributes and their values in the page structure. By default, <code>id</code> and <code>class</code> tag attributes are included. To add tag attributes:</p> <ol style="list-style-type: none"><li>a. Type the attribute name in the <b>Tag item</b> box. Do not include tag brackets (<code>&lt;</code> and <code>&gt;</code>).</li><li>b. Click <b>ADD</b>.</li></ol> <p>The tag attribute is added to the <b>Tag attributes to include</b> list.</p> |

| Setting | Description                                                                                                                                                                                                |
|---------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|         | <b>Tip:</b> Certain sites may be primarily composed of one type of tag, such as <div>. Including these attributes creates a more rigid page match. Excluding these attributes creates a less strict match. |

## Enabling SAST Correlation in Base Settings

SAST correlation correlates the static and dynamic findings for your web application in Fortify Software Security Center. Correlation allows you to see the static findings that were also found in a dynamic scan. It can help you to prioritize which issues to fix and help verify that those issues are not false positives.

To enable SAST correlation:

- Select **Enable SAST Correlation**.

## Applying Base Settings to Applications

Base settings are applied at the application level. Therefore, when configuring base settings, you must select one or more applications to which the settings will apply.

To select applications:

- In the **APPLICATIONS** list on the **Applications** page, select the check box(es) for the application(s) to which you want to apply the settings.

The selected applications are added to the APPLICATIONS SELECTED list.

## What's Next?

After you selected applications, click **NEXT** and proceed with ["Reviewing and Saving Base Settings" below](#).

## Reviewing and Saving Base Settings

On the Review page, you can review a summary of the base settings that you configured and save the settings for others to use.

To save the base settings:

1. On the **Review** page, type a name for the base settings in the **Name** box.
2. Click **SAVE**.

The base settings are added to the DAST database and appear in the base settings list. For more information, see ["Understanding the Base Settings List" on page 178](#).

# Chapter 13: Working with Application Settings

Application settings apply to applications and generally override settings that are made in scan settings. Application settings are created and maintained by Fortify Software Security Center users who have permission to manage ScanCentral DAST deny intervals and other global settings.

## Application Settings are Global Settings

Global settings are those that apply or may apply to all of your applications, scans, scan schedules, sensors, or sensor pools.

## Priority

Scans for an application are run using a priority ranking from 0 to 10, where 0 is the lowest priority and 10 is the highest. Applications are configured with a default priority level in the application settings. For more information, see ["Configuring Scan Priority" on page 107](#) or ["Configuring Scan Priority in Base Settings" on page 192](#).

## Data Retention

When a scan is run, it creates several artifacts, including scan logs, an FPR, a site tree, and a scan file. Configuring data retention settings for an application can aid in preventing your ScanCentral DAST database from becoming full. Purging the scan data from ScanCentral DAST does not delete the FPR from Fortify Software Security Center.

## Accessing the Application Settings

After you configure your Fortify ScanCentral DAST environment and enable DAST in the ADMINISTRATION view in Fortify Software Security Center, you can work with DAST application settings directly in Fortify Software Security Center.

To access DAST application settings in Fortify Software Security Center:

1. Select **SCANCENTRAL > DAST**.  
The scans list appears.

2. In the left panel, select **Application Settings**.

The application settings list appears.

## User Role Determines Capabilities

Your user role and permissions in Fortify Software Security Center determine which tasks you can perform on applications and DAST scans, sensors, sensor pools, settings, and scan schedules. For more information, see ["Permissions in Fortify Software Security Center" on page 27](#).

## Understanding the Application Settings List

The Application Settings list table displays the settings for each of the applications in the ScanCentral DAST database.

You can select the information you want to display, as well as customize other aspects of the table. For more information, see ["Working with Tables" on page 77](#).

The following table describes the columns of information provided for each application in the list.

| Column                | Description                                                                                                                                                                                                                                      |
|-----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Application</b>    | Identifies the application to which the settings apply.                                                                                                                                                                                          |
| <b>Priority</b>       | Specifies the default priority of scans that are run for the application.<br><br>For more information, see <a href="#">"Configuring Scan Priority" on page 107</a> or <a href="#">"Configuring Scan Priority in Base Settings" on page 192</a> . |
| <b>Data Retention</b> | Indicates whether data retention is configured for the scans of the application. Settings are <b>enabled</b> and <b>disabled</b> .                                                                                                               |
| <b>Retention Days</b> | Specifies the number of days to retain scan data in the ScanCentral DAST database.                                                                                                                                                               |

## Managing Application Settings

You can edit existing application settings and refresh the settings that are displayed in the settings list.

## Editing Application Settings

To edit application settings:

1. In the **Application Settings** list, select one or more check boxes for the application settings to edit.
2. Click **EDIT**.

The APPLICATION SETTINGS dialog box opens pre-populated with the selected application settings.

**Note:** If you select multiple application settings to edit, then the APPLICATION SETTINGS dialog box will display default settings rather than those of the selected applications.

3. Continue according to the following table.

| To...                    | Then...                                                                                                                                                                                                                                                  |
|--------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Edit scan priority       | In the <b>Priority</b> drop-down list, select a new priority.                                                                                                                                                                                            |
| Enable data retention    | <ol style="list-style-type: none"><li>a. Slide the <b>Data Retention Disabled</b> toggle to <b>Data Retention Enabled</b>.</li><li>b. In the <b>Number of days for retention</b> box, select a number of days to retain scans in the database.</li></ol> |
| Disable data retention   | Slide the <b>Data Retention Enabled</b> toggle to <b>Data Retention Disabled</b> .                                                                                                                                                                       |
| Enable SAST correlation  | Slide the <b>SAST Correlation Disabled</b> toggle to <b>SAST Correlation Enabled</b> .                                                                                                                                                                   |
| Disable SAST correlation | Slide the <b>SAST Correlation Enabled</b> toggle to <b>SAST Correlation Disabled</b> .                                                                                                                                                                   |

A SAVE COMPLETE dialog box appears.

4. Click **OK**.



## Refreshing the Application Settings List

Generally, the changes that you make to the application settings appear right away on the Application Settings page. However, if other users have access to the same applications, any changes they make will not be updated in your view. To see such changes, you can manually refresh the application settings list.

To view an updated application settings list:

- Click **REFRESH**.

# Appendix A: Troubleshooting ScanCentral DAST

If you encounter issues when setting up your Fortify ScanCentral DAST environment or with using it after a successful set up, the following pages might help determine possible causes and solutions.

## Locating Log Files

This topic provides information about log files generated by the various DAST components, including where to find logs for each component and how to extract log files if necessary.

### Log File Names

The log file name is in the format of YYYY-MM-DD.log, such as 2021-05-04.log. There is one log file per day. If you run the Configuration Tool more than once during a single day, the file is appended with new entries for each successive run.

ScanCentral DAST keeps a maximum of seven log files per service. A new log file is created daily or when a log file reaches 100 MB. The 100 MB limit prevents log files from becoming too large.

### Extracting Log Files

You must use the Docker `cp` command to copy log files from the DAST API, DAST global service, Fortify WebInspect on Docker, and DAST utility service containers to your local file system. If any of the directory paths contain spaces, then you must enclose the path within quotation marks in the Docker `cp` command as shown in the following example:

```
docker cp <ContainerName>:"C:\Program Files\Fortify\<ServiceName>\logs"
<Drive>:\<Directory>
```

### API Logs

To obtain log files for the DAST API, you must extract them while the container is *not* running.

To extract the log files:

1. In PowerShell on the Docker container, enter the following command:

```
docker stop scancentral-dast-api
```

The API container stops.

2. Enter the following command to extract the log files:

```
docker cp scancentral-dast-api:\app\logs <Drive>:\<Directory>
```

The API logs are copied to the directory you specify in the command.

## DAST Configuration Tool Logs

You can find the DAST Configuration Tool log files in the following location:

```
c:\Users\<CurrentUser>\AppData\Local\Programs\das-t.-configuration-  
tool\resources\bin\logs
```

## Global Service Logs

To obtain log files for the DAST global service, you must extract them while the container is *not* running.

To extract the log files:

1. In PowerShell on the Docker container, enter the following command:

```
docker stop scancentral-dast-globalservice
```

The global service container stops.

2. Enter the following command to extract the log files:

```
docker cp scancentral-dast-globalservice:\app\logs <Drive>:\<Directory>
```

The global service logs are copied to the directory you specify in the command.

## Scanner Service Logs

If you are using the Fortify WebInspect on Docker image, then you must extract the scanner service logs while the container is *not* running.

To extract the log files:

1. In PowerShell on the Docker container, enter the following command:

```
docker stop <ContainerName>
```

The container stops.

2. Enter the following command to extract the log files:

```
docker cp <ContainerName>:"C:\Program Files\Fortify\DAST-  
ScannerService\logs" <Drive>:\<Directory>
```

The scanner service logs are copied to the directory you specify in the command.

If you are using a classic Fortify WebInspect installation with the Fortify ScanCentral DAST sensor service, then you can find the scanner service log files in the following location:

```
C:\Program Files\Fortify\DAST-ScannerService\logs
```

## Utility Service Logs

To obtain log files for the DAST utility service, you must extract them while the container is *not* running.

To extract the log files:

1. In PowerShell on the Docker container, enter the following command:

```
docker stop scancentral-dast-utilityservice
```

The utility service container stops.

2. Enter the following command to extract the log files:

```
docker cp scancentral-dast-utilityservice:"C:\Program  
Files\Fortify\DAST-UtilityService\logs" <Drive>:\<Directory>
```

The utility service logs are copied to the directory you specify in the command.

## Troubleshooting the Configuration Tool

If the DAST Configuration Tool fails to create and seed the database or fails at any other point, review the tool log file for errors.

**Tip:** If you need to uninstall the DAST Configuration Tool, an uninstaller is located at:

```
C:\Users\<user>\AppData\Local\Programs\das-t.-configuration-tool\Uninstall  
DAST Config Tool
```

The following table describes possible causes and solutions related to the Configuration Tool.

| Error or Symptom                                    | Possible Cause                                                              | Possible Solution                                                                                                                                                           |
|-----------------------------------------------------|-----------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| The Configuration Tool application does not launch. | Your OS may have the environment variable for HTTP_PROXY set for proxy use. | The Configuration Tool requires that the environment variable for NO_PROXY be set to localhost.<br><br>Refer to your OS documentation and change this environment variable. |
| You configured a proxy                              | The Fortify Software Security Center host name,                             | Do the following:                                                                                                                                                           |

| Error or Symptom                                                                                                                                                                                                                                           | Possible Cause                                                                                                     | Possible Solution                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in the Configuration Tool, but do not want to access Fortify Software Security Center through the proxy. Now the Configuration Tool cannot validate a connection to Fortify Software Security Center using the host name, machine name, or container name. | machine name, or container name is not in the <b>Proxy bypass list</b> .                                           | <ol style="list-style-type: none"> <li>1. Add the Fortify Software Security Center host name, machine name, or container name to the <b>Proxy bypass list</b> on the <b>Environment configuration</b> page. For more information, see <a href="#">"Configuring Environment Settings" on page 45</a>.</li> <li>2. If your OS has an HTTP_PROXY or HTTPS_PROXY environment variable or both, then add the Fortify Software Security Center host name, machine name, or container name in a comma-separated list to the NO_PROXY variable.<br/><br/>For example, if the Fortify Software Security Center URL is <code>http://MySSCMachine:8080/ssc</code>, then the comma-separated list in the NO_PROXY variable would be as follows:<br/><br/><code>localhost,MySSCMachine</code><br/>If the previous steps do not correct the issue, then use the Fortify Software Security Center IP address instead of the host name, machine name, or container name as follows: <ul style="list-style-type: none"> <li>• In the <b>Proxy bypass list</b> on the <b>Environment configuration</b> page</li> <li>• In the <b>SSC URL</b> field under the <b>SSC SETTINGS</b> on the <b>Settings configuration</b> page</li> </ul> </li> </ol> |
| You configured a proxy in the Configuration Tool, but do not want to access the LIM through the proxy. Now                                                                                                                                                 | A known issue prevents using the host name, machine name, or container name in the <b>Proxy bypass list</b> on the | <p>When configuring ScanCentral DAST settings, do one of the following:</p> <ul style="list-style-type: none"> <li>• Use the LIM IP address in the <b>Proxy bypass list</b> on the <b>Environment configuration</b> page.</li> </ul>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |

| Error or Symptom                                                                                                     | Possible Cause                         | Possible Solution                                                                                                                                                                                                                                        |
|----------------------------------------------------------------------------------------------------------------------|----------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| the Configuration Tool cannot validate a connection to the LIM using the host name, machine name, or container name. | <b>Environment configuration</b> page. | <ul style="list-style-type: none"> <li>Clear the <b>Use proxy</b> option and configure HTTP_PROXY and NO_PROXY environment variables instead.</li> </ul> <p>For more information, see <a href="#">"Configuring Environment Settings"</a> on page 45.</p> |

## Troubleshooting Upgrade Issues

If you perform an incomplete upgrade, you may encounter compatibility issues when attempting to use Fortify ScanCentral DAST. The following table describes possible causes and solutions related to upgrade issues.

**Important!** When upgrading your ScanCentral DAST environment, follow these requirements:

- Use the ScanCentral DAST Configuration Tool that is packaged with the version of ScanCentral DAST software that you downloaded. Do *not* use a previous version of the tool.
- Upgrade your Fortify Software Security Center to the current compatible version. For version compatibility, see "Software Integrations for Fortify ScanCentral DAST" in the *Micro Focus Fortify Software System Requirements*.
- Upgrade all ScanCentral DAST components, including the DAST database, DAST API container, DAST Global Service container, DAST Utility Service container, and the Fortify WebInspect on Docker image or the classic Fortify WebInspect installation with the Fortify ScanCentral DAST sensor service.

| Error or Symptom                                                                                                                                                                              | Possible Cause                                                                                                                                              | Possible Solution                                                                                                                                                                                                                                                                                                                     |
|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <p>The following error appears in the global service log file:</p> <pre>IsVersionCompatible failed. ProcessName = DAST.GlobalWorkerService, Version = &lt;DAST Version&gt;, Type = DAST</pre> | The global service attempted to start, but it is not compatible with the database. The DAST database was updated, but the global service container was not. | <p>Do one of the following:</p> <ul style="list-style-type: none"> <li>Use the docker-compose.yml file that the Configuration Tool created when you upgraded your DAST database to upgrade all containers to the same version as your DAST database. For more information, see <a href="#">"Using the Compose File"</a> on</li> </ul> |

| Error or Symptom                                                                                                                                                                                  | Possible Cause                                                                                                                                                                                              | Possible Solution                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                                                                                                                                                                                   |                                                                                                                                                                                                             | <p><a href="#">page 52.</a></p> <ul style="list-style-type: none"> <li>Use the PowerShell scripts that the Configuration Tool created when you upgraded your DAST database to upgrade all containers to the same version as your DAST database. For more information, see <a href="#">"Using PowerShell Scripts" on page 53.</a></li> </ul>                                                                                                                                                                     |
| <p>The following warning appears in the scanner service log file:</p> <pre>Scanner application version is not compatible and will have limited functionality. Version = &lt;dastVersion&gt;</pre> | <p>The scanner service started, but it is not compatible with the database. The DAST database was updated, but the scanner service was not. The service cannot start new scans or create scan settings.</p> | <p>Do one of the following:</p> <ul style="list-style-type: none"> <li>Pull and run a compatible version of the Fortify WebInspect on Docker image. For more information, see the <i>Micro Focus Fortify WebInspect on Docker User Guide</i>.</li> <li>Upgrade your classic Fortify WebInspect installation and upgrade the Fortify ScanCentral DAST sensor service to compatible versions. For more information, see <a href="#">"Using Fortify WebInspect with the Sensor Service" on page 55.</a></li> </ul> |
| <p>The following error appears in the scanner service log file:</p> <pre>IsVersionCompatible failed. ProcessName = DAST.ScannerWorkerService, Version =</pre>                                     | <p>The scanner service attempted to start, but it is not compatible with the database. The DAST database was updated, but the scanner</p>                                                                   | <p>Do one of the following:</p> <ul style="list-style-type: none"> <li>Pull and run a compatible version of the Fortify WebInspect on Docker image. For more</li> </ul>                                                                                                                                                                                                                                                                                                                                         |

| Error or Symptom                                                                                                                                                                                                                                                                                             | Possible Cause                                                                                                                                             | Possible Solution                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>&lt;webInspectVersion&gt;, Type = WebInspect</code>                                                                                                                                                                                                                                                    | <p>service was not.</p>                                                                                                                                    | <p>information, see the <i>Micro Focus Fortify WebInspect on Docker User Guide</i>.</p> <ul style="list-style-type: none"> <li>Upgrade your classic Fortify WebInspect installation and upgrade the Fortify ScanCentral DAST sensor service to compatible versions. For more information, see <a href="#">"Using Fortify WebInspect with the Sensor Service" on page 55</a>.</li> </ul>                                                                                                                                                                                                                                        |
| <p>One of the following errors appears in the utility service log file:</p> <pre>IsVersionCompatible failed. ProcessName = DAST.UtilityWorkerService, Version = &lt;DAST Version&gt;, Type = DAST  IsVersionCompatible failed. ProcessName = DAST.Web.API, Version = &lt;DAST Version&gt;, Type = DAST</pre> | <p>The utility service attempted to start, but it is not compatible with the database. The DAST database was updated, but the utility service was not.</p> | <p>Do one of the following:</p> <ul style="list-style-type: none"> <li>Use the <code>docker-compose.yml</code> file that the Configuration Tool created when you upgraded your DAST database to upgrade all containers to the same version as your DAST database. For more information, see <a href="#">"Using the Compose File" on page 52</a>.</li> <li>Use the PowerShell scripts that the Configuration Tool created when you upgraded your DAST database to upgrade all containers to the same version as your DAST database. For more information, see <a href="#">"Using PowerShell Scripts" on page 53</a>.</li> </ul> |



## Troubleshooting the DAST API

The following table describes possible causes and solutions when you cannot connect to the DAST API from Fortify Software Security Center.

| Error or Symptom                                                                                                                             | Possible Cause                                                                             | Possible Solution                                                                                                                                                                                                                                                                                      |
|----------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| In Fortify Software Security Center, you receive the following error on the ScanCentral DAST page:<br><br>"UNABLE TO CONNECT TO DYNAMIC API" | ScanCentral DAST might be using an untrusted or self-signed certificate.                   | To resolve this issue, do one of the following: <ul style="list-style-type: none"> <li>Ask your administrator to redeploy using a trusted certificate.</li> <li>Navigate to the &lt;ScanCentral DAST API Swagger&gt;, export the certificate, and add it to your trusted certificate store.</li> </ul> |
|                                                                                                                                              | The ScanCentral DAST API URL may be configured improperly.                                 | Do the following: <ol style="list-style-type: none"> <li>Navigate to <b>Administration &gt; Configuration &gt; ScanCentral DAST</b>.</li> <li>Update the URL.</li> </ol>                                                                                                                               |
|                                                                                                                                              | The ScanCentral DAST API might be inaccessible from the current browser.                   | Verify the following: <ul style="list-style-type: none"> <li>The &lt;ScanCentral DAST API Swagger&gt; is not blocked by firewall rules.</li> <li>The host is resolvable by way of DNS.</li> <li>The API service is running properly.</li> </ul>                                                        |
|                                                                                                                                              | Fortify Software Security Center's content security policy (CSP) might be too restrictive. | Ask your administrator to navigate to <b>Administration &gt; Configuration &gt; Security</b> to adjust the CSP policy.                                                                                                                                                                                 |

| Error or Symptom | Possible Cause                                                                                         | Possible Solution                                                                                                                                                                                                                   |
|------------------|--------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                  | Cross-origin resource sharing (CORS) might have been misconfigured when ScanCentral DAST was deployed. | Ask your administrator to run the ScanCentral DAST Configuration Tool to validate CORS is configured properly, and to adjust if necessary.<br><br>For more information, see <a href="#">"Configuring API Settings" on page 47</a> . |

## Troubleshooting DAST Scans

The following table describes possible causes and solutions when a DAST scan fails to start or fails to complete.

| Error or Symptom                                                                                                                                                                            | Possible Cause                                                                                                                                                                                                                                                 | Possible Solution                                                                                                                                                                                                  |
|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| You are running Fortify WebInspect with the DAST sensor service and a scan status is "Failed to Start."                                                                                     | The WebInspect REST API might not be running.                                                                                                                                                                                                                  | Verify that the WebInspect REST API is configured and started. For more information, see <a href="#">"Using Fortify WebInspect with the Sensor Service" on page 55</a> .                                           |
| A scan is stuck in one of the following transitional states: <ul style="list-style-type: none"> <li>Queued</li> <li>Resume Scan Queued</li> <li>Resume Scan Queued Deny Interval</li> </ul> | If the transitional state persists, it could be due to network errors or the scanner service being down. In such cases, the command to resume the scan will not have been sent or the scanner service will not have acknowledged receiving the resume command. | You may see network-related errors in the scanner service log files. Also check the DAST global service log files for any errors. For more information, see <a href="#">"Locating Log Files" on page 202</a> .     |
|                                                                                                                                                                                             |                                                                                                                                                                                                                                                                | To determine if the scanner service is down: <ol style="list-style-type: none"> <li>1. Check the sensor status in the Sensors list. If the status is <b>Offline</b>, then correct this issue first. For</li> </ol> |

| Error or Symptom                                                                                                                                                                                                                                         | Possible Cause                                                                                                                                                                                                                     | Possible Solution                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                                                                                                                                                                                                                                          |                                                                                                                                                                                                                                    | <p>more information, see <a href="#">"Understanding the Sensor List"</a> on page 148.</p> <ol style="list-style-type: none"> <li>2. Ensure that the WebInspect API service is running. For more information, see <a href="#">"Checking and Restarting the WebInspect REST API Service"</a> on page 213.</li> <li>3. Restart the sensor service. For more information, see <a href="#">"Troubleshooting the Sensor Service"</a> on page 214.</li> </ol> |
| <p>A scheduled scan fails to start, and the following entry appears in the global service log file:</p> <pre>Failed to process scan schedule. The scanner assigned is no longer active. ScanScheduleId = &lt;Id&gt;, ScannerId = &lt;ScannerId&gt;</pre> | <p>The scheduled scan was configured with the <b>Use this sensor only</b> option, but the original sensor container that was assigned to the scheduled scan no longer exists due to upgrading the ScanCentral DAST components.</p> | <p>Edit the scheduled scan settings to use the new sensor container. For more information, see <a href="#">"Editing a Schedule"</a> on page 164.</p>                                                                                                                                                                                                                                                                                                   |
| <p>A scan using a client certificate fails upon startup.</p>                                                                                                                                                                                             | <p>The certificate must be a valid CER, PEM, or PFX format.</p>                                                                                                                                                                    | <p>Update the scan settings with a valid client certificate.</p>                                                                                                                                                                                                                                                                                                                                                                                       |
|                                                                                                                                                                                                                                                          | <p>The certificate might not be installed on the machine where the sensor service is running or the private key might not be exportable.</p>                                                                                       | <p>Do one of the following:</p> <ul style="list-style-type: none"> <li>• Install the certificate on the machine where the sensor service is running.</li> <li>• Verify that the certificate's private key is exportable.</li> </ul>                                                                                                                                                                                                                    |
|                                                                                                                                                                                                                                                          | <p>If the certificate is password protected, the password provided might be incorrect.</p>                                                                                                                                         | <p>Update the scan settings with the correct certificate password.</p>                                                                                                                                                                                                                                                                                                                                                                                 |

## Troubleshooting Alerts

Alerts do not always indicate that there is a scan quality issue. Some alerts may be false positive. However, alerts may provide insight into issues that could adversely affect the scan.

**Important!** The alerts feature is provided as a technology preview.

### Technology Preview

Technology preview features are currently unsupported, may not be functionally complete, and are not suitable for deployment in production. However, these features are provided as a courtesy and the primary objective is for the feature to gain wider exposure with the goal of full support in the future.

### Disabling Alerts

You cannot currently disable alerts in the ScanCentral DAST user interface. For assistance in disabling individual alerts, contact Micro Focus Fortify Customer Support. For more information, see ["Preface" on page 17](#).

### Alerts Troubleshooting Table

**Important!** Any solutions involving changes to scan settings must be made for a future scan. You cannot change the scan settings for the current scan.

The following table describes possible causes and solutions for alerts.

| Alert             | Possible Cause                                                                                                                                                               | Possible Solution                                                                                                                                                                                                                                 |
|-------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EXCESSIVE LOGIN   | The login macro has been played an excessive number of times for the number of requests made. The login credentials may be incorrect or the logout signature may be invalid. | Do one of the following: <ul style="list-style-type: none"><li>• Perform troubleshooting procedures on the macro.</li><li>• Record a new login macro.</li></ul> For more information, see the <i>Micro Focus Fortify WebInspect Tools Guide</i> . |
| REDUNDANT CONTENT | Redundant content has been detected.                                                                                                                                         | You might be able to improve performance in a future scan by                                                                                                                                                                                      |

| Alert         | Possible Cause                                                                                                                                   | Possible Solution                                                                                                                                                                                                        |
|---------------|--------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|               |                                                                                                                                                  | enabling redundant page detection. For more information, see <a href="#">"Configuring Redundant Page Detection" on page 116</a> or <a href="#">"Configuring Redundant Page Detection in Base Settings" on page 196</a> . |
| RESPONSE TIME | Responses coming from the Web server are taking longer than average or longer than expected. A longer response time may result in a slower scan. | Check your network connectivity or the performance of the application under test (AUT).                                                                                                                                  |
| WAF DETECTED  | A Web application firewall (WAF) signature has been detected.                                                                                    | Disable the WAF that is protecting the AUT.                                                                                                                                                                              |

## Checking and Restarting the WebInspect REST API Service

You can check to see whether the WebInspect REST API service is running, and then stop and/or restart the service if needed.

### Checking the WebInspect REST API Service Status in a Classic Fortify WebInspect Installation

To check the service status:

- Right-click the **Micro Focus Fortify Monitor** icon.  
If the service is running, you will see the "Stop WebInspect API" option in the menu.

### Restarting the Service in a Classic Fortify WebInspect installation

If the service is currently running, but you need to stop it:

- Right-click the **Micro Focus Fortify Monitor** icon, and then click **Stop WebInspect API**.

To restart the service:

- Right-click the **Micro Focus Fortify Monitor** icon, and then click **Start WebInspect API**.

**Note:** The start option may not be available until the service has fully stopped.

## Checking the WebInspect REST API Service Status in Fortify WebInspect on Docker

To check the service status:

- In Windows PowerShell, enter the following command:

```
Get-Service -Name "WebInspect API"
```

## Restarting the Service for Fortify WebInspect on Docker

**Tip:** If you need to restart both the WebInspect API and the sensor service, restarting the container restarts both.

If the service is currently running, but you need to stop it:

- In Windows PowerShell, enter the following command:

```
net stop "WebInspect API"
```

To start the service again:

- In Windows PowerShell, enter the following command:

```
net start "WebInspect API"
```

## Troubleshooting the Sensor Service

The following table describes possible causes and solutions when the sensor service fails to start.

| Error or Symptom                                                                                                                                                                                          | Possible Cause                                                                                                                                                  | Possible Solution                                                                                                                                                                                                                 |
|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| The sensor service fails to start, and the following entry appears in the scanner service log file:<br><br>The remote certificate is invalid because of errors in the certificate chain:<br>UntrustedRoot | Encrypted communication is used for the DAST API service, but the API SSL certificate is not installed in the Trusted Store on the DAST sensor service machine. | <ol style="list-style-type: none"><li>1. Copy the API SSL certificate from the Configuration Tool artifacts.</li><li>2. Add the certificate to the Trusted Store on the machine where the DAST sensor service will run.</li></ol> |

| Error or Symptom | Possible Cause | Possible Solution                                                                                        |
|------------------|----------------|----------------------------------------------------------------------------------------------------------|
|                  |                | For more information, see <a href="#">"Using Fortify WebInspect with the Sensor Service" on page 55.</a> |

You can check to see whether the sensor service is running, and then stop and/or restart the service if needed, as described in the following paragraphs.

## Checking the Sensor Service Status in a Classic Fortify WebInspect Installation

To check the service status:

1. Open Windows Services Manager (`services.msc`). For more information, refer to your Windows documentation.
2. In Windows Services Manager, look for the service named **ScannerWorkerService**.
3. Check the **Status** column.

## Restarting the Sensor Service in a Classic Fortify WebInspect Installation

If the service is currently running, but you need to stop it:

- In Windows Services Manager, right-click the service named **ScannerWorkerService**, and then select **Stop**.

To restart the service:

- In Windows Services Manager, right-click the service named **ScannerWorkerService**, and then select **Start**.

## Checking the Sensor Service Status in Fortify WebInspect on Docker

To check the service status:

- In Windows PowerShell, enter the following command:  

```
get-process -Name "DAST.ScannerWorkerService"
```

If the service is running, you will see statistics for a process named "DAST.ScannerWorkerService."  
If the service is not running, you will get the following error:

```
get-process : Cannot find a process with the name "WebInspect". Verify the process name and call the cmdlet again.
```

## Restarting the Sensor Service in Fortify WebInspect on Docker

**Tip:** If you need to restart both the WebInspect API and the sensor service, restarting the container restarts both.

If the service is currently running, but you need to stop it:

- In Windows PowerShell, enter the following command:  
`stop-process -Name "DAST.ScannerWorkerService.exe"`

To start the service again:

- In Windows PowerShell, enter the following command:  
`start-process -Name "DAST.ScannerWorkerService.exe"`



# Appendix B: Scanning with a Postman Collection

You can use your existing Postman automation test scripts, also known as collections, to conduct scans of REST API applications. This section provides general information about Postman, tips for creating a good Postman collection, and instructions for manually configuring dynamic tokens for authentication.

## What is Postman?

Postman is an API development environment that allows you to design, collaborate on, and test APIs. Postman lets you create collections for your API calls, where each collection can be organized into subfolders and multiple requests. You can import and export collections, making it easy to share files across your development and testing environment. Using a Collection Runner such as Newman, tests can be run in multiple iterations, saving time on repetitive tests.

## Benefits of a Postman Collection

A REST API application does not expose all the endpoints in a format that a human with a browser or an automated tool can consume. It is often simply a collection of endpoints that accepts various posts, puts, and gets with a specific set of request data. To successfully audit these endpoints, the ScanCentral DAST sensor needs to understand key details about the API. A well-defined Postman collection can expose these endpoints so that the sensor can audit the API application.

## Known Limitations with Postman Variables

ScanCentral DAST does not support Global variables or Data variables in Postman. However, it does support Environment and Collection variables, as well as Local variables in a collection.

As a workaround, you can specify Global variables and Data variables in an Environment, which is a set of variables that you can use in your Postman requests.

## Postman Prerequisites

A Postman collection version 2.0 or 2.1 is required for conducting scans in ScanCentral DAST. The remaining prerequisite software is installed on the Fortify WebInspect Docker image.

However, if you are using a classic Fortify WebInspect installation with the Fortify ScanCentral DAST sensor service, you must install Newman command-line collection runner, Node.js, and Node Package Manager (NPM). For specific version information and additional instructions, see the *Micro Focus Fortify Software System Requirements*.

## Tips for Preparing a Postman Collection

This topic provides tips for creating a good Postman collection.

### Ensure Valid Responses

To get valid responses, the collection must be complete and executable. Requests must include:

- A valid request URL
- The correct HTTP method (POST, GET, PUT, PATCH, or DELETE)
- Valid parameter data that allows proper exercising of the API

For example, if you have a “name” parameter, then you must provide actual sample data such as “King Lear” or “Hamlet,” rather than the default data type “string.”

### Order of Requests

Remember that the order of operations or requests is important. For example, you must create (or POST) sample data to a parameter before you can do a GET or a DELETE operation on the data.

**Tip:** To avoid URL errors while running the collection in the ScanCentral DAST sensor, after bundling the API requests in the correct order in your collection, save each request individually by clicking the request and then clicking **Save**.

### Handling Authentication

If your API requires authentication, you must configure it in the Postman collection. Follow these guidelines when configuring authentication:

- The user credentials must be current and not expired.
- If you use an environment to specify authentication information, select the type of authentication environment in the Postman collection.
- It is possible that not all requests in the collection require authentication or not all requests require the same type of authentication. If this is the case in your collection, be sure to specify the appropriate authentication type for each request in the collection.

**Important!** If session state is lost while using various authentication types in a scan, it will not be restored correctly. For proper restoration of session state, use a login macro or Postman login collection with a single type of authentication.

## Using Static Authentication

When using static authentication, you must hard-code user credentials as a name/value pair in the Postman collection. When the ScanCentral DAST sensor parses the collection file, it determines the type of authentication being used and retrieves the key name and value from the collection. These values are then added to the scan settings.

The ScanCentral DAST sensor supports the following types of static authentication:

- API Key
- Basic
- Bearer Token
- Digest
- NTLM
- OAuth 1.0
- OAuth 2.0

## Using Dynamic Authentication

When using dynamic authentication, you must store the Bearer token or API key authentication variables in either a Postman environment file or a collection file. For example, a Bearer Token may use a variable such as `{{bearerToken}}`.

You must use regular expressions in a response state rule to dynamically supply the Bearer token or API key during the scan. The response state rule provides search and replace options that enable the token or key to be retrieved from a response and then used in future sessions.

## Using a Postman Login Macro

You can provide a login macro and a workflow macro in the form of Postman collection files when configuring scan settings. For example, you can specify a login macro file such as

`LoginBearer.json`. When using a login macro, however, you must also specify a logout condition, such as the regular expression `The\token\sis\snot\svalid`.

## Postman Auto-configuration

Auto-configuration for static authentication is supported when the authentication values are known, such as when the username and password are hard-coded in the authentication section of the collection. If auto-configuration is not disabled, ScanCentral DAST checks the authentication portion of the collection file for valid values that are then applied to the scan settings.

Auto-configuration for dynamic authentication attempts to automatically provide a login macro and response state rule. It is useful when the Bearer token or API key is stored in a variable. If successfully validated, the authentication sessions are added to the sessions table. If a Bearer token was detected

but a stable configuration was not created, then no authentication sessions are added to the sessions table.

**Important!** Auto-configuration for dynamic authentication works only for simple cases using Bearer token authentication.

If auto-configuration fails, you must manually configure authentication. For more information, see ["Manually Configuring Postman Login for Dynamic Tokens" below](#).

## Sample Postman Scripts

Sample code for leveraging the Postman API can be found at <https://github.com/fortify/WebInspectAutomation>.

A sample Postman collection is available for download on the Fortify repository on GitHub at <https://github.com/fortify/WebInspectAutomation/tree/master/PostmanSamples>.

## Manually Configuring Postman Login for Dynamic Tokens

This topic describes how to configure dynamic authentication manually if auto-configuration fails for a Postman scan. Dynamic authentication uses dynamic tokens.

### What are Dynamic Tokens?

Dynamic tokens are authentication tokens that are generated by software and are unique for each instance of authentication. Tokens can be created for a short period of time, and each instance is renewed individually.

### Before You Begin

You must know the following to configure manual login:

- The type of authentication used in your application (such as Bearer, API key, OAuth1.0, OAuth 2.0, Cookie)
- How to create regular expression search arguments

### Process Overview

The process to manually configure login is described in the following table.

| Stage | Description                                                                                                                                                                                                                                                                                                                                                                           |
|-------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1.    | Identify and isolate the login request or requests in a separate Postman collection. For more information, see <a href="#">"Identifying and Isolating the Login Request" below</a> .                                                                                                                                                                                                  |
| 2.    | Create a logout condition regular expression. For more information, see <a href="#">"Creating a Logout Condition with Regular Expressions" below</a>                                                                                                                                                                                                                                  |
| 3.    | Create a response state rule. For more information, see: <ul style="list-style-type: none"><li>• <a href="#">"Creating a Response State Rule for a Bearer Token" on the next page</a></li><li>• <a href="#">"Creating a Response State Rule for an API Key" on the next page</a></li></ul> <div><b>Note:</b> A response state rule is not needed for cookie session management.</div> |

## Identifying and Isolating the Login Request

To identify and isolate the login request:

1. Examine the Postman collection contents to identify the login request.

**Tip:** Typically, the login request is the first request in the Postman collection that obtains an authentication token. However, authentication could involve several requests.

2. Copy this request or multiple requests.
3. Paste the request(s) in a separate file.
4. Save the file as a Postman collection.

## Creating a Logout Condition with Regular Expressions

To create a logout condition:

1. Find several requests that require authentication.
2. Do one of the following:
  - For a bearer token, replace the auth token with an incorrect value and send it to the application.
  - For an API key, send an incorrect APIKey value to the application.
3. Use the reply from these requests to create a regular expression that matches these responses and does not match a valid session.

For example, if you see the word “unauthorized” in most cases, then it is the best word to use in the regular expression, such as:

```
[STATUSCODE]200 AND [BODY]unauthorized
```

If an incorrect APIKey value gets a reply of “{“status”: “Access Deny”}”, then the best regular expression would be:

```
[BODY]Access\sDeny
```

## Creating a Response State Rule for a Bearer Token

To create a response state rule for a bearer token, you must create two regular expressions.

The first regular expression searches all responses for an authentication token update. Typically, this token will be in response to the login request that was identified in Stage 1 of the process.

For example, in the following response, we see a reference to "token."

```
{"success":true,"message":"Authentication  
successful!","token":"eyJhbGciOiJIUzI1NiIs  
InR5cCI6IkpXVCJ9.eyJ1c2VybmFtZSI6ImFkbWluI  
iwiaWF0IjoxNTg1NzQzNzgzLCJleHAiOjE1ODU3NDc  
zOTN9.i8uXa20JQt00t10jd1twRD76jTnsG-0xiU97  
QWy6jkg"}"
```

For this response, we can create the following regular expression:

```
"token": "(?<Token>[-a-zA-Z0-9._~+/\ ]+?=*)"$
```

In this regular expression, the `(?<Token>[-a-zA-Z0-9._~+/\ ]+?=*)` identifies the value of the token.

**Note:** XML uses character escaping. When you use regular expressions that include `<` and `>` symbols in XML format, the `<` symbol escapes with `&lt;` and the `>` symbol escapes with `&gt;`.

The second regular expression indicates where to store this token. For a bearer token, it will be in the “Authorization: Bearer ....” header.

The following is an example for a bearer token:

```
"Authorization:\sBearer\s(?<Token>[^\r\n]*)\r\n"
```

In this second regular expression, the `(?<Token>[^\r\n]*)` identifies the value that should be replaced with the value from the first regular expression.

## Creating a Response State Rule for an API Key

To create a response state rule for an API key, you must create two regular expressions.

The first regular expression searches all responses for an authentication token update. Typically, this token will be in response to the login request that was identified in Stage 1 of the process.

For example, assume that you have a header API key type of auth. A request sends the username and password to the path “/Login” and returns a response similar to the following:

```
"{"success":true,"APIToken":  
  "tp8989ieupgrjynsfbnfgh9ysdopfghsprohjo"}"
```

All protected requests send an “APIKey: ....” header to authorize access.

For this response, we can create the following regular expression:

```
"APIToken": "(?<APIToken>[a-zA-Z0-9]+?)"$
```

**Note:** XML uses character escaping. When you use regular expressions that include < and > symbols in XML format, the < symbol escapes with &lt; and the > symbol escapes with &gt;.

The second regular expression indicates where to store this token. For an APIKey, it could be a custom header name and value or a custom query parameter name and value.

```
APIKey: \s(?<APIToken>[^\r\n]*)\r\n
```

# Appendix C: Reference Lists

The following pages provide a list of policies that are available for use in Fortify ScanCentral DAST, as well as HTTP status codes for reference.

## Policies

A policy is a collection of vulnerability checks and attack methodologies that the Fortify WebInspect sensor deploys against a Web application. Each policy is kept current through SmartUpdate functionality, ensuring that scans are accurate and capable of detecting the most recently discovered threats.

Fortify ScanCentral DAST contains the following packaged policies that you can use to determine the vulnerability of your Web application.

**Note:** This list might not match the policies that you see in your product. SmartUpdate might have added or deprecated policies since this document was produced.

## Best Practices

The Best Practices group contains policies designed to test applications for the most pervasive and problematic web application security vulnerabilities.

- **API:** This policy contains checks that target various issues relevant to an API security assessment. This includes various injection attacks, transport layer security, and privacy violation, but does not include checks to detect client-side issues and attack surface discovery such as directory enumeration or backup file search checks. All vulnerabilities detected by this policy may be directly targeted by an attacker. This policy is not intended for scanning applications that consume Web APIs.
- **CWE Top 25 <version>:** The Common Weakness Enumeration (CWE) Top 25 Most Dangerous Software Errors (CWE Top 25) is a list created by MITRE. The list demonstrates the most widespread and critical software weaknesses that can lead to vulnerabilities in software.
- **DISA STIG <version>:** The Defense Information Systems Agency (DISA) Security Technical Implementation Guide (STIG) provides security guidance for use throughout the application development lifecycle. This policy contains a selection of checks to help the application meet the secure coding requirements of the DISA STIG <version>. Multiple versions of the DISA STIG policy may be available in the **Best Practices** group.
- **General Data Protection Regulation (GDPR):** The EU General Data Protection Regulation (GDPR) replaces the Data Protection Directive 95/46/EC and provides a framework for organizations on how to handle personal data. The GDPR articles that pertain to application security and require businesses to protect personal data during design and development of their products and services



are as follows:

- Article 25, data protection by design and by default, which requires businesses to implement appropriate technical and organizational measures for ensuring that, by default, only personal data that is necessary for each specific purpose of the processing is processed.
- Article 32, security of processing, which requires businesses to protect their systems and applications from accidental or unlawful destruction, loss, alteration, unauthorized disclosure of or access to personal data.

This policy contains a selection of checks to help identify and protect personal data specifically related to application security for the GDPR.

- **NIST-SP80053R5:** NIST Special Publication 800-53 Revision 5 - (NIST SP 800-53 Rev.5) provides a list of security and privacy controls designed to protect federal organizations and information systems from security threats. This policy contains a selection of checks that must be audited to meet the guidelines and standards of NIST SP 800-53 Rev.5.
- **OWASP Application Security Verification Standard (ASVS):** The Application Security Verification Standard (ASVS) is a list of application security requirements or tests that can be used by architects, developers, testers, security professionals, tool vendors, and consumers to define, build, test, and verify secure applications.

This policy uses OWASP ASVS suggested CWE mapping for each category of SecureBase checks to include. Because CWE is a hierarchical taxonomy, this policy also includes checks that map to additional CWEs that are implied from OWASP ASVS suggested CWE using a "ParentOf" relationship.

- **OWASP Top 10 <year>:** This policy provides a minimum standard for web application security. The OWASP Top 10 represents a broad consensus about the most critical web application security flaws. Adopting the OWASP Top 10 is perhaps the most effective first step towards changing the software development culture within your organization into one that produces secure code. Multiple releases of the OWASP Top Ten policy may be available. For more information, consult the [OWASP Top Ten Project](#).
- **SANS Top 25<year>:** The SANS Top 25 Most Dangerous Software Errors provides an enumeration of the most widespread and critical errors, categorized by [Common Weakness Enumeration \(CWE\)](#) identifiers, that lead to serious vulnerabilities in software. These software errors are often easy to find and exploit. The inherent danger in these errors is that they can allow an attacker to take over the software completely, steal data, or prevent the software from working altogether.
- **Standard:** A standard scan includes an automated crawl of the server and performs checks for known and unknown vulnerabilities such as SQL Injection and Cross-Site Scripting as well as poor error handling and weak SSL configuration at the web server, web application server, and web application layers.

## By Type

The By Type group contains policies designed with a specific application layer, type of vulnerability, or generic function as its focus. For instance, the Application policy contains all checks designed to test an application, as opposed to the operating system.

- **Aggressive SQL Injection:** This policy performs a comprehensive security assessment of your web application for SQL Injection vulnerabilities. SQL Injection is an attack technique that takes advantage of non-validated input vulnerabilities to pass arbitrary SQL queries and/or commands through the web application for execution by a backend database. This policy performs a more accurate and decisive job, but has a longer scan time.
- **Apache Struts:** This policy detects supported known advisories against the Apache Struts framework.
- **Blank:** This policy is a template that you can use to build your own policy. It includes an automated crawl of the server and no vulnerability checks. Edit this policy to create custom policies that only scan for specific vulnerabilities.
- **Client-side:** This policy intends to detect all issues that require an attacker to perform phishing in order to deliver an attack. These issues are typically manifested on the client, thus enforcing the phishing requirement. This includes Reflected Cross-site Scripting and various HTML5 checks. This policy may be used in conjunction with the Server-side policy to provide coverage across both the client and the server.
- **Criticals and Highs:** Use the Criticals and Highs policy to quickly scan your web applications for the most urgent and pressing vulnerabilities while not endangering production servers. This policy checks for SQL Injection, Cross-Site Scripting, and other critical and high severity vulnerabilities. It does not contain checks that may write data to databases or create denial-of-service conditions, and is safe to run against production servers.
- **Cross-Site Scripting:** This policy performs a security scan of your web application for cross-site scripting (XSS) vulnerabilities. XSS is an attack technique that forces a website to echo attacker-supplied executable code, such as HTML code or client-side script, which then loads in a user's browser. Such an attack can be used to bypass access controls or conduct phishing expeditions.
- **DISA STIG <version>:** The Defense Information Systems Agency (DISA) Security Technical Implementation Guide (STIG) provides security guidance for use throughout the application development lifecycle. This policy contains a selection of checks to help the application meet the secure coding requirements of the DISA STIG <version>. Multiple versions of the DISA STIG policy may be available in the **By Type** group.
- **Mobile:** A mobile scan detects security flaws based on the communication observed between a mobile application and the supporting backend services.
- **NoSQL and Node.js:** This policy includes an automated crawl of the server and performs checks for known and unknown vulnerabilities targeting databases based on NoSQL, such as MongoDB, and server side infrastructures based on JavaScript, such as Node.js.
- **Passive Scan:** The Passive Scan policy scans an application for vulnerabilities detectable without active exploitation, making it safe to run against production servers. Vulnerabilities detected by this policy include issues of path disclosure, error messages, and others of a similar nature.

- **PCI Software Security Framework <version> (PCI SSF <version>):** The PCI SSF provides a baseline of requirements and guidance for building secure payment systems and software that handle payment transactions. This policy contains a selection of checks that must be audited to meet the secure coding requirements of PCI SSF.
- **Privilege Escalation:** The Privilege Escalation policy scans your web application for programming errors or design flaws that allow an attacker to gain elevated access to data and applications. The policy uses checks that compare responses of identical requests with different privilege levels.
- **Server-side:** This policy contains checks that target various issues on the server-side of an application. This includes various injection attacks, transport layer security, and privacy violation, but does not include attack surface discovery such as directory enumeration or backup file search. All vulnerabilities detected by this policy may be directly targeted by an attacker. This policy may be used in conjunction with the Client-side policy to provide coverage across both the client and the server.
- **SQL Injection:** The SQL Injection policy performs a security scan of your web application for SQL injection vulnerabilities. SQL injection is an attack technique that takes advantage of non-validated input vulnerabilities to pass arbitrary SQL queries and/or commands through the web application for execution by a backend database.
- **Transport Layer Security:** This policy performs a security assessment of your web application for insecure SSL/TLS configurations and critical transport layer security vulnerabilities, such as Heartbleed, Poodle, and SSL Renegotiation attacks.
- **WebSocket:** This policy detects vulnerabilities related to WebSocket implementation in your application.

## Custom

The Custom group contains all user-created policies and any custom policies modified by a user.

## Hazardous

The Hazardous group contains a policy with potentially dangerous checks, such as a denial-of-service attack, that could cause production servers to fail. Use this policy against non-production servers and systems only.

- **All Checks:** An All Checks scan includes an automated crawl of the server and performs all active checks from SecureBase, the database. This scan includes all checks that are listed in the compliance reports that are available in Fortify web application and web services vulnerability scan products. This includes checks for known and unknown vulnerabilities at the web server, web application server, and web application layers.

**Caution!** An All Checks scan includes checks that may write data to databases, submit forms, and create denial-of-service conditions. Fortify strongly recommends using the All Checks policy only in test environments.

## Deprecated Checks and Policies

The following policies and checks are deprecated and are no longer maintained.

- **Application (Deprecated):** The Application policy performs a security scan of your web application by submitting known and unknown web application attacks, and only submits specific attacks that assess the application layer. When performing scans of enterprise level web applications, use the Application Only policy in conjunction with the Platform Only policy to optimize your scan in terms of speed and memory usage.
- **Assault (Deprecated):** An assault scan includes an automated crawl of the server and performs checks for known and unknown vulnerabilities at the web server, web application server, and web application layers. An assault scan includes checks that can create denial-of-service conditions. It is strongly recommended that assault scans only be used in test environments.
- **Deprecated Checks:** As technologies go end of life and fade out of the technical landscape it is necessary to prune the policy from time to time to remove checks that are no longer technically necessary. Deprecated checks policy includes checks that are either deemed end of life based on current technological landscape or have been re-implemented using smart and efficient audit algorithms that leverage latest enhancements of core WebInspect framework.
- **Dev (Deprecated):** A Developer scan includes an automated crawl of the server and performs checks for known and unknown vulnerabilities at the web application layer only. The policy does not execute checks that are likely to create denial-of-service conditions, so it is safe to run on production systems.
- **OpenSSL Heartbleed (Deprecated):** This policy performs a security assessment of your web application for the critical TLS Heartbeat read overrun vulnerability. This vulnerability could potentially disclose critical server and web application data residing in the server memory at the time a malicious user sends a malformed Heartbeat request to the server hosting the site.
- **OWASP Top 10 Application Security Risks - 2010 (Deprecated):** This policy provides a minimum standard for web application security. The OWASP Top 10 represents a broad consensus about what the most critical web application security flaws are. Adopting the OWASP Top 10 is perhaps the most effective first step towards changing the software development culture within your organization into one that produces secure code. This policy includes elements specific to the 2010 Top Ten list. For more information, consult the [OWASP Top Ten Project](#).
- **Platform (Deprecated):** The Platform policy performs a security scan of your web application platform by submitting attacks specifically against the web server and known web applications. When performing scans of enterprise-level web applications, use the Platform Only policy in conjunction with the Application Only policy to optimize your scan in terms of speed and memory usage.
- **QA (Deprecated):** The QA policy is designed to help QA professionals make project release decisions in terms of web application security. It performs checks for both known and unknown web application vulnerabilities. However, it does not submit potentially hazardous checks, making it safe to run on production systems.
- **Quick (Deprecated):** A Quick scan includes an automated crawl of the server and performs checks for known vulnerabilities in major packages and unknown vulnerabilities at the web server, web application server and web application layers. A quick scan does not run checks that are likely to

create denial-of-service conditions, so it is safe to run on production systems.

- **Safe (Deprecated):** A Safe scan includes an automated crawl of the server and performs checks for most known vulnerabilities in major packages and some unknown vulnerabilities at the web server, web application server and web application layers. A safe scan does not run any checks that could potentially trigger a denial-of-service condition, even on sensitive systems.
- **Standard (Deprecated):** Standard (Deprecated) policy is copy of the original standard policy before it was revamped in R1 2015 release. A standard scan includes an automated crawl of the server and performs checks for known and unknown vulnerabilities at the web server, web application server and web application layers. A standard scan does not run checks that are likely to create denial-of-service conditions, so it is safe to run on production systems.

## HTTP Status Codes

The following list of status codes was extracted from the Hypertext Transfer Protocol version 1.1 standard (RFC 2616). You can find more information at <http://www.w3.org/Protocols/>.

| Code                              | Definition                                                                                                                                                                                                                                                                      |
|-----------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 100                               | Continue                                                                                                                                                                                                                                                                        |
| 101                               | Switching Protocols                                                                                                                                                                                                                                                             |
| 200 OK                            | Request has succeeded                                                                                                                                                                                                                                                           |
| 201 Created                       | Request fulfilled and new resource being created                                                                                                                                                                                                                                |
| 202 Accepted                      | Request accepted for processing, but processing not completed.                                                                                                                                                                                                                  |
| 203 Non-Authoritative Information | The returned metainformation in the entity-header is not the definitive set as available from the origin server, but is gathered from a local or a third-party copy.                                                                                                            |
| 204 No Content                    | The server has fulfilled the request but does not need to return an entity-body, and might want to return updated metainformation.                                                                                                                                              |
| 205 Reset Content                 | The server has fulfilled the request and the user agent should reset the document view which caused the request to be sent.                                                                                                                                                     |
| 206 Partial Content               | The server has fulfilled the partial GET request for the resource.                                                                                                                                                                                                              |
| 300 Multiple Choices              | The requested resource corresponds to any one of a set of representations, each with its own specific location, and agent-driven negotiation information (section 12) is being provided so that the user (or user agent) can select a preferred representation and redirect its |

| Code                   | Definition                                                                                                                                                                                    |
|------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                        | request to that location.                                                                                                                                                                     |
| 301 Moved Permanently  | The requested resource has been assigned a new permanent URI and any future references to this resource should use one of the returned URIs.                                                  |
| 302 Found              | The requested resource resides temporarily under a different URI.                                                                                                                             |
| 303 See Other          | The response to the request can be found under a different URI and should be retrieved using a GET method on that resource.                                                                   |
| 304 Not Modified       | If the client has performed a conditional GET request and access is allowed, but the document has not been modified, the server should respond with this status code.                         |
| 305 Use Proxy          | The requested resource MUST be accessed through the proxy given by the Location field.                                                                                                        |
| 306 Unused             | Unused.                                                                                                                                                                                       |
| 307 Temporary Redirect | The requested resource resides temporarily under a different URI.                                                                                                                             |
| 400 Bad Request        | The request could not be understood by the server due to malformed syntax.                                                                                                                    |
| 401 Unauthorized       | The request requires user authentication. The response MUST include a WWW-Authenticate header field (section 14.47) containing a challenge applicable to the requested resource.              |
| 402 Payment Required   | This code is reserved for future use.                                                                                                                                                         |
| 403 Forbidden          | The server understood the request, but is refusing to fulfill it.                                                                                                                             |
| 404 Not Found          | The server has not found anything matching the Request-URI.                                                                                                                                   |
| 405 Method Not Allowed | The method specified in the Request-Line is not allowed for the resource identified by the Request-URI.                                                                                       |
| 406 Not Acceptable     | The resource identified by the request is only capable of generating response entities which have content characteristics not acceptable according to the accept headers sent in the request. |

| Code                                | Definition                                                                                                                                                                                                                                                                                              |
|-------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 407 Proxy Authentication Required   | This code is similar to 401 (Unauthorized), but indicates that the client must first authenticate itself with the proxy.                                                                                                                                                                                |
| 408 Request Timeout                 | The client did not produce a request within the time that the server was prepared to wait.                                                                                                                                                                                                              |
| 409 Conflict                        | The request could not be completed due to a conflict with the current state of the resource.                                                                                                                                                                                                            |
| 410 Gone                            | The requested resource is no longer available at the server and no forwarding address is known.                                                                                                                                                                                                         |
| 411 Length Required                 | The server refuses to accept the request without a defined Content-Length.                                                                                                                                                                                                                              |
| 412 Precondition Failed             | The precondition given in one or more of the request-header fields evaluated to false when it was tested on the server.                                                                                                                                                                                 |
| 413 Request Entity Too Large        | The server is refusing to process a request because the request entity is larger than the server is willing or able to process.                                                                                                                                                                         |
| 414 Request-URI Too Long            | The server is refusing to service the request because the Request-URI is longer than the server is willing to interpret.                                                                                                                                                                                |
| 415 Unsupported Media Type          | The server is refusing to service the request because the entity of the request is in a format not supported by the requested resource for the requested method.                                                                                                                                        |
| 416 Requested Range Not Satisfiable | A server should return a response with this status code if a request included a Range request-header field (section 14.35), and none of the range-specifier values in this field overlap the current extent of the selected resource, and the request did not include an If-Range request-header field. |
| 417 Expectation Failed              | The expectation given in an Expect request-header field (see section 14.20) could not be met by this server, or, if the server is a proxy, the server has unambiguous evidence that the request could not be met by the next-hop server.                                                                |
| 500 Internal Server Error           | The server encountered an unexpected condition which prevented it from fulfilling the request.                                                                                                                                                                                                          |

| Code                           | Definition                                                                                                                                                                                                                                                    |
|--------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 501 Not Implemented            | The server does not support the functionality required to fulfill the request. This is the appropriate response when the server does not recognize the request method and is not capable of supporting it for any resource.                                   |
| 502 Bad Gateway                | The server, while acting as a gateway or proxy, received an invalid response from the upstream server it accessed in attempting to fulfill the request.                                                                                                       |
| 503 Service Unavailable        | The server is currently unable to handle the request due to a temporary overloading or maintenance of the server.                                                                                                                                             |
| 504 Gateway Timeout            | The server, while acting as a gateway or proxy, did not receive a timely response from the upstream server specified by the URI (e.g., HTTP, FTP, LDAP) or some other auxiliary server (e.g., DNS) it needed to access in attempting to complete the request. |
| 505 HTTP Version Not Supported | The server does not support, or refuses to support, the HTTP protocol version that was used in the request message.                                                                                                                                           |



# Send Documentation Feedback

If you have comments about this document, you can [contact the documentation team](#) by email.

**Note:** If you are experiencing a technical issue with our product, do not email the documentation team. Instead, contact Micro Focus Fortify Customer Support at <https://www.microfocus.com/support> so they can assist you.

If an email client is configured on this computer, click the link above to contact the documentation team and an email window opens with the following information in the subject line:

## **Feedback on Configuration and Usage Guide (Fortify ScanCentral DAST 21.2.0)**

Just add your feedback to the email and click send.

If no email client is available, copy the information above to a new message in a web mail client, and send your feedback to [fortifydocteam@microfocus.com](mailto:fortifydocteam@microfocus.com).

We appreciate your feedback!