PROGRESS OF A STATE OF THE PROGRESS OF THE PRO

Administrator's Guide

Version 6.3.5, July 2011



© 2011 Progress Software Corporation and/or its subsidiaries or affiliates. All rights reserved.

These materials and all Progress® software products are copyrighted and all rights are reserved by Progress Soft ware Corporation. The information in these materials is subject to change without notice, and Progress Software Corporation assumes no responsibility for any errors that may appear therein. The references in these materials to specific platforms supported are subject to change.

Actional, Apama, Artix, Business Empowerment, Business Making Progress, DataDirect (and design), DataDi rect Connect, DataDirect Connect64, DataDirect Technologies, DataDirect XML Converters, DataDirect XOuery, DataXtend, Dynamic Routing Architecture, EdgeXtend, Empowerment Center, Fathom, Fuse Media tion Router, Fuse Message Broker, Fuse Services Framework, IntelliStream, IONA, Making Software Work Together, Mindreef, ObjectStore, OpenEdge, Orbix, PeerDirect, POSSENET, Powered by Progress, Pow erTier, Progress, Progress DataXtend, Progress Dynamics, Progress Business Empowerment, Progress Empowerment Center, Progress Empowerment Program, Progress OpenEdge, Progress Profiles, Progress Results, Progress Software Business Making Progress, Progress Software Developers Network, Progress Sonic, ProVision, PS Select, Savvion, SequeLink, Shadow, SOAPscope, SOAPStation, Sonic, Sonic ESB, SonicMO, Sonic Orchestration Server, SpeedScript, Stylus Studio, Technical Empowerment, WebSpeed, Xcalia (and design), and Your Software, Our Technology-Experience the Connection are registered trademarks of Progress Software Corporation or one of its affiliates or subsidiaries in the U.S. and/or other countries. AccelEvent, Apama Dashboard Studio, Apama Event Manager, Apama Event Modeler, Apama Event Store, Apama Risk Firewall, AppsAlive, AppServer, ASPen, ASP-in-a-Box, BusinessEdge, Cache-Forward, CloudEdge, DataDirect Spy, DataDirect SupportLink, Fuse, FuseSource, Future Proof, GVAC, High Performance Integration, Object Store Inspector, ObjectStore Performance Expert, OpenAccess, Orbacus, Pantero, POSSE, ProDataSet, Progress Arcade, Progress CloudEdge, Progress Control Tower, Progress ESP Event Manager, Progress ESP Event Modeler, Progress Event Engine, Progress RFID, Progress RPM, PSE Pro, SectorAlliance, SeeThinkAct, Shadow z/Services, Shadow z/Direct, Shadow z/Events, Shadow z/ Presentation, Shadow Studio, SmartBrowser, SmartComponent, SmartDataBrowser, SmartDataObjects, SmartDataView, SmartDialog, SmartFolder, Smart Frame, SmartObjects, SmartPanel, SmartOuery, SmartViewer, SmartWindow, Sonic Business Integration Suite, Sonic Process Manager, Sonic Collaboration Server, Sonic Continuous Availability Architecture, Sonic Database Service, Sonic Workbench, Sonic XML Server, The Brains Behind BAM, WebClient, and Who Makes Progress are trademarks or service marks of Progress Software Corporation and/or its subsidiaries or affiliates in the U.S. and other countries. Java is a registered trademark of Oracle and/or its affiliates. Any other marks con tained herein may be trademarks of their respective owners.

Third Party Acknowledgements:

Progress Orbix v6.3.5 incorporates Jakarata-struts 1.0.2 from the Apache Software Foundation (http://www.apache.org). Such Apache Technology is subject to the following terms and conditions: The Apache Soft ware License, Version 1.1 Copyright (c) 1999-2001 The Apache Software Foundation. All rights reserved. Redistribution and use in source

and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copy right notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (http://www.apache.org/)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "The Jakarta Project", "Struts", and "Apache Software Foundation" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED ``AS IS'' AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MER CHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DIS CLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBU TORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUEN TIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO. PROCUREMENT OF SUB STITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY. WHETHER IN CONTRACT, STRICT LIA BILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the Apache Soft ware Foun dation. For more information on the Apache Software Foundation, please see http://www.apache.org/>.

Progress Orbix v6.3.5 incorporates Jakarta-bcel 5.0 from the Apache Software Foundation (http:// www.apache.org). Such Apache Technology is subject to the following terms and conditions: The Apache Software License, Version 1.1 Copy right (c) 2001 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the docu mentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (http://www.apache.org/)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "Apache" and "Apache Software Foundation" and "Apache BCEL" must not be used to endorse or promote products derived from this software with out prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", "Apache BCEL", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED "AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES. INCLUDING. BUT NOT LIMITED TO. THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL. EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,

PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSI NESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see http://www.apache.org/>.

Progress Orbix v6.3.5 incorporates Jakarat-regexp 1.2 from the Apache Software Foundation (http:// www.apache.org). Such Apache Technology is subject to the following terms and conditions: The Apache Software License, Version 1.1 Copyright (c) 1999 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistri bution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (http://www.apache.org/)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "The Jakarta Project", "Jakarta -Regexp", and "Apache Software Foundation" and "Apache BCEL" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED ``AS IS'' AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIA BLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL. EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES: LOSS OF USE, DATA, OR PROFITS: OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see http://www.apache.org/>.

Progress Orbix v6.3.5 incorporates the Jakarta-log4j 1.2.6 from the Apache Software Foundation (http://www.apache.org). Such Apache Technology is subject to the following terms and conditions: The Apache Software License, Version 1.1 Copyright (c) 1999 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software

developed by the Apache Software Foundation (http://www.apache.org/)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "log4j" and "Apache Software Foundation" and "Apache BCEL" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written per mission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABIL ITY. WHETHER IN CONTRACT, STRICT LIABILITY. OR TORT (INCLUD ING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see http:// www.apache.org/>.

Progress Orbix v6.3.5 incorporates Ant 1.5 from the Apache Software Foundation (http://www.apache.org). Such technology is subject to the following terms and conditions: The Apache Software License, Version 1.1 Copyright (c) 2000-2002 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution, 3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (http://www.apache.org/)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "Ant" and "Apache Software Foundation" and "Apache BCEL" must not be used to endorse or promote products derived from this software without prior writ ten permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MER CHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS: OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contri butions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see http://www.apache.org/>.

Progress Orbix v6.3.5 incorporates Xalan-j 2.3.1 from the Apache Software Foundation (http:// www.apache.org). Such Apache Technology is subject to the following terms and conditions: The Apache Soft ware License, Version 1.1. Copyright (c) 1999 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (http://www.apache.org/)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "Xalan" and "Apache Software Foundation" and "Apache BCEL" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED "AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MER CHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE. EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see http://www.apache.org/

Progress Orbix v6.3.5 incorporates the Xerces-c++ 2.4 from the Apache Software Foundation (http://www.apache.org). Such Apache Technology is subject to the following terms and conditions: The Apache Software License, Version 1.1. Copyright (c) 1999-2001 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redis tributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (http://www.apache.org/)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "Xerces" and "Apache Software Foundation" and "Apache BCEL" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be

called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANT ABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see http://www.apache.org/.

Progress Orbix v6.3.5 incorporates xerces-j 2.5 from the Apache Software Foundation (http:// www.apache.org). Such Apache Technology is subject to the following terms and conditions: The Apache Software License, Version 1.1. Copy right (c) 1999-2002 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (http://www.apache.org/)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "Xerces" and "Apache Software Foundation" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTIC ULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES: LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see http://www.apache.org/>.

Progress Orbix v6.3.5 incorporates the Tomcat 4.0.4 from the Apache Software Foundation (http://www.apache.org). Such Apache Technology is subject to the following terms and conditions: The Apache Software License, Version 1.1. Copyright (c) 1999, 2000 The Apache Software Foundation. All rights

reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redis tributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (http://www.apache.org/)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "The Jakarta Project", "Tomcat" and "Apache Software Foundation" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED "AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES. INCLUDING BUT NOT LIMITED TO. THE IMPLIED WARRANTIES OF MERCHANT ABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see http://creativecommons.org/linearing-nc-4 www.apache.org/>.

Progress Orbix v6.3.5 incorporates MCPP 2.6.4 from the MCPP Project. Such technology is subject to the following terms and conditions: Copyright (c) 1998, 2002-2007 Kiyoshi Matsui kmatsui@t3.rim.or.ip All rights reserved. This software including the files in this directory is provided under the following license. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. THIS SOFTWARE IS PROVIDED BY THE AUTHOR ``AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCURE MENT OF SUBSTITUTE GOODS OR SERVICES: LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CON TRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Progress Orbix v6.3.5 incorporates Xalan c++ v1.7 from The Apache Software Foundation. Such technology is subject to the following terms and conditions: The Apache Software License, Version 1.1

Copyright (c) 1999-2004 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redis tributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (http://www.apache.org/)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "Xalan" and "Apache Software Foundation" must not be used to endorse or promote prod ucts derived from this software without prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED "AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICU LAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL. EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation and was originally based on software copyright (c) 1999, Lotus Development Corporation., http://www.lotus.com. For more information on the Apache Software Foundation, please see http://www.apache.org/>.

Progress Orbix v6.3.5 incorporates Tcl 8.4.15 from Regents of the University of California, Sun Microsystems, Inc., Scriptics Corporation, and other parties. Such technology is subject to the following terms and conditions: This software is copyrighted by the Regents of the University of California, Sun Microsystems, Inc., Scriptics Corporation, and other parties. The following terms apply to all files associated with the software unless explicitly disclaimed in individual files. The authors hereby grant permission to use, copy, modify, distribute, and license this software and its documentation for any purpose, provided that existing copyright notices are retained in all copies and that this notice is included verbatim in any distributions. No written agreement, license, or royalty fee is required for any of the authorized uses. Modifications to this software may be copyrighted by their authors and need not follow the licensing terms described here, provided that the new terms are clearly indicated on the first page of each file where they apply. IN NO EVENT SHALL THE AUTHORS OR DISTRIBUTORS BE LIABLE TO ANY PARTY FOR DIRECT, INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OF THIS SOFTWARE, ITS DOCUMENTATION, OR ANY DERIVATIVES THEREOF. EVEN IF THE AUTHORS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. THE AUTHORS AND DISTRIBUTORS SPE CIFICALLY DISCLAIM ANY WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WAR RANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, AND NON-INFRINGEMENT.

THIS SOFTWARE IS PROVIDED ON AN "AS IS" BASIS, AND THE AUTHORS AND DISTRIBUTORS HAVE NO OBLIGATION TO PROVIDE MAINTENANCE, SUPPORT, UPDATES, ENHANCEMENTS, OR MODIFI CATIONS. GOVERNMENT USE: If you are acquiring this software on behalf of the U.S. government, the Government shall have only "Restricted Rights" in the software and related documentation as defined in the Federal Acquisition Regulations (FARs) in Clause 52.227.19 (c) (2). If you are acquiring the software on behalf of the Department of Defense, the software shall be classified as "Commercial Computer Software" and the Government shall have only "Restricted Rights" as defined in Clause 252.227-7013 (c) (1) of DFARs. Notwithstanding the foregoing, the authors grant the U.S. Government and others acting in its behalf permission to use and distribute the software in accordance with the terms specified in this license.

Progress Orbix v6.3.5 incorporates bzip2 1.0.2 from Julian Seward. Such Technology is subject to the following terms and conditions: This program, "bzip2" and associated library "libbzip2", are copyright (C) 1996-2002 Julian R Seward. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2.

The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required. 3. Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software. 4. The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission. THIS SOFTWARE IS PROVIDED BY THE AUTHOR "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING BUT NOT LIMITED TO. THE IMPLIED WARRANTIES OF MERCHANT ABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. Julian Seward, Cambridge, UK. iseward@acm.org bzip2/libbzip2 version 1.0.2 of 30 December 2001.

Progress Orbix v6.3.5 incorporates zlib 1.2.3 from Jean-loup Gailly and Mark Adler. Such Technology is subject to the following terms and conditions: License /* zlib.h -- interface of the 'zlib' general purpose compression library version 1.2.3, July 18th, 2005 Copyright (C) 1995-2000 Jean-loup Gailly and Mark Adler. This software is provided 'as-is', without any express or implied warranty. In no event will the authors be held liable for any damages arising from the use of this software. Permission is granted to anyone to use this software for any purpose, including commercial applications, and to alter it and redistribute it freely, subject to the following restrictions: 1. The origin of this software must not be mis represented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required. 2. Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software. 3. This notice may not be removed or altered from any source distribution. Jean-loup Gailly jloup@gzip.org Mark Adler madler@alumni.caltech.edu */

Progress Orbix v6.3.5 incorporates the MinML 1.7 from John Wilson. Such Technology is subject to the following terms and conditions: Copyright (c) 1999, John Wilson (tug@wilson.co.uk). All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: Redistributions of source code must retain the above copyright notice... this list of conditions and the following disclaimer. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following dis claimer in the documentation and/or other materials provided with the distribution. All advertising materials mention ing features or use of this software must display the following acknowledgement: This product includes software devel oped by John Wilson. The name of John Wilson may not be used to endorse or promote products derived from this software without specific prior written permission. THIS SOFTWARE IS PROVIDED BY JOHN WILSON "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL JOHN WILSON BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABIL ITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Progress Orbix v6.3.5 incorporates JDOM vbeta9 from JDOM. Such Technology is subject to the following terms and conditions: LICENSE.txt, v 1.10 2003/04/10 08:36:05 jhunter Exp \$ Copyright (C) 2000-2003 Jason Hunter & Brett McLaughlin. All rights reserved. Redistribution and use in source and binary forms, with or with out modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions, and the following disclaimer. 2. Redistribu tions in binary form must reproduce the above copyright notice, this list of conditions, and the dis claimer that follows these conditions in the documentation and/or other materials provided with the distribution. 3. The name "JDOM" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact < license AT jdom DOT org>. 4. Prod ucts derived from this soft ware may not be called "JDOM", nor may "JDOM" appear in their name, without prior written permission from the JDOM Project Management AT jdom DOT org>. In addition, we request (but do not require) that you include in the end-user documentation provided with the redistribution and/or in the soft ware itself an acknowledgement equivalent to the following: "This product includes software developed by the JDOM Project (http://www.jdom.org/)." Alternatively, the acknowledgment may be graphical using the logos available at http://www.jdom.org/ images/logos. THIS SOFTWARE IS PROVIDED "AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WAR RANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DIS CLAIMED. IN NO EVENT SHALL THE JDOM AUTHORS OR THE PROJECT CONTRIBUTORS BE LIA BLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS: OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABIL ITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the JDOM Project and was originally created by Jason Hunter <jhunter AT jdom DOT org> and Brett McLaughlin

 for more information on the JDOM Project, please see <http://www.jdom.org/>.

Progress Orbix v6.3.5 incorporates OpenSSL 0.9.8i Copyright (c) 1998-2008 The OpenSSL Project Copyright (c) 1995-1998 Eric A. Young, Tim J. Hudson All rights reserved. Such Technology is subject to the following terms and conditions: The OpenSSL toolkit stays under a dual license, i.e. both the conditions of the OpenSSL License and the original SSLeav license apply to the toolkit. See below for the actual license texts. Actually both licenses are BSD-style Open Source licenses. In case of any license issues related to OpenSSL please contact openssl-core@openssl.org. OpenSSL License - Copyright (c) 1998-2008 The OpenSSL Project. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted pro vided that the following conditions are met: 1. Redistributions of source code must retain the above copy right notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. All advertising materials mentioning features or use of this software must display the following acknowledgment: "This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit. (http://www.openssl.org/)" 4. The names "OpenSSL Toolkit" and "OpenSSL Project" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact openssl-core@openssl.org. 5. Products derived from this software may not be called "OpenSSL" nor may "OpenSSL" appear in their names without prior written permission of the OpenSSL Project. 6. Redistributions of any form whatsoever must retain the following acknowledgment: "This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit (http://www.openssl.org/)" THIS SOFTWARE IS PROVIDED BY THE OpenSSL PROJECT ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES. INCLUDING BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE OpenSSL PROJECT OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT. INDIRECT. INCIDENTAL. SPECIAL. EXEMPLARY, OR CONSEQUENTIAL DAM AGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERV ICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This product includes cryp tographic software written by Eric Young (eay@cryptsoft.com). This product includes software written by Tim Hudson (tih@cryptsoft.com). - Original SSLeav License - Copyright (C) 1995-1998 Eric Young (eay@crypt soft.com) All rights reserved. This package is an SSL implementation written by Eric Young (eay@crypt soft.com). The implementation was written so as to conform with Netscapes SSL. This library is free for commercial and non-commer cial use as long as the following conditions are aheared to. The following conditions apply to all code found in this distribution, be it the RC4, RSA, lhash, DES, etc., code; not just the SSL code. The SSL documentation included with this distribution is covered by the same copyright terms except that the holder is Tim Hudson (tih@cryptsoft.com), Copy right remains Eric Young's, and as such any Copyright notices in the code are not to be removed. If this package is used in a product, Eric Young should be given attribution as the author of the parts of the library used. This can be in the form of a textual message at program startup or in documentation (online or textual) provided with the package. Redistri bution and use in source and binary forms, with or with out modification, are permitted

provided that the following conditions are met: 1. Redistributions of source code must retain the copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of con ditions and the following dis claimer in the documentation and/or other materials provided with the distribution. 3. All advertising materials mention ing features or use of this software must display the following acknowledge ment: "This product includes crypto graphic software written by Eric Young (eay@cryptsoft.com)" The word 'cryptographic' can be left out if the rou tines from the library being used are not crypto graphic related:-). 4. If you include any Windows specific code (or a deriv ative thereof) from the apps directory (application code) you must include an acknowledgement: "This product includes software written by Tim Hudson (tjh@cryptsoft.com)" THIS SOFTWARE IS PROVIDED BY ERIC YOUNG ``AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANT ABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPE CIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCURE MENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT. STRICT LIABILITY. OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE. EVEN IF ADVISED OF THE POSSI BILITY OF SUCH DAMAGE. The licence and distribution terms for any publically available version or deriva tive of this code cannot be changed. i.e. this code cannot simply be copied and put under another distribution licence [including the GNU Public Licence.]

Progress Orbix v6.3.5 incorporates PCRE v7.8 from the PCRE Project. Such Technology is subject to the following terms and conditions:

PCRE LICENCE

PCRE is a library of functions to support regular expressions whose syntax and semantics are as close as possible to those of the Perl 5 language. Release 7 of PCRE is distributed under the terms of the "BSD"licence, as specified below. The documentation for PCRE, supplied in the "doc" directory, is distributed under the same terms as the software itself. The basic library functions are written in C and are freestanding. Also included in the distribution is a set of C++ wrapper functions.

THE BASIC LIBRARY FUNCTIONS

Written by: Philip Hazel Email local part: ph10 Email domain: cam.ac.uk

University of Cambridge Computing Service,

Cambridge, England.

Copyright (c) 1997-2008 University of Cambridge

All rights reserved.

THE C++ WRAPPER FUNCTIONS

Administrator's Guide

Contributed by: Google Inc.

Copyright (c) 2007-2008, Google Inc.

All rights reserved.
THE "BSD" LICENCE

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. Neither the name of the University of Cambridge nor the name of Google Inc. nor the names of their contributors may be used to endorse or promote products derived from this software without specific prior written permission. THIS SOFT WARE IS PRO VIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRAN TIES OF MERCHANT ABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT. INDI RECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCURE MENT OF SUBSTITUTE GOODS OR SERVICES: LOSS OF USE, DATA, OR PROFITS: OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Progress Orbix v6.3.5 incorporates IDL Compiler Front End 1 from Sun Microsystems, Inc. Copyright 1992, 1993, 1994 Sun Microsystems, Inc. Printed in the United States of America. All Rights Reserved. Such tech nology is subject to the following terms and conditions: This product is protected by copyright and distrib uted under the following license restricting its use. The Interface Definition Language Compiler Front End (CFE) is made available for your use provided that you include this license and copyright notice on all media and documentation and the software program in which this product is incorporated in whole or part. You may copy and extend functionality (but may not remove functionality) of the Interface Definition Language CFE without charge, but you are not authorized to license or distribute it to anyone else except as part of a product or program developed by you or with the express written consent of Sun Microsystems, Inc. ("Sun"). The names of Sun Microsystems, Inc. and any of its subsidiaries or affiliates may not be used in advertising or publicity per taining to distribution of Interface Definition Language CFE as permitted herein. This license is effective until termi nated by Sun for failure to comply with this license. Upon termination, you shall destroy or return all code and documentation for the Interface Definition Language CFE. INTERFACE DEFINITION LANGUAGE CFE IS PROVIDED AS IS WITH NO WARRANTIES OF ANY KIND INCLUDING THE WARRANTIES OF DESIGN, MERCHANTIBILITY AND FITNESS FOR A PARTICULAR PURPOSE, NONINFRINGEMENT, OR ARISING FROM A COURSE OF DEALING, USAGE OR TRADE PRACTICE. INTERFACE DEFINITION LANGUAGE CFE IS PROVIDED WITH NO SUPPORT AND WITHOUT ANY OBLIGATION ON THE PART OF Sun OR ANY OF ITS SUBSIDIARIES OR AFFILIATES TO ASSIST IN ITS USE, CORREC TION, MODIFICATION OR ENHANCEMENT. SUN OR ANY OF ITS SUBSIDIARIES OR AFFILIATES SHALL HAVE NO LIABILITY WITH RESPECT TO THE INFRINGEMENT OF COPYRIGHTS. TRADE SECRETS OR ANY PATENTS BY INTERFACE DEFINITION LANGUAGE CFE OR ANY

PART THEREOF. IN NO EVENT WILL SUN OR ANY OF ITS SUBSIDIARIES OR AFFILIATES BE LIABLE FOR ANY LOST REVENUE OR PROFITS OR OTHER SPECIAL, INDIRECT AND CONSE QUENTIAL DAMAGES, EVEN IF SUN HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. Use, duplication, or disclosure by the government is subject to restrictions as set forth in subpara graph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.227-7013 and FAR 52.227-19. Sun, Sun Microsystems and the Sun logo are trademarks or registered trademarks of Sun Microsystems, Inc. SunSoft, Inc. 2550 Garcia Avenue, Mountain View, California 94043 NOTE: SunOS, Sun Soft, Sun, Solaris, Sun Microsystems or the Sun logo are trademarks or registered trademarks of Sun Micro systems, Inc.

Progress Orbix v6.3.5 incorporates LibXML2 2.4.24 from Daniel Veillard. Such Technology is subject to the following terms and conditions: Except where otherwise noted in the source code (trio files, hash.c and list.c) covered by a similar license but with different Copyright notices: Copyright (C) 1998-2002 Daniel Veillard. All Rights Reserved. Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including with out limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Soft ware, and to permit persons to whom the Software is furnished to do so, subject to the following conditions: The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software. THE SOFTWARE IS PROVIDED "AS IS". WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTA BILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE DANIEL VEILLARD BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIA BILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE. Except as contained in this notice, the name of Daniel Veillard shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization from him.

=== trio.c, trio.h: Copyright (C) 1998 Bjorn Reese and Daniel Stenberg. Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies. THIS SOFTWARE IS PROVIDED "AS IS" AND WITH OUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTIBILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE AUTHORS AND CONTRIB UTORS ACCEPT NO RESPONSIBILITY IN ANY CONCEIVABLE MANNER. ==== triop.h: Copyright (C) 2000 Bjorn Reese and Daniel Stenberg. Permission to use, copy, modify, and dis tribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies. THIS SOFTWARE IS PROVIDED "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTIBILITY AND FITNESS FOR A PARTIC ULAR PURPOSE. THE AUTHORS AND CONTRIBUTORS ACCEPT NO RESPONSIBILITY IN ANY CONCEIVABLE MANNER.

==== hash.c: Copyright (C) 2000 Bjorn Reese and Daniel Veillard. Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permis sion notice appear in all copies. THIS SOFTWARE IS PROVIDED "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHAN TIBILITY AND FITNESS FOR A

PARTICULAR PURPOSE. THE AUTHORS AND CONTRIBUTORS ACCEPT NO RESPONSIBILITY IN ANY CONCEIVABLE MANNER.

==== list.c: Copyright (C) 2000 Gary Pennington and Daniel Veillard. Permission

to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies. THIS SOFTWARE IS PROVIDED ``AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTIBILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE AUTHORS AND CONTRIBUTORS ACCEPT NO RESPONSIBILITY IN ANY CONCEIVABLE MANNER. ===

triodef.h, trionan.c, trionan.h: Copyright (C) 2001 Bjorn Reese Permission to use, copy, modify, and distribute this soft ware for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permis sion notice appear in all copies. THIS SOFTWARE IS PROVIDED ``AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MER CHANTIBILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE AUTHORS AND CONTRIBUTORS ACCEPT NO RESPONSIBILITY IN ANY CONCEIVABLE MANNER.

==== triostr.c, triostr.h: Copyright (C) 2001 Bjorn Reese and Daniel Stenberg.

Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, pro vided that the above copyright notice and this permission notice appear in all copies. THIS SOFTWARE IS PRO VIDED ``AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTIBILITY AND FITNESS FOR A PARTICULAR PUR POSE. THE AUTHORS AND CONTRIBUTORS ACCEPT NO RESPONSIBILITY IN ANY CONCEIVABLE MANNER.

Progress Orbix v6.3.5 incorporates ICU library 2.6 from IBM. Such Technology is subject to the following terms and conditions: Copyright (c) 1995-2009 International Business Machines Corporation and others. All rights reserved. Per mission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documenta tion files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, and/or sell copies of the Software, and to permit persons to whom the Soft ware is fur nished to do so, provided that the above copyright notice(s) and this permission notice appear in all copies of the Software and that both the above copyright notice(s) and this permission notice appear in supporting documentation. THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY. FITNESS FOR A PARTICU LAR PUR POSE AND NONINFRINGEMENT OF THIRD PARTY RIGHTS. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR HOLDERS INCLUDED IN THIS NOTICE BE LIABLE FOR ANY CLAIM, OR ANY SPECIAL INDIRECT OR CONSEQUENTIAL DAMAGES, OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TOR TIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE. Except as contained in this notice, the name of a copyright holder shall not be used in advertising or other wise to promote the sale, use or other dealings in this Software without prior written authorization of the copyright holder. All trademarks and registered trademarks mentioned herein are the property of their respective owners.

Updated: July 29, 2011

Contents

List of Figures	xvii
List of Tables	xix
Preface	xxi
Part I Introduction	
Chapter 1 The Orbix Environment	1
Basic CORBA Model	2
Simple Orbix Application	4
Portable Object Adapter	5
Broader Orbix Environment	7
Managing Object Availability	8
Scaling Orbix Environments with Configuration Domains	11
Using Dynamic Orbix Applications	14
Orbix Administration	15
Chapter 2 Selecting an Orbix Environment Model	17
Orbix Development Environment Models	18
Independent Development Environments	19
Distributed Development and Test Environments	22
Configuration Models	23
Getting the Most from Your Orbix Environment	26
Using Capabilities of Well-Designed Orbix Applications	27
Using the Right Data Storage Mechanism	29
Getting the Most from Orbix Configuration	30

Part II Managing an Orbix Environment

Chapter 3 Managing Orbix Configuration	33
How an ORB Gets its Configuration	34
Locating the Configuration Domain	36
Obtaining an ORB's Configuration	38
Configuration Variables and Namespaces	45
Managing Configuration Domains	47
Chapter 4 Managing Persistent CORBA Servers	49
Introduction	50
Registering Persistent Servers	51
Server Environment Settings	56
Windows Environment Settings	57
UNIX Environment Settings	58
Managing a Location Domain	60
Managing Server Processes	61
Managing the Locator Daemon	62
Managing Node Daemons	65
Listing Location Domain Data	68
Modifying a Location Domain	69
Ensuring Unique POA Names	70
Using Direct Persistence	72
CORBA Applications	73
Orbix Services	77
Chapter 5 Configuring Scalable Applications	79
Fault Tolerance and Replicated Servers	81
About Replicated Servers	82
Automatic Replica Failover	85
Direct Persistence and Replica Failover	86
Building a Replicated Server	89
Example 1: Building a Replicated Server to Start on Demand	90
Example 2: Updating a Replicated Server	93
Example 3: Dynamically Changing the Load Balancing Algorithm	94
Replicating Orbix Services	95
PSS Master-Slave Replication	98

Active Connection Management	103
Setting Buffer Sizes	105
Chapter 6 Managing the Naming Service	107
Naming Service Administration	107
Naming Service Commands	111
Controlling the Naming Service	112
Building a Naming Graph	113
Creating Naming Contexts	115
Creating Name Bindings	116
Maintaining a Naming Graph	118
Managing Object Groups	119
Chapter 7 Managing an Interface Repository	121
Interface Repository	122
Controlling the Interface Repository Daemon	123
Managing IDL Definitions	124
Browsing Interface Repository Contents	125
Adding IDL Definitions	127
Removing IDL Definitions	128
Chapter 8 Managing the Firewall Proxy Service	131
Orbix Firewall Proxy Service	132
Configuring the Firewall Proxy Service	133
Known Restrictions	136
Chapter 9 Managing Orbix Service Databases	137
Berkeley DB Environment	138
Performing Checkpoints	139
Managing Log File Size	140
Troubleshooting Persistent Exceptions	141
Database Recovery for Orbix Services	142
Replicated Databases	147
Chapter 10 Configuring Orbix Compression	149
Introduction	150
Configuring Compression	152

Example Configuration	156
Message Fragmentation	158
Chapter 11 Configuring Advanced Features	159
Configuring Java NIO	160
Configuring Internet Protocol Version 6	163
Configuring Shared Memory	166
Configuring Bidirectional GIOP	168
Enabling Bidirectional GIOP	169
Migration and Interoperability Issues	172
Chapter 12 Orbix Mainframe Adapter	175
CICS and IMS Server Adapters	176
Using the Mapping Gateway Interface	177
Locating Server Adapter Objects Using itmfaloc	181
Part III Monitoring Orbix Applications	40=
Chapter 13 Configuring Orbix Logging	187
Setting Logging Filters	188
Logging Subsystems	190
Logging Severity Levels	192
Configuring Log Output	194
Dynamic Logging	198
Chapter 14 Monitoring GIOP Message Content	201
Introduction to GIOP Snoop	202
Configuring GIOP Snoop	203
GIOP Snoop Output	206
Chapter 15 Debugging IOR Data	213
IOR Data Formats	214
Using iordump	217
iordump Output	219
Stringified Data Output	222
ASCII-Hex Data Output	223

Data, Warning, Error and, Information Text	224
Errors	225
Warnings	228
Part IV Command Reference	
Starting Orbix Services	233
Starting and Stopping Configured Services	234
Starting Orbix Services Manually	235
itconfig_rep run	236
itlocator run	237
itnode_daemon run	238
itnaming run	240
itifr run	241
itevent run	242
itnotify run	243
Stopping Services Manually	244
Event Log	245
logging get	245
logging set	246
Managing Orbix Services With itadmin	247
Using itadmin	248
Command Syntax	251
Services and Commands	254
Bridging Service	255
bridge create	256
bridge destroy	257
bridge list	257
bridge show	257
bridge start	257
bridge stop	257
bridge suspend	257
endpoint admin show	258

endpoint destroy	258
endpoint list	258
endpoint show	259
JMS Broker	260
jms start	260
jms stop	260
Configuration Domain	261
Configuration Repository	262
config dump	262
config list_servers	263
config show_server	263
config stop	264
file_to_cfr.tcl	264
Namespaces	266
namespace create	266
namespace list	267
namespace remove	268
namespace show	268
Scopes	269
scope create	269
scope list	269
scope remove	270
scope show	270
Variables	271
variable create	271
variable modify	273
variable remove	274
variable show	274
Event Service	275
Event Service Management	276
event show	276
event stop	277
Event Channel	278
ec create	279
ec create_typed	279
ec list	279

ec remove	280
ec remove_typed	280
ec show	281
ec show_typed	281
Interface Repository	283
IDL Definitions	284
idl -R=-v	284
Repository Management	285
ifr cd	285
ifr destroy_contents	286
ifr ifr2idl	286
ifr list	286
ifr pwd	286
ifr remove	287
ifr show	287
ifr stop	287
Location Domain	289
Locator Daemon	290
locator heartbeat_daemons	290
locator list	291
locator show	291
locator stop	292
Named Key	293
named_key create	294
named_key list	294
named_key remove	295
named_key show	295
Node Daemon	296
node_daemon list	297
node_daemon remove	297
node_daemon show	297
.node_daemon stop	298
add_node_daemon.tcl	298
ORB Name	300
orbname create	300
orbname list	300

orbname modify	301
orbname remove	302
orbname show	303
POA	304
poa create	304
poa list	307
poa modify	307
poa remove	309
poa show	310
Server Process	311
process create	311
process disable	314
process enable	314
process kill	314
process list	315
process modify	316
process remove	318
process show	319
process start	320
process stop	321
Mainframe Adapter	323
mfa add	325
mfa change	325
mfa delete	326
mfa -help	326
mfa list	326
mfa refresh	327
mfa reload	327
mfa resetcon	327
mfa resolve	328
mfa save	328
mfa stats	329
mfa stop	329
mfa switch	329
Naming Service	331
Names	332

ns bind	332
ns list	333
ns list_servers	333
ns newnc	333
ns remove	334
ns resolve	334
ns show_server	335
ns stop	335
ns unbind	335
Object Groups	336
nsog add_member	337
nsog bind	337
nsog create	338
nsog list	338
nsog list_members	338
nsog modify	339
nsog remove	339
nsog remove_member	340
nsog set_member_timeout	340
nsog show_member	341
nsog update_member_load	342
Notification Service	343
Notification Service Management	344
notify checkpoint	344
notify post_backup	345
notify pre_backup	345
notify show	345
notify stop	347
Event Channel	348
nc create	348
nc list	349
nc remove	350
nc show	350
nc set_qos	351
Object Transaction Service	355
tx begin	355

tx commit	356
tx resume	356
tx rollback	357
tx suspend	357
Object Transaction Service Encina	359
encinalog add	360
encinalog add_mirror	361
encinalog create	361
encinalog display	362
encinalog expand	363
encinalog init	364
encinalog remove_mirror	364
otstm stop	365
Persistent State Service	367
pss_db archive_old_logs	368
pss_db checkpoint	368
pss_db delete_old_logs	369
pss_db list_replicas	369
pss_db name	369
pss_db post_backup	369
pss_db pre_backup	370
pss_db remove_replica	370
pss_db show	371
Security Service	373
Logging On	375
admin_logon	375
Managing Checksum Entries	376
checksum confirm	376
checksum create	377
checksum list	377
checksum new_pw	378
checksum remove	378
Managing Pass Phrases	379
kdm_adm change_pw	379
kdm adm confirm	380

kdm_adm create	380
kdm_adm list	381
kdm_adm new_pw	382
kdm_adm remove	382
Trading Service	383
Trading Service Administrative Settings	384
trd_admin get	384
trd_admin set	386
trd_admin stop	388
Federation Links	389
trd_link create	389
trd_link list	390
trd_link modify	390
trd_link remove	391
trd_link show	392
Regular Offers	393
trd_offer list	393
trd_offer remove	393
trd_offer show	394
Proxy Offers	395
trd_proxy list	395
trd_proxy remove	395
trd_proxy show	396
Type Repository	397
trd_type list	397
trd_type mask	397
trd_type remove	398
trd_type show	398
trd_type unmask	399
Part V Appendices	
Appendix A Orbix Windows Services	403
Managing Orbix Services on Windows	405
Orbix Windows Service Commands	406
continue	406

help	407
install	407
pause	407
prepare	407
query	408
run	408
stop	408
uninstall	408
Orbix Windows Service Accounts	409
Running Orbix Windows Services	411
Logging Orbix Windows Services	412
Uninstalling Orbix Windows Services	413
Troubleshooting Orbix/Windows Services	414
Appendix B Run Control Scripts for Unix Platforms	415
Solaris	417
AIX	420
HP-UX	424
IRIX	428
Red Hat Linux	431
Appendix C ORB Initialization Settings	435
Domains directory	436
Domain name	436
Configuration directory	437
ORB name	437
Initial reference	438
Default initial reference	438
Product directory	439
Appendix D Development Environment Variables	441
IT IDL CONFIG FILE	441
IT_IDLGEN_CONFIG_FILE	442
Appendix E Named Keys for Orbix Services	443
Orbix Service Named Key Strings	444
Configuration for Advertising Services	447

Glossary	449
Index	457

List of Figures

Figure 1: Basic CORBA Model	3
Figure 2: Overview of a Simple Orbix Application	4
Figure 3: A POA's Role in Client-Object Communication	5
Figure 4: Simple Configuration Domain and Location Domain	12
Figure 5: Multiple Configuration Domains	13
Figure 6: An Independent Development and Test Environment	19
Figure 7: Multiple Independent Development and Test Environments	20
Figure 8: A Distributed Development and Test Environment	22
Figure 9: Orbix Environment with Local Configuration	24
Figure 10: Orbix Environment with Centralized Configuration	25
Figure 11: How an Orbix Application Obtains its Configurations	34
Figure 12: Hierarchy of Configuration Scopes	38
Figure 13: Replicated Naming Service	96
Figure 14: Naming Context Graph	113
Figure 15: Overview of ZIOP Compression	150
Figure 16: Locator Service Details	409

List of Tables

Table 1: Configuration Domain Management Tasks	47
Table 2: Commands that List Location Domain Data	68
Table 3: Commands that Modify a Location Domain	69
Table 4: Commands that Remove Location Domain Components	69
Table 5: Naming Graph Maintenance Commands	118
Table 6: Orbix Logging Subsystems	190
Table 7: Orbix Logging Severity Levels	193
Table 8: Commands to Manually Start Orbix Services.	235
Table 9: Commands for Stopping Orbix Services	244
Table 10: Event Log Commands	245
Table 11: Bridging Service Commands	255
Table 12: JMS Broker Commands	260
Table 13: Configuration Repository Commands	262
Table 14: Configuration Namespace Commands	266
Table 15: Configuration Scope Commands	269
Table 16: Configuration Variable Commands	271
Table 17: Event Service Commands	276
Table 18: Event Channel Commands	278
Table 19: Interface Repository Commands	285
Table 20: Locator Daemon Commands	290
Table 21: Named Key Commands	293
Table 22: Node Daemon Commands	296
Table 23: ORB Name Commands	300
Table 24: POA Commands	304
Table 25: Server Process Commands	311

LIST OF TABLES

Table 26: Mainframe Adapter itadmin Commands	323
Table 27: Naming Service Commands	332
Table 28: Object Group Commands	336
Table 29: Notification Service Commands	344
Table 30: Event Channel Commands	348
Table 31: Object Transaction Service Commands	355
Table 32: Persistent State Service Commands	367
Table 33: Checksum Entry Commands	376
Table 34: Pass Phrase Commands	379
Table 35: Trading Service Commands	384
Table 36: Federation Link Commands	389
Table 37: Regular Offer Commands	393
Table 38: Proxy Offer Commands	395
Table 39: Server Type Repository Commands	397
Table 40: Orbix Service Key Strings	444
Table 41: Advertise Service Configuration Variables	447

Preface

Introduction

Orbix is a software environment for building and integrating distributed object-oriented applications. Orbix provides a full implementation of the Common Object Request Broker Architecture (CORBA) from the Object Management Group (OMG). Orbix is compliant with version 2.4 of the OMG'S CORBA specification. This guide explains how to configure and manage the components of an Orbix environment.

Audience

This guide is aimed at administrators managing Orbix environments, and programmers developing Orbix applications.

Organization

This guide is divided into the following parts:

- Introduction introduces the Orbix environment, and the basic concepts required to understand how it works.
- Managing an Orbix Environment explains how to manage each component of an Orbix environment. It provides task-based information and examples.
- Command Reference provides a comprehensive reference for all Orbix configuration variables and administration commands.
- Appendices explain how to use Orbix components as Windows NT services. They also provide reference information for initialization parameters and environment variables.

Related documentation

Orbix documentation also includes the following related books:

- Management User's Guide
- Deployment Guide
- CORBA Programmer's Guide
- CORBA Programmer's Reference
- CORBA Code Generation Toolkit Guide

Additional resources

The following additional resources are available:

 The most up-to-date versions of Orbix technical documentation are available from:

http://communities.progress.com/pcom/docs/DOC-105909

- The Orbix Knowledge Base is a database of articles that contain practical advice on specific development issues, contributed by developers, support specialists, and customers. This is available from: http:// www.progress.com/orbix/orbix-support.html
- Contact Orbix technical support at: http://www.progress.com/orbix/orbix-support.html

Document conventions

This guide uses the following typographical conventions:

Constant width

Constant width font in normal text represents commands, portions of code and literal names of items (such as classes, functions, and variables). For example, constant width text might refer to the itadmin orbname create command.

Constant width paragraphs represent information displayed on the screen or code examples. For example the following paragraph displays output from the itadmin orbname list command:

ifr
naming
production.test.testmgr
production.server

Italic

Italic words in normal text represent emphasis and new terms (for example, *location domains*).

Code italic

Italic words or characters in code and commands represent variable values you must supply; for example, process names in your particular system:

itadmin process create process-name

Code bold

Code bold font is used to represent values that you must enter at the command line. This is often used in conjunction with constant width font to distinguish

between command line input and output. For example: itadmin process list

ifr naming my_app

The following keying conventions are observed:

No prompt	When a command's format is the same for multiple platforms, a prompt is not used.
8	A percent sign represents the UNIX command shell prompt for a command that does not require root privileges.
#	A number sign represents the UNIX command shell prompt for a command that requires root privileges.
>	The notation > represents the DOS or Windows command prompt.
	Horizontal ellipses in format and syntax descriptions indicate that material has been eliminated to simplify a discussion.
[]	Italicized brackets enclose optional items in format and syntax descriptions.
{}	Braces enclose a list from which you must choose an item in format and syntax descriptions.
1	A vertical bar separates items in a list of choices. Individual items can be enclosed in {} (braces) in format and syntax descriptions.

Part I

Introduction

				-	,
1	pai	ic	th	ln	
	oai	IIS.	τn	ın	

This part contains the following chapters:

The Orbix Environment	page 1
Selecting an Orbix Environment Model	page 17

The Orbix Environment

Orbix is a network software environment that enables programmers to develop and run distributed applications.

Overview

This chapter introduces the main components of an Orbix environment, explains how they interact, and gives an overview of Orbix administration.

In this chapter

This chapter contains the following sections:

Basic CORBA Model	page 2
Simple Orbix Application	page 4
Broader Orbix Environment	page 7
Orbix Administration	page 15

Basic CORBA Model

Overview

An Orbix environment is a networked system that makes distributed applications function as if they are running on one machine in a single process space. Orbix relies on several kinds of information, stored in various components in the environment. When the environment is established, programs and Orbix services can automatically store their information in the appropriate components.

To establish and use a proper Orbix environment, administrators and programmers need to know how the Orbix components interact, so that applications can find and use them correctly. This chapter starts with a sample application that requires a minimal Orbix environment. Gradually, more services are added.

The basic model for CORBA applications uses an object request broker, or *ORB*. An ORB handles the transfer of messages from a client program to an object located on a remote network host. The ORB hides the underlying complexity of network communications from the programmer. In the CORBA model, programmers create standard software objects whose member methods can be invoked by client programs located anywhere in the network. A program that contains instances of CORBA objects is known as a *server*.

When a client invokes a member function on a CORBA object, the ORB intercepts the function call. As shown in Figure 1, the ORB redirects the function call across the network to the target object. The ORB then collects results from the function call and returns these to the client.




Figure 1: Basic CORBA Model

Simple Orbix Application

Overview

A simple Orbix application might contain a client and a server along with one or more objects (see Figure 2). In this model, the client obtains information about the object it seeks, using *object references*. An object reference uniquely identifies a local or remote object instance.




Figure 2: Overview of a Simple Orbix Application

How an ORB enables remote invocation

Figure 2 shows how an ORB enables a client to invoke on a remote object:

- When a server starts, it creates one or more objects and publishes their
 object references in a *naming service*. A naming service uses simple names
 to make object references accessible to prospective clients. Servers can
 also publish object references in a file or a URL.
- 2. The client program looks up the object reference by name in the naming service. The naming service returns the server's object reference.
- The client ORB uses the object reference to pass a request to the server object

Portable Object Adapter

Overview

For simplicity, Figure 2 on page 4 omits details that all applications require. For example, Orbix applications use a portable object adapter, or *POA*, to manage access to server objects. A POA maps object references to their concrete implementations on the server, or *servants*. Given a client request for an object, a POA can invoke the referenced object locally.

POA functionality

A POA can divide large sets of objects into smaller, more manageable subsets; it can also group related objects together. For example, in a ticketing application, one POA might handle reservation objects, while another POA handles payment objects.

Figure 3 shows how the POA connects a client to a target object. In this instance, the server has two POAs that each manage a different set of objects.




Figure 3: A POA's Role in Client–Object Communication

POA names

Servers differentiate between several POAs by assigning them unique names within the application. The object reference published by the server contains the complete or *fully qualified POA name* (*FQPN*) and the object's ID. The client request embeds the POA name and object ID taken from the published object reference. The server then uses the POA name to invoke the correct POA. The POA uses the object ID to invoke the desired object, if it exists on the server.

Limitations of a simple application

This simple model uses a naming service to pass object references to clients. It has some limitations and does not support all the needs of enterprise-level applications. For example, naming services are often not designed to handle frequent updates. They are designed to store relatively stable information that is not expected to change very often. If a process stops and restarts frequently, a new object reference must be published with each restart. In production environments where many servers start and stop frequently, this can overwork a naming service. Enterprise applications also have other needs that are not met by this simple model—for example, on-demand activation, and centralized administration. These needs are met in a broader Orbix environment, as described in the next section.

Broader Orbix Environment

Overview

Along with the naming service, Orbix offers a number of features that are required by many distributed applications, for flexibility, scalability, and ease of use. These include:

- Location domains enable a server and its objects to move to a new process or host, and to be activated on demand.
- Configuration domains let you organize ORBs into independently manageable groups. This brings scalability and ease of use to the largest environments.
- The interface repository allows clients to discover and use additional objects in the environment—even if clients do not know about these objects at compile time.
- The *event service* allows applications to send events that can be received by multiple objects.

In this section

This section discusses the following topics:

Managing Object Availability	page 8
Scaling Orbix Environments with Configuration Domains	page 11
Using Dynamic Orbix Applications	page 14

Managing Object Availability

Overview

A system with many servers cannot afford the overhead of manually assigned fixed port numbers, for several reasons:

- Over time, hardware upgrades, machine failures, or site reconfiguration require you to move servers to different hosts.
- To optimize resource usage, rarely used servers only start when they are needed, and otherwise are kept inactive.
- To provide fault tolerance and high availability for critical objects, they
 can be run within redundant copies of a server. In case of server overload
 or failure, clients can transparently reconnect to another server

Orbix location domains provide all of these benefits, without requiring explicit programming.

Transient and persistent objects

A server makes itself available to clients by publishing interoperable object references, or *IOR*s. An IOR contains an object's identity and address. This address can be of two types, depending on whether the object is transient or persistent:

- The IORs of transient objects always contain the server host machine's
 address. A client that invokes on this object sends requests directly to the
 server. If the server stops running, the IORs of its transient objects are no
 longer valid, and attempts to invoke on these objects raise the
 OBJECT_NOT_EXIST exception.
- The IORs of persistent objects are exported from their server with the
 address of the domain's *locator daemon*. This daemon is associated with a
 database, or *implementation repository*, which dynamically maps
 persistent objects to their server's actual address.

Invocations on persistent objects

When a client invokes on a persistent object, Orbix locates the object as follows:

- 1. When a client initially invokes on the object, the client ORB sends the invocation to the locator daemon.
- The locator daemon searches the implementation repository for the actual address of a server that runs this object in the implementation repository.
 The locator daemon returns this address to the client.

3. The client connects to the returned server address and directs this and all subsequent requests for this object to that address.

All of this work is transparent to the client. The client never needs to contact the locator daemon explicitly to obtain the server's location.

Locator daemon benefits

Using the locator daemon provides two benefits:

- By interposing the locator daemon between client and server, a location domain isolates the client from changes in the server address. If the server changes location—for example, it restarts on a different host, or moves to another port—the IORs for persistent objects remain valid. The locator daemon supplies the server's new address to clients.
- Because clients contact the locator daemon first when they initially invoke
 on an object, the locator daemon can launch the server on behalf of the
 client. Thus, servers can remain dormant until needed, thereby optimizing
 use of system resources.

Components of an Orbix location domain

An Orbix location domain consists of two components: a locator daemon and a node daemon:

locator daemon: A CORBA service that acts as the control center for the entire location domain. The locator daemon has two roles:

- Manage the configuration information used to find, validate, and activate servers running in the location domain.
- Act as the contact point for clients trying to invoke on servers in the domain.

node daemon: Acts as the control point for a single host machine in the system. Every machine that runs an server must run a node daemon. The node daemon starts, monitors, and manages servers on its machine. The locator daemon relies on node daemons to start processes and tell it when new processes are available.

Scaling Orbix Environments with Configuration Domains

Overview

Small environments with a few applications and their ORBs can be easy to administer manually: you simply log on to systems where the ORBs run and adjust configuration files as needed. However, adding more ORBs can substantially increase administrative overhead. With configuration domains, you can scale an Orbix environment and minimize overhead.

Grouping related applications

Related application ORBs usually have similar requirements. A configuration domain defines a set of common configuration settings, which specify available services and control ORB behavior. For example, these settings define libraries to load at runtime, and initial object references to services.

File- and repository-based configurations

Configuration domain data can be maintained in two ways:

- As a set of files distributed among domain hosts.
- In a centralized configuration repository.

Each ORB gets its configuration data from a domain, regardless of how it is implemented. Orbix environments can have multiple configuration domains organized by application, by geography, by department, or by some other appropriate criteria. You can divide large environments into smaller, independently manageable Orbix environments.

Simple configuration domain and location domain

Figure 4 shows a simple configuration, where all ORBs are configured by the same domain. Such a configuration is typical of small environments. In fact, many environments begin with this configuration and grow from there.




Figure 4: Simple Configuration Domain and Location Domain

Multiple configuration and location domains

Figure 5 shows an environment with multiple configuration domains. This environment can be useful in a organization that must segregate user groups. For example, separate configurations can be used for production and finance departments, each with different security requirements. In this environment, all clients and servers use the same locator daemon; thus, the two configuration domains are encompassed by a single location domain.




Figure 5: Multiple Configuration Domains

Using Dynamic Orbix Applications

Overview

Within the CORBA model, client programs can invoke on remote objects, even if those objects are written in a different programming language and run on a different operating system. CORBA's Interface Definition Language (*IDL*) makes this possible. IDL is a declarative language that lets you define interfaces that are independent of any particular programming language and operating system.

Orbix includes a CORBA IDL compiler, which compiles interface definitions along with the client and server code. A client application compiled in this way contains internal information about server objects. Clients use this information to invoke on objects.

This model restricts clients to using only those interfaces that are known when the application is compiled. Adding new features to clients requires programmers to create new IDL files that describe the new interfaces and to recompile clients along with the new IDL files.

Orbix provides an interface repository, which enables clients to call operations on IDL interfaces that are unknown at compile time. The interface repository (IFR) provides centralized persistent storage of IDL interfaces. Orbix programs can query the interface repository at runtime, to obtain information about IDL definitions.

Managing an interface repository

Administrators and programmers can use interface repository management commands to add, remove, and browse interface definitions in the repository. Interfaces and types that are already defined in a system do not need to be implemented separately in every application. They can be invoked at runtime through the interface repository. For more details on managing an interface repository, see Chapter 7.

Orbix Administration

Overview

Orbix services, such as the naming service, and Orbix components, such as the configuration repository, must be configured to work together with applications. Applications themselves also have administration needs.

This section identifies the different areas of administration. It explains the conditions in the environment and in applications that affect the kind of administration you are likely to encounter. Orbix itself usually requires very little administration when it is set up and running properly. Applications should be easy to manage when designed with management needs in mind.

Administration tasks

Orbix administration tasks include the following:

- Managing an Orbix environment
- Application deployment and management
- Troubleshooting

Managing an Orbix environment

This involves starting up Orbix services, or adding, moving, and removing Orbix components. For example, adding an interface repository to a configuration domain, or modifying configuration settings (for example, initial references to Orbix services). Examples of location domain management tasks include starting up the locator daemon and adding a node daemon. See Part II of this manual for more information.

Application deployment and management

An application gets its configuration from configuration domains, and finds persistent objects through the locator daemon. Both the configuration and location domains must be modified to account for application requirements. For more information, see Chapter 3.

Troubleshooting

You can set up Orbix logging in order to collect system-related information, such as significant events, and warnings about unusual or fatal errors. For more information, see Chapter 13.

Administration tools

The Orbix itadmin command interface lets you control all aspects of Orbix administration. Administration commands can be executed from any host. For detailed reference information about Orbix administration commands, see Part IV of this manual.

Selecting an Orbix Environment Model

This chapter shows different ways in which Orbix can be configured in a network environment.

In this chapter

This chapter contains the following sections:

Orbix Development Environment Models	page 18
Configuration Models	page 23
Getting the Most from Your Orbix Environment	page 26
Getting the Most from Orbix Configuration	page 30

Orbix Development Environment Models

Overview

Business applications must be capable of scaling to meet enterprise level needs. Such applications often extend beyond departments, and even beyond corporate boundaries. Orbix domain and service infrastructures offer a framework for building and running applications that range from small, department-level applications to full-scale enterprise applications with multiple servers and hundreds or thousands of clients.

This chapter offers an overview of Orbix environment models that can handle one or many applications. It also explains Orbix configuration mechanisms, and how to scale an Orbix environment to support more applications, more users, and a wider geographical area. For detailed information on how to set up your Orbix environment, see the *Orbix Deployment Guide*.

Orbix development environments

Orbix development environments are used for creating or modifying Orbix applications. A minimal Orbix development environment consists of the Orbix libraries and the IDL compiler, along with any prerequisite C++ or Java files and development tools.

Application testing requires deployment of Orbix runtime services, such as the configuration repository and locator daemon, naming service, and interface repository.

In environments with multiple developers, each developer must install the Orbix development environment, and the necessary C++ or Java tools. Runtime services can either be installed in each development environment, or distributed among various hosts and accessed remotely.

In this section

This section discusses the following topics:

Independent Development Environments	page 19
Distributed Development and Test Environments	page 22

Independent Development Environments


Overview

This section discusses some typical models of Orbix development (and testing) environments. Actual development environments might contain any one or a blend of these models.

Testing and deployment environment

Figure 6 shows a simple environment that can support application development and testing.

Windows NT



Note. C++ or Java tools must exist on each development platform.

A dotted outline indicates an optional runtime service.


Figure 6: An Independent Development and Test Environment

To test an application, it must first be deployed. This involves populating the necessary Orbix repositories (for example, the configuration domain, location domain, and naming service), with appropriate Orbix application data.

This private environment is useful for testing applications on a local scale before introducing them to an environment distributed across a network. Figure 6 shows this environment on Windows NT, but it can be established on any supported platform.

Multiple private environments

Figure 7 is a variant of the model shown in Figure 6 on page 19. In this model, multiple private environments are established on a single multi-user machine. Each of these private environments can be used to create, deploy, and test applications.



Note. C++ or Java tools must exist on each development platform.

A dotted outline indicates an optional runtime service.

Figure 7: Multiple Independent Development and Test Environments

Setting up independent environments

To establish independent development and test environments, first ensure that the appropriate C++ or Java libraries are present. You should then install Orbix on the desired platforms. For information on what C++ or Java libraries are required, and instructions on how to install Orbix, see the *Orbix Installation Guide*.


For information on how to configure and deploy Orbix runtime services in your environment (for example, a locator daemon), see the *Orbix Deployment Guide*.

Distributed Development and Test Environments

Overview

Figure 8 on page 22 illustrates a runtime test environment shared by multiple development platforms. This scenario more closely models the distributed environments in which applications are likely to run. Most applications should be tested in an environment like this before they are deployed into a production environment.

To establish this environment, install the Orbix runtime services in your environment. Ensure that the appropriate C++ or Java libraries are present on your development platforms. Then install the Orbix developer's kit on each platform. For information on how to configure and deploy Orbix runtime services such as the interface repository in your environment, see *Orbix Deployment Guide*.



A dotted outline indicates an optional runtime service.

Figure 8: A Distributed Development and Test Environment

Configuration Models

Overview

Orbix provides two configuration mechanisms:

- Local file-based configuration
- Configuration repository

For information on managing Orbix configuration domains, see Chapter 3.

Local file-based configuration

A local configuration model is suitable for environments with a small number of clients and servers, or when configuration rarely changes. The local configuration mechanism supplied by Orbix uses local configuration files.

Figure 9 on page 24 shows an example Orbix environment where the configuration is implemented in local files on client and server machines.

The Orbix components in Figure 9 on page 24 consist of Orbix management tools, the locator daemon, and configuration files that store the configuration of the Orbix components. When Orbix is installed, it stores its configuration in the same configuration file, but in a separate configuration scope. Application clients store their configurations in files on their host machines. Application clients and servers also include necessary Orbix runtime components, but for simplicity these are not shown in Figure 9 on page 24.

This simple model is easy to implement and might be appropriate for small applications with just a few clients. Keeping these separate files properly updated can become difficult as applications grow or more servers or clients are added.

You can minimize administrative overhead by using a centralized configuration file, which is served to many ORBs using NFS, Windows Networking, or a similar network service. A centralized file is easier to maintain than many local files, because only one file must be kept updated.




Figure 9: Orbix Environment with Local Configuration

Configuration repository

A centralized configuration model is suitable for environments with a potentially large number of clients and servers, or when configuration is likely to change. The Orbix configuration repository provides a centralized database for all configuration information.

The Orbix components in Figure 10 on page 25 consist of the Orbix management tools, the locator daemon, and a configuration repository. The configuration repository stores the configuration for all Orbix components. When servers and clients are installed, they store their configuration in separate configuration scopes in the configuration repository. Application clients and servers also include their own Orbix runtime components, but these are not shown.

This model is highly scalable because more applications can be added to more hosts in the environment, without greatly increasing administration tasks. When a configuration value changes, it must be changed in one place only. In this model, the host running Orbix, the configuration repository, and locator daemon must be highly reliable and always available to all clients and servers.




Figure 10: Orbix Environment with Centralized Configuration

Getting the Most from Your Orbix Environment

Overview

As you add more or larger applications to your Orbix environment, scalability becomes more crucial. This section discusses some Orbix features that support scalability, and shows how to use them. The following topics are discussed:

- "Using Capabilities of Well-Designed Orbix Applications" on page 27
- "Using the Right Data Storage Mechanism" on page 29

Moving other Orbix services (for example, a naming service), or moving servers also requires some administration to ensure continuation of these services. However, handling these changes is relatively simple and does not involve much administration.

Using Capabilities of Well-Designed Orbix Applications

Orbix optimizations

Like a major highway, Orbix is designed to handle a lot of traffic. For example, when Orbix clients seek their configuration from a centralized configuration mechanism, they compare the version of the locally cached configuration to the version of the live configuration. If versions match, the client uses the cached version. Not reading the entire configuration from the central repository saves time and network bandwidth. Many other programmatic techniques are used throughout Orbix to make it efficient. On the administrative side, proper domain management keeps applications and their clients in an orderly, efficient, and scalable framework.

For such reasons, most applications and environments will not come close to any limitations imposed by Orbix. It is more likely that other network or host-related limitations will get in the way first. Nevertheless, extremely large applications, or large environments with huge numbers of applications and users, are special cases and there are guidelines for keeping such applications and their environments running smoothly.

Special cases

For example, imagine a very large database application with thousands of POAs registered with the locator daemon. If a server restarts, programmatic re-registering of POA state information with the locator daemon can take some time, and even slow down other applications that are using the locator daemon. In such cases, programmers should use the Orbix dynamic activation capability to avoid an unnecessary server-side bottleneck. With dynamic activation, POAs are registered during application deployment. POA state information is handled only if an object is invoked, and only for the POA that is hosting the object.

Looking now at the client side of very large applications, imagine a locator daemon with thousands of registered POAs (for example, an airline ticketing application) handling thousands of client requests per minute. Programmatic optimizations (for example, efficient use of threads, proper organization of the application's POA system or load balancing) help to minimize bottlenecks here. Administrators can take additional steps, such as active connection management, to optimize performance.

Other issues

Other application design issues include multi-threading, how to partition objects across POAs, how to partition POAs across servers, and what POA policies would be best to use under certain circumstances). For more information, see the *CORBA Programmer's Guide*.

Using the Right Data Storage Mechanism

Overview

Orbix provides standard storage mechanisms for storing persistent data used by Orbix and by applications. Access to these standard mechanisms uses the CORBA persistent state service. This service allows alternative storage mechanisms to be used within an environment for storing data for configuration, location, and the naming service. If your applications encounter limitations imposed by a specific storage mechanism, consider moving to an industrial strength database (for example, Oracle or Sybase) at the backend.

Information about implementing alternative storage mechanisms is outside the scope of this guide. Consult your Orbix vendor for more information.

Getting the Most from Orbix Configuration

Overview

This section answers some basic questions administrators might have about using:

- Separate Orbix environments
- Multiple configuration domains

Separate Orbix environments

Companies can use separate Orbix environments to insulate development, test, and production environments from each other. While you can use separate configuration scopes for this, having separate sets of Orbix services reduces the risk of development and test efforts interfering with production-level Orbix services.

Multiple configuration domains

Development environments might use separate configuration domains to isolate development and test efforts from one another. Security policies might also require multiple configuration domains within a single customer environment. For example, separate organizations in a company might have different administrators with different network security credentials.

Geographic separation or network latency issues might also drive a decision to have separate configuration domains.

Part II

Managing an Orbix Environment

In this part

This part contains the following chapters:

Managing Orbix Configuration	page 33
Managing Persistent CORBA Servers	page 49
Configuring Scalable Applications	page 79
Managing the Naming Service	page 107
Managing an Interface Repository	page 121
Managing the Firewall Proxy Service	page 131
Managing Orbix Service Databases	page 137
Configuring Orbix Compression	page 149
Configuring Advanced Features	page 159

Managing Orbix Configuration

All Orbix clients and servers, including Orbix services such as the locator or naming service, belong to a configuration domain that supplies their configuration settings.

Orbix identifies a client or server by the name of its ORB, which maps to a *configuration scope*. This scope contains configuration variables and their settings, which control the ORB's behavior. Configuration domains can be either based on a centralized configuration repository, or on configuration files that are distributed among all application hosts. Both configuration types operate according to the principles described in this chapter.

Note: For details on how to set up an Orbix environment, see the *Orbix Deployment Guide*. For details on using a secure configuration repository-based domain, see the *Orbix Security Guide*.

In this chapter

This chapter contains the following sections:

How an ORB Gets its Configuration	page 34
Locating the Configuration Domain	page 36
Obtaining an ORB's Configuration	page 38
Managing Configuration Domains	page 47

How an ORB Gets its Configuration

Overview

Every ORB runs within a configuration domain, which contains variable settings that determine the ORB's runtime behavior. Figure 12 summarizes how an initializing ORB obtains its configuration information in a configuration repository-based system, where services are distributed among various hosts.




Figure 11: How an Orbix Application Obtains its Configurations

1. The initializing ORB reads the local configuration file, which is used to contact the configuration repository.

Note: In repository-based configuration domains, the local configuration file contains a domain configuration variable, which is set to the repository's IOR. For example:

```
domain = "itconfig://00034f293b922...00d3";
```

In a file-based configuration, the <code>domain-name.cfg</code> file does not contain a domain variable; instead, the local configuration file itself contains all configuration data.

- 2. The ORB reads configuration data from the configuration repository, and obtains settings that apply to its unique name. This establishes the normal plug-ins and locates other CORBA services in the domain.
- The fully initialized ORB communicates directly with the services defined for its environment.

Configuration steps

An initializing ORB obtains its configuration in two steps:

- 1. Locates its configuration domain.
- 2. Obtains its configuration settings.

The next two sections describe these steps.

Locating the Configuration Domain

An ORB locates its configuration domain as described in the following language-specific sections.

C++ applications

In C++ applications, the ORB obtains the domain name from one of the following, in descending order of precedence:

- 1. The -ORBconfig_domain command-line parameter
- 2. The IT_CONFIG_DOMAIN environment variable
- 3. default-domain.cfg

The domain is located in one of the following, in descending order of precedence:

- 1. The path set in either the -ORBconfig_domains_dir command line parameter or the IT_CONFIG_DOMAINS_DIR.environment variable.
- The domains subdirectory to the path set in either the -ORBconfig_dir command-line parameter or the IT_CONFIG_DIR.environment variable.
- 3. The default configuration directory:

UNIX

/etc/opt/iona

Windows

%IT_PRODUCT_DIR%\etc

Java applications

In Java applications, the ORB obtains the domain name from one of the following, in descending order of precedence:

- 1. The -ORBconfig_domain command-line parameter.
- 2. The ORBconfig_domain Java property.
- default-domain.cfg.

The domain is located in one of the following, in descending order of precedence:

- 1. The path set in either the -ORBconfig_domains_dir command-line parameter or the ORBconfig_domains_dir Java property.
- 2. The domains subdirectory to the path set in either the -ORBconfig_dir command-line parameter or the ORBconfig_dir Java property.
- 3. All directories specified in the classpath.

Note: Java properties can be set for an initializing ORB in two ways, in descending order of precedence:

- As system properties.
- In the iona.properties properties file. See "Java properties" on page 435 for information on how an ORB locates this file.

Obtaining an ORB's Configuration

Overview

All ORBs in a configuration domain share the same data source—either a configuration file or a repository. Configuration data consists of variables that determine ORB behavior. These are typically organized into a hierarchy of scopes, whose fully-qualified names map directly to ORB names. By organizing configuration variables into various scopes, you can provide different settings for individual ORBs, or common settings for groups of ORBs.

Configuration scopes apply to a subset of ORBs or a specific ORB in an environment. Orbix services such as the naming service have their own configuration scopes. Orbix services scopes are automatically created when you configure those services into a new domain.

Applications can have their own configuration scopes and even specific parts of applications (specific ORBs) can have ORB-specific scopes.

Scope organization

Figure 12 shows how a configuration domain might be organized into several scopes:




Figure 12: Hierarchy of Configuration Scopes

Five scopes are defined:

- company
- company.production
- company.operations
- company.operations.finance
- company.operations.hr

Given these scopes, and the following ORB names:

```
company.operations.finance.ORB001
company.operations.finance.ORB002
company.operations.finance.ORB003
company.operations.finance.ORB004
```

All ORBs whose names are prefixed with company.operations.finance obtain their configuration information from the company.operations.finance configuration scope.

Variables can also be set at a configuration's root scope—that is, they are set outside all defined scopes. Root scope variables apply to all ORBs that run in the configuration domain.

Scope name syntax

An initializing ORB must be supplied the fully qualified name of its configuration scope. This name contains the immediate scope name and the names of all parent scopes, delimited by a period (.). For example:

```
company.operations.hr
```

ORB name mapping

An initializing ORB maps to a configuration scope through its ORB name. For example, if an initializing ORB is supplied with a command-line -ORBname argument of company.operations, it uses all variable settings in that scope, and the parent company and root scopes. Settings at narrower scopes such as company.operations.finance, and settings in unrelated scopes such as company.production, are unknown to this ORB and so have no effect on its behavior.

If an initializing ORB doesn't find a scope that matches its name, it continues its search up the scope tree. For example, given the hierarchy shown earlier, ORB name company.operations.finance.payroll will fail to find a scope that matches. An ORB with that name next tries the parent scope company.operations.finance. In this case, ORB and scope names match and the ORB uses that scope. If no matching scope is found, the ORB takes its configuration from the root scope.

Defining configuration scopes

After you create a configuration domain, you can modify it to create the desired scopes:

- A file-based configuration can be edited directly with any text editor, or with itadmin commands scope create and scope remove.
- A repository-based configuration can only be modified with itadmin commands scope create and scope remove.

File-based configuration

In a file-based configuration, scopes are defined as follows:

```
scope-name
{
   variable settings
   ...
   nested-scope-name
   {
     variable settings
     ...
   }
}
```

For example, the following file-based Orbix configuration information defines the hierarchy of scopes shown in Figure 12 on page 38:

itadmin commands

You can create the same scopes with itadmin commands, as follows:

```
itadmin scope create company itadmin scope create company.production itadmin scope create company.operations itadmin scope create company.operations.finance itadmin scope create company.operations.hr
```

Precedence of variable settings

Configuration variables set in narrower configuration scopes override variable settings in wider scopes. For example, the <code>company.operations.orb_plugins</code> variable overrides <code>company.orb_plugins</code>. Thus, the plug-ins specified at the <code>company</code> scope apply to all ORBs in that scope, except those ORBs that belong specifically to the <code>company.operations</code> scope and its child scopes, hr and <code>finance</code>. Example 1 shows how a file-based configuration might implement settings for the various configurations shown in Figure 12 on page 38:

Example 1: File-Based Configuration

```
1
  company
       # company-wide settings
       # Standard ORB plug-ins
       orb_plugins =
           ["local_log_stream", "iiop_profile", "giop", "iiop"];
       # Standard initial references.
      initial_references:RootPOA:plugin = "poa";
       initial references: ConfigRepository: reference
                                        = "IOR:010000002000...00900";
      initial_references:InterfaceRepository:reference
                                        = "IOR:010000002000...00900";
     # Standard IIOP configuration
         policies:iiop:buffer_sizes_policy:max_buffer_size = -1
2
      operations
         # Settings common to both finance and hr
         # limit binding attempts
         max_binding_iterations = "3";
3
         finance
         {
             # finance-specific settings
             # set 5-second timeout on invocations
            policies:relative_binding_exclusive_request_timeout =
                                                              "5000"
```

Example 1: File-Based Configuration

- 1. The company scope sets the following variables for all ORBs within its scope:
 - orb_plugins specifies the plug-ins available to all ORBs.
 - Sets initial references for several servers.
 - Sets an unlimited maximum buffer size for the IIOP transport.
- 2. ORBs in the operations scope limit all invocations to three rebind attempts.
- 3. All ORBs in the finance scope set invocation timeouts to 5 seconds.
- 4. All ORBs in the hr scope set invocation timeouts to 15 seconds.
- 5. The production scope overrides the company-scope setting on policies:iiop:buffer_sizes_policy:max_buffer_size, and limits maximum buffer sizes to 4096.

Sharing scopes

All ORBs in a configuration domain must have unique names. To share settings among different ORBs, define a common configuration scope for them. For example, given two ORBs with common configuration settings, a file-based configuration might define their scopes as follows:

Thus, the two ORBs—common.server1 and common.server2—share common scope settings.

If an ORB has no settings that are unique to it, you can omit defining a unique scope for it. For example, if common.server2 has no unique settings, you might modify the previous configuration as follows:

```
common {
    # common settings here
    # ...
    server1 {
          #unique settings to server1
    }
} # close common scope
```

When the common.server2 ORB initializes, it fails to find a scope that matches its fully qualified names. Therefore, it searches up the configuration scope tree for a matching name, and takes its settings from the parent scope, common.

Configuration Variables and Namespaces

Variable components

Configuration variables determine an ORB's behavior, and are organized into namespaces. For example, a configuration might contain the following entry:

initial_references:IT_Locator:reference ="IOR:010000...0900";

This variable consists of three components:

- The initial_references:IT_Locator namespace.
- The variable name reference.
- A string value.

Namespaces

Configuration namespaces are separated by a colon (:). Configuration namespaces group related variables together—in the previous example, initial references. Orbix defines namespaces for its own variables. You can define your own variables within these namespaces, or create your own namespaces.

Data types

Each configuration variable has an associated data type that determines the variable's value. When creating configuration variables, you must specify the variable type.

Data types can be categorized into two types:

- Primitive types
- Constructed types

Primitive types

Three primitive types, boolean, double, and long, correspond to IDL types of the same name. See the *CORBA Programmer's Guide* for more information.

Constructed types

Orbix supports two constructed types: string and ConfigList (a sequence of strings).

A string type is an IDL string whose character set is limited to the character set supported by the underlying configuration domain type. For example, a configuration domain based on ASCII configuration files could only support ASCII characters, while a configuration domain based on a remote configuration repository might be able to perform character set conversion.

Variables of the string type also support string composition. A composed string variable is a combination of literal values and references to other string variables. When the value is retrieved, the configuration system replaces the variable references with their values, forming a single complete string.

The ConfigList type is simply a sequence of string types. For example:

Setting configuration variables

itadmin provides two commands for setting configuration domain variables:

- itadmin variable create creates a variable or namespace in the configuration domain.
- itadmin variable modify changes the value of a variable or namespace in a configuration domain.

In a file-based domain, you can use these commands, or you can edit the configuration file manually. In a file-based configuration, all variable values must be enclosed in quotes ("") and terminated by a semi-colon (;). ConfigList variables can include empty entries, for example:

```
binding:server_binding_list = ["OTS", ""];
```

This can be added to the configuration file manually, or specified on the command line as follows:

```
itadmin variable create -type list -value OTS,\"\"
  binding:server_binding_list
```

Managing Configuration Domains

Configuration management generally consists of the tasks outlined in Table 1.

Note: For details on using a secure configuration repository-based domain, see the *Orbix Security Guide*.

 Table 1:
 Configuration Domain Management Tasks

Perform this task	By running
Start the configuration repository	One of the following:
	start_domain-name_services script starts the configuration repository and other domain services.
	itconfig_rep run starts the configuration repository only.
Stop the configuration repository	itadmin config stop
View configuration repository contents	itadmin config dump
List all replicas of the configuration repository	itadmin config list_servers
Convert from a file to a configuration repository	itadmin file_to_cfr.tcl
Create scope	itadmin scope create
List scopes	itadmin scope list
View scope contents	itadmin scope show
Create namespace	itadmin namespace create
List namespaces	itadmin namespace list
View namespace contents	itadmin namespace show
Remove namespace	itadmin namespace remove

Table 1: Configuration Domain Management Tasks

Perform this task	By running
Create variable	itadmin variable create
View variable	itadmin variable show
Modify variable	itadmin variable modify
Remove variable	itadmin variable remove

Troubleshooting configuration domains

By default, itadmin manages the same configuration that it uses to initialize itself. This can be problematic if you need to run itadmin in order to repair a configuration repository that is unable to run. In this case, you can run itadmin in another configuration domain by supplying the following command-line parameters (or the equivalent environment variable or Java property):

-ORBdomain_name Specifies the configuration for itadmin. This

is typically a temporary file-based

configuration created for this purpose only.

-ORBadmin_domain_name Specifies the configuration domain repository

to modify.

-ORBadmin_config_domains_dir Specifies the directory in which to find the

the administered configuration. This parameter is required only if the

configuration's location is different from the

default domain's directory.

For example, the following itadmin command runs the itadmin tool in the temp-domain domain, and adds the orb_plugins variable to the repository of the acme-products domain:

itadmin -ORBdomain_name temp-domain
 -ORBadmin_domain_name acme-products
 variable create -type list
 -value iiop_profile,giop,iiop orb_plugins

Managing Persistent CORBA Servers

Location and activation data for persistent CORBA servers are maintained by the locator daemon in the implementation repository.

In this chapter

This chapter explains how to register and manage server information in a location domain. It contains the following sections:

Introduction	page 50
Registering Persistent Servers	page 51
Server Environment Settings	page 56
Managing a Location Domain	page 60
Using Direct Persistence	page 72

Introduction

Overview

CORBA servers that export persistent objects must be registered with a locator daemon using its implementation repository. Servers that are registered with the same locator daemon comprise a *location domain*. Through the implementation repository, a locator daemon can locate persistent objects on any server in its domain. A server can also be configured for automatic activation, if necessary, through a *node daemon* that runs on each domain host.

Management tasks

After you register persistent servers in an implementation repository, servers and clients use this repository transparently. A configured location domain typically requires very little outside management. However, occasional circumstances might require you to manage a location domain. For example:

- The locator daemon stops and needs to be restarted, or runtime parameters need to be updated.
- An application is installed, moved, or removed, and application data needs to be updated.
- Activation parameters need to be changed—for example, the command line arguments passed into a server.

itadmin commands

itadmin commands lets you update and view data in the implementation repository. You can issue these commands manually from the command line or the itadmin command shell, or automatically through an application setup script. You can execute these commands from any host that belongs to the location domain.

Registering Persistent Servers

CORBA persistent servers

A persistent CORBA server is one whose ORB contains persistent POAs. All persistent POAs must be registered in the implementation repository of that server's location domain. When the server initializes, the following occurs:

- 1. The server's ORB creates communication endpoints for its persistent POAs, where POA managers listen for incoming object requests.
- The ORB sends POA endpoint addresses to the locator daemon, which registers them in the implementation repository against the corresponding entry.
- The locator daemon returns its own address to the server's ORB. Persistent POAs that run in this ORB embed that address in all persistent object references.

Because a persistent object's IOR initially contains the locator daemon's address, the locator daemon receives the initial invocation and looks up the object's actual location in the implementation repository. It then returns this address back to the client, which sends this and later invocations on the object directly to the server.

By relying on the locator daemon to resolve their location, persistent objects and their servers can exist anywhere in the location domain. Furthermore, an implementation repository can register server processes for on-demand activation and for per-client activation.

Persistent server registration process

In general, registration of a persistent server is a three-step process:

- 1. "Register the server process for on-demand activation".
- 2. "Register the ORB" that runs in that process.
- 3. "Register POAs" that run in the ORB.

This section shows how to use itadmin commands to perform these tasks. You can enter these commands either on the command line, or using a script.

Per-client activation is a special case of on-demand activation that provides a one-to-one mapping between clients and server processes. See "Per-client activation" on page 54 for more details.

Register the server process for on-demand activation

itadmin process create lets you register a process with a location domain for on-demand activation. When a locator daemon receives an invocation for an object whose server process is inactive, it contacts the node daemon that is registered for that process, which activates the process.

The following example registers the my_app server process with the oregon node daemon:

In this example, the process create command takes the following parameters:

-node_daemon	Specifies the node daemon that resides on the process's host. This node daemon is responsible for starting the process.
-startupmode	When set to on_demand, this specifies that the node daemon restarts the server process when requested.
-args	Specifies command-line arguments. Use the -args argument to specify the ORB name and (for Java executables) the Java class name. You can also use this argument to set the Java class path.

For more about these and other parameters, see process create.

Register the ORB

After you register a server process, associate it with the name of the ORB that it initializes, using itadmin orbname create. This name must be the same as -ORBname argument that you supply the server during startup. For example, the following command associates the registered process, my_app, with the my_app.server_orb ORB:

itadmin orbname create -process my_app my_app.server_orb

The ORB name must be unique in the location domain; otherwise an error is returned.

Note: If you change an ORB name to make it unique in the location domain, also be sure to change the ORB name that is specified for the server. If an ORB-specific scope has been established in the configuration domain, also change the configuration scope name.

Register POAs

After you register a server process and its ORB, register all persistent POAs and their ancestors—whether persistent or transient—using itadmin poa create. Persistent POAs must be registered with the ORB name (or in the case of replicated POAs, ORB names) in which they run. For example, the following command registers the banking_service/account/checking persistent POA and its immediate ancestors banking_service/checking and banking service with the my app.server orb ORB:

```
itadmin poa create -orbname my_app.server_orb \
   banking_service
itadmin poa create \
   banking_service/account -transient
itadmin poa create -orbname my_app.server_orb \
   banking_service/account/checking
```

All POA names within a location domain must be unique. For more information about avoiding name conflicts, see "Ensuring Unique POA Names" on page 70.

Transient POAs

A transient POA does not require state information in the implementation repository. However, you must register its POA name in the implementation repository if it is in the path of any persistent POAs below it. In the previous example, the banking_service/account transient POA is registered as the parent of the banking_service/account/checking persistent POA.

POA replicas

Orbix implements server replication at the POA level. To create POA replicas, specify the ORB names in which they run using the -replicas argument. For more details, refer to "Building a Replicated Server" on page 89.

Per-client activation

You can register a process for per-client activation using the itadmin process create command. In this case, instead of multiple clients sharing the same server, a new process is created for each client. When the locator daemon receives an invocation for an object whose server process is registered as per_client, it creates a new ORB name and process, and contacts the registered node daemon to launch the server.

The following example registers the my_app server process with the oregon node daemon for per-client activation:

```
itadmin process create
 -node_daemon iona_services.node_daemon.oregon
 -pathname "d:/bin/myapp.exe"
 -startupmode per_client
 -args "training.persistent.my_server
        -ORBname %o" my_app
```

In this example, the process create command takes the following parameters:	
-node_daemon	Specifies the node daemon that resides on the process's host. This node daemon is responsible for starting the process.
-startupmode	When set to per_client, specifies that the locator creates a new process and ORB name for each client invoking on objects in the associated persistent POA, and requests the node daemon to start the process.
-args	Specifies the command-line arguments. Because the locator generates the ORB name, any string matching %o in the process's argument list is replaced with the name of the new ORB. Similarly, any string matching %p is replaced with the name of the process created by the locator.

To ensure that multiple servers containing the same object can co-exist, the locator creates a new ORB name and a new process for each client. The new ORB name is created by appending an id string to the registered ORB name, where id is an integer value. In this example, the created ORB names might be my_app.12 and my_app.3. This naming scheme ensures that configuration variables can be shared between the server processes. New process names are created in a similar manner. When a server process has terminated, the locator can reuse the ORB name and process name.

WARNING: The locator or node daemons do not terminate the server process when the server's associated client terminates. It is the application's responsibility to terminate the server process by, for example:

- adding a shutdown operation that is invoked by the client before the client terminates;
- using the leasing plug-in to detect when the client has completed;
- making the server to terminate after a certain amount of time has elapsed without any invocation.

The persistent POA associated with a per-client activated process must support dynamic addition of replicas. This support is automatically enabled when creating a POA whose associated process's startup-mode is per-client. See poa create and poa modify for more details.

For more information about these and other parameters, see process create.

Server Environment Settings

Overview	When a registered server process starts, it is subject to its current environment.
Overview	When a registered server process starts, it is subject to its current environment.

In this section The following sections discuss:

Windows Environment Settings	page 57
UNIX Environment Settings	page 58

Windows Environment Settings

Creation flag settings

The following creation flag settings apply:

DETACHED_PROCESS for console processes, denies the newly created process access to the console of the parent process.

CREATE_NEW_PROCESS_GROUP identifies the created process as the root process of a new process group. The process group includes all processes that are descendants of this root process.

CREATE_DEFAULT_ERROR_MODE specifies that the created process does not inherit the error mode of the calling process.

NORMAL_PRIORITY_CLASS indicates a normal process with no special scheduling needs.

Handle inheritance

Open handles are not inherited from the node daemon.

Security

The new process's handle and thread handle each get a default security descriptor.

UNIX Environment Settings

File access permissions

You can set user and group IDs for new processes using the -user and -group arguments to itadmin process create. Before setting user or group IDs for the target process, ensure that the following applies on the host where the target process resides:

- The specified user exists in the user database.
- The specified group exists in the group database.
- The specified group matches the primary group of the specified user in the user database.

If the specified group does not match the primary group in the users database, the specified user must be a member of the specified group in the group database.

Note: If you cannot edit the /etc/group file, specify the user's primary group. This allows the server to operate normally, even if the /etc/group file is not well maintained.

Before a server starts, the file access privilege of the activated process is lowered if the node daemon is the superuser. If the node daemon is not the superuser, the activated process has the same privileges as the node daemon.

Check whether newly activated target processes have set-uid/set-gid permissions. These allow the server to change the effective user and group IDs, enabling a possible breach of security.

The user and group ID settings affect the working directory settings (if directory paths are created) and the open standard file-descriptor processing.

File creation permissions

The file mode creation mask is set by supplying the -umask argument to itadmin process create. By default, the umask is 022 and the actual creation mode is 755 (rwxr-xr-x).

The umask setting affects the current directory setting (if directory paths are created) and the open standard file-descriptor processing.

Open file descriptors

The activated server has only standard input, output, and error open for both reading and writing, and is connected to /dev/null instead of to a terminal.

Resource limits	Resource limits are inherited from the node daemon.	
Session leader	The activated server creates a new session and becomes leader of the session and of a new process group. It has no controlling terminal.	
Signal disposition	All valid signals between 1 and NSIG-1 are set to their default dispositions for the activated server.	

Managing a Location Domain

Management tasks

Location domain management generally consists of the following tasks:

- Managing server processes.
- Managing the locator daemon.
- Managing node daemons.
- Listing location domain data.
- Modifying a location domain.
- Ensuring that all POA names within a domain are unique.

Managing Server Processes

Starting and stopping registered server processes

Server processes that are registered for on-demand activation do not require any manual intervention. You only need to explicitly start and stop processes that are not set for on-demand activation.

To manually start a registered target server process on a host where a node daemon resides, use the itadmin process start command. For example:

itadmin process start my_app

To stop a registered target server process on the host where the node daemon resides, use the itadmin process stop command. For example:

itadmin process stop my_app

Securing server processes

You can specify that the node daemon can launch processes only from a list of secure directories, in one of two ways:

- Set the itnode_daemon run's -ORBsecure_directories parameter.
- Set the secure_directories configuration variable.

Both specify a list of secure directories in which the node daemon can launch processes. When the node daemon attempts to launch a registered process, it checks its pathname against the secure_directories list. If a match is found, the process is activated; otherwise, the node daemon returns a StartProcessFailed exception to the client.

Moving manually launched processes

A process that is not registered to be launched on demand can be moved to a new host by stopping it on its current host, and restarting it on the new host.

This behavior can be disabled by setting the following configuration variable to false, and restarting the locator:

plugins:locator:allow_node_daemon_change

Attempting to move a process that is already active or is registered to be launched on demand results in an error.

Managing the Locator Daemon

Overview

A locator daemon enables clients to locate servers in a network environment. Normally, a locator daemon runs as root on UNIX, or with administrator privileges on Windows NT. To start and stop a locator daemon, you must be logged on as UNIX root or with Windows NT administrator privileges.

This section assumes that Orbix has been installed and configured to run within your network environment. For more on configuring and deploying Orbix, see *Orbix Deployment Guide*.

Starting a locator daemon

To start a locator daemon:

- On the machine where the locator daemon runs, log on as root or NT administrator.
- 2. Open a terminal or command window.
- 3. Enter itlocator run.

By default, this runs the locator daemon in the foreground.

4. Complete the appropriate actions for your platform as specified below.

Windows

Leave the command window open while the locator is running.

UNIX

Leave the terminal window open or use operating system commands to run the process in the background.

Note: In a configuration repository domain, the configuration repository must be running before starting the locator daemon.

Stopping a locator daemon

To stop a locator daemon, use the itadmin locator stop command. This command has the following syntax:

itadmin locator stop locator-name

Stopping all daemons and monitored processes

To stop the locator, all registered node daemons, and monitored processes running in the location domain, use the -alldomain argument:

itadmin locator stop -alldomain locator-name

Restarting a locator daemon

If a locator daemon is stopped and restarted while server processes are active, it recovers information about the active processes when it starts up again. The locator daemon validates that server processes, ORBs and POAs that were active when it was shutdown are still responding. If these server processes are no longer running, the locator daemon can detect this.

Starting the locator under a heavy client load

When a server receives a large number of client requests, the server's node daemon may not be able to register itself with the locator, which prevents the server from starting properly.

To handle this, Orbix provides a message-level interceptor plug-in that closes the connection on receiving locator requests from hosts other than those specified. Orbix does this until a node daemon has registered (the filter is effectively switched off). The clients must be able to handle the CORBA::Exception as a result of the connection being closed.

Example configuration

The following shows how to configure this interceptor:

```
plugins:connection_filter:shlib_name = "it_connection_filter";
# Add the connection filter to the locator binding list
plugins:giop:message_server_binding_list = ["BiDir_GIOP",
   "FILTER+GIOP", "GIOP"];
# Add the connection filter to the locator orb plugins list
orb_plugins = ["local_log_stream", "iiop_profile", "giop",
"connection_filter", "ots", "iiop"];
# enable the interceptor
plugins:node_daemon:registration:required = "true";
# Accept connections from these hosts
plugins:connection_filter:address:list = ["10.2.2.127"];
# Optional
# Limit the number of threads that are getting created in the
# locator - this is optional, but could prevent core dumps
thread_pool:high_water_mark = "200";
# See what the filter is doing
event_log:filters = ["IT_POA_LOCATOR=*", "IT_LOCATOR=*",
"IT_PSS_DB=INFO_HIGH+WARN+ERROR+FATAL",
   "IT CONNECTION FILTER=*"];
```

Managing Node Daemons

Overview

In an Orbix location domain, the node daemon is responsible for activating and managing server processes. Every host running an server must also run a node daemon. The node daemon performs the following tasks:

- Starts processes on demand.
- Monitors all child processes of registered server processes, and informs the
 locator daemon about any events relating to these child processes—in
 particular, when a child process terminates. This enables the locator
 daemon to remove the outdated dynamic process state information from
 the implementation repository, and to restart the process if necessary.
- Monitors all services via heartbeating. If a manually started service crashes, the node daemon detects this and returns all requests routed to this server with the appropriate exception.
- Acts as the contact point for servers starting on this machine. When an
 server starts on a machine, it contacts the locally running node daemon to
 announce its presence. The node daemon informs the locator daemon of
 the new server's presence.

Target server processes that are manually started do not need to register their process information with the locator daemon. Even when process information is not registered with the locator daemon, these processes should behave normally with respect to other location domain capabilities (for example, object location).

However, if you enter process information for a manually started server, you can still use manual starting by setting its automatic start-up mode to disabled. You might wish to store this information, to keep a record of all processes installed in the location domain.

Starting a node daemon

To start a node daemon, log on to the host where you want to run the daemon and enter itnode daemon run.

By default, at startup, the node daemon attempts to contact the CORBA servers that it managed during the previous time it ran. If the node daemon was managing a large number of CORBA servers, this can take up to several minutes, and delay the node daemon from starting up.

In certain circumstances—for example, restarting after a reboot—it is not necessary for the node daemon to contact running CORBA servers. This is because it can be guaranteed that those servers are not running. You can use the following configuration variable to turn off this default behavior:

```
plugins:node_daemon:recover_processes="false";
```

This enables the node daemon to complete its initialization more quickly. You should set this variable in the node daemon's configuration scope.

Running multiple node daemons on a single host

One node daemon can control multiple server processes; and normally one node daemon runs on a given host. Sometimes an application might require a separate node daemon (for example, to launch servers as different users). In this case, you can run multiple node daemons on a single host. For example, one node daemon might run as root, and another as a different user with fewer privileges.

Multiple node daemons on the same host must have different names, which should reflect their application name in some way.

To configure multiple node daemons, perform the following steps:

- In the default node_daemon configuration scope, create a sub-scope (for example, node_daemon.engineering).
- 2. Provide a value for the node daemon name configuration variable. For example:

```
itadmin variable create -scope node_daemon.engineering
-type string -value "eng_node_daemon"
plugins:node_daemon:name
```

Run the node daemon in the new scope, using the -ORBname argument:
 For example, the following commands start two node daemons on the same host:

```
itnode_daemon -ORBname node_daemon.engineering
```

Stopping a node daemon

To terminate a node daemon, use itadmin .node_daemon stop. This command also stops all the server processes that the node daemon monitors. For example, the following command stops the node daemon on alaska:

itadmin node_daemon stop alaska

Viewing a node daemon's processes

Before you stop a node daemon, you might want to list all the active processes that it currently monitors. To do so, run itadmin process list -active. For example, this command lists the active processes for the node daemon on alaska:

itadmin process list -active -node_daemon alaska
 my_server_process

Listing Location Domain Data

With itadmin commands, you can list the names and attributes of registered entries in the implementation repository.

 Table 2:
 Commands that List Location Domain Data

Command	Action
process list	Lists the names of all target processes registered in the location domain.
process show	Lists the attributes of server processes registered with the locator daemon.
orbname list	Lists all ORB names in the location domain.
orbname show	Lists the attributes of ORB names registered with the locator daemon.
poa list	Lists the names of all POAs in the location domain.
poa show	Lists the attributes of all registered POA names.

Modifying a Location Domain

Overview

With itadmin commands, you can modify and remove registered processes, ORB names, and POA names from the implementation repository. For detailed information, see Chapter 23 on page 289.

Modifying entries

The itadmin commands listed in Table 3 modify entries for processes, ORB names, and POA names that are registered with a location domain.

 Table 3:
 Commands that Modify a Location Domain

Command	Action
process modify	Modifies the specified process entry.
orbname modify	Associates an ORB name with the specified process name.
poa modify	Modifies the specified POA name.

Removing entries

You can remove any entry from the implementation repository, whether the target object is running or not. The itadmin commands listed in Table 4 remove entries for processes, ORB names, and POA names that are registered with a location domain.

 Table 4:
 Commands that Remove Location Domain Components

Command	Action
process remove	Removes a process entry.
orbname remove	Removes an ORB name from the location domain. If there is an active ORB entry for the ORB name in the locator's active ORB table, this is also removed.
poa remove	Removes the entry for the specified POA and its descendants from the location domain. By default, all active entries for the POA and its descendants are also removed.

Ensuring Unique POA Names

Overview

The locator daemon finds persistent objects by looking up their POA names in the implementation repository. Consequently, POA names must be unique in a location domain.

If you use a repository-based configuration, the implementation repository prevents name duplication and raises the following error:

ERROR: Unable to add an implementation repository entry for the POA: EntryAlreadyExists

If different Orbix applications use the same POA names, you can avoid name conflicts by setting plugins:poa:root_name. The root_name variable names the application's root POA, which is otherwise unnamed. By setting this variable for each application's ORB to a unique string, you can ensure unique names for all POAs.

Procedure

The following procedure shows how to register a root POA's name within a location domain, and use it with all descendant persistent POAs:

 To define a root POA name for a server, create a plugins:poa:root_name configuration variable in the server ORB's configuration scope:

```
itadmin variable create
  -scope production.test.servers.server001 -type string
  -value "my_app" plugins:poa:root_name
```

When the server initializes, it reads its root POA name and applies this to all its POA names.

2. Register the root POA's name in the implementation repository:

```
itadmin poa create -transient my_app
```

3. When you register persistent POAs for this server in the implementation repository, prefix their names (and the names of all ancestor POAs) with the root POA's prefix. The following commands register two persistent POAs:

```
itadmin poa create -transient my_app/poa1
itadmin poa create -orbname
   production.test.servers.server001 my_app/poa1/poa2
itadmin poa create -orbname
   production.test.servers.server001 my_app/poa1/poa2/poa3
```

Using Direct Persistence

Using direct persistence enables Orbix to bypass the locator daemon when resolving persistent object references or contacting Orbix services.

In this section

This section discusses the following topics:

CORBA Applications	page 73
Orbix Services	page 77

CORBA Applications

In general, a CORBA applications rely on the location daemon to resolve persistent object references. Alternatively, you might want to avoid the overhead that is incurred by relying on the location daemon. In this case, you can set up a server that generates direct persistent object references—that is, object references whose IORs contain a well-known address for the server process. This section includes:

- "Requirements".
- "Example".
- "Setting direct persistence in configuration only".

Requirements

Two requirements apply:

- The server that generates the object references must set its POA policies to PERSISTENT, DIRECT_PERSISTENCE. The POA must also have a WELL_KNOWN_ADDRESSING_POLICY whose value is set to *prefix* (see the *CORBA Programmer's Guide*).
- The configuration must contain a well-known address configuration variable, with the following syntax:

```
address-prefix::transport:addr_list=[ address-spec [,...] ]
where address-spec has the following syntax:
```

```
"[+]host-spec:port-spec"
```

The plus (+) prefix is optional, and only applies to replicated servers, where multiple addresses might be available for the same object reference (see "Direct Persistence and Replica Failover" on page 86).

Note: These requirements involve setting direct persistence programatically. As an alternative for C++ servers, see also "Setting direct persistence in configuration only".

Example

For example, you might create a well-known address configuration variable in scope MyConfigApp as follows:

```
MyConfigApp {
    ...
    my_server:iiop:addr_list=["host.com:1075"];
    ...
}
```

Given this configuration, a POA created in the MyConfigApp ORB can have its PolicyList set so it generates persistent object references that use direct persistence, as follows:

C++

```
CORBA::PolicyList policies;
policy.length(4);
CORBA:: Any persistence_mode_policy;
CORBA:: Any well_known_addressing_policy;
persistence_mode_policy_value <<=
   IT PortableServer::DIRECT PERSISTENCE;
well_known_addressing_policy_value <<=
   CORBA::Any::from_string("wka", IT_TRUE);
policy[0] = poa->create_lifespan_policy
                 (PortableServer::PERSISTENT);
policy[1] = poa->create_id_assignment_policy
                 (PortableServer::USER_ID);
policy[2] = orb->create_policy
                 (IT PortableServer::PERSISTENCE MODE POLICY ID,
                  persistence_mode_policy);
policy[3] = orb->create_policy
                 (IT_CORBA::WELL_KNOWN_ADDRESSING_POLICY_ID,
                  well_known_addressing_policy);
```

Java

```
import com.iona.corba.*;
import com.iona.IT CORBA.*;
import com.iona.IT PortableServer.*;
// Set up IONA policies
org.omg.CORBA.Any persistent mode policy value =
   global_orb.create_any();
org.omg.CORBA.Any well known addressing policy value =
   global orb.create any();
PersistenceModePolicyValueHelper.insert(
    persistent_mode_policy_value,
    PersistenceModePolicyValue.DIRECT PERSISTENCE);
well_known_addressing_policy_value.insert_string("wka");
org.omg.CORBA.Policy[] policies=new Policy[]
  root poa.create lifespan policy(
        LifespanPolicyValue.PERSISTENT),
  root_poa.create_id_assignment_policy(
        IdAssignmentPolicyValue.USER_ID),
  global_orb.create_policy(
        PERSISTENCE_MODE_POLICY_ID.value,
        persistence_mode_policy_value),
  global_orb.create_policy(
        WELL_KNOWN_ADDRESSING_POLICY_ID.value,
        well known addressing policy value),
};
```

Setting direct persistence in configuration only

Orbix has two configuration variables that enable POAs to use direct persistence and well-known addressing, if the policies have not been set programatically. Both variables specify the policy for individual POAs by specifying the fully qualified POA name for each POA. They take the form of poa: fqpn: variable-name (fqpn is frequently used POA name). For example, to set the well-known address for a POA whose fully qualified POA name is darleen you would set the variable poa:darleeen:well_known_address.

poa: fqpn:direct_persistent specifies if a POA runs using direct persistence. If this is set to true the POA generates IORs using the well-known address that is specified in the well_known_address variable. Defaults to false.

poa: FQPN:well_known_address specifies the address used to generate IORs for the associated POA when that POA's direct_persistent variable is set to true.

For example, by default, the simple_persistent demo creates an indirect persistent POA called simple_persistent. If you want to run this server using direct persistence, and well known addressing, add the following to your configuration:

```
simple_orb {
   poa:simple_persistent:direct_persistent = "true";
   poa:simple_persistent:well_known_address = "simple_server";
   simple_server:iiop:port = "5555";
};
```

All object references created by the simple_persistent POA will now be direct persistent containing the well known IIOP address of port 5555.

Obviously, if your POA name was different the configuration variables would need to be modified. The scheme used is the following:

```
poa:FQPN:direct_persistent=<BOOL>;
poa:FQPN:well_known_address=<address_prefix>;
AddressPrefix:iiop:port=<LONG>;
```

FQPN is the fully qualified POA name. This introduces the restriction that your POA name can only contain printable characters, and may not contain white space.

AddressPrefix is the string that gets passed to the well-known addressing POA policy. Specify the actual port used using the variable

AddressPrefix:iiop:port. You can also use iiop_tls instead of iiop.

Note: This functionality is currently only implemented in the C++ ORB. If you are using the Java ORB, you must set the direct persistence and well known addressing policies programmatically.

Orbix Services

In general, Orbix uses the locator daemon to resolve the initial reference for each of the services. Alternatively, you might want to avoid the overhead that is incurred by relying on the location daemon. In this case, you would configure the service to run in direct persistence mode.

Technical details

When a service runs in direct persistence mode it listens on a fixed host and port number. This information is embedded into the IOR that the service exports as an initial reference.

When a CORBA client asks for the service's initial reference, it receives the IOR containing the host and port information for the service. The client uses the embedded information to directly contact the service, bypassing the locator and node daemon normally used by Orbix services.

Performance issues

While direct persistence reduces the overhead of using the locator and node daemons, it also has a cost in terms of fault tolerance and flexibility. When running in direct persistence mode a service cannot be started on demand and it must always listen on the configured host and port number.

Configuration variables

To configure a service to run in direct persistence mode, three configuration variables need to be modified:

plugins: ServiceName:**direct_persistence** Indicates whether the service uses direct or indirect persistence. The default value is FALSE, which indicates indirect persistence.

plugins: ServiceName:iiop:port Specifies the port number that the service will listen on. If security is installed, then a TLS port is also required.

initial_references:ServiceReferenceString:reference specifies the IOR of
the service.

If the service is clustered, plugins: ServiceName: iiop:host must also be set.

Configuring direct persistence

To configure a service to run in direct persistence mode complete the following steps:

- 1. If the service is running, shut it down.
- 2. Set plugins: ServiceName: direct_persistence to TRUE within the service's configuration scope.
- 3. Within the same configuration scope, set plugins: ServiceName: iiop:port to some open port number.
- 4. Prepare the service. This causes the service to generate a new IOR for itself. The new IOR will be printed to the console. Save it for use in the next step.
- 5. Within the same configuration scope as used in steps 2 and 3, replace the value of initial_references: ServiceReferenceString: reference with the IOR returned in step 4.
- 6. Restart the service.

Configuring Scalable Applications

Enterprise-scale systems, which are distributed across multiple hosts, networks, and applications, must be designed to handle a wide variety of contingencies.

For example, mechanical or electrical malfunctions can cause host machines to stop working. A network can be cut apart by an excavator that accidentally slices through phone lines. Operating systems can encounter fatal errors and fail to reboot. Compiler or programming errors can cause software applications to crash.

Poor design can also cause problems. For example, you might run multiple copies of a web server to handle higher levels of browser activity. However, if you run all copies on the same underpowered host machine, you may reduce, rather than increase, system performance and scalability. Running all web servers on the same host also makes the entire web site dependent on that machine—if it fails, it brings down the entire site.

In general, a distributed enterprise system must facilitate reliability and availability. Otherwise, users and applications are liable to encounter service bottlenecks and outages.

In this chapter

This chapter contains the following sections:

Fault Tolerance and Replicated Servers	page 81
Building a Replicated Server	page 89
Replicating Orbix Services	page 95
Fault Tolerance and Replicated Servers	page 81
Setting Buffer Sizes	page 105

Further information

See Chapter 11 for information on additional features that are designed to enhance scalability and performance (for example, Java new I/O and shared memory).

Fault Tolerance and Replicated Servers

Overview

Reliable and available CORBA applications require an ORB that supports fault tolerance—that is, an ORB that avoids any single point of failure in a distributed application. With the enterprise edition of Orbix, you can protect your system from single points of failure through *replicated servers*.

A replicated server is comprised of multiple instances, or *replicas*, of the same server; together, these act as a single logical server. Clients invoke requests on the replicated server, and Orbix routes the requests to one of the member replicas. The actual routing to a replica is transparent to the client.

Benefits

Orbix replicated servers provide the following benefits:

Client transparency: Client applications can invoke requests on replicated servers without requiring any changes.

Transparent failover: If one replica in a replicated server fails, Orbix automatically redirects clients to another replica, without the clients' knowledge.

Dynamic management: You can modify a replicated server by adding or removing replicas at runtime, without affecting client applications or other replicas.

Replicated infrastructure: Critical services such as the locator daemon, configuration repository, and naming service are configured as replicated servers. This ensures that they are always available.

Load balancing: Client invocations can be routed to different replicas within a replicated server, thus balancing the client load across all, and improving system performance. Orbix provides out-of-the-box round robin, random, and preferred local load balancing strategies. The Orbix load-balancing framework is pluggable, so you can easily implement your own strategies.

About Replicated Servers

Overview

Orbix replicates servers with the same infrastructure that supports persistent CORBA objects—that is, objects that are maintained in POAs with a lifetime policy of PERSISTENT. Orbix locates persistent objects using the locator daemon, which maintains their addresses on a physical server (see "Managing Object Availability" on page 8). A client that invokes on a persistent object for the first time sends its request to the locator daemon, which redirects the request to the server's current host and port. Thus, a client invoking on these objects is insulated from any knowledge of their actual location.

Orbix uses the locator daemon to support replicated servers. If a persistent object is instantiated on a replicated server, its references contain the address of the locator daemon. The locator daemon is responsible for redirecting client requests on that object to one of the server's replicas.

POA replicas

Object persistence is always set by POA policies. Therefore, Orbix implements replication through registration of multiple instances, or *replicas*, of a POA, in a location domain's implementation repository. This provides the necessary level of granularity without adding significant administrative overhead. POA replicas ensure continuous access to persistent objects; and the Orbix infrastructure is required only to monitor POA activity.

Deployment of a replicated server

For example, you might want to deploy a replicated server that implements the replicated POA ozzy on hosts zep, floyd, and cream. To do this, complete the following steps:

Note: The following procedure assumes that a locator daemon and a naming service are already deployed.

- Register replicas of POA OZZY in the location domain's implementation repository. At runtime, each server sends the replica's actual address to the domain's locator daemon. For details on registering POA replicas, see "Example 1: Building a Replicated Server to Start on Demand" on page 90.
- Make persistent object references in a replicated server available to
 prospective clients—typically, by advertising object references through the
 CORBA naming service.
- 3. Ensure that the node daemon activates servers on the initial client request. Otherwise, you must manually activate those servers.

Replicated server startup

When the servers start up, the following occurs:

- Each server's ORB creates communication endpoints for its persistent POAs, where POA managers listen for incoming object requests.
- The ORB sends POA endpoint addresses to the locator daemon, which
 registers them in the implementation repository against the corresponding
 POA entry. If a persistent POA is replicated across multiple servers, each
 replica's address is registered against the corresponding replica entry.
 Thus, the locator daemon can maintain multiple addresses for the same
 POA.
- 3. The locator daemon returns its own address to each ORB. Persistent POAs that run in this ORB embed that address in all persistent object references.

Invocations on replicated persistent objects

When a client invokes on a persistent object in the replicated server, the following occurs:

- The client ORB sends a locate request to the object reference's communication endpoint, which is the locator daemon.
- When the locator daemon receives the locate request, it searches the
 implementation repository for the target object's POA. In this case, it finds
 that the ozzy POA is replicated across three servers that run on zep, floyd,
 and cream.

- 3. The locator daemon uses the load-balancing algorithm that is associated with the ozzy POA to determine which POA replica should handle the request—for example, the replica on zep.
- 4. The locator daemon obtains the address to the ozzy POA on zep, and returns a *direct object reference* that contains this address to the requesting client's ORB.
- 5. The client's ORB sends another locate request for the object, this time with the direct object reference, to zep. The replica confirms the object's existence with an object-here reply.
- 6. When the client ORB receives the object-here reply, it resends the client's request to the object instantiated in the ozzy replica on zep.

Except for the original invocation, all steps in this process are transparent to the client. Thus, clients can invoke on a server in exactly the same way, whether it exists alone or as a replica within a replicated server.

Automatic Replica Failover

Replica Failure

If a replica becomes unavailable—for example, because of machine or network failure—another replica enables clients to access the same objects as follows:

- As soon as a direct object reference fails, the client ORB retrieves the object's original IOR, and sends a locate request to the locator daemon.
- The locator daemon reapplies the load balancing algorithm for the target POA against the remaining viable replicas, to determine which one should handle requests on this object. It then returns a direct object reference to the client for the chosen replica.
- 3. All client invocations on the object, including the forwarded one, are handled by the new replica.

Replica restoration

If a failed replica is restored, it can transparently rejoin the replicated server by reregistering its address with the locator daemon. The locator daemon reassociates that replica with the name of the replicated POA in its database, thus making that replica available for subsequent client requests.

Restarting on a different host

A replica must be restarted on the host with which it is registered. If the failed replica needs to be restarted on a different host, you must modify the replicas registration using the following command:

Direct Persistence and Replica Failover

Overview

The failover mechanism described thus far relies upon the locator daemon to forward persistent object references from a failed replica to another replica that is still active. However, you can also create a persistent POA that circumvents the overhead of a locator daemon. This POA publishes persistent object references that embed a well-known address—that is, the address where the POA listens for incoming requests.

Requirements

To ensure failover in a replicated POA with direct persistence, the following requirements apply:

- The well-known address list that each replica obtains from its configuration must specify all addresses for each replica, including its own. Thus, the object references published by each replica must list the addresses of all replicas.
- The well-known address list for a given replica must always single out one address as its listening address. In the IORs that it generates, all other addresses are for publication only.

When a client request uses a direct object reference, it is directed to the first replica address in the list. If that replica is not available, it tries the next replica in the list, and so on, until it finds an available replica.

Example configuration

For example, given replicas that are instantiated on host1 and host2, you can create the following configuration for each replica as follows:

```
MyConfigApp {
    ...
    wka_1:iiop:addr_list=["host1.com:1075", "+host2.com:2075"];
    wka_2:iiop:addr_list="+host1.com:1075", "host2.com:2075"];
    ...
}
```

The plus (+) prefix indicates that an address is for publication only in the IOR; a non-prefixed address is for publication and listening. Each POA replica obtains a different listening address as follows:

- The replica on host1 specifies well-known address prefix wka_1, so it listens on the non-prefixed address host1.com:1075.
- The replica on host2 specifies well-known address prefix wka_2, so it listens on the non-prefixed address host2.com: 2075.

Note: For full details of all configuration required for direct persistence and well-know addressing, see "Setting direct persistence in configuration only" on page 75.

Example server code

The server code shown earlier is modified on each host as follows:

C++

```
// on host1:
// ...
CORBA:: Any well known addressing policy value;
well_known_addressing_policy_value <<=</pre>
    CORBA::Any::from_string("wka_1", IT_TRUE);
// ...
policies[3] = orb->create policy(
    IT_CORBA::WELL_KNOWN_ADDRESSING_POLICY_ID,
    well_known_addressing_policy_value );
// on host2:
// ...
CORBA:: Any well_known_addressing_policy_value;
well_known_addressing_policy_value <<=
    CORBA::Any::from_string("wka_2", IT_TRUE);
// ...
policies[3] = orb->create_policy(
    IT_CORBA::WELL_KNOWN_ADDRESSING_POLICY_ID,
    well_known_addressing_policy_value );
```

Java

```
//on host1:
// ...
PersistenceModePolicyValueHelper.insert(
    persistent_mode_policy_value,
    PersistenceModePolicyValue.DIRECT_PERSISTENCE);
well_known_addressing_policy_value.insert_string(
    "wka_1");
// ...

//on host2:
// ...
PersistenceModePolicyValueHelper.insert(
    persistent_mode_policy_value,
    PersistenceModePolicyValue.DIRECT_PERSISTENCE);
well_known_addressing_policy_value.insert_string(
    "wka_2");
// ...
```

The object references for both replicas contain the same address list. Thus, requests on these IORs are first directed to host1 address. If the replica on host1 is unavailable, the request is redirected to the address on host2.

Building a Replicated Server

Overview

Sample code

The following sections walk you through the process of building a replicated server, including the ability to load balance clients across multiple servers, activate multiple servers in response to a single client request, and dynamically change replicas in a replicated server.

These examples are based on several demos in the Orbix demos\corba\enterprise\clustering directory. These demos consist of a simple client and server. The server program exports a single object, SimpleClusteredObject, which has the following interface:

```
module Clustering
{
    interface SimpleClusteredObject
    {
        string
        server_name();
    };
};
```

SimpleClusteredObject has a single operation, server_name(), which returns the name of the server as passed on the server command line. This is used to demonstrate the Orbix load-balancing features. Each server that runs the simple object is passed a different server name on the command line. Clients that connect to the object get and display the server name, thereby showing the server that they have been connected to.

This section includes the following examples:

```
"Example 1: Building a Replicated Server to Start on Demand"
```

"Example 2: Updating a Replicated Server"

"Example 3: Dynamically Changing the Load Balancing Algorithm"

Example 1: Building a Replicated Server to Start on Demand

The following example shows how to register a replicated server for on-demand activation in a location domain.

1. Build the application. For example:

```
$ cd c:\iona\asp\version\demos\enterprise\clustering
$ nmake
```

Start an itadmin session, and use the process create command to create
an entry in the implementation repository for each replica in a replicated
server:

```
$ itadmin
% process create \
    -pathname
      /opt/iona/asp/version/demos/enterprise/clustering/ \
      cxx_server/server \
      -node_daemon_name \
      -startupmode on_demand \
      -args "--ORBname demos.clustering.server_1 server_1" \
      demos.clustering.server_process_1
% process create \
      # same arguments as before \
      -args "--ORBname demos.clustering.server_2 server_2"\
      demos.clustering.server_process_2
% process create \
      \dots same arguments as before \
      -args "--ORBname demos.clustering.server_3 server_3" \
      demos.clustering.server_process_3
```

These process create commands create entries for three servers to start on demand. This command requires the following arguments:

- The path name for the server executable.
- The name of the node daemon to start the server.

Note: The server must always be started on the same host as its associated node daemon. Otherwise, you will receive a PROCESS_IN_DIFFERENT_NODE_DAEMON exception.

- A list of command line arguments passed to the server using the

 args argument. These include a unique ORB name that is associated with each server replica.
- 3. Call orbname create to associate an ORB name with each server instance. The -process argument associates the new ORB name with the corresponding process name created in step 3. The process name must be the same one that specified the new ORB name:

```
% orbname create \
    -process demos.clustering.server_process_1 \
    demos.clustering.server_1
% orbname create
    -process demos.clustering.server_process_2 \
    demos.clustering.server_2
% orbname create \
    -process demos.clustering.server_process_3 \
    demos.clustering.server_3
```

- 4. Call poa create to create a replicated POA, supplying two arguments:
 - The -replicas argument replicates the POA ClusterDemo on the three ORB names created in step 3.
 - The -load_balancer argument specifies the load-balancing strategy to associate with the replicated POA; this tells the locator daemon how to route requests to the POA replicas. In this case, the random strategy is specified, which routes requests randomly among the POA's available replicas.

```
$ itadmin
% poa create -replicas demos.clustering.server_1, \
   demos.clustering.server_2, demos.clustering.server_3 \
   -load_balancer random ClusterDemo
```

5. Run the servers.

Each server is passed an <code>-ORBname</code> parameter to identify the server. This parameter is passed to <code>ORB_init()</code>, which passes it on to the locator to identify the server when it creates the POA. Each of the servers must also be passed a server name parameter (for example, <code>server_1</code>), which is returned to the client to identify the server.

The following shows how you might run these servers.

6. Run the client against the server.

The client output shows how the locator randomly selects a server for each client that is running, load balancing the clients across the set of servers. If you kill one of the servers, the locator continues to forward clients to the remaining two servers, choosing between them at random.

Example 2: Updating a Replicated Server

Orbix replication is implemented so that you can add new servers on-the-fly without shutting down your system. The following commands add a server replica to the set already registered in the clustering demo:

Example 2: Commands for Updating a Replicated Server

```
1
      process create \
            -pathname $server_name \
            -node_daemon_sdaemon_name \
            -startupmode on demand \
            -args "--ORBname demos.clustering.server_4 server_4" \
         demos.clustering.server_process_4
      orbname create
            -process demos.clustering.server_process_4
         demos.clustering.server_4
      poa modify \
            -replicas \
               demos.clustering.server_1, \
               demos.clustering.server_2, \
               demos.clustering.server_3, \
               demos.clustering.server 4 \
         ClusterDemo
```

- process create registers a new location domain process, demos.clustering.server_process_4.
- orbname create associates a new ORB name, demos.clustering.server_4, with the new process.
- 3. poa modify redefines the ClusterDemo POA, specifying a fourth POA replica to run in the demos.clustering.server_4 ORB.

After following these steps, run the clients against the server again. As before, the client output shows how the locator randomly selects a server for each client that is running, and eventually prints out the name of the fourth server.

Example 3: Dynamically Changing the Load Balancing Algorithm

Orbix enables you to dynamically change the load balancing algorithm used for a replicated POA. Orbix supports the following load balancing algorithms:

round_robin The locator uses a round-robin algorithm to select from the list

of active servers. The first client is sent to the first server, the second client to the second server, and so on.

random The locator randomly selects an active server to handle the

client.

prefer_local The locator tries to use a server whose IP address matches that

of the client.

For example, you can change the load-balancing algorithm used by the clustering demo by issuing the following itadmin poa modify command:

\$ itadmin poa modify -load_balancer round_robin ClusterDemo

You can verify this by running several clients. The names of the servers now print out in the order in which they were started.

Per-Request Load Balancing

By default the locator load balancing is performed on a per-client ORB basis therefore once a binding to a replica has been established all requests from that ORB use the initial binding. You can choose to select an option that will allow load balancing to occur within the ORB, on a per-request basis.

To activate per-request load balancing, set the policy in the configuration file as follows:

policies:per_request_lb = "true"

Replicating Orbix Services

Overview

Clients that use replicated Orbix services, such as the locator, are automatically routed to the first available server. If a server fails, clients are transparently rerouted to another server. Orbix services are normally replicated across a number of hosts, but it is also possible to replicate services on the same host.

The following Orbix services can be replicated:

- Locator daemon.
- Naming service.
- Configuration repository (CFR).
- Security service.

Figure 13 shows an example of a replicated naming service. This shows updates being pushed across from the master naming service to the slave naming service.

Note: To replicate an Orbix service, you must first use the **Orbix Configuration** GUI tool (itconfigure) to specify a replica host (see the *Orbix Deployment Guide*).

Replicating locator daemon and naming service

Continuous availability is especially important for the locator daemon and naming service. Replicating these services ensures that:

- Clients can always access persistent servers.
- New persistent servers can be activated on demand.
- itadmin commands that read the implementation repository always work (for example, itadmin poa list, and itadmin process show).
- Clients can always obtain object references from the naming service.




Figure 13: Replicated Naming Service

CFR-based versus file-based replication domains

Orbix services can be replicated in both CFR-based domains and in configuration file-based domains.

In a CFR-based domain, it is recommended that the CFR service is replicated, in addition to any other replicated services (for example, the security service). This ensures that all clients and servers can continue to run in the event of a failure.

Note: For details on using a secure configuration repository-based domain, see the *Orbix Security Guide*.

Replicating the security service

In a secure domain, replicating the security service is important to ensure that all services are accessible even in the event of a host failure.

To replicate the security service, use the **Orbix Configuration** GUI tool (itconfigure) to specify a replica host, like with other services (see the *Orbix Deployment Guide*). The generated configuration will contain the all relevant CORBA clustering information.

However, with the security service, you must also edit your is2.properties file, and create a cluster.properties file. For details on these files, see the *Orbix Security Guide*.

Master and slave replicas

The locator daemon, naming service, and configuration repository use the persistent state service (PSS) to replicate their state. The PSS uses a master-slave model where a single replica is designated the master, and can process both read and write operations. All other replicas are slaves and can only process read operations. For more details, see "PSS Master-Slave Replication" on page 98.

Note: All replicas in a PSS-based replicated service must be run on identical operating systems.

Adding and removing replicas

New server replicas can be added dynamically into a running system, and existing replicas can also be removed. For more details, see the *Orbix Deployment Guide*.

PSS Master-Slave Replication

Overview

The locator, naming service, and configuration repository all use PSS-based master slave replication. In this model, one replica is designated as the master, and the remaining replicas are designated as slaves. Only the master can provide both read and write access; while slave replicas provide read-only access. In addition, only the master can process any read operation that is part of a distributed transaction.

If a slave replica receives a write or a read request in a distributed transaction, this request is either delegated to the master, or rejected if there is no master available. If the master fails, the remaining slaves hold an election to determine the new master. The automatic promotion of a slave to master is transparent to clients. This section includes the following:

- "Startup of master-slave services".
- "Master election protocol".
- "Setting replica priorities".
- "Setting a refresh master interval".
- "Relaxing majority rule".
- "Setting heartbeats"
- "Enabling master demotion"
- "Overcoming deadlock with duplicate masters"
- "Replica administration".

Startup of master-slave services

When a group of replicated services has been deployed, all services are started as slaves. A majority of a service's replicas must have started before an election to select the master replica can take place.

This means, for example, in a replica group with four replicas (including the master), that at least three replicas must be running before an election can take place and write requests are possible.

Having a majority of replicas running ensures that a network partition can not result in duplicate masters. It also guarantees that previously committed updates are not lost.

Master election protocol

When the master is unavailable, an election protocol is used to determine the new master. If a majority of replicas are running, the slave that is most up-to-date with updates from the master is elected as the new master. If there is a tie, a priority system is used to elect the master. If there is still a tie, a random selection is made.

Note: To support the automatic promotion of a slave, the minimum number of replicas in a group is three (one master and two slaves). For more details, see "Relaxing majority rule" on page 100".

Setting replica priorities

You can configure the priority of a replica in elections using the following configuration variable:

```
plugins:pss_db:envs:env-name:replica_priority = "1";
```

The default value is 1. Higher values mean a higher priority; while a priority of 0 means that slave is not to be promoted. For more details, see plugins:pss db:envs:env-name in the *Orbix Configuration Reference*.

By default, the first replica deployed is given a higher priority than the remaining replicas. This increases the likelihood that the first replica runs as master when the services are started. This avoids unnecessary delegation for write operations.

In addition, replica priorities are more likely to be honoured if services are shutdown cleanly (using the stop_domain_name_services command).

Setting a refresh master interval

Each of the replicated Orbix services that use PSS replication enable you to configure the amount of time that a slave replica waits for a new master to be elected:

```
plugins:naming:refresh_master_interval
plugins:locator:refresh_master_interval
plugins:config_rep:refresh_master_interval
```

This interval specifies the maximum number of seconds that a write request is blocked at a slave while waiting for a master to be elected. For example, to set a time limit on the naming service to 30 seconds:

```
plugins:naming:refresh_master_interval = "30";
```

For more details, see the following sections in the *Orbix Configuration Reference*:

- plugins:naming
- plugins:locator
- plugins:config_rep
- plugins:pss_db:envs:env-name

Relaxing majority rule

To promote a slave, a majority of replicas must be running. This means that in a replica group with two replicas (one master and one slave), the slave can never be promoted. As a special case, it is possible to allow the slave to be promoted. You can do this by setting the following variable to true:

plugins:pss_db:envs:env-name:allow_minority_master = "true";

For more details, see plugins:pss_db:envs:env-name in the *Orbix Configuration Reference*.

Note: Setting allow_minority_master to true means that it is possible for duplicate masters to exist if there is a network partition. It also means that updates may be lost if services are started in different orders. To minimize the possibility of this, perform the following steps:

- 1. Only set the allow_minority_master variable to true on one replica (the one most likely to be the slave).
- 2. The replica with this variable set to true should always be started second.
- 3. If the master fails, and the slave is promoted, the previous master must be restarted only when the new master is running.

Setting heartbeats

Orbix replicated services send heartbeats to handle network partitions and enable promotion of slaves:

- Slave replicas monitor the health of the master by sending periodic heartbeat messages. This enables a slave to be promoted in a timely manner.
- Heartbeats are sent from the master to unresponsive slaves. An
 unresponsive slave is detected if it has not sent a heartbeat message to the
 master in a while.
- Heartbeats are sent from replicas to replicas in an unknown state. When
 any message sent to a replica fails, the replica is marked as unknown until
 it re-joins, is removed, or a network partition is repaired.

This support is controlled by the following configuration variables:

plugins:pss_db:envs:env-name:hearbeat_interval specifies the interval in seconds between heartbeats. A value of 0 means that no heartbeats are sent. The default value is 10 seconds.

plugins:pss_db:envs:env-name:heartbeat_missed_interval specifies the time interval between the last heartbeat from a slave and when the master decides to send a heartbeat to the slave. A value of 0 means this heartbeat and heartbeats between unknown replicas are not sent. The default value is 0 seconds.

Note: plugins:pss_db:envs:env-name:master_heartbeat_interval is deprecated.plugins:pss_db:envs:env-name:hearbeat_interval takes precedence if both are set.

Enabling master demotion

An master replica can demote itself if there is the possibility that unconnected replicas can form a majority and elect a new master. The

plugins:pss_db:envs:env-name:allow_demotion variable specifies whether the master demotes itself if unconnected replicas can form a majority and elect a master. The default value is false.

This variable only needs to be set to true if there are three or more nodes in a replica group, or if there are two replicas in the group, and allow_minority_master is set to true (see "Relaxing majority rule" on page 100).

Overcoming deadlock with duplicate masters

Orbix PSS-based replicated services can overcome potential deadlock when there are duplicate masters. The

plugins:pss_db:envs:env-name:lsn_timeout variable specifies the maximum time in seconds to wait for a replication message for a particular log record.

When this time is exceeded, the pss_db plug-in no longer waits for the log message and continues normal processing. A negative value means the pss_db plug-in never waits for a log record. A value of 0 means the timeout is infinite. Defaults to 10.

Replica administration

The itadmin tool provides several commands to examine the state of replicated services:

```
itadmin ns list_servers
itadmin ns show_server
itadmin locator list_servers
itadmin locator show
itadmin config list_servers
itadmin config show_server
itadmin pss_db list_replicas
itadmin pss_db show
```

For more details on these itadmin commands, see the following:

- "Naming Service" on page 331.
- "Location Domain" on page 289.
- "Configuration Domain" on page 261.
- "Persistent State Service" on page 367.

In addition, for details on administration of PSS databases, see "Managing Orbix Service Databases" on page 137.

Active Connection Management

Overview

Orbix active connection management lets servers scale up to large numbers of clients without encountering connection limits. Using active connection management, Orbix recycles least recently used connections as new connections are required.

You can control active connection management in Orbix with configuration variables, that specify the maximum number of incoming and outgoing client–server connections. Two settings are available for both client-side and server-side connections:

- A hard limit specifies the number of connections beyond which no new connections are permitted.
- A soft limit specifies the number of connections at which Orbix begins closing connections.

Setting incoming server-side connections

To limit the number of incoming server-side connections, set the following configuration variables:

plugins:iiop:incoming_connections:hard_limit specifies the maximum number of incoming (server-side) connections permitted to IIOP. IIOP does not accept new connections above this limit. This variable defaults to -1 (disabled).

plugins:iiop:incoming_connections:soft_limit specifies the number of connections at which IIOP starts closing incoming (server-side) connections. This variable defaults to -1 (disabled).

For example, the following file-based configuration entry sets a server's hard connection limit to 1024:

plugins:iiop:incoming_connections:hard_limit=1024;

The following itadmin command sets this variable:

itadmin variable create -type long -value 1024
 plugins:iiop:incoming_connections:hard_limit

Setting outgoing client-side connections

To limit the number of outgoing client-side connections, set the following configuration variables:

plugins:iiop:outgoing_connections:hard_limit specifies the maximum number of outgoing (client-side) connections permitted to IIOP. IIOP does not allow new outgoing connections above this limit. This variable defaults to -1 (disabled).

plugins:iiop:outgoing_connections:soft_limit specifies the number of connections at which IIOP starts closing outgoing (client-side) connections. This variable defaults to -1 (disabled).

For example, the following file-based configuration entry sets a hard limit for outgoing connections to 1024:

```
plugins:iiop:outgoing_connections:hard_limit=1024;
```

The following itadmin command sets this variable:

```
itadmin variable create -type long -value 1024
    plugins:iiop:outgoing_connections:hard_limit
```

Setting Buffer Sizes

Overview

If the IIOP buffer size within an ORB is configured to a sufficiently large number, fragmentation is not required by the ORB and does not occur. This section describes how to set the buffer size in the C++ and Java CORBA ORBs.

C++ configuration

policies:cprotocol-name>:buffer_sizes_policy:default_buffer_size
This variable is used as the initial size for the buffer and also as the increment
size if the buffer is too small.

For example, when sending a message of 60,000 bytes (including GIOP header overhead, remember depending on the types used by GIOP, this overhead may be large), if the default_buffer_size value is set to 10000, the buffer is initially 10,000 bytes. The C++ ORB then sends out 6 message fragments of 10,000 bytes each. If the default_buffer_size value is set to 64000, only one unfragmented message is sent out.

Java configuration

policies:cprotocol-name>:buffer_sizes_policy:max_buffer_size
This value is used as the initial size for the buffer if smaller than default_buffer_size. For example, when sending a message with an overall size of 60,000 bytes, if the lower of the buffer_size values mentioned above is set to 10000, the buffer is initially 10,000 bytes. The Java ORB then sends out 6 message fragments of 10,000 bytes each. If the lower of the buffer_size values mentioned above is set to 64000, only one unfragmented message is sent out.

Note: These configuration settings apply to secure or non-secure IIOP, depending on whether the iiop or iiop_tls scope is used. For alignment purposes, buffer size values should be a multiple of 8 (i.e. 32,000 or 64,000).

Data fragmentation

For a CORBA ORB to be considered compliant with the OMG GIOP 1.1 specification, the ORB implementation must support data fragmentation.

Some CORBA ORB implementations do not support data fragmentation but claim GIOP 1.1 compliance. Orbix ORBs support fragmentation and are fully compliant with the GIOP 1.1 specification.

Managing the Naming Service

The naming service lets you associate abstract names with CORBA objects in your applications, enabling clients to locate your objects.

The interoperable naming service is a standard CORBA service, defined in the Interoperable Naming Specification. The naming service allows you to associate abstract names with CORBA objects, and enables clients to find those objects by looking up the corresponding names. This service is both very simple and very useful. Most CORBA applications make some use of the naming service. Locating a particular object is a common requirement in distributed systems and the naming service provides a simple, standard way to do this. The naming service is installed by default as part of every Orbix installation.

In addition to naming service functionality, Orbix also provides naming-based load balancing, using *object groups*. An object group is a collection of objects that can increase or decrease in size dynamically. When a bound object is an object group, clients can resolve object names in a naming graph, and transparently obtain references to different objects.

In this chapter

This chapter contains the following sections:

Naming Service Administration	page 109
Controlling the Naming Service	page 112
Building a Naming Graph	page 113

Maintaining a Naming Graph	page 118
Managing Object Groups	page 119

Naming Service Administration

Overview

The naming service maintains hierarchical associations of names and object references. An association between a name and an object is called a *binding*. A client or server that holds a CORBA object reference *binds* a name to the object by contacting the naming service. To obtain a reference to the object, a client requests the naming service to look up the object associated with a specified name. This is known as *resolving* the object name. The naming service provides interfaces, defined in IDL, that enables clients and servers to bind to and resolve names to object references.

The naming service has an administrative interface and a programming interface. These enable administrators and programmers to create new bindings, resolve names, and delete existing bindings. For information about the programming interface to the naming service, see the *CORBA Programmer's Guide*.

Typical administration tasks

While most naming service operations are performed by programs, administrative tasks include:

- Controlling the naming service (for example, starting and stopping the naming service).
- Viewing naming information (for example, bindings between names and objects).
- Adding or modifying naming information that has not been properly
 maintained by programs. For instance, you might need to remove outdated
 information left behind by programs that have been moved or removed
 from the environment.

You can perform these tasks administratively with itadmin commands. This is especially useful when testing applications that use the naming service. You can use itadmin commands to create, delete, and examine name bindings in the naming service.

Name formats and naming graphs

Naming service names adhere to the CORBA naming service format for string names. You can associate names with two types of objects: a *naming context* or an *application object*. A naming context is an object in the naming service within which you can resolve the names of application objects.

Naming contexts are organized into a *naming graph*. This can form a naming hierarchy, much like that of a filing system. Using this analogy, a name bound to a naming context would correspond to a directory and a name bound to an application object would correspond to a file.

The full name of an object, including all the associated naming contexts, is known as a *compound name*. The first component of a compound name gives the name of a naming context, in which the second component is accessed. This process continues until the last component of the compound name has been reached.

A compound name in the CORBA naming service can take two forms:

- An IDL sequence of name components
- A human-readable StringName in the Interoperable Naming Service (INS) string name format

Naming Service Commands

itadmin provides commands for browsing and managing naming service information. Many naming service commands take a *path* argument. This specifies the path to the context or object on which the command is performed.

Note: Many of these commands take object references as command-line arguments. These object references are expected in the string format returned from CORBA::ORB::object_to_string(). By default, this string format represents an interoperable object reference (IOR).

For reference information about these itadmin commands, see "Naming Service" on page 331. The rest of this chapter uses itadmin commands to build an example naming graph and populate it with name bindings.

Controlling the Naming Service

Starting the naming service

You must start up the naming service on the machine where it runs. To start the naming service:

- 1. Log in as root on UNIX, or as administrator on Windows NT.
- 2. Open a terminal or command window.
- 3. Enter itnaming run
- 4. Do the following depending on your platform:

Windows

Leave the command window open.

UNIX

Leave the terminal window open, or push the process into the background and close the window.

Stopping the naming service

itadmin ns stop stops the naming service.

Building a Naming Graph

Overview

A naming context is an object in the naming service that can contain the names of application objects. Naming contexts are organized into a hierarchical naming graph. This section uses itadmin commands to build the naming graph shown in Figure 14.




Figure 14: Naming Context Graph

Names are given in the INS string name format id.kind (for example, john.person). The kind component can be empty (for example, john). The combination of id and kind fields must unambiguously specify the name.

In this section

Using the example naming graph in Figure 14, this section explains the following tasks:

- Creating Naming Contexts.
- Creating Name Bindings.

Creating Naming Contexts

itadmin ns newnc provides the simplest way to create a naming context. This command takes an optional path argument, which takes the form of an INS string name. For example, the following command creates a new context that is bound to a simple name with an id of company, and an empty kind value:

itadmin ns newnc company

The following example creates a new naming context that is bound to the name company/engineering; the context company must already exist.

itadmin ns newnc company/engineering

The following example creates a new context that is bound to the name company/engineering/support; the context company/engineering must already exist.

itadmin ns newnc company/engineering/support

Creating an unbound naming context

You can also use itadmin ns newnc to create an unbound context. If the path argument is not specified, itadmin ns newnc prints the IOR to standard out. For example:

itadmin ns newnc

"IOR:00000000002356702b4944c3a6f6d672e6f7267...."

On UNIX, to bind the context created with ns newnc, use the ns bind -context command, as follows:

itadmin ns bind -c -path company/staff 'itadmin ns newnc'

This binds the new context to the name company/staff.

Creating Name Bindings

To bind a name to an object, use itadmin ns bind -object. Given the naming context graph shown in Figure 14 on page 113, this section assumes the application objects are associated with the following object reference strings:

```
james IOR:0000000037e276f47a4b94874c64648e949...
john IOR:0000028e276f47a40b9248474c64646F3E5...
paula IOR:00000000569a2e8034b94874d6583f09e24...
```

You can bind these objects to appropriate names within the company/staff naming context, as follows:

```
itadmin ns bind -o -path company/staff/james.person
"IOR:0000000037e276f47a4b94874c64648e949..."

itadmin ns bind -o -path company/staff/john.person
"IOR:0000028e276f47a40b9248474c6464646F3E5..."

itadmin ns bind -o -path company/staff/paula.person
"IOR:00000000569a2e8034b94874d6583f09e24..."
```

These commands assign a kind of person in the final component of each employee name.

itadmin ns bind takes an IOR from the command line. For example, on UNIX, if you have Paula's IOR in a file named paula.ior, you can bind it, as follows:

```
itadmin ns bind -o -path company/staff/paula.person 'cat
  paula.ior'
```

To build the naming graph further, create additional bindings that are based on the departments that employees are assigned to. The following example takes IORs from files printed to standard input.

```
itadmin ns bind -o -path
    company/engineering/support/james.person 'cat james.ior'
itadmin ns bind -o -path company/engineering/john.person 'cat
    john.ior'
itadmin ns bind -o -path company/engineering/paula.person 'cat
    paula.ior'
```

To enable an application to find the manager of a department easily, add the following bindings:

```
itadmin ns bind -o -path company/engineering/manager.person 'cat
   paula.ior'

itadmin ns bind -o -path
   company/engineering/support/manager.person 'cat paula.ior'
```

The following names now resolve to the same object:

```
company/staff/paula.person
company/engineering/paula.person
company/engineering/manager.person
company/engineering/support/manager.person
```

The naming contexts and name bindings created by this sequence of commands builds the complete naming graph shown in Figure 14 on page 113.

Maintaining a Naming Graph

Maintenance commands

After you create a naming graph, it is likely you will need to periodically modify its contents—for example, remove bindings, or to change the bindings for an object reference. Table 5 describes the itadmin commands that you can use to maintain naming contexts and bindings.

 Table 5:
 Naming Graph Maintenance Commands

Command	Task
ns list	List all bindings in a naming context
ns resolve	Print the object reference for the application object or naming context to which a name is bound.
ns unbind	Unbind the binding for an object reference.
ns remove	Unbind and destroy a name binding.

Note: unbind and remove can be disabled by setting plugins:naming:destructive_methods_allowed to false.

Rebinding a name to an object or naming context

To change the binding for an object reference, perform the following steps:

1. Use itadmin ns resolve to obtain the object reference bound to the current path and write it to a file:

itadmin ns resolve path > file

The path argument takes the form of a string name.

2. Call itadmin ns unbind to unbind the current path:

itadmin ns unbind path

3. Call itadmin ns bind to bind the saved object reference to the new path. For example, on UNIX:

itadmin ns bind -c newpath 'cat file'

Managing Object Groups

Overview

An *object group* is a naming service object that provides transparent naming-based load balancing for clients. An object group contains application objects, and can increase or decrease in size dynamically when member objects are added or removed.

An object group object can be bound to a path in a naming graph like any other object. Each object group contains a pool of member objects associated with it. When a client resolves the path that an object group is bound to, the naming service returns one of the member objects according to the group's *selection policy*.

Creating an object group

You can create an object group using the itadmin commands in the following steps:

- Create the object group using itadmin nsog create and specify the desired selection algorithm (see "Selection algorithms" on page 120).
- 2. Add application objects to the newly created object group using itadmin nsog add member on it.
- Bind an existing naming context to the object group using itadmin nsog bind.

When you create the object group, you must supply a group identifier. This identifier is a string value that is unique among other object groups.

Similarly, when you add a member to the object group, you must supply a reference to the object and a corresponding member identifier. The member identifier is a string value that must be unique within the object group.

Selection algorithms

Each object group has a selection algorithm that is set when the object group is created. This algorithm is applied when a client resolves the name associated with the object group. Three selection algorithms are supported:

- Round-robin
- Random
- Active load balancing

The naming service directs client requests to objects according to the group's selection algorithm.

Active load balancing

In an object group that uses active load balancing, each object group member is assigned a load value. The naming service satisfies client resolve() invocations by returning references to members with the lowest load values.

Default load values can be set administratively using the configuration variable plugins:naming:lb_default_initial_load. Thereafter, load values should be updated programmatically by periodically calling

ObjectGroup::update_member_load().itadmin provides an equivalent command, nsog update_member_load, in cases where manual intervention is required.

You should also set or modify member timeouts using itadmin nsog set_member_timeout, or programmatically using ObjectGroup::set_member_timeout(). You can configure default timeout values by updating plugins:naming:lb_default_load_timeout. If a member's load value is not updated within its timeout interval, its object reference becomes unavailable to client resolve() invocations. This typically happens because the object itself or an associated process is no longer running, and therefore cannot update the object's load value.

A member reference can be made available again to client resolve() invocations by resetting its load value using

ObjectGroup::update_member_load() or itadmin nsog update_member_load. In general, an object's timeout should be set to an interval greater than the frequency of load value updates.

Commands

"Object Groups" on page 336 describes the itadmin commands that you can use to create and administer object groups.

Managing an Interface Repository

An interface repository stores information about IDL definitions, and enables clients to retrieve this information at runtime. This chapter explains how to manage the contents of an interface repository.

In this chapter

This chapter contains the following sections:

Interface Repository	page 122
Controlling the Interface Repository Daemon	page 123
Managing IDL Definitions	page 124

Interface Repository

Overview

An interface repository maintains information about the IDL definitions implemented in your system. Given an object reference, a client can use the interface repository at runtime to determine the object's type and all information about that type. Clients can also browse the contents of an interface repository. Programmers can add sets of IDL definitions to an interface repository, using arguments to the IDL compiler command.

Interface repository administration

An interface repository database is centrally located. When Orbix environments have more than one interface repository, they are often organized so that each application or set of related applications uses a common interface repository. When an interface repository has been configured, it requires minimal administrative intervention. Typical tasks include stopping and restarting the interface repository, when necessary, removing outdated definitions, when applications are removed, and troubleshooting, when necessary.

This chapter provides information for administrators on how start and stop the interface repository. It also provides information for programmers on how to add, examine, and remove IDL definitions.

For details on advanced interface repository features, see the *CORBA Programmer's Guide*.

Controlling the Interface Repository Daemon

Overview

The primary interface repository tasks for administrators are starting and stopping the interface repository daemon.

Starting the interface repository daemon

Run the interface repository daemon on the machine where the interface repository runs. To start the interface repository:

- 1. Log in as root on UNIX, or as administrator on Windows.
- 2. Open a terminal or command window.
- 3. Enter itifr run.
- 4. Follow the directions for your platform:

Windows

Leave the command window open.

UNIX

Leave the terminal window open, or push the process into the background and close the window.

Stopping the interface repository daemon

itadmin ifr stop stops the interface repository daemon.

Managing IDL Definitions

Overview

Orbix includes an API that offers applications complete programmatic control over managing and accessing IDL definitions in the interface repository. Occasionally, you might require manual control to list definitions, remove invalid definitions, and so on. This is especially useful during application development and troubleshooting.

The interface repository has a structure that mirrors the natural containment of the IDL types in the repository. Understanding these types and their relationships is key to understanding how to use the interface repository. Refer to the *CORBA Programmer's Guide* for more information.

In this section

This section provides information on using the interface repository to perform the following tasks manually:

Browsing Interface Repository Contents	page 125
Adding IDL Definitions	page 127
Removing IDL Definitions	page 128

For a complete reference of the commands used to manage the interface repository, see "Repository Management" on page 285.

Browsing Interface Repository Contents

Overview

This section shows how to use itadmin commands to perform these tasks:

- List the current container
- Display the containment hierarchy
- Navigate to other levels of containment

The foo.idl interface provides a simple example of containment, in which interface Foo contains a typedef and two operations:

```
// Begin foo.idl
interface Foo {
   typedef long MyLong;
   MyLong op1();
   void op2();
};
```

List the current container

itadmin ifr list lists the specified or current container's contents.

```
itadmin ifr list
Foo/
```

Display the containment hierarchy

itadmin ifr show displays the entire containment hierarchy, beginning with the current container. For example:

```
itadmin ifr show Foo
interface Foo
{
    ::Foo::MyLong
    op1();
    typedef long MyLong;
    void
    op2();
};
```

Navigate to other levels of containment

itadmin ifr cd lets you navigate to other levels of containment. For example:

itadmin ifr cd Foo
itadmin ifr list
op1 MyLong op2

Adding IDL Definitions

Overview

Adding IDL definitions to an interface repository makes application objects available to other applications that have access to the same interface repository.

Procedure

You can add IDL definitions to the interface repository with the idl -R=-v command, as follows:

- 1. Go to the directory where the IDL files are located.
- 2. Enter the following command:

```
idl -R=-v filename
```

Example

The following example shows how to add a simple IDL interface definition to the interface repository with the IDL command. The interface definition is:

```
// Begin foo.idl
interface Foo {
   typedef long MyLong;
   MyLong op1();
   void op2();
};
```

The command to add this IDL definition to the interface repository is:

```
$ idl -R=-v foo.idl
Created Alias MyLong.
Created Operation op1.
Created Operation op2.
Created Interface Foo.
$
```

Removing IDL Definitions

Overview

You might wish to remove IDL definitions from the interface repository when they are invalid, or make them unavailable to other applications. To remove an IDL definition, use itadmin ifr remove scoped-name.

Alternatively, to remove the entire contents of the interface repository, use itadmin ifr destroy_contents.

Removing an IDL definition

The following example removes the operation op2 from the foo.idl definition:

itadmin ifr list
Foo/
itadmin ifr cd Foo
itadmin ifr list
op1 MyLong op2
itadmin ifr remove op2
itadmin ifr list
op1 MyLong
itadmin ifr quit

Removing the entire contents of the IFR

To remove the entire contents of the interface repository, use ifr destroy_contents. This destroys the entire contents of the interface repository, leaving the repository itself intact.

If you have loaded a very large number of IDL interfaces into the interface repository, and then want destroy the contents of the IFR, you should first increase the value of the following configuration variable:

```
plugins:pss_db:envs:ifr_store:lk_max
```

This variable specifies the maximum number of locks available to the Berkeley DB. The default is 1000.

The following example increases this value to 10000

```
iona_services {
    ...
    ifr {
        ...
        plugins:pss_db:envs:ifr_store:lk_max = "10000";
    };
};
```

This prevents the IFR from crashing with the following entry in the IFR log file:

```
ERROR: DB del failed; env is ifr_store, db is
IRObjectPSHomeImpl:1.0, errno is 12 (Not enough space)
```

CHAPTER 7 | Managing an Interface Repository

Managing the Firewall Proxy Service

The Orbix firewall proxy service provides an added layer of security to your CORBA servers by placing a configurable proxy between the server and its clients.

In this chapter

This chapter discusses the following topics:

Orbix Firewall Proxy Service	page 132
Configuring the Firewall Proxy Service	page 133
Known Restrictions	page 136

Orbix Firewall Proxy Service

Overview

The main goal of the firewall proxy service is to enable the firewall administrator to reduce the number of ports that need to be opened to enable access from clients outside the firewall to services inside the firewall. To accomplish this the firewall proxy service creates and registers a proxy for each POA created by a server using the service. The proxies then intercept requests made by clients and forwards the requests on to the appropriate server.

Server registration

Any server using the firewall proxy service will exchange IOR template information with the firewall proxy service during a registration process that is kicked off by the creation of a POA. When a server creates a new POA, the firewall proxy service creates a separate proxy which will forward client requests.

Request forwarding

When a server has registered with the firewall proxy service, it will generate IORs that point clients to proxies managed by the firewall proxy service. When a client invokes a request on one of these IORs, the request is intercepted by the firewall proxy service. The firewall proxy service then uses the stored template information to forward the request to the appropriate server.

Persistence of registrations

The firewall proxy service maintains a persistent store of registration information. When the firewall proxy service initializes, it recreates the bindings for any server that registered with the service during a previous execution. This assures that server registration is persistent across many executions of the firewall proxy service.

Configuring the Firewall Proxy Service

Overview

The firewall proxy service is designed to act as an application level proxy mechanism for servers configured to utilize the service at run time. Configuration from the server's point of view is trivial and only requires that a plug-in be initialized in the ORB.

Configuring a server to use the firewall proxy service

Any server that wishes to use the firewall proxy service needs to include the firewall proxy plug-in to the list of plug-ins that are loaded for the server's ORB. You add the plug-in to the ORB's plug-in list using itadmin. The itadmin command is:

itadmin variable modify -scope ORBName -type list -value iiop_profile,giop,iiop,fps orb_plugins

Once the firewall proxy plug-in has been added to the ORB's plug-in list and the firewall proxy service is running, the server will automatically register with the firewall proxy service and the service will relay requests on the client's behalf.

For example, you could configure the typetest demo to use the firewall proxy service. To do this complete the following steps:

1. Create a configuration scope for the typetest demo.

itadmin scope create typetest

2. Add the ORB's plug-in list to the scope.

itadmin variable create -scope ORBName -type list -value iiop_profile,giop,iiop,fps orb_plugins

3. Run the typetest demo server and specify the ORB name.

server -ORBname typetest

Java libraries

To use Java services, such as trader, with the firewall proxy service, you need to ensure that the firewall proxy service's registration agent's jar file, fps_agent.jar, is added to the services CLASSPATH.

Managing the number of proxies

By default, the firewall proxy service imposes no restrictions on the number of servers for which it will proxy requests. The maximum is a factor of system resources. However, you can configure the firewall proxy service to employ a least recently used (LRU) eviction algorithm to select which server bindings to remove. The LRU eviction strategy has configurable soft and hard limits that affect its behavior. The soft limit specifies the point at which the firewall proxy service should proactively begin attempting to reclaim resources. The hard limit specifies the point at which new registrations should be rejected.

The limits are controlled by the following configuration variables:

```
fps:proxy_evictor:soft_limit
fps:proxy_evictor:hard_limit
```

Setting the hard limit to zero effectively disables the services resource control features.

Disabling POA registration

If you develop an application containing a number of "outward" facing objects that you want to place behind the firewall proxy service as well as a number of "inward" facing objects that do not need to be placed behind the firewall proxy service, you can use the INTERDICTION POA policy.

The INTERDICTION policy controls the behavior of the firewall proxy service plug-in, if it is loaded. The INTERDICTION policy has two settings:

ENABLE	This is the default behavior of the firewall proxy service
	plug-in. A POA with its INTERDICTION policy set to ENABLE

will be proxified.

DISABLE This setting tells the firewall proxy service plug-in to not

proxify the POA. POAs with their INTERDICTION policy set to DISABLE will not use the firewall proxy service and requests made on objects under its control will come directly

from the requesting clients.

The following code samples demonstrate how to set the INTERDICTION policy on a POA. In the examples, the policy is set to DISABLE which disables the proxification of the POA. For more information on POA policies read the *CORBA Programmer's Guide*.

Java

```
import com.iona.corba.IT_FPS.*;

// Create a PREVENT interdiction policy.
Any interdiction = m_orb.create_any();
InterdictionPolicyValueHelper.insert(interdiction,
    InterdictionPolicyValue.DISABLE);

Policy[] policies = new Policy[1];
polices[0] = m_orb.create_policy(INTERDICTION_POLICY_ID.value,
    interdiction);

// Create and return new POA.
return m_poa.create_POA("no_fps_poa", null, policies);
```

C++

```
#include <orbix/fps.hh>

// Create a PREVENT interdiction policy.

CORBA::Any interdiction;
interdiction <<= IT_FPS::DISABLE;

CORBA::PolicyList policies(1);
policies.length(1);
policies[0] =
    m_orb->create_policy(IT_FPS::INTERDICTION_POLICY_ID, interdiction);

// Create and return new POA.
return m_poa->create_POA("no_fps_poa", 0, policies);
```

Known Restrictions

The current implementation of the firewall proxy service has the following known restrictions:

- There have are problems using the firewall proxy service and POA collocated calls on UNIX platforms. Calls which should be collocated are being routed through the firewall proxy service in a CORBA mediated call and the call being blocked. The work-around is to remove POA_Coloc from the client_binding_list configuration parameter.
- Transport Layer Security (TLS) is not supported by the firewall proxy service. This means that the firewall proxy service does not work with Iona's IS2 security infastructure or any other systems that use TLS.
- The J2EE portion of your systems cannot be hidden behind a proxy.

Managing Orbix Service Databases

This chapter explains how to manage databases that store persistent data about Orbix services. It explains the Berkeley DB database management system embedded in Orbix.

A number of Orbix services maintain persistent information (for example, the locator daemon, node daemon, naming service, IFR and CFR). By default, these Orbix services use an embedded Berkeley DB database management system. Typically, Berkeley DB requires little or no administration. The default settings are sufficient for most environments. Tasks that you might want to perform include performing checkpoints, and managing backups, recoveries and log files.

In this chapter

This chapter contains the following sections:

Berkeley DB Environment	page 138
Performing Checkpoints	page 139
Managing Log File Size	page 140
Troubleshooting Persistent Exceptions	page 141
Database Recovery for Orbix Services	page 142
Replicated Databases	page 147

Berkeley DB Environment

Overview

A Berkeley DB environment consists of a set of database files and log files. In Orbix, only a single Berkeley DB environment can be used by one process at a time. Multiple processes using the same Berkeley DB environment concurrently can lead to crashes and data corruption. This means that different Orbix services must use different Berkeley DB environments.

This section explains Berkeley DB environment file types and how they should be stored.

Berkeley DB environment files

A Berkeley DB environment consists of two kinds of files:

Data files contain the real persistent data. By default, these files are stored in the data subdirectory of the Berkeley DB environment home directory. For example:

install-dir\var\domain-name\dbs\locator\data

Transaction log files record changes made to the data files using transactions. By default, these files are stored in the logs subdirectory of the Berkeley DB environment home directory. For example:

install-dir\var\domain-name\dbs\locator\logs

All Orbix services use only transactions to update their persistent data.

Transaction log files can be used to recreate the data files (for example, if these files are corrupted or accidently deleted).

Storing environment files

To maximize performance and facilitate recovery, store all the Berkeley DB environment files on a file system that is local to the machine where the Berkeley DB environment is used.

Log files are of more value than data files because data files can be reconstructed from log files (but not vice-versa). Using different disks and disk controllers for the data and the log files further facilitates recovery.

Performing Checkpoints

Overview

The Berkeley DB transaction logs must be checkpointed periodically to force the transfer of updates to the data files, and also to speed up recovery. By default, each Orbix service checkpoints the transaction logs of its Berkeley DB environment every 15 minutes.

Using configuration variables

You can control checkpoint behavior using the following configuration variables:

plugins:pss_db:envs:env_name:checkpoint_period
plugins:pss_db:envs:env_name:checkpoint_min_size

For example, the following variable sets the checkpoint period for the locator database to 10 minutes.

plugins:pss_db:envs:locator:checkpoint_period = 10;

For more information, see the section on the plugins:pss_db namespace in the *Configuration Reference Guide*.

Using the command line

You can also checkpoint the transaction logs of a Berkeley DB environment using the itadmin command. For example:

itadmin pss_db checkpoint env-home/env.ior

For more information, see "Persistent State Service" on page 367.

Managing Log File Size

Setting log file size

The Berkeley DB transaction logs are not reused. They grow until they reach a specified level. By default, a transaction log file grows until its size reaches 10 MB. Berkeley DB then creates a new transaction log file.

You can control the maximum size of transaction log files using the following configuration variable:

plugins:pss_db:envs:env_name:lg_max

lg_max is measured in bytes and its value must be to the power of 2.

Deleting and archiving old log files

When a transaction log file does not contain any information pertaining to active transactions, it can be archived or deleted by either of the following:

Using configuration settings By default, each Orbix service checks after each periodic checkpoint to see if any transaction log files are no longer used. By default, old log files are then deleted. You can disable the deletion of old log files by setting the following configuration variable to false:

plugins:pss_db:envs:env_name:checkpoint_deletes_old_logs

Old log files can also be archived (moved to the old_logs directory). To archive old log files, set the following variable to true:

plugins:pss_db:envs:env_name:checkpoint_archives_old_logs

Using itadmin commands You can also delete or archive the old transaction logs of a Berkeley DB environment using itadmin commands:

```
itadmin pss_db archive_old_logs env-home/env.ior
itadmin pss_db delete_old_logs env-home/env.ior
```

For more information, see "Persistent State Service" on page 367.

WARNING: Deleting old transaction log files can make recovery from a catastrophic failure impossible. See "Database Recovery for Orbix Services" on page 142.

Troubleshooting Persistent Exceptions

Overview

This section explains what has happened if you received a PERSIST_STORE exception from your Orbix service, and how to recover.

PERSIST_STORE exception

When you see an IDL:omg.org/CORBA/PERSIST_STORE:1.0 error from an Orbix service, it typically means that the service's persistent storage has become corrupted. The exception is usually accompanied with a minor code representing a Persistent State Service (PSS) exception (for example, IT_PSS_DB). Such an error is usually caused by some form of corruption in the underlying database. This corruption can be caused by the following:

- There is limited space on the disk for the underlying database files, and thus it is no longer possible to log transactions. If you find this to be the problem, free disk space immediately and restart the service.
- A service has been shutdown ungracefully (without using the stop_<domain_name>_services scripts). For example, this could be caused by executing kill -9 on the service. This can possibly cause corruption on the database due to unfinished transactions.
- You have put your Orbix services databases on an NFS mounted drive, which is either not available, or your machine's NFS client might have a problem.

When the IDL:omg.org/CORBA/PERSIST_STORE:1.0 error occurs, contact IONA support with a copy of logs that show the exact exception, and a description of any unusual activity that may have led up to the problem.

How to recover from a PERSIST_STORE error

To recover from the PERSIST_STORE error, it is likely you will need to recover the most recent stable state of your underlying database. If precautions are taken beforehand, your system can be brought back to this stable state with minimal downtime. It is important to determine the level of recovery that is acceptable within your production environment.

For example, you may wish to recover all data prior to the system going down. Alternatively, there may not be as much concern for loss of data, and it may be satisfactory to simply get back to a stable state such that the services can be restarted.

Database Recovery for Orbix Services

Overview

Each time you start an Orbix service that uses Berkeley DB, the service performs a *normal recovery*. If the service was stopped in the middle of an update, the transaction is rolled back, and the service persistent data is restored to a consistent state.

In some cases, however, the data files or the log files are missing or corrupted, and normal recovery is not sufficient. Then you must perform a *catastrophic recovery*. This section explains how to back up your data and log files and perform a full or incremental recovery. It includes the following:

- "Full backup".
- "Performing a full backup".
- "Full backup recovery".
- "Incremental backup".
- "Enabling incremental backup".
- "Performing an incremental backup".
- "Performing an incremental recovery".

Full backup

It is important that you archive a stable snapshot of your services database, which can be used in case a recovery is needed. This is referred to as a *full backup* and can be performed by making a backup of the entire dbs directory. The purpose of this backup is that if a PERSIST_STORE error occurs for any Orbix services, you can replace the corrupted directory with the backup. The services should then start without a problem.

The backup can be made at any time. The only requirement is that the service be in a stable state (can run and function without errors). You can take the backup directly after configuring your domain, or after the system has been running for a while. The backup that you make will determine the snapshot that your system will return to in the case of a recovery. For example, if you have numerous entries into the IMR (registered POAs, ORBs, and so on), you may wish to add these entries before backing up the locator database. This prevents you from having to do the extra re-configuration if you ever need to recover.

Performing a full backup

To do a full backup, perform the following steps:

Note: If you can bring the services down before doing the backup, you can skip the first step. If you have a live system, and are unable to bring down the services, you can do a backup while the services are running.

 You must first disable the default periodic deletion and/or archival of old log files during the period while you are backing up the database To disable run the following command:

itadmin pss_db pre_backup env.ior

The env.ior represents a handle to the database. Each service should have its corresponding env.ior file within the dbs/<service name>.

2. Make a backup of the following directories

dbs/<service name>/data directory
dbs/<service name>/ logs directory

Store these backups in a safe location. After a successful full backup, you can discard older full backups (if any).

3. Re-enable the default periodic deletion and/or archival of old log files:

itadmin pss_db post_backup env.ior

Full backup recovery

To do a full backup recovery, perform the following steps:

- 1. Determine which service is failing on startup.
- 2. Ensure that your Orbix services are stopped.
- 3. Make a temporary backup the dbs/<service_name> directory for the service you wish to recover.
- Delete the dbs/<service_name> directory for the service you wish to recover.
- Replace the deleted dbs/<service_name> directory in your environment with the latest full backup of this directory.
- Restart the services.

The environment should now be in the state that it was in at the time the last full backup was performed.

Incremental backup

You should determine whether you also need to do regular *incremental backups*. Generally, these are performed in an environment that requires a large amount of additional configuration beyond initial domain creation, or undergoes constant changes to the configuration. For example, it might make sense to do incremental backups of the locator database in an environment where POA and ORB names are being created or modified constantly, and you need to be able to recover to the most recent state possible. Similarly, if the naming service is constantly undergoing changes of objects references, naming contexts, and so on, and any recovery needs to reflect the most recent state of the underlying database. Another candidate would be for a configuration repository where variables are added or modified regularly.

Enabling incremental backup

If you determine that you need to do regular incremental backups, you should perform the following steps first. These steps apply to the locator, but similarly can be applied to naming service, CFR, and so on.

 To enable incremental backup, you should tell the service not to automatically delete old log files. By default, old log files are automatically deleted when it is determined the log file is no longer being used. To disable this default behavior, set the following configuration variable:

```
plugins:pss_db:envs:it_locator:
checkpoint_deletes_old_logs = "false"
```

You can easily apply this to other services by changing it_locator to another service (for example, it_naming).

2. To enable the automatic archival of old log files, set the following configuration variable:

```
plugins:pss_db:envs:it_locator:checkpoint_archives_old_logs
```

This will specify whether old log files are automatically archived to the old_logs directory. To archive old log files, set this variable to true. This defaults to false.

3. To specify where the old log files get archived to, set a value for the following:

```
plugins:pss_db:envs:it_locator:old_logs_dir =
"<path/to/old_logs>"
```

The path is usually set relative to db_home directory. You must ensure you have sufficient space in the above directory, and also, in the location specified by:

```
plugins:pss_db:envs:it_locator:db_home
```

Note: It is critical to the stability of your system that you have sufficient space in these locations to hold the database files and transaction logs for the service.

Performing an incremental backup

The following assumes that you have previously performed a complete backup (see "Full backup" on page 142) at least once in your environment. An incremental backup performs a backup of the log files that have changed or have been created since the last full or incremental backup.

On a predetermined schedule (once a day or week), do a incremental backup of each service as follows:

 Disable the default periodic deletion and/or archival of old log files during the period while you are doing an incremental backup of the database. To disable, run the following command:

```
itadmin pss_db pre_backup env.ior
```

The env.ior represents a handle to the database. Each service should have its corresponding env.ior file within the dbs/<service name>.

- Make a backup of files (if any) in <service_name>/old_logs directory.
 When you have made the backup, it is then safe to remove the contents of the <service_name>/old_logs directory in your production database.
- Make a backup of the <service_name>/logs directory. This contains the most recent (current) transaction log.

Performing an incremental recovery

The following explains the steps needed to recover if data and/or log files have been corrupted. These steps assume you have taken regular incremental backups as described in "Incremental backup" on page 144. Perform the following steps:

- 1. Determine which service is failing on startup.
- 2. Ensure that your Orbix services are stopped.
- Make a temporary backup the dbs/<service_name> directory for the service you wish to recover.
- Delete the dbs/<service_name> directory for the service you wish to recover.
- Replace the deleted dbs/<service_name> directory in your environment with the latest full backup of this directory (see "Full backup recovery" on page 143).
- 6. In the order of oldest to the newest, copy the files from
 <service_name/old_logs and <service_name>/logs from each
 incremental backup. Put the incremental backup versions of the log files in
 <service_name/old_logs and <service_name>/logs into the
 dbs/<service_name>/logs directory of your environment.
- 7. Set the following configuration variable to true:

plugins:pss_db:envs:env_name:recover_fatal

- 8. Start the Orbix services.
- 9. Set the following configuration variable to false: plugins:pss_db:envs:env_name:recover_fatal

The environment should now be in the state it was in when the last archived log file was written. These steps apply to the locator but similarly can be applied to naming service, CFR, and so on.

Further information

For more information, SleepyCat Software provides full details of Berkeley DB administration at http://www.sleepycat.com/docs/.

Replicated Databases

Overview

The Berkeley DB supports replicated databases using the master-slave model with automatic promotion of slaves. The following Orbix services use this functionality to increase their availability:

- Locator daemon
- Naming service
- Configuration repository

Using configuration variables

You can control replicated databases with the following configuration variables:

```
pss_db:envs:env-name:allow_minority_master
pss_db:envs:env-name:always_download
pss_db:envs:env-name:election_backoff_ratio
pss_db:envs:env-name:election_delay
pss_db:envs:env-name:election_init_timeout
pss_db:envs:env-name:init_rep
pss_db:envs:env-name:master_heartbeat_interval
pss_db:envs:env-name:max_elections
pss_db:envs:env-name:replica_priority
```

For more details, see plugins:pss_db:envs:env-name in the Orbix Configuration Reference.

Using the command line

You can examine the state of a replicated database and remove replicas using the itadmin commands. For example:

```
itadmin pss_db list_replicas env-home/env.ior
```

For more details on these commands, see "Persistent State Service" on page 367.

CHAPTER 9 | Managing Orbix Service Databases

Configuring Orbix Compression

This chapter explains how to configure the Orbix ZIOP compression plug-in. This can enable significant performance improvements on low bandwidth networks.

In this chapter

This chapter includes the following topics

Introduction	page 150
Configuring Compression	page 152
Example Configuration	page 156
Message Fragmentation	page 158

Introduction

Overview

The Orbix ZIOP compression plug-in provides optional compression/decompression of GIOP messages on the wire. Compressed and uncompressed transports can be mixed together. This can enable significant performance improvements on low bandwidth networks.

These performance improvements depend on the network and the message data. For example, if the requests contain already compressed data, such as <code>.jpeg</code> images, there is virtually no compression. However, with repetitive string data, there is good compression.

ZIOP stands for Zipped Inter-ORB Protocol, which is an proprietary IONA feature. Figure 15 shows a simple overview of ZIOP compression in a client-server environment.




Figure 15: Overview of ZIOP Compression

Implementation

Orbix ZIOP compression has been implemented in both C++ and Java and is available on all platforms. The Orbix compression plug-in (ziop) supports the following compression algorithms:

- gzip
- pkzip
- bzip2

The compression is performed using a configurable compression library. Compression can be configured on a per-ORB basis, and also on a per-binding basis (using ORB policies).

Per-ORB settings can be made in the client or server scope of your configuration file (described in this chapter). More fine grained per-binding settings can be made programmatically (see the *Orbix CORBA Programmer's Guide* for details).

Additional components

The following Orbix components have also been updated for ZIOP compression:

- The giop_snoop plug-in has been updated to detect ZIOP compressed messages.
- The iordump tool has been updated to parse the new IOR component for ZIOP compression.

Configuring Compression

Overview

Orbix uses symbolic names to configure plug-ins and then associates them with a Java or a C++ implementation. The compression/decompression plug-in is named ziop. This is implemented in Java by the

 $\verb|com.iona.corba.ziop.ZIOPPlugIn class|, and in $C++$ by the it_ziop shared library.$

This section shows how to configure the behavior of the compression plug-in for your client or servers. It includes the following:

- "Configuring the ziop plug-in".
- "Configuring binding lists".
- "Enabling compression".
- "Setting the compression algorithm".
- "Setting the compression level".
- "Setting the compression threshold".

Note: These settings must be added to your client or server configuration scope, as appropriate.

Configuring the ziop plug-in

To configure the ziop plug-in, perform the following steps:

 Ensure that the following entries are present in your Orbix configuration file:

```
plugins:ziop:shlib_name = "it_ziop";
plugins:ziop:ClassName = "com.iona.corba.ziop.ZIOPPlugIn";
```

2. Include the ziop plug-in the ORB plug-ins list:

```
orb_plugins = [ .... "ziop" ...];
```

For example:

Configuring binding lists

To enable compression/decompression for CORBA IIOP communication, ensure that your binding lists contain the following entries.

For clients:

```
binding:client_binding_list = ["GIOP+ZIOP+IIOP"];
```

For servers:

```
plugins:giop:message_server_binding_list = ["ZIOP+GIOP"];
```

The client or server binding lists can be much more complicated than these simple examples, although these are adequate for compressed GIOP/IIOP communication. Here is an example of more complex binding lists:

Enabling compression

To enable or disable compression, use the

policies: ziop: compression_enabled configuration variable. For example:

```
policies:ziop:compression_enabled = "true";
```

The default value is true. This means that even when this entry does not appear in the configuration, compression is enabled. However, the ziop plug-in must first be loaded in the orb_plugins list, and selected by a server or client binding.

Setting the compression algorithm

The default compression algorithm can be set using the policies:ziop:compressor_id configuration variable. For example:

```
policies:ziop:compressor_id = "1";
```

Possible values are as follows:

- 1 gzip algorithm
- 2 pkzip algorithm
- 3 bzip2 algorithm

If this configuration variable is not specified, the default value is 1 (gzip compression).

The ZIOP compression plug-in can be extended with additional compression algorithms using the IT_ZIOP::CompressionManager API. See the *Orbix CORBA Programmer's Guide* for details.

Setting the compression level

To set compression levels, use the

policies:ziop:compressor:compressor_id:level variable.

Using this variable, you can specify the compression level for each of the algorithms registered in the ziop plug-in. The permitted values are specific to the selected algorithm. For example:

```
policies:ziop:compressor:1:level = "9";
```

For the gzip and pkzip algorithms, possible values are in the range between 0 (no compression) and 9 (maximum compression). The default value is 9.

For the bzip2 algorithm, (compressor_id = 3), possible values are in the range between 1 (least compression) and 9 (maximum compression). The default value is 9.

Setting the compression threshold

The compression threshold defines the message size above which compression occurs.

To specify the minimum message size that is compressed, use the policies:ziop:compression_threshold variable. For example:

```
policies:ziop:compression_threshold = "50";
```

Using this setting, messages smaller than 50 bytes are not compressed. The default setting is 0, which means that all messages are compressed.

If you set this to a negative value, the compression threshold is equal to infinity, which means that messages are never compressed. This can be of use if you want to enable compression in one direction only. For example, you can compress messages sent from the server to the client, while in the other direction, messages from the client to the server remain uncompressed.

Example Configuration

Overview

This section shows some example compression configurations. It includes the following:

- "Standard ziop configuration".
- "Debug configuration with giop_snoop".

Standard ziop configuration

The following example shows a standard compression configuration in the ziop test configuration scope:

Depending on the particular circumstances, these settings must be added to the client or the server scope, as appropriate.

If you do not use a scope for your client or server, you can put the settings into the global scope, however, this is not recommended.

Debug configuration with giop_snoop

The following example shows a debug configuration using the giop_snoop plug-in:

```
ziop_test {
plugins:ziop:ClassName = "com.iona.corba.ziop.ZIOPPlugIn";
plugins:ziop:shlib_name = "it_ziop";
plugins:giop snoop:shlib name = "it giop snoop";
plugins:giop_snoop:ClassName =
   "com.iona.corba.giop_snoop.GIOPSnoopPlugIn";
orb_plugins = ["local_log_stream", "iiop_profile", "giop",
   "giop_snoop", "ziop", "iiop"];
binding:client_binding_list = ["GIOP+ZIOP+GIOP_SNOOP+IIOP"];
plugins:giop:message_server_binding_list =
   ["GIOP_SNOOP+ZIOP+GIOP"];
event log:filters = ["IT GIOP=*"];
policies:ziop:compression_enabled = "true";
policies:ziop:compressor_id = "1";
policies:ziop:compression_level = "9";
policies:ziop:compression_threshold = "80";
};
```

Using this configuration, you can trace the compression/decompression behavior. The <code>giop_snoop</code> plug-in logs the parameters to standard out before or after the <code>ziop</code> plug-in (depending on its position before or after the <code>ZIOP</code> plug-in).

To send the output to a file instead of standard out, use the following setting:

```
plugins:local_log_stream:filename = "c:\temp\test.log";
```

Message Fragmentation

Overview

The GIOP/IIOP protocol from version 1.1 can fragment messages. The default setting for Orbix is to use message fragmentation. The default fragment size is 16 KB.

This is relevant to the ziop plug-in, because the compression algorithm can access at most a single fragment at a time. The compression plug-in therefore operates at the granularity of a single fragment. In this way, message fragmentation can potentially have a large effect on the compression rate.

Increasing message fragment size

Depending on the structure of your data, it might make sense to increase the fragment size so that the compression algorithm is optimized for larger blocks of data. You can configure the fragment size using the

 $\verb|policies:iiop:buffer_sizes_policy:default_buffer_size configuration| variable. For example:$

policies:iiop:buffer_sizes_policy:default_buffer_size = "65536";

This sets the fragment size to 64 KB.

Fragmentation example

Only the overall message size is transmitted. For example, if the message is only 4 KB, only these 4 KB are transmitted. Only if the message is larger than the maximum fragment size will it be transmitted in fragments.

For example, if the maximum fragment size is 16 KB. And the message size is 44 KB. The message will be sent in fragments of 16 KB, 16 KB, and 12 KB.

Configuring Advanced Features

This chapter explains some how to configure advanced features such as Java new I/O, IPv6, and bidirectional GIOP.

In this chapter

This chapter includes the following topics

Configuring Java NIO	page 160
Configuring Internet Protocol Version 6	page 163
Configuring Shared Memory	page 166
Configuring Bidirectional GIOP	page 168

Configuring Java NIO

Overview

Java's new I/O (NIO) provides enhanced connection scalability. It enables you to manage more connections with fewer resources (specifically, fewer threads). This section includes the following:

- "ATLI2/Java NIO".
- "Requirements".
- "Enabling Java NIO".
- "CFR-based domains".
- "File-based domains".
- "Further information".

ATLI2/Java NIO

IONA's current transport layer implementation is called the Abstract Transport Layer Interface, version 2 (ATLI2). Orbix offers an ATLI2 implementation based on Java NIO. The default ATLI2 plugin is based on Java classic I/O (CIO).

In addition to allowing more connections to be managed with fewer threads, ATLI2/Java NIO also performs better than ATLI2/Java CIO in the presence of many incoming connections.

Requirements

To use ATLI2/Java NIO, you must have JDK version 1.4.x installed.

Note: Applications that use either Transport Layer Security (TLS) or Endpoint Granularity Multicast Inter-ORB Protocol (EGMIOP) must use the default Java CIO. Java NIO does not support TLS or multicast sockets.

Enabling Java NIO

To enable Java NIO, you must change the plugins:atli2_ip:ClassName configuration variable, which is set to Java CIO by default:

```
plugins:atli2_ip:ClassName
=com.iona.corba.atli2.ip.cio.ORBPlugInImpl
```

You should update this variable to Java NIO as follows:

```
plugins:atli2_ip:ClassName
=com.iona.corba.atli2.ip.nio.ORBPlugInImpl
```

CFR-based domains

When setting Java NIO or CIO in a configuration repository-based domain, if you wish to override plugins:atli2_ip:ClassName at an inner configuration scope, some additional configuration is required.

Enabling Java NIO at an inner scope

When setting Java NIO in CFR-based domain, to override plugins:atli2_ip:ClassName at an inner configuration scope, perform the following steps:

1. Set the following variable at the global scope:

```
plugins:atli2_ip_nio:ClassName=
   "com.iona.corba.atli2.ip.nio.ORBPlugInNIOImpl";
```

2. Set the following at the inner scope:

```
initial_references:IT_IPTransport:plugin = "atli2_ip_nio";
```

Enabling Java CIO at an inner scope

Similarly, when setting Java CIO in a CFR-based domain, to override plugins:atli2_ip:ClassName at an inner scope:

1. Set the following variable at the global scope:

```
plugins:atli2_ip_cio:ClassName=
   "com.iona.corba.atli2.ip.cio.ORBPlugInCIOImpl";
```

2. Set the following at the inner scope:

```
initial_references:IT_IPTransport:plugin = "atli2_ip_cio";
```

File-based domains

When setting Java NIO or Java CIO in a configuration file-based domain, you can override plugins:atli2_ip:ClassName at an inner configuration scope, without the additional configuration required for overriding in a CFR-based domain.

Further information

For more information about Java NIO, see the Sun web site:

http://java.sun.com/j2se/1.4.1/docs/guide/nio/

Configuring Internet Protocol Version 6

Overview

Orbix provides support for Internet Protocol version 4 (IPv4) and Internet Protocol version 6 (IPv6). Orbix supports IPv4 connections by default. IPv6 fixes a number of issues in IPv4, such as the limited number of available IPv4 addresses, and adds improvements in routing and network configuration.

Supported platforms

Orbix supports IPv6 on the following platforms:

- Windows XP and Vista
- Sun Solaris version 8, 9, and 10
- Red Hat Linux AS version 3 and 4

Configuring IPv6 in Orbix

You can configure Orbix servers to listen for the following connections:

- IPv4 only
- IPv4 and IPv6
- IPv6 only

The default behavior is for servers to listen for IPv4 connections only. The following configuration variables control this behavior for Orbix servers and clients:

- policies:network:interfaces:prefer_ipv4
- policies:network:interfaces:prefer ipv6

For example, to enable Orbix communication over IPv6 only, add the following setting in the ORB or global configuration scope:

policies:network:interfaces:prefer_ipv6 = "true";

Configuring IPv4 only communication

By default, prefer_ipv4 is set to true and prefer_ipv6 is set to false. To continue using Orbix where there is no requirement for IPv6 communication, you do not need to make any changes to configuration.

Note: This is the default behavior on any host (including dual-stack) where the hostname can be resolved to an IPv4 address. However, if the hostname can only be resolved to an IPv6 address, by default, prefer_ipv4 set to false and prefer_ipv6 is set to true.

Configuring IPv4 and IPv6 communication

On hosts that are configured for IPv4 and IPv6 (dual-stack), you can configure Orbix servers to listen for connections from clients communicating over both IPv4 and IPv6. To run Orbix servers in this mode, use the following setting in the ORB or global configuration scope:

```
policies:network:interfaces:prefer_ipv4 = "false";
```

Servers started with this configuration listen for both IPv4 and IPv6 client connections. No special configuration is required for Orbix clients connecting to an Orbix server started in this mode.

Configuring IPv6 only communication

On hosts that are configured for IPv4 and IPv6 (dual-stack), you can configure Orbix servers and clients to communicate over IPv6 only using the following setting

```
policies:network:interfaces:prefer_ipv6 = "true";
```

Servers started with this variable set at the global or ORB configuration scope listen for connections from clients connecting over IPv6. Clients with this configuration try to connect over IPv6 to the server.

Note: When this is set to true, no communication is possible from IPv4 clients trying to connect to the server where the server is running on Windows or the server is configured to write numeric addresses into the IOR.

If the hostname can only be resolved to an IPv6 address, by default, the server only listens for IPv6 communication; there is no need to set any configuration for the server or client.

Deploying IPv6 services

The Orbix Configuration tool (itconfigure) does not support enabling services to use IPv6 at deployment time. However, you can to enable Orbix services for IPv6 after deployment using the prefer_ipv4 and prefer_ipv6 configuration variables.

This is only possible when the hostname is written to the IOR for the service. This is because when publishing numeric addresses to the IOR, itconfigure only publishes IPv4 numeric addresses.

Backward compatibility

Enabling a server for IPv6 by setting prefer_ipv4 to false does not affect the ability of older Orbix clients, or clients that have not been enabled for IPv6, to connect to the server.

For more details on compatibility, see "Configuring IPv6 only communication" on page 164.

Direct persistence and replica failover with IPv6

When configuring direct persistence and replica failover, you should enclose IPv6 numeric addresses in brackets. For example:

```
MyConfigApp {
    ...
    wka_1:iiop:addr_list=["[2001:cc1e:1:3:203:baff:fe66:240b]:10
    75", "+host2.com:2075"];
    ...
}
```

For more details, see "Fault Tolerance and Replicated Servers" on page 81.

Specifying IPv6 addresses in a corbaloc

The use of numeric IPv6 addresses is supported since IIOP version 1.2. You must enclose numeric IPv6 addresses in brackets in the corbaloc URL. For example:

"corbaloc::1.2@[fe80::203:baff:fe6f:3e91]:125/OneAddress"

Configuring Shared Memory

Overview

Shared memory is an inter-process communication mechanism, available on certain operating systems. It provides an efficient means of passing data between programs that are executing on the same host. One process creates a memory portion that other processes can access.

When the client and server are located on the same host, using shared memory to communicate is usually faster than using network calls. This section includes the following:

- "Shared memory segment size".
- "Enabling shared memory".
- "Shared memory logging".
- "Shared memory segment size".

Platform availability

The shared memory plug-in is available for C++ ORBs on the following platforms:

- Solaris
- HP-UX
- Windows

Note: Java ORBs can not read their orb_plugins list if it specifies the shared memory plug-in. For this reason, a shared memory configuration domain should not be shared between C++ and Java ORBs.

Enabling shared memory

Orbix provides the shmiop transport plugin, which uses shared memory as its underlying communication mechanism.

To use shared memory with Orbix, perform the following steps:

1. Modify the orb_plugins list in your configuration to include the SHMIOP plugin. For example:

```
orb_plugins = ["local_log_stream", "iiop_profile", "giop",
    "iiop", "shmiop"];
```

On the client side, add the shmiop plugin to the client_binding_list, for example:

```
binding:client_binding_list = ["GIOP+SHMIOP", "GIOP+IIOP"];
```

When the client_binding_list is set, Orbix first attempts to bind to the server using the faster shared memory transport. If this is unsuccessful—for example, if the server is not on the same host as the client—Orbix then uses the standard IIOP transport as normal.

Shared memory logging

To enable logging output from the shared memory plugin, turn on the log stream, and add the following filter in your configuration:

```
event_log:filters = ["IT_ATLI2_SHM=*"];
```

IONA's transport layer implementation is referred to as the Abstract Transport Layer Interface, version 2 (ATLI2).

Shared memory segment size

You can configure the size of the shared memory segment created (for example, in the call to mmap on Solaris). You can set this using the following configuration variable:

```
plugin:atli2_shm:shared_memory_size
```

The default value is 8*1024*1024. This size should be larger than the largest data payload passed between a client and server. If the setting is too small, the shared memory transport will run out of memory, and will be unable to marshal the data. If there is danger of this occurring, add GIOP+IIOP to your client_binding_list setting. This enables the ORB to use the normal network transport if a large payload can not make it through shared memory.

Further information

For information on additional shared memory configuration variables, see the plugin:atli2_shm and policies:shmiop namespaces in the *Orbix Configuration Reference*. The default configuration settings are sufficient for most cases.

Configuring Bidirectional GIOP

Overview

This section explains how to set up your system to use bidirectional GIOP. This allows callbacks to be made using a connection opened by the client, instead of requiring the server to open a new connection for the callback.

Bidirectional GIOP is decoupled from IIOP, and is applicable over arbitrary connection-oriented transports (for example, IIOP/TLS or SHMIOP). Bidirectional GIOP may be used regardless of how the callback IOR is passed to the server. For example, it can be passed over an IDL interface, using a shared file, or using a naming or trader service.

GIOP specifications

Orbix supports bidirectional GIOP (General Inter-ORB Protocol), as described in the firewall submission:

http://www.omg.org/docs/orbos/01-08-03.pdf.

As originally specified, GIOP connections were restricted to unidirectional. This proved to be very inconvenient in certain deployment scenarios where the callback pattern was in use, and clients could not accept incoming connections (for example, due to sandbox restrictions on Java applets, or the presence of client-side firewalls). This restriction was relaxed for GIOP 1.2, allowing bidirectional connections to be used under certain conditions.

This section includes the following:

- "Enabling Bidirectional GIOP" on page 169.
- "Migration and Interoperability Issues" on page 172.

Enabling Bidirectional GIOP

Overview

Bidirectional GIOP is enabled by overriding policies in the client and server applications. To enable bidirectional GIOP, perform the following steps:

- 1. "Set the export policy to allow".
- 2. "Set the offer policy to allow".
- 3. "Set the accept policy to allow".

Set the export policy to allow

The POA used to activate the client-side callback object must have an effective BiDirPolicy::BiDirExportPolicy set to BiDirPolicy::ALLOW. You can do this programmatically by including this policy in the list that is passed to POA::create_POA(). Alternatively, you can do this in configuration, using the following setting:

policies:giop:bidirectional_export_policy="ALLOW";

This results in including an IOP::TAG_BI_DIR_GIOP component in the callback IOR. This indicates that bidirectional GIOP is enabled and advertising a GIOP::BiDirId generated for that POA.

If necessary, you can control the lifespan of the BiDirId by using the proprietary IT_BiDirPolicy::BiDirIdGenerationPolicy, either allowing random or requiring repeatable IDs be generated. This is only an issue if the callback POA is persistent, in which case repeatable IDs are required. This would be unusual because callbacks are usually purely transient, in which case the default BiDirIdGenerationPolicy is appropriate.

Note: Setting policies programatically gives more fine-grained control than setting policies in configuration. See "Implications for pre-existing application code" on page 172 for more details.

Set the offer policy to allow

A bidirectional offer is triggered for an outgoing connection by setting the effective BiDirPolicy::BiDirOfferPolicy to ALLOW for an invocation. This policy may be overridden in the usual way—in descending order of precedence, either on the object reference, current thread, ORB policy manager.

Alternatively, you can do this in configuration, using the following setting:

```
policies:giop:bidirectional_offer_policy="ALLOW";
```

The client_policy demo illustrates the different ways of overriding client policies. This results in an IOP::BI_DIR_GIOP_OFFER service context being passed with the request, unless the policies effective for the callback POA conflict with the outgoing connection (for example, if the former requires security but the latter is insecure).

Set the accept policy to allow

On the server side, the effective BiDirPolicy::BiDirAcceptPolicy for the callback invocation must be set to ALLOW. You can do this in configuration, using the following setting:

```
policies:giop:bidirectional_accept_policy="ALLOW";
```

This accepts the client's bidirectional offer, and uses an incoming connection for an outgoing request, as long the policies effective for the invocation are compatible with the connection.

Confirming bidirectional GIOP is in use

The simplest way to check that bidirectional GIOP is in use is to examine your log file. First, ensure that the level configured for the IT_GIOP sub-system includes INFO_LOW events, for example:

```
event_log:filters = [ "IT_GIOP=INFO_LOW+WARN+ERROR+FATAL", ...];
```

For each client binding established, LocateRequest/Request and/or LocateReply/Reply sent or received in the bidirectional sense, the log message includes a [bidirectional] suffix.

You can also use the iordump utility to check that the TAG_BI_DIR_GIOP component is present in the callback IOR. For information on using iordump, see Appendix 15 on page 213.

Server and client binding lists

In a generated configuration domain, by default, your client and server binding lists are set to include <code>BiDir_GIOP</code>. You do not have to configure these configuration settings manually. The default settings are explained as follows:

• On the server-side, the binding:client_binding_list includes an entry for BiDir_GIOP, for example:

```
binding:client_binding_list = [ "OTS+BiDir_GIOP",
    "BiDir_GIOP", "OTS+GIOP+IIOP", "GIOP+IIOP", ... ];
```

This enables the existing incoming message interceptor chain to be re-used, so that the outgoing client binding dispatches the callback invocation.

• On the client-side, the plugins:giop:message_server_binding_list includes an entry for BiDir_GIOP, for example:

```
plugins:giop:message_server_binding_list=
["BiDir_GIOP","GIOP"];
```

This enables the existing outgoing message interceptor chain to be re-used for an incoming server binding.

Migration and Interoperability Issues

Overview

This section includes the following bidirectional GIOP issues:

- "Implications for pre-existing application code".
- "Incompatible ORBs".
- "Interoperability with Orbix 3".
- "Orbix 6.x restrictions".

Implications for pre-existing application code

There are no implications for existing applications that do not need bidirectional GIOP. This feature is disabled by default.

Otherwise, the code impact can be minimized by setting the relevant policies using configuration, as explained "Enabling Bidirectional GIOP" on page 169. However, this is quite a coarse grained approach, and often its not necessary or desirable to enable bidirectional GIOP for the entire ORB. The recommended approach is to selectively override the relevant programmatic policies in a fine-grained manner on exactly those elements (POAs, ORBs, threads, object references) that require it.

Also, currently existing persistent callback IORs (for example, those bound in the naming service) must be regenerated to include the TAG_BI_DIR_GIOP component. However, this is unlikely to impact many real applications as callback references are usually transient and regenerated every time the client application is run.

Incompatible ORBs

There are several incompatible bidirectional schemes in use. For example, Orbacus uses a proprietary mechanism, and several commercial and open source ORBs support the soon-to-be obsolete bidirectional standard; while Orbix 2000 and Orbix E2A 5.x/6.0 do not have any analogous functionality.

All of these schemes are mutually incompatible and non-interoperable. Hence, Orbix 6.x reverts to unidirectional GIOP when interoperating with any of these ORBs.

Interoperability with Orbix 3

Orbix 6.x includes support for interoperability with Orbix 3.x (Generation 3). This enables an Orbix 6.x server to invoke on an Orbix 3.x callback reference in a bidirectional fashion. To configure interoperability with Orbix 3.x, perform the following steps:

Set the IT_BiDirPolicy::BidirectionalGen3AcceptPolicy to ALLOW.
 This is a proprietary policy analogous to
 BiDirPolicy::BidirectionalAcceptPolicy. It enables an Orbix 6.x
 server to accept an Orbix 3.x bidirectional offer.

 You can do this either programmatically or using the following

```
policies:giop:bidirectional gen3 accept policy="ALLOW";
```

2. Include the appropriate BiDir_Gen3 entry in the server's configured binding:client_binding_list. For example,

configuration setting:

For more details, see "Server and client binding lists" on page 171.

Orbix 3 restrictions The following restrictions apply to bidirectional GIOP in Orbix 3:

- Orbix 3 bidirectional callback references may only be passed to the server
 as a request parameter. Orbix 6.x bidirectional callback references can be
 passed in any way (for example, using the naming service, or a shared file).
- Orbix 3 bidirectional callback references may only be invoked on in a
 bidirectional fashion during the lifetime of the connection over which it
 was received. Orbix 6.x bidirectional invocations may be made after the
 connection is reaped by Active Connective Management and
 re-established.

The Orbix 6.x and Orbix 3 bidirectional mechanisms will co-exist peacefully. An incoming connection can only be considered for bidirectional invocations by, at most, one of the two schemes, depending on whether the client is based on Orbix 6.x or Orbix 3.x.

Orbix 6.x restrictions

Orbix 6.x includes the following restrictions:

- Orbix 6.x support for Orbix 3 bidirectional GIOP is asymmetric. An Orbix 6.x server can invoke on a Orbix 3 callback reference using bidirectional GIOP. However, an Orbix 6.x client can not produce a callback reference that an Orbix 3 server could invoke on using bidirectional GIOP.
- To be compatible with GIOP 1.2 (that is, not be dependent on GIOP 1.4
 NegotiateSession messages), only weak BiDirIds are used, and the
 challenge mechanism to detect client spoofing is not supported. This
 functionality will be added in a future release, when GIOP 1.4 is
 standardized.

Orbix Mainframe Adapter

The Orbix Mainframe Adapter (MFA) plugin enables you to communicate with Orbix Mainframe CICS and IMS server adapters from Windows and UNIX. It includes a Mapping Gateway interface and an itmfaloc URL resolver. This chapter introduces the CICS and IMS server adapters, and explains how to use the Mapping Gateway interface and the itmfaloc URL resolver.

In this chapter

This chapter contains the following sections:

CICS and IMS Server Adapters	page 176
Using the Mapping Gateway Interface	page 177
Locating Server Adapter Objects Using itmfaloc	page 181

Note: In addition to Orbix, you must have Orbix Mainframe installed and running before you can use the MFA.

CICS and IMS Server Adapters

Overview

The Orbix Mainframe product includes a CICS server adapter and an IMS server adapter. This section gives a brief description of each of these adapters and includes the following to topics:

- CICS server adapter
- IMS server adapter
- More information

CICS server adapter

The Orbix CICS server adapter is an Orbix Mainframe service that can be deployed in either a native OS/390 or UNIX System Services environment. The CICS server adapter acts as a bridge between CORBA/EJB clients and CICS servers. It enables you to set up a distributed system that combines the powerful online transaction processing capabilities of CICS with the consistent and well-defined structure of a CORBA environment.

IMS server adapter

The Orbix IMS server adapter is an Orbix Mainframe service that can be deployed in a native OS/390 or UNIX System Services environment. It provides a simple way to integrate distributed CORBA and EJB clients on various platforms with existing and new IMS transactions running on OS/390. The IMS server adapter allows you to develop and deploy Orbix COBOL and PL/I servers in IMS, and to integrate these IMS servers with distributed CORBA clients running on various platforms. It also facilitates the integration of existing IMS transactions, not developed using Orbix, with distributed CORBA clients, without the need to change these existing transactions.

More information

For more information, see the *Orbix Mainframe CICS Adapters Administrator's Guide* and *IMS Adapters Administrator's Guide*, which are available on the IONA documentation web pages at:

http://www.iona.com/support/docs/orbix/mainframe/6.0/index.xml

Using the Mapping Gateway Interface

Overview

The Mapping Gateway interface is used to control CICS or IMS server adapters running on the mainframe. You can use the Mapping Gateway interface to list the transaction mappings that the server adapter supports, to add or delete individual interfaces and operations, or to change the transaction that an operation is mapped to. A new mapping file can be read, or the existing mappings can be written to a new file. Access to the Mapping Gateway interface using <code>itadmin</code> is provided as a plug-in. This plug-in is selected with the <code>mfa</code> keyword.

In this section

This section provides some examples of how you can to use the itadmin mfa plugin to control CICS and IMS server adapters running on the mainframe. The following topics are covered:

- Configuring the Mapping Gateway interface
- Listing itadmin mfa commands
- Printing a list of supported mappings
- Changing an operation's transaction mapping
- Saving mappings to a specified file and reloading current mappings
- Switching the mapping file
- Invoking on exported interfaces
- Selecting a specific server adapter

Configuring the Mapping Gateway interface

The Mapping Gateway interface is configured by default. The following configuration values are added to the configuration file:

```
plugins:mfa_adm:grammar_db = "admin_plugins = [..., "mfa_adm"];
plugins:mfa_adm:shlib_name = "it_mfa_adm";
plugins:mfa_adm:grammar_db = "mfa_adm_grammar.txt";
plugins:mfa_adm:help_db = "mfa_adm_help.txt";
```

You must, however, add the mainframe IOR to the configuration file as follows:

```
initial_references:IT_MFA:reference = "IOR: ....";
```

For details of how to obtain the IOR, see the CICS Adapters Administrator's Guide and the IMS Adapters Administrator's Guide.

Listing itadmin mfa commands

To obtain a list of all the commands provided by the itadmin mfa plug-in, use the following command:

```
$ itadmin mfa -help
```

The output is follows:

```
mfa list
   add     -interface < name> -operation < name> < mapped value>
   change     -interface < name> -operation < name> < mapped value>
   delete     -interface < name> -operation < name>
   resolve < interface name>
   refresh [-operation < name>] < interface name>
   reload
   save [<mapping_file name>]
   switch < mapping_file name>
   stats
   resetcon
   stop
```

Items shown in angle brackets (<...>) must be supplied and items shown in square brackets ([...]) are optional. Modules names form part of the interface name and are separated from the interface name with a / character. For detailed information on these commands, see Chapter 24.

Printing a list of supported mappings

To print a list of the mappings (interface, operation and name) that the server adapter supports, use the following command:

itadmin mfa list

For example, the output is as follows:

```
Simple/SimpleObject,call_me, SIMPLESV nested_seqs,test_bounded,NSTSEQSV nested_seqs,test_unbounded,NSTSEQSV
```

Changing an operation's transaction mapping

You can use the mfa change command to change the transaction to which an existing operation is mapped. For example, to change the transaction to which the call_me operation is mapped, from SIMPLESV to NSTSEQSV, use the following command:

```
itadmin mfa change -interface Simple/SimpleObject -operation
  call me NSTSEOSV
```

To view the result, use the mfa list command:

itadmin mfa list

For example, the output is as follows:

```
Simple/SimpleObject,call_me, NSTSEQSV
nested_seqs,test_bounded,NSTSEQSV
nested_seqs,test_unbounded,NSTSEQSV
```

Saving mappings to a specified file and reloading current mappings

You can use the mfa save command to get the server adapter to save its current mappings to either its current mapping file or to a filename that you provide. For example, to cause the server adapter to save its current mappings to a file called myMappings.map, but reload the list of mappings from its mapping file, use the following commands:

```
itadmin mfa save "c:\myMappings.map" itadmin mfa reload
```

To view the result, use the mfa list command:

itadmin mfa list

For example, the output is as follows:

Simple/SimpleObject,call_me, SIMPLESV nested_seqs,test_bounded,NSTSEQSV nested seqs,test unbounded,NSTSEOSV

Switching the mapping file

You can get the server adapter to switch to using a new mapping file and export only the mappings contained within it. For example, to get the server adapter to switch from its current mapping file to myMappings.map, use the following command:

itadmin mfa switch "c:\myMappings.map"

To view the result, use the mfa list command:

itadmin mfa list

The output looks as follows:

Simple/SimpleObject,call_me, NSTSEQSV nested_seqs,test_bounded,NSTSEQSV nested_seqs,test_unbounded,NSTSEQSV

Invoking on exported interfaces

The Mapping Gateway interface provides the means by which IIOP clients can invoke on the exported interfaces. Using the resolve operation, an IOR can be retrieved for any exported interface. This IOR can then be used directly by IIOP clients, or registered with an Orbix naming service as a way of publishing the availability of the interface. For example, to retrieve an IOR for Simple IDL, use the following command:

itadmin mfa resolve Simple/SimpleObject

Selecting a specific server adapter

To select a specific server adapter, provide the ORBname for the server adapter on a request. For example, to specify the CICS server adapter and obtain the IOR for the Simple interface, use the following command:

itadmin -ORBname iona_utilities.cicsa mfa resolve Simple/SimpleObject

Locating Server Adapter Objects Using itmfaloc

Overview

The CICS and IMS server adapter maintains object references that identify CORBA server programs running in CICS and IMS respectively. A client must obtain an appropriate object reference in order to access the target server. The <code>itmfaloc</code> URL resolver plug-in facilitates and simplifies this task.

Note: The itmfaloc URL resolver is only available in C++.

In this section

This section discusses how you can use the itmfaloc URL resolver as an alternative to the itadmin mfa resolve command. The following topics are covered:

- Locating server adapters using IORs
- Locating objects using itmfaloc
- Format of an itmfaloc URL
- What happens when itmfaloc is used
- Example of using itmfaloc

Locating server adapters using IORs

One way of obtaining an object reference for a target server, managed by the CICS or IMS server adapter, is to retrieve the IOR using the itadmin tool. This calls the resolve() method on the server adapter's Mapping Gateway interface and returns a stringified IOR. For example, to retrieve an IOR for Simple IDL, use the following command:

itadmin mfa resolve Simple/SimpleObject

When retrieved, the IOR can be distributed to the client and used to invoke on the target server running inside CICS.

Locating objects using itmfaloc

In some cases, the use of <code>itadmin</code> and the need to persist stringified IORs is not very manageable, and a more dynamic approach is desirable. The <code>itmfaloc</code> URL resolver is designed to provide an alternative approach. It follows a similar scheme to that of the corbaloc URL technique.

In this way, the Orbix CORBA client can specify a very simple URL format which identifies the target service required. This text string can be used programmatically in place of the rather cumbersome stringified IOR representation.

Format of an itmfaloc URL

An itmfaloc URL is a string of the following format:

itmfaloc:<InterfaceName>

<InterfaceName> is the fully-scoped name of the IDL interface implemented by the target server (as specified in the server adapter mapping file).

What happens when itmfaloc is used

When an itmfaloc URL is used in place of an IOR, the Orbix client application contacts the server adapter to attain an object reference for the desired CICS or IMS server. The itmfaloc URL string only encodes the interface name and not the server adapter's location. To establish the initial connection to the server adapter, the value of the IT_MFA:initial_references variable is used.

If multiple server adapters are deployed, the client application must specify the correct <code>IT_MFA:initial_references</code> setting in order to contact the correct server adapter. You can do this by specifying the appropriate ORB name, which represents the particular configuration scope. For example, for the CICS server adapter, <code>-ORBname iona_utilities.cicsa</code>

If the client application successfully connects to the server adapter, it calls the resolve() operation on the Mapping Gateway object reference, retrieving an object reference for the target server managed by the server adapter.

Example of using itmfaloc

The simple demo client code that is shipped with Orbix uses a file-based mechanism to access the target server's stringified IOR. If the target server resides in CICS or IMS, an alternative approach is to specify an itmfaloc URL string in the string-to-object call; for example:

CHAPTER 12 | Orbix Mainframe Adapter

Part III

Monitoring Orbix Applications

In this part

This part contains the following chapters:

Configuring Orbix Logging	page 187
Monitoring GIOP Message Content	page 201
Debugging IOR Data	page 213

Configuring Orbix Logging

Orbix logging enables you to collect system-related information, such as significant events, and warnings about unusual or fatal errors.

Through a configuration domain's logging variables, you can specify the kinds of messages to collect, and where to direct them.

Note: For information on logging Orbix Windows NT Services, refer to "Logging Orbix Windows Services" on page 412.

In this chapter

This chapter covers the following topics:

Setting Logging Filters	page 188
Logging Subsystems	page 190
Logging Severity Levels	page 192
Configuring Log Output	page 194
Dynamic Logging	page 198

Setting Logging Filters

Overview

The event_log:filters configuration variable sets the level of logging for specified subsystems, such as POAs or the naming service. You can set this variable in an Orbix configuration file or using itadmin commands.

In addition, you can also set logging levels dynamically using itadmin commands and the IONA Administrator Web Console.

Logging syntax

The event_log:filters variable is set to a list of filters, where each filter sets logging for a specified subsystem with the following format:

subsystem=severity-level[+severity-level]...

For example, the following filter specifies that only errors and fatal errors for the naming service should be reported:

IT_NAMING=ERR+FATAL

The subsystem field indicates the name of the Orbix subsystem that reports the messages (see Table 6 on page 190). The severity field indicates the severity levels that are logged by that subsystem (see Table 7 on page 193).

You can set this variable by directly editing a configuration file, or using itadmin commands. In the examples that follow, logging is enabled as follows:

- For POAs, enable logging of warnings, errors, fatal errors, and high-priority informational messages.
- For the ORB core, enable logging of all events.
- For all other subsystems, enable logging of warnings, errors, and fatal errors.

Set in a configuration file

In a configuration file, event_log:filters is set as follows:

```
event_log:filters=["log-filter"[,"log-filter"]...]
```

The following entry in a configuration file explicitly sets message severity levels for the POA and ORB core, and all other subsystems:

Set with itadmin

You can use itadmin commands variable create and variable modify to set and modify event_log:filters. For example, the following command creates the same setting as shown before, this time specifying to set this logging for the locator daemon:

```
itadmin variable modify -scope locator -type list -value\
   IT_POA=INFO_HI+WARN+ERROR+FATAL, \
   IT_CORE=*, \
   *=WARN+ERR+FATAL \
   event_log:filters
```

Dynamic logging

The itadmin logging get and logging set commands enable the Orbix event log filters to be displayed or updated dynamically on the command line. You can also perform these actions using the IONA Administrator Web Console. For more details, see "Dynamic Logging" on page 198.

Logging Subsystems

You can apply one or more logging severity levels to any or all ORB subsystems. Table 6 shows the available ORB subsystems. By default, Orbix logs warnings, errors, and fatal errors for all subsystems.

 Table 6:
 Orbix Logging Subsystems

Subsystem	Description
*	All logging subsystems.
IT_ACTIVATOR	Activator daemon.
IT_ATLI2_IOP	Abstract Transport Layer Inter-ORB Protocol.
IT_ATLI2_IP	Abstract Transport Layer Internet Protocol Plug-in.
IT_ATLI2_ITMP	Abstract Transport Layer Multicast Plug-in.
IT_ATLI2_ITRP	Abstract Transport Layer Reliable Multicast Plug-in.
IT_ATLI2_SHM	Abstract Transport Layer Shared Memory Plug-in.
IT_ATLI_TLS	Abstract Transport Layer (secure).
IT_CFR	Configuration repository.
IT_ClassLoading	Classloading plug-in (Java).
IT_CODESET	Internationalization plug-in.
IT_CONFIG_REP	Configuration repository.
IT_CORE	Core ORB.
IT_CSI	Common Secure Interoperability.
IT_GIOP	General Inter-Orb Protocol (transport layer).
IT_GSP	Generic Security Plug-in.
IT_IFR	Interface repository.
IT_IIOP	Internet Inter-Orb Protocol (transport layer).

 Table 6:
 Orbix Logging Subsystems

Subsystem	Description
IT_IIOP_PROFILE	Internet Inter-Orb Protocol profile (transport layer).
IT_IIOP_TLS	Internet Inter-Orb Protocol (secure transport layer).
IT_JAVA_SERVER	Java server plug-in
IT_LEASE	Session management service.
IT_LOCATOR	Server locator daemon.
IT_MGMT	Management instrumentation plug-in.
IT_MGMT_SVC	Management service.
IT_NAMING	Naming service.
IT_NOTIFICATION	Event service.
IT_NodeDaemon	Node daemon.
IT_OTS_LITE	Object transaction service.
IT_POA	Portable object adapter.
IT_POA_LOCATOR	Server locator daemon (POA specific).
IT_PSS	Persistent state service.
IT_PSS_DB	Persistent state service (raw database layer).
IT_PSS_R	Persistent state service (database driver).
IT_SCHANNEL	Microsoft Schannel (Windows only).
IT_TLS	Transport Layer Security.
IT_TS	Threading/synchronization package.
IT_XA	X/Open XA standard (transactions).

Logging Severity Levels

Overview

Orbix supports four levels of message severity:

- Informational
- Warning
- Error
- Fatal error

Informational

Informational messages report significant non-error events. These include server startup or shutdown, object creation or deletion, and information about administrative actions.

Informational messages provide a history of events that can be valuable in diagnosing problems. Informational messages can be set to low, medium, or high verbosity.

Warning

Warning messages are generated when Orbix encounters an anomalous condition, but can ignore it and continue functioning. For example, encountering an invalid parameter, and ignoring it in favor of a default value.

Error

Error messages are generated when Orbix encounters an error. Orbix might be able to recover from the error, but might be forced to abandon the current task. For example, an error message might be generated if there is insufficient memory to carry out a request.

Fatal error

Fatal error messages are generated when Orbix encounters an error from which it cannot recover. For example, a fatal error message is generated if the ORB cannot connect to the configuration domain.

Table 7 shows the syntax used to specify Orbix logging severity levels.

 Table 7:
 Orbix Logging Severity Levels

Severity Level	Description
INFO_LO[W]	Low verbosity informational messages.
INFO_MED[IUM]	Medium verbosity informational messages.
INFO_HI[GH]	High verbosity informational messages.
INFO_ALL	All informational messages.
WARN[ING]	Warning messages.
ERR[OR]	Error messages.
FATAL [_ERROR]	Fatal error messages.
*	All messages.

Configuring Log Output

Overview

By default, Orbix is configured to log messages to standard error. You can change this behavior for an ORB by setting a logstream plug-in to be loaded by the ORB. For example, you can set the output stream to a local file owned by the ORB, or to the host's system error log.

As with all other configuration variables, these can be set using the itadmin commands variable create and variable modify.

This section includes the following:

- "Setting the output stream to a local file".
- "Using rolling log files".
- "Setting the output stream to the system log".
- "Buffering the output stream before writing to a file".
- "Setting precision logging".
- "Setting request logging".

Setting the output stream to a local file

To set the output stream to a local file, set the following configuration variable:

plugins:local_log_stream:filename = filename

For example:

plugins:local_log_stream:filename = "/var/adm/mylocal.log";

Note: In a configuration repository domain, this variable is set by default (for example: "/var/logs/boot-orb.log"). To enable logging to standard error, remove (or comment out) this variable.

Using rolling log files

Normally, the local log stream uses a rolling file to prevent the log from growing indefinitely. In this model, the stream appends the current date to the configured filename. This produces a complete filename (for example,

/var/adm/art.log.02172002). A new file begins with the first event of the day and ends at 23:59:59 each day.

You can disable rolling file behavior by setting the rolling_file variable to false. For example:

```
plugins:local_log_stream:rolling_file = "false";
```

Setting the output stream to the system log

The system log stream reports events to the host's system log—syslog on UNIX, and the event log on Windows. Each log entry is tagged with the current time and logging process ID, and the event priority is translated into a format appropriate for the native platform.

To set the output stream to the system log, add the system_log_stream value to the orb_plugins configuration variable. You can use the system_log_stream output stream concurrently with the local_log_stream, if necessary.

The following orb_plugins variable includes the system_log_stream value:

```
orb_plugins=["system_log_stream", "iiop_profile", "giop",
"iiop",];
```

Buffering the output stream before writing to a file

You can also set the output stream to a buffer before writing to a local log file. Use the plugins:local_log_stream:buffer_file configuration variable to specify this behavior. When this variable is set to true, by default, the buffer is output to the local file every 1000 milliseconds when there are more than 100 messages logged. The log interval and the number of log elements can also be configured.

For example, the following configuration writes the log output to the /var/adm/art.log file every 400 milliseconds if there are more then 20 log messages in the buffer.

```
plugins:local_log_stream:filename = "/var/adm/art.log";
plugins:local_log_stream:buffer_file = "true";
plugins:local_log_stream:milliseconds_to_log = "400";
plugins:local_log_stream:log_elements = "20";
```

Setting precision logging

You can also specify whether events are logged with time precision, or at the granularity of seconds. Precision logging is disabled by default (to avoid changing the logging output of deployed systems). To enable precision logging, set the value to true. For example:

```
plugins:local_log_stream:precision_logging = "true";
```

Application code can also provide its own LogStream to receive precision events by implementing the PrecisionLogStream interface. For details, see the *Orbix Configuration Reference*.

Setting request logging

For C++ applications, you can use the request logger plug-in to output logging that combines connection information with GIOP request information.

Request logging format

The request_logger plug-in logs one log statement for each incoming request and one log statement for each outgoing reply. The format of the request log statement is as follows:

```
[REQUEST] IPaddress, port, operation, NO PRINCIPAL giop principal[, TransactionName]
```

The format of the reply log statement is as follows:

```
[REPLY] IPaddress, port, operation, NO PRINCIPAL giop principal[, TransactionName], ReturnStatus
```

The TransactionName is only logged for Orbix mainframe, and only if the operation name is one of the known operations of the imsraw or cicsraw interfaces. The cicsraw operations are as follows:

```
run_program
run_program_binary
run_program_with_trans
run_program_binary_with_trans
```

The imsraw operations are as follows:

```
run_transaction
run_transaction_binary
run_transaction_no_reply
run_transaction_binary_no_reply
```

If no GIOP principal is contained in the request, the NO PRINCIPAL string is logged. Otherwise, the GIOP principal is logged.

policies:giop:interop_policy in the *Orbix Configuration Reference* explains how to specify that a GIOP principal is sent by the client and received by the server.

Request logging configuration

The configuration variable that identifies the shared library (or DLL in Windows) that contains the request logger plug-in implementation is included in a generated configuration domain:

```
plugins:request_logger:shlib_name = "it_request_logger";
```

To enable the request logger server interceptor to included in a server binding, add the request logger plug-in to the orb_plgins list after the giop plug-in, for example:

```
orb_plugins = ["local_log_stream", "iiop_profile", "giop",
    "iiop", "request_logger"];
```

In addition, you must add the server interceptor name to the server_binding_list, for example:

```
binding:server_binding_list = ["request_logger", ""];
```

Dynamic Logging

Overview

Dynamic logging enables you to modify the event_log:filters setting of a deployed server ORB on the fly, without needing to stop, reconfigure the static setting, and restart the server. You can change logging dynamically using itadmin commands or the IONA Administrator Web Console.

Note: You must ensure that dynamic logging has been enabled for a service when the domain was created using the **Orbix Configuration** tool. For details, see the *Orbix Deployment Guide*.

using itadmin commands

The itadmin logging get and logging set commands enable the Orbix event log filters to be displayed or updated dynamically on the command line.

For example, the following command dynamically updates the event log filters that are used by the currently running naming service.

itadmin logging set -orbname iona_services.naming -value IT_GIOP=*,IT_MGMT=*

For full details, see "Event Log" on page 245.

C++ management agent registration plug-in

The C++ management agent registration plug-in is designed for use in a domain were the Java-based Orbix management service is not deployed. It is available as C++ implementation only. This plug-in is not intended as a replacement for the management service but as a means to dynamically change logging levels of servers using itadmin.

You do not need to use this plug-in in a domain were the management service is deployed. In such a domain, you can dynamically update log levels of servers using itadmin and the IONA Administrator Web Console.

Note: To use C++ management agent registration plug-in, the naming service must be deployed.

To enable this plug-in, use the following configuration:

IONA Administrator Web Console

For details on using the IONA Administrator Web Console, see the *Orbix Management User's Guide*.

CHAPTER 13 | Configuring Orbix Logging

Monitoring GIOP Message Content

Orbix includes the GIOP Snoop tool for intercepting and displaying GIOP message content.

In this chapter

This chapter contains the following sections:

Introduction to GIOP Snoop	page 202
Configuring GIOP Snoop	page 203
GIOP Snoop Output	page 206

Introduction to GIOP Snoop

Overview

GIOP Snoop is a GIOP protocol level plug-in for intercepting and displaying GIOP message content. This plug-in implements message level interceptors that can participate in client and/or server side bindings over any GIOP-based transport. The primary purposes of GIOP Snoop are to provide a protocol level monitor and debug aid.

GIOP plug-ins

The primary protocol for inter-ORB communications is the General Inter-ORB Protocol (GIOP) as defined the CORBA Specification. Orbix provides several GIOP based plug-ins that map GIOP to a number of transports. For example, CORBA IIOP (for TCP/IP), and proprietary IONA transport mappings, such as SIOP (a shared memory transport), and MPI (a multicast transport for GIOP). GIOP Snoop may be used with these (and any future) GIOP-based plug-ins.

Configuring GIOP Snoop

Overview

GIOP Snoop can be configured for debugging in client, server, or both depending on configuration. This section includes the following configuration topics:

- "Loading the GIOP Snoop plug-in".
- "Client-side snooping".
- "Server-side snooping".
- "GIOP Snoop verbosity levels".
- "Directing output to a file".
- "Using the Java version of GIOP Snoop"

Loading the GIOP Snoop plug-in

For either client or server configuration, the GIOP Snoop plug-in must be included in the Orbix orb_plugins list (... denotes existing configured settings):

```
orb_plugins = [..., "giop", "giop_snoop", "iiop" ...];
```

Note: The giop_snoop plug-in must be placed between giop and iiop. Failing to do so results in a message similar to the following:

```
Wed, 30 Oct 2005 10:09:43.0000000 [merge:11654] (IT_CORE:200) E - could not resolve initial reference for IT_GIOP_ServerFactoryManager: not registered or configured Unexpected CORBA exception: InvalidName (IDL:omg.org/CORBA/ORB/InvalidName:1.0) Server exiting
```

Additional settings

In addition, the giop_snoop plug-in must be located and loaded using the following settings:

```
// C++
plugins:giop_snoop:shlib_name = "it_giop_snoop";

// Java
plugins:giop_snoop:ClassName =
   "com.iona.corba.giop_snoop.GIOPSnoopPlugIn";
```

Client-side snooping

To enable client-side snooping, include the GIOP_SNOOP factory in the client binding list. In this example, GIOP Snoop is enabled for IIOP-specific bindings:

When setting bindings for the client and server side make sure the GIOP snoop binding goes before the GIOP+IIOP (client) and GIOP (server), as shown in the examples. Failing to do so will produce no additional output from the GIOP snoop plug-in.

Server-side snooping

To enable server-side snooping, include the GIOP_SNOOP factory in the server binding list.

```
plugins:giop:message_server_binding_list = [...
    "GIOP_SNOOP+GIOP", "GIOP" ...];
```

Note: For Orbix 6.x, the ordering of this setting has been reversed to correct consistency issues in previous releases of Orbix across Java and C++ configuration.

GIOP Snoop verbosity levels

You can use the following variable to control the GIOP Snoop verbosity level:

```
plugins:giop_snoop:verbosity = "1";
```

The verbosity levels are as follows:

- 1 LOW2 MEDIUM3 HIGH
- 4 VERY HIGH

These verbosity levels are explained with examples in "GIOP Snoop Output" on page 206.

Directing output to a file

By default, GIOP Snoop output is directed to standard error (stderr). However, you can specify an output file using the following configuration variable:

```
plugins:giop_snoop:filename = "<some-file-path>";
```

You can include a month/day/year time stamp in the output filename with the following general format:

```
<filename>.MMDDYYYY
```

The following setting enables you to include a time stamp in the output filename:

```
plugins:giop_snoop:rolling_file = "true";
```

As a result, applications running for several days create a new log file each day. To enable administrators to control the size and content of output files, GIOP Snoop does not hold output files open.

Using the Java version of GIOP Snoop

To use the Java version of the GIOP Snoop plug-in, add the following to your classpath:

UNIX

```
export
```

CLASSPATH=\$CLASSPATH:\$IT_PRODUCT_DIR/lib/platform/java_trans ports/1.3/giop_snoop.jar: \$IT_PRODUCT_DIR/asp/6.3/lib/asp-corba.jar

Windows

set

CLASSPATH=%CLASSPATH%;%IT_PRODUCT_DIR%\lib\platform\java_transports\1.3\giop_snoop.jar
%IT_PRODUCT_DIR%\asp\6.3\lib\asp-corba.jar

GIOP Snoop Output

Overview

The output shown in this section uses a simple example that shows client-side output for a single binding and operation invocation. The client establishes a client-side binding that involves a message interceptor chain consisting of IIOP, GIOP Snoop, and GIOP. The client then connects to the server and first sends a [LocateRequest] to the server to test if the target object is reachable. When confirmed, a two-way invocation [Request] is sent, and the server processes the request. When complete, the server sends a [Reply] message back to the client.

Output detail varies depending on the configured verbosity level. With level 1 (LOW), only basic message type, direction, operation name and some GIOP header information (version, and so on) is given. More detailed output is possible, as described under the following examples. This section includes the following:

- "LOW verbosity client-side snooping"
- "MEDIUM verbosity client-side snooping"
- "HIGH verbosity client side snooping"
- "VERY HIGH verbosity client side snooping"
- "Troubleshooting"

LOW verbosity client-side snooping

An example of LOW verbosity output is as follows:

This example shows an initial conversation from the client-side perspective. The client transmits a [LocateRequest] message to which it receives a [LocateReply] indicates that the server supports the target object. It then makes an invocation on the operation null_op.

The Conn indicates the logical connection. Because GIOP may be mapped to multiple transports, there is no transport specific information visible to interceptors above the transport (such as file descriptors) so each connection is given a logical identifier. The first incoming and outgoing GIOP message to pass through each connection are indicated by (first for binding).

The direction of the message is given (Out for outgoing, In for incoming), followed by the GIOP and message header contents. Specific information includes the GIOP version (version 1.2 above), message length and a unique request identifier (ReqId), which associates [LocateRequest] messages with their corresponding [LocateReply] messages. The (two-way) indicates the operation is two way and a response (Reply) is expected. String lengths such as len 8 specified for Operation includes the trailing null.

MEDIUM verbosity client-side snooping

An example of MEDIUM verbosity output is as follows:

```
16:24:39 [Conn:1] Out:(first for binding) [LocateRequest]
   GIOP v1.2 MsgLen: 39
  Endian: big ReqId: 0
  Target Address (0: KeyAddr)
  ObjKey (len 27) ':>.11......
16:24:39 [Conn:1] In: (first for binding) [LocateReply]
                                                      GIOP
   v1.2 MsqLen: 8
  Endian: big RegId: 0
  Locate status: OBJECT_HERE
16:24:39 [Conn:1] Out: [Request]
                                     GIOP v1.2 MsgLen: 60
  Endian: big RegId: 1 (two-way)
  Target Address (0: KeyAddr)
  ObjKey (len 27) ':>.11......
  Operation (len 8) 'null_op'
16:24:39 [Conn:1] In: [Reply]
                                     GIOP v1.2 MsgLen: 12
  Endian: big ReqId: 1
  Reply status (0) NO_EXCEPTION
```

For MEDIUM verbosity output, extra information is provided. The addition of time stamps (in hh:mm:ss) precedes each snoop line. The byte order of the data is indicated (Endian) along with more detailed header information such as the target address shown in this example. The target address is a GIOP 1.2 addition in place of the previous object key data.

HIGH verbosity client side snooping

The following is an example of HIGH verbosity output:

```
16:24:39 [Conn:1] Out:(first for binding) [LocateRequest]
  GIOP v1.2 MsgLen: 39
   Endian: big ReqId: 0
   Target Address (0: KeyAddr)
     GIOP Hdr (len 12):
   [47] [49] [4f] [50] [01] [02] [00] [03] [00] [00] [00] [27]
   Msq Hdr (len 39):
   [02][31][31][0c][00][00][00][00][00][00][0f][05][00][00][41][c6
  ][08][00][00][00]
10011001100110011001
[---- end of message ----]
16:31:37 [Conn:1] In: (first for binding) [LocateReply]
  GIOP v1.2 MsgLen: 8
   Endian: big RegId: 0
   Locate status: OBJECT_HERE
   GIOP Hdr (len 12):
   [47][49][4f][50][01][02][00][04][00][00][00][08]
   Msg Hdr (len 8): [00][00][00][00][00][00][01]
[---- end of message ----]
16:31:37 [Conn:1] Out: [Request]
                                   GIOP v1.2 MsgLen: 60
   Endian: big RegId: 1 (two-way)
   Target Address (0: KeyAddr)
     Operation (len 8) 'null_op'
   No. of Service Contexts: 0
   GIOP Hdr (len 12):
   [47][49][4f][50][01][02][00][00][00][00][00][3c]
   Msg Hdr (len 60):
   [00][00][00][01][03][00][00][00][00][00][00][00][00]
[00] [1b] [3a] [3e] [02] [31] [31] [0c] [00] [00] [00] [00] [00] [00] [05]
  ][00][00][41][c6]
][6c][6c][5f][6f]
[70] [00] [00] [00] [00] [00]
[---- end of message ----]
```

This level of verbosity includes all header data, such as service context data. ASCII-hex pairs of GIOP header and message header content are given to show the exact on-the-wire header values passing through the interceptor. Messages are also separated showing inter-message boundaries.

VERY HIGH verbosity client side snooping

This is the highest verbosity level available. Displayed data includes HIGH level output and in addition the message body content is displayed. Because the plug-in does not have access to IDL interface definitions, it does not know the data types contained in the body (parameter values, return values and so on) and simply provides ASCII-hex output. Body content display is truncated to a maximum of 4 KB with no output given for an empty body. Body content output follows the header output, for example:

Troubleshooting

When trying to start your application, you might get the following message:

```
Wed, 30 Oct 2005 10:39:39.0000000 [merge:11672] (IT_GIOP:32) ? -
The GIOP server side message interceptor factory 'GIOP_SNOOP'
specified in configuration setting
'plugins:giop:message_server_binding_list' is unknown.
Unexpected CORBA exception: IDL:omg.org/CORBA/INITIALIZE:1.0:
minor = 0x49540201
(IT_GIOP:SERVER_BINDING_LIST_UNKNOWN_FACTORY), completion
status = NO Server exiting
```

This happens when the GIOP snoop plug-in configuration settings are made at the global scope level, but no corresponding configuration adjustments have been made to the <code>iona_services</code> scope.

Typically, the orb_plugins configuration variable is redefined in the scope of important services (for example, locator, node daemon and naming), and it does not include the giop_snoop plug-in by default. The error gets generated when the server binding list setting gets picked up from the root level as follows:

From the point of view of the service scope, the ${\tt GIOP_SNOOP}$ reference is unknown because of the orb_plugins redefinition.

To correct this problem, you can add the <code>giop_snoop</code> plug-in in the <code>orb_plugins</code> list for each service scope where <code>orb_plugins</code> has been redefined. However, be aware that setting GIOP snoop at the root level produces a large amount of data because it affects all your servers and services. Instead, consider setting it for each individual service as follows:

```
plugins:giop_snoop:shlib_name = "it_giop_snoop";
plugins:giop_snoop:ClassName =
    "com.iona.corba.giop_snoop.GIOPSnoopPlugIn";
plugins:giop_snoop:verbosity = "1";

iona_services
{
    locator
    {
          ...
          orb_plugins = ["local_log_stream", "iiop_profile", "giop",
          "giop_snoop", "iiop", "ots"];

    plugins:giop:message_server_binding_list =
        ["GIOP+GIOP_SNOOP", "GIOP"];
          ...
    };
};
```

Debugging IOR Data

Orbix includes iordump tool for analyzing IOR data and finding possible causes for badly formed IORs.

In this chapter

This chapter contains the following sections:

IOR Data Formats	page 214
Using iordump	page 217
iordump Output	page 219
Data, Warning, Error and, Information Text	page 224

IOR Data Formats

Overview

CORBA Inter-operable Object Reference (IOR) data can be presented in one of two forms:

- Stringified form which is coded by converting each binary byte of coded data into an ASCII pair of characters representing the hex equivalent in readable form.
- CDR encoded (and aligned) binary data, which encodes each CORBA defined data type on its natural boundary. Short values are encoded on a 2-byte boundary, long values on a 4-byte boundary and, so on. Data contains padding between data types in order to ensure aligned data.

Stringified IOR data

Stringified IOR data is in the format IOR: followed by a series of hex value pairs. For example:

IOR:010000001c00000049444c3a53696d706c652f53696d706c654f626a6

It is best known as the CORBA IOR: URL passed to the IDL operation CORBA::ORB::string_to_object(). The stringified IOR data format of an encoded IOR can be obtained by using the IDL operation CORBA::ORB::object_to_string().

IDL definition

Raw IOR data is encoded as the CDR representation of the IOR structure, defined in the CORBA GIOP specification, declared by the IDL shown in Example 3:

Example 3: IOR data IDL definition

```
// IDL
typedef unsigned long ProfileId;
const ProfileId TAG_INTERNET_IOP = 0;
const ProfileId TAG_MULTIPLE_COMPONENTS = 1;
// A TaggedProfile contains opaque profile and component
// data and a tag to indicate the type and format of the data.
struct TaggedProfile
  ProfileId tag;
  sequence <octet> profile_data;
// IOR is a sequence of object specific protocol profiles
// (TaggedProfiles) plus a type id.
struct IOR
  string type_id;
  sequence <TaggedProfile> profiles;
  };
// A MultipleComponentProfile is contained in a TaggedProfile
// with the tag TAG_MULTIPLE_COMPONENTS.
typedef unsigned long ComponentId;
struct TaggedComponent
  {
  ComponentId tag;
  sequence <octet> component_data;
  };
typedef sequence <TaggedComponent> MultipleComponentProfile;
```

Example 3: *IOR data IDL definition*

```
// This declares IIOP ProfileBody data contained in a
// TaggedProfile with the tag TAG_INTERNET_IOP.
// IIOP 1.0/1.1/1.2 revisions are given.
struct Version
  {
  octet major;
  octet minor;
  };
struct ProfileBody_1_0
  {
  Version iiop_version;
  string host;
  unsigned short port;
  sequence <octet> object_key;
  };
struct ProfileBody_1_1
  {
  Version iiop_version;
  string host;
  unsigned short port;
  sequence <octet> object_key;
  sequence <IOP::TaggedComponent> components; // Added in 1.1
  };
typedef ProfileBody_1_1 ProfileBody_1_2;
                                                // Same as 1.1
```

Using iordump

Overview iordump is a utility that decodes CORBA inter-operable object reference (IOR)

content and presents it in readable format through stdout. This utility's output also includes debugging information to assist in analyzing the cause of

malformed IOR data.

Synopsis iordump [-no_host_check] {file | -}

iordump [-no_host_check] IOR:...

Description iordump reads the IOR data either from a specified file (- for stdin), or given as

a command line argument, and prints the detailed contents of the IOR data. The IOR may be specificed either in the standard CORBA defined stringified form or raw binary CDR encoded data. The IOR content is displayed in both stringified and ASCII-hex formats. The tools emphasis is on reporting all possible erroneous values or suspect data, while also displaying the meaning and value of each data

item.

Parameters iordump takes the following parameters:

-no_host_check The default behavior is to attempt a host lookup on each host

specified in the IOR. This option prevents this host lookup

check.

file Specifies the name of the file from which to read the IOR

data.

Specifies that the IOR data is to be read from stdin.

IOR:... Specifies the IOR to decode on the command line.

Examples

To analyze the contents of a stringified IOR read from stdin:

```
> echo "IOR:..." | iordump -
```

To analyze the contents of the IOR generated by the simple CORBA demo:

```
> iordump simple1.ior
```

To analyze the contents of a stringified IOR specified as a command line argument:

```
> iordump IOR:000001.....
```

Notes

Data other than a single IOR in a file will result in the whole data being analyzed as a single IOR. Only in the case of stringified IORs are trailing newlines, carriage returns and nulls removed.

iordump Output

Overview

iordump decodes the IOR data provided and outputs the data to the screen in both stringified format and ASCII-hex fomat. All lines beginning with a '>>' prefix contain ASCII-hex data. Interspersed with the ASCII-hex data may be errors, warnings, and other data messages. These are explained in "Data, Warning, Error and, Information Text" on page 224.

Example

Example 4 shows a sample output from iordump.

Example 4: Sample iordump Output

```
C:\>iordump simple1.ior
Stringified IOR is: ([string/coded data] length: 312 / 154 bytes)
   IOR: 010000001c00000049444c3a53696d706c652f53696d706c654f626a6
   563743a312e300001000000000000006a000000010102000e00000036332e
   36352e3133332e32353000a70f1b0000003a3e0231310c00000000ec09000
   08d2000000800000000000000000020000001000000180000001000000\\
   0100010000000000001010001000000090101000600000060000001000
   0001100
>> +0 [01]
        Byte order of IOR: (1) Little Endian
>> +1 [00][00][00]
        (padding)
>> +4 [1c][00][00][00]
        TypeId length: 28 bytes (including null)
   [49][44][4c][3a][53][69][6d][70][6c][65][2f][53][69][6d][70][
   6c] [65] [4f] [62] [6a] [65] [63] [74] [3a] [31] [2e] [30] [00]
        TypeId value: 'IDL:Simple/SimpleObject:1.0.'
>> +36 [01][00][00][00]
        Number of tagged profiles: 1
```

Example 4: Sample iordump Output

```
Profile 1:
>> +40 [00][00][00][00]
               Tag: (0) TAG_INTERNET_IOP
>> +44 [6a][00][00][00]
               Profile length: 106 bytes
>> +48 [01]
               Byte Order: (1) Little Endian
>> +49 [01][02]
               Version: 1.2
>> +52 [0e][00][00][00]
               Host length: 14 bytes (including null)
>> +56 [36][33][2e][36][35][2e][31][33][33][2e][32][35][30][00]
               Host string: '63.65.133.250.'
               * host IP address lookup succeeded, but failed to
   find a hostname (warning)
>> +70 [a7][0f]
               Port: 4007
>> +72 [1b][00][00][00]
               Object Key length: 27 bytes (including any
   trailing null)
>> +76
   [3a][3e][02][31][31][0c][00][00][00][00][ec][09][00][00][8d][
   20][00][00][
[00][00][00][00][00][00][00][00]
               Object key data: ':>.11......'
                (looks like an Orbix ART Transient key)
>> +103 [00]
        (padding)
>> +104 [02][00][00][00]
               Number of tagged components: 2
```

Example 4: Sample iordump Output

```
Component 1:
>> +108 [01][00][00][00]
                        Tag: (1) CODE_SETS
>> +112 [18][00][00][00]
                        Component length: 24 bytes
>> +116 [01]
                        Component Byte Order: (1) Little Endian
>> +117 [00][00][00]
        (padding)
>> +120 [01][00][01][00]
                        Native CodeSet id (for char): 65537
                         (ISO 8859-1:1987; Latin Alphabet No. 1)
>> +124 [00][00][00][00]
                        Number of conversion code sets (CCS): 0
>> +128 [00][01][01][00]
                        Native CodeSet id (for wchar): 65792
                         (ISO/IEC 10646-1:1993; UCS-2, Level 1)
>> +132 [01][00][00][00]
                        Number of conversion code sets (CCS): 1
>> +136 [09][01][01][00]
                        CCS(1) CodeSet Id 65801
                         (ISO/IEC 10646-1:1993; UTF-16, UCS
   Transformation Format 16-bit form)
                Component 2:
>> +140 [06][00][00][00]
                        Tag: (6) ENDPOINT_ID_POSITION
>> +144 [06][00][00][00]
                        Component length: 6 bytes
>> +148 [01]
                        Component Byte Order: (1) Little Endian
>> +149 [00]
        (padding)
>> +150 [00][00]
                        EndpointId begin (index): 0
>> +152 [11][00]
                        EndpointId end (index): 17
```

Stringified Data Output

All output begins with the stringified IOR such as:

The first line gives the string length as the number of characters in the following IOR string, including the IOR: prefix. The coded data length indicates the number of bytes of encoded data which is represented by the stringified IOR, as per the CDR rules for encoding IOR data.

ASCII-Hex Data Output

Display format

All ASCII-hex pairs are printed as [ab] pairs in the output, where ab is a character pair in the range 00 to FF.

Each line of ASCII-hex output contain segments of ASCII-hex data taken from the stringified IOR, including the byte offset of the data relative to the start of the equivalent binary coded IOR, beginning at byte zero:

>> +offset [ab][ab][ab]...

Example

For example, the following output text:

>> +4 [00][00][00][18]

indicates the four ASCII pairs which are coded four bytes into the IOR binary data, in this case being the TypeId string length value of 24 bytes.

Note also that all printed data is shown in the byte order as coded into the IOR. The above, for example, is the value 24 as coded on a Big Endian machine and is displayed as such regardless of the byte order of the machine iordump is running on. Iordump only byte-swaps the values, if needed, in order to decode and print their actual value.

Data, Warning, Error and, Information Text

Overview

All other output consists of data text for each data type and its value, and any relevant text to inform of errors, warnings or simple informative message text of conditions detected for each specific data item.

Example

For example, the following output shows the data type/value output ${\tt TypeId}$ length: . . . and an error message indicating an invalid data value.

```
>> +4 [40][32][40][32]

TypeId length: 843067968 bytes (including null)

* bad TypeId sequence length (843067968)
```

In this section

This section discusses the following topics:

Errors	page 225
Warnings	page 228

Errors

The errors include the following:

- * unknown General error indicating the specified data value is not a known or standard value. This typically includes Tag values and other well known values.
- * number of profiles is zero (should at least have one!) The IOR TaggedProfile sequence length value indicates there are no tagged profiles, only a TypeId string. If this is not the case, the length value may be set incorrectly to zero.
- * empty profile (zero length); skip to next profile ATaggedProfile is of zero length. This may be possible although it is currently flagged as a possible error.
- * gone beyond the end of the profile data; must exit (number of profiles suggests more data) The number of profiles value has caused iordump to skip beyond the end of the data. The tool expects to see more profiles. This occurs because the value is corrupt or has been coded in the IOR incorrectly. A few reasons for this error is: a value is encoded using the wrong alignment, or a value is decoded based on an incorrect byte order setting, or the wrong value was encoded.
- * unknown HOP version (attempting to read as 1.0 data) The ProfileBody is not one of the supported HOP versions recognized by iordump. An attempt is made to interpret the initial part of the data as 1.0 HOP profile data.
- * unknown profile tag/format The profile tag is unknown, either because it is corrupt or because it is an unknown vendor-defined tag not registered with the OMG.
- * gone beyond the end of the component data; skip component An invalid length has caused the component data to be exhausted. If possible, iordump will skip the invalid component data and move onto the next to the next component.
- * only one ORB_TYPE component allowed The OMG specification only allows one TAG_ORB_TYPE component per profile, so the IOR is not OMG-compliant.

* missing CodeSetComponent for wchar / * missing conversion code sets for wchar ATAG_CODE_SETS component consists of two CodeSetComponents, one for char conversions and one for wchar conversions. Each CodeSetComponent is a struct containing a native CodeSetId, specified as a ulong and conversion code sets, specified as a sequence of CodeSetId. The encapsulated data contained in the tagged component is a CodeSetComponentInfo which is defined as follows:

```
typedef unsigned long CodeSetId;
struct CodeSetComponent
{
   CodeSetId native_code_set;
   sequence<CodeSetId> conversion_code_sets;
   };
struct CodeSetComponentInfo
   {
   CodeSetComponent ForCharData;
   CodeSetComponent ForWcharData;
   };
```

These errors are reported if part of this data structure is missing from the IOR tagged component.

- * null wchar native code set; client will throw INV_OBJREF The CORBA specification includes a requirement that a native code set is specified at least for a server that supports the IDL wchar type because there is no default wchar conversion code set. If the native code set for wchar is set to zero this is an error and according to the spec; the client will throw an INV_OBJREF exception.
- * a zero string length is illegal, client will throw MARSHAL A string is encoded as <length><characters> where the length includes a terminating null. All strings contain a null, therefore a zero length is illegal.
- * should be 0 or 1; assuming (1) Little Endian The octet containing the byte order flag in an IOR may only contain the values 0 or 1 to indicate Big or Little Endian.
- * bad <data type> sequence length (<n>) The length check on a sequence<octet> coded length value indicates an invalid length field.

* stringified IOR should have an even length; added trailing'0' to continue

The stringified IOR always contains an even number of characters because it contains ASCII-Hex pairs. An additional 0 is added to the data to allow it to be decoded and analyzed. Possible errors will result when analyzing the last bytes.

* tried to skip <n> byte(s) of padding beyond the remaining data; exit..

Tried to align for a data type when the alignment has skipped beyond the amount of remaining data.

- * attempt to read <n> byte data type, only <m> remaining; exit.. After skipping padding bytes and aligning to read the next data item, a check is also made that the number of bytes required to read the data type does not exceed what data is actually left to read.
- * no more data; exit.. Unexpectedly ran over the end of data.

Warnings

The warnings include the following.

- * non zero padding (warning) This indicates that unused octets in the data contain non-zero values. Unused bytes exist because of required padding bytes between data values in order to maintain the correct data alignment. The CORBA specification does not insist on having all padding zeroed although this potentially creates problems when an IOR is published, or used for hashing, or any situation which results in two IORs being considered different simply because of differences in unused padding data.
- * no null character at end (warning) In some cases, a sequence<octet> may be used to store string values. This warning indicates that a data value that can be interpreted as a string does not contain a terminating null. If the data is meant to be used as a string, this can cause problems when trying to decode and use the string. An example is the use of strings to represent the object key by some vendors. Otherwise, this warning may be ignored.

A simple mistake made when coding such a string is in using the string length given by strlen(1) to code the sequence length, without adding 1 for the null.

- * should TypeId begin with 'IDL:' prefix? (warning) A check was made on the TypeId string and the expected IDL: prefix was not found.
- * num profiles sounds excessive, only printing <n> If the value containing the number of profiles exceeds a reasonable limit (100 as set by iordump), only the number of profiles up to the limit is printed.
- * IOR contains <n> garbage trailing byte(s): Any remaining bytes in the data, beyond the last decoded data value are printed before exit.
- * empty component data, zero length (warning) A TaggedComponent length field indicates a zero length component.
- * previous component sequence length may be wrong (warning) The sequence length of a previous component may be wrong and caused the data of the following component to be considered part of it. This is only a possible explanation for a missing component, particularly if the previous component reported an unknown or illegal data value.

- * host unknown; possibly unqualified (warning) An attempt is made to do a lookup of the host contained in an IIOP profile. If the host lookup fails, this is printed as a warning. This would result if the host is really unknown, or is not fully qualified with the complete domain.
- * host name lookup succeeded, but failed to find an IP address (warning)
 The specified host lookup succeeded, but an attempt to lookup the IP address
 mapping for the specified host failed.
- * host IP address lookup succeeded, but failed to find a hostname (warning)
 The specified IP address lookup succeeded, but an attempt to lookup the host
 mapping for the specified address failed.

CHAPTER 15 | Debugging IOR Data

Part IV

Command Reference

In this part

This part contains the following chapters:

Starting Orbix Services	page 233
Managing Orbix Services With itadmin	page 247

Starting Orbix Services

This chapter describes commands that start Orbix services. For information on starting Orbix services as Windows NT services, see Appendix A on page 403.

In this chapter

This chapter contains the following sections:

Starting and Stopping Configured Services	page 234
Starting Orbix Services Manually	page 235
Stopping Services Manually	page 244

Starting and Stopping Configured Services

Start and stop scripts

The Orbix configuration tool generates two scripts that start and stop all configured Orbix services:

UNIX

start_domain-name_services.sh
stop_domain-name_services.sh

Windows

start_domain-name_services.bat
stop_domain-name_services.bat

The startup script starts all Orbix services you configured using the configuration tool. For example, given a domain name of AcmeServices, the following command starts all services on Windows:

start_AcmeServices_services.bat

Start-up order

Orbix services, when configured, start up in the following order:

- 1. Configuration repository
- 2. Locator daemon
- 3. Node daemon
- 4. Naming service
- 5. Interface repository
- 6. Event service

For example, you might decide to configure the event service but not the naming service. In this case, the event service takes a priority of 5.

Starting Orbix Services Manually

Orbix also provides separate commands for starting each service manually, with the following syntax:

```
itservice-name [run]
```

run is optional. For example, the following commands both start the interface repository:

```
itifr
itifr run
```

Table 8 lists all commands for running services manually:

 Table 8:
 Commands to Manually Start Orbix Services.

Command	Starts
itconfig_rep run	Configuration repository
itlocator run	Locator daemon
itnode_daemon run	A node daemon
itnaming run	Naming service database
itifr run	Interface repository
itevent run	Event service
itnotify run	Notification service

Note: In a configuration repository-based domain, the configuration repository must be running before starting additional services.

itconfig_rep run

Synopsis

itconfig_rep -ORBdomain_name cfr-domain-name [-ORBname ORB-name]
[run] [-background]

Description

Starts the configuration repository. The configuration repository must already be configured in your Orbix environment. This command requires you to be logged in as administrator (Windows) or root (UNIX).

Note: For details on using a secure configuration repository-based domain, see the *Orbix Security Guide*.

UNIX

You can push the process into the background.

Windows

Leave the command window open.

Options

-ORBdomain_name

cfr-domain-name

The configuration repository's domain file name, which is generated when you create the domain. The generated configuration domain file has the name

cfr-domain-name.cfg.

For example, given configuration domain acmeproducts, the configuration repository initializes

itself from cfr-acmeproducts.cfg.

-ORBname ORB-name

Directs the initializing configuration repository to retrieve its configuration from the specified configuration scope.

By default, this is the config_rep scope. Use the -ORBname argument to specify a different configuration scope. For example:

itconfig_rep -ORBname config_rep.config2 run

-background

Runs the configuration repository in the background. Control returns to the command line only after the service successfully launches. If you omit the -background argument, the configuration repository runs in the foreground. This argument can be abbreviated to -bg. For example:

itconfig_rep run -bg

The -background argument is especially useful in scripts that start multiple services. It guarantees that services always launch in the same sequence as the script specifies.

itlocator run

Synopsis

itlocator [-ORBname ORB-name] run [-background]

Description

Starts the locator daemon. The locator daemon must already be configured in your Orbix environment. In a location domain, the locator daemon controls read and write operations to the implementation repository. By default, entering itlocator without specifying the run command starts the default locator daemon.

UNIX

You can push the process into the background.

Windows

Leave the command window open.

Options

-ORBname ORB-name

Directs the initializing locator daemon to retrieve its configuration from the specified configuration scope.

By default, this is the locator scope. Use the -ORBname argument to specify a different configuration scope. For example:

itlocator -ORBname locator.locator2 run

-background

Runs the locator daemon in the background. Control returns to the command line only after the service successfully launches. If you omit the -background argument, the locator daemon runs in the foreground. You can abbreviate this argument to -bg. For example:

itlocator run -bg

The -background argument is especially useful in scripts that start multiple services. It guarantees that services always launch in the same sequence as the script specifies.

itnode_daemon run

Synopsis

Description

itnode_daemon [-ORBname ORB-name] run [-background]

Starts a node daemon. A node daemon controls registered server processes to ensure that they are always running, starts processes on demand, or disables them from starting. The node daemon also monitors all child processes of registered server processes, and informs the locator daemon about any events relating to these child processes—in particular, when a child process terminates. By default, entering <code>itnode_daemon</code> without specifying the <code>run</code> command starts the default node daemon.

UNIX

You can push the process into the background.

Windows

Leave the command window open.

Options

-ORBname ORB-name

Directs the initializing node daemon to retrieve its configuration from the specified configuration scope.

By default, this is the iona_services.node_daemon scope. Use the -ORBname argument to specify a different configuration scope. For example:

itnode_daemon -ORBname
 iona_services.node_daemon.nd2 run

-background

Runs the node daemon in the background. Control returns to the command line only after the service successfully launches. If you omit the -background argument, the node daemon runs in the foreground. You can abbreviate this argument to -bg. For example:

itnode_daemon run -bg

The -background argument is especially useful in scripts that start multiple services. It guarantees that services always launch in the same sequence as the script specifies.

-ORBsecure_directories Specifies a list of secure directories in which the node daemon launches processes. This overrides the path specified for the registered process. For example:

> itnode daemon -ORBsecure directories [c:\Acme\bin,c:\my_app]

You must enclose the directory list in square brackets. If you omit this argument, the node daemon launches processes from the path specified in the location domain.

itnaming run

Synopsis

itnaming [-ORBname ORB-name] run

Description

Starts the naming service, assuming it is already configured in your Orbix environment. By default, entering itnaming without specifying the run command starts the naming service.

UNIX

You can push the process into the background.

Windows

Leave the command window open.

Options

-ORBname ORB-name

Directs the initializing naming service to retrieve its configuration from the specified configuration scope.

By default, this is the naming scope. Use the -ORBname argument to specify a different configuration scope. For example:

itnaming -ORBname naming.naming2 run

-background

Runs the naming service in the background. Control returns to the command line only after the service successfully launches. If you omit the -background argument, the naming service runs in the foreground. You can abbreviate this argument to -bg. For

example:

itnaming run -bg

The -background argument is especially useful in scripts that start multiple services. It guarantees that services always launch in the same sequence as the

script specifies.

itifr run

Synopsis

itifr [-ORBname ORB-name] run [-background]

Description

Starts the interface repository daemon. The interface repository must already be configured in your Orbix environment. By default, entering itifr without specifying the run command starts the interface repository.

UNIX

You can push the process into the background.

Windows

Leave the command window open.

Options

-ORBname ORB-name

Directs the initializing interface repository to retrieve its configuration from the specified configuration

scope.

By default, this is the ifr scope. Use the -ORBname argument to specify a different configuration scope. For example:

itifr -ORBname ifr.ifr2 run

-background

Runs the interface repository in the background. Control returns to the command line only after the service successfully launches. If you omit the -background argument, the interface repository runs in the foreground. You can abbreviate this argument to -bg. For example:

itifr run -bg

The -background argument is especially useful in scripts that start multiple services. It guarantees that services always launch in the same sequence as the script specifies.

itevent run

Synopsis

itevent [-ORBname ORB-name] run [-background]

Description

Starts the event service. The event service must already be configured in your Orbix environment. By default, entering itevent without specifying the run command starts the event service.

UNIX

You can push the process into the background.

Windows

Leave the command window open.

Options

-ORBname ORB-name

Directs the initializing event service to retrieve its configuration from the specified configuration scope.

By default, this is the event scope. Use the -ORBname argument to specify a different configuration scope.

For example:

itevent -ORBname event.event2 run

-background

Runs the event service in the background. Control returns to the command line only after the service successfully launches. If you omit the -background argument, the event service runs in the foreground. You can abbreviate this argument to -bg. For

itevent run -bg

example:

The -background argument is especially useful in scripts that start multiple services. It guarantees that services always launch in the same sequence as the script specifies.

itnotify run

Synopsis

itnotify [-ORBname ORB-name] run [-background]

Description

Starts the notification service. The notification service must already be configured in your Orbix environment. By default, entering itnotify without specifying the run command starts the event service.

UNIX

You can push the process into the background.

Windows

Leave the command window open.

Options

-ORBname ORB-name

Directs the initializing notification service to retrieve its configuration from the specified configuration

scopes.

By default, this is the notify scope. Use the -ORBname argument to specify a different configuration scope. For example:

itnotify -ORBname notify.notify2 run

-background

Runs the notification service in the background. Control returns to the command line only after the service successfully launches. If you omit the -background argument, the notification service runs in the foreground. You can abbreviate this argument to -bg. For example:

itnotify run -bg

The -background argument is especially useful in scripts that start multiple services. It guarantees that services always launch in the same sequence as the script specifies.

Stopping Services Manually

Any service that can be started manually can also be stopped manually using <code>itadmin</code> commands. The order in which you shut down services should be determined by the dependencies among them. For example, in a repository-based domain, you should not shut down the configuration repository until all other services are shut down.

Shut-down commands have the following syntax:

itadmin service-name stop

Table 9 lists the itadmin commands for shutting down Orbix services:

 Table 9:
 Commands for Stopping Orbix Services

Service	Shut-down command
Configuration repository	itadmin config stop
Locator	itadmin locator stop
Node daemon	itadmin .node_daemon stop
Naming service	itadmin ns stop
Interface repository	itadmin ifr stop
Event service	itadmin event stop

Event Log

Overview

The event log commands enable the Orbix event log filters to be displayed or updated dynamically using the itadmin command line. You can also perform these actions using the IONA Administrator Web Console:

Table 10: Event Log Commands

logging get	Displays the event log filter settings.
logging set	Updates the event log filter.

logging get

Synopsis logging get -orbname orb_name

Description Displays the event log filter settings for the specified ORB name.

Arguments

-orbname The specified ORB name of the event log to display.

Examples

itadmin logging set -orbname iona_services.naming

This command displays the event log filter settings that are used by the currently running naming service.

logging set

Synopsis logging set -orbname orb_name -value new_event_log_filter

Description Updates the event log filter settings for the specified ORB name.

Arguments

-orbname The specified ORB name of the event log to update.

-value The new event log setting.

Examples

itadmin logging set -orbname iona_services.naming -value IT_GIOP=*,IT_MGMT=*

This command updates the event log filters that are used by the currently running naming service.

Managing Orbix Services With itadmin

This chapter provides an overview of using the command-line tool itadmin to manage Orbix services. Typical management tasks in Orbix include creating, viewing, and removing data stored in service repositories.

In this chapter

This chapter contains the following sections:

Using itadmin	page 248
Command Syntax	page 251
Services and Commands	page 254

Using itadmin

Overview

itadmin lets you manage information used by Orbix services. You can use itadmin in various modes and contexts:

- Command-line utility
- Command shell
- Tcl script
- Transactions

Command-line utility

To use itadmin as a command-line utility, simply enter the appropriate command at the command prompt. For example, the following command registers an ORB name with the locator daemon:

itadmin orbname create my_orb_name

In command-line mode, you must specify the itadmin prefix before each command. For a list of itadmin commands, see "Services and Commands" on page 254.

Command shell

To use the itadmin shell, enter itadmin at the command line. The itadmin prompt is displayed. Once you have entered the command shell, you do not need to enter itadmin before each command. For example:

itadmin
% orbname create my_orb_name

To leave the itadmin shell mode, enter exit.

Nested itadmin commands

In shell and Tcl script mode, you can use nested itadmin commands by enclosing each command in square brackets. When itadmin commands are nested, innermost command are executed first.

Tcl script

You can write your own Tcl scripts that incorporate itadmin commands. For example, you could develop a Tcl script called my_script that contains one itadmin command per line. You would invoke this script by entering:

```
itadmin my_script.tcl
```

You can use Tcl scripts at the command prompt and in the command shell. Incorporating itadmin commands in reusable Tcl scripts provides an extremely powerful way of automating administration tasks (for example, populating a configuration domain or location domain).

Sample scripts

The following example shows the contents of a simple Tcl script that calls an itadmin variable create command:

```
if { [catch {variable create -type string -value poa
    initial_references:POACurrent:plugin} result] } {
    puts $result
    flush stdout
    exit 1
}
```

This command creates a configuration variable named

initial_references: POACurrent: plugin and assigns it a value of poa. The remaining Tcl in this simple example is used for Tcl script management. For example, catch prevents a Tcl stack dump if an exception is thrown during execution.

The following is a more realistic example of how to use itadmin commands within Tcl scripts:

```
# do_cmd installs an exception handler for each itadmin command
proc do_cmd {cmd} {
    set fail [catch {eval $cmd} result]
    if {$fail} {
        puts stderr "Problem in \"$cmd\": $result"
        flush stderr
        exit 1
    }
}

# Each itadmin command is sent as a parameter to do_cmd

do_cmd {variable create -type string -value poa
        initial_references:RootPOA:plugin}

do_cmd {variable create -type string -value poa
        initial_references:POACurrent:plugin}

do_cmd {variable modify ... }

do_cmd {poa create ...}
exit 0
```

The do_cmd procedure installs an exception handler for each itadmin command. Each itadmin command is in turn sent as a parameter to do_cmd. For example, the first call to do_cmd creates initial_references:RootPOA:plugin and assigns it a value of poa.

Transactions

itadmin supports the object transaction service (OTS). Using itadmin commands in transactions provides itadmin with multiple undo capability. Orbix provides itadmin commands to start, commit, rollback, suspend, and resume transactions. This are bloss you to use other its daily commands in

resume transactions. This enables you to use other itadmin commands in transactional mode. For more details, see "Object Transaction Service" on page 355.-

Multiple itadmin sessions

itadmin does not perform any record locking while it is making changes to the configuration database. Therefore, running multiple sessions of itadmin in parallel will corrupt your Orbix configuration.

Command Syntax

Overview

itadmin syntax takes the following general form:

actor [actor modifiers] action [action modifiers] [target]

For example, the following command registers a process name with the locator daemon:

orbname create -process process-name ORB-name

In this example, the actor is orbname, the action is create, the action modifier is -process, and the target is ORB-name.

Note: The order of itadmin components is significant. Each component must be separated by a space.

In this section

The following topics are discussed in this section:

Specifying lists	page 251
Specifying negative values	page 252
Abbreviating command parameters	page 253
Obtaining help	page 253

Specifying lists

When a command takes a list, separate the list elements with spaces and enclose the entire list in double quotation marks. For example, the following command creates a server process entry in the location domain with the specified environment values:

% process create -env "mode=listen priority=low startup=yes"
 process-name

In this example, the value of the -env modifier is a list with three elements, and the equal sign is treated as a character.

Double quotation marks group a set of elements into a single entity in which spaces are not significant. For example, the -args argument to the process create command is treated as a single list element, which must be enclosed by double quotes:

```
% process create -args "foo bar baz" process-name
```

When using itadmin in command line mode, the quotation marks must be escaped or they will be stripped away by the command line interpreter. It is unnecessary to escape the quotation marks when using itadmin in shell or script modes.

Specifying spaces in values

When a value specified to itadmin includes a space, you can use the itadmin escape character ^ to specify the space. For example, the following command shows how to specify a space in a value included in a list:

```
% process modify -env "name1=value1 name2=value^ 2"
```

Specifying negative values

When the first character of a value supplied to an argument is a minus sign or hyphen, you must supply an additional hyphen. For example:

```
-modifier --3
```

When the first character is not a hyphen, an additional hyphen is not necessary. For example:

```
-modifier 4,-1,99
```

You must supply an additional hyphen even if the first character is enclosed in quotation marks. For example:

```
% variable create -type long -value "--99" my_variable
```

Abbreviating command parameters

You can abbreviate all itadmin command parameters. For example, the following commands all have the same effect:

```
% orbname list -p process-name
% orbname list -pr process-name
% orbname list -pro process-name
...
% orbname list -process process-name
```

Abbreviations must be unique. For example, if two parameters begin with the same letter, their abbreviations must use at least the minimum number of letters that differentiate between them.

Obtaining help

To obtain command line help for itadmin, enter:

```
itadmin -help
```

You can obtain context-sensitive help by entering a command (in its entirety, or in part) and adding the keyword help. For example, for help on the orbname create command, enter any of the following:

```
% orbname -help
% orbname create -help
% orbname create -process -help
% orbname create -process process-name -help
% orbname create -process process-name ORB-name -help
% orbname create ORB-name -help
```

Services and Commands

In this section

The following sections group itadmin commands according to Orbix services:

Bridging Service	page 255
Configuration Domain	page 261
Event Log	page 245
Event Service	page 275
Interface Repository	page 283
Location Domain	page 289
Naming Service	page 331
Notification Service	page 343
Object Transaction Service	page 355
Object Transaction Service Encina	page 359
Persistent State Service	page 367
Security Service	page 373
Trading Service	page 383

Bridging Service

Overview

The bridge service allows JMS and CORBA notification clients to share messages. itadmin provides a set of commands for managing the bridging service:

Table 11: Bridging Service Commands

bridge create	Creates a bridge.
bridge destroy	Destroys a bridge.
bridge list	Lists all of the instantiated bridges in a deployment.
bridge show	Displays the status of a bridge.
bridge start	Starts the flow of messages through a bridge.
bridge stop	Stops the flow of messages through a bridge.
bridge suspend	Suspends the flow of messages through a bridge.
endpoint_admin show	Displays a bridge's endpoint admin's name and the type of endpoints it supports.
endpoint destroy	Destroys an endpoint.
endpoint list	Lists the endpoints associated with an endpoint admin.
endpoint show	Display the status and attributes of a particular endpoint for the specified bridge.

bridge create

Synopsis

bridge create [-source_admin IOR | INIT_REF_KEY] [-source_type topic | queue | channel] -source name source name [-sink admin IOR | INIT REF KEY | -sink type [topic | queue | channel | -sink name sink name bridge name

Description

Creates a bridge.

Arguments

The IOR or initial reference of the administrative object -source admin used to connect to the message source. To use the default notification endpoint admin use "IT NotificationEndpointAdmin"; to use the default JMS endpoint admin use "IT_JMSEndpointAdmin". -source_type The type of object that passes messages into the bridge. It can take one of three values: topic if the messages originate from a JMS topic, queue if the messages originate from a JMS queue and channel if the messages originate from a notification channel. -source_name The name of the object that passes messages to the bridge. -sink_admin The IOR or initial reference of the administrative object used to connect to where messages are being forwarded. If the message source is a notification channel, the message sink should be a JMS Destination. To use the default notification admin use "IT_NotificationEndpointAdmin"; to use the default JMS admin use "IT_JMSEndpointAdmin". -sink_type The type of object that receives messages from the bridge. It can take one of three values: topic if the messages are being forwarded to a JMS topic, queue if the messages are being forwarded to a JMS queue and channel if the

messages are being forward to a notification channel.

-sink_name

The name of the object that receives messages from the

bridge.

bridge name

The name of the bridge. This must be a unique string value that is used to identify this bridge.

256

bridge destroy

Synopsis bridge destroy bridge name

Description Destroys a bridge.

bridge list

Synopsis bridge list

Description Lists all of the instantiated bridges in a deployment.

bridge show

Synopsis bridge show bridge name

Description Displays the status of a bridge.

bridge start

Synopsis bridge start bridge name

Description Starts the flow of messages through a bridge.

bridge stop

Synopsis bridge stop bridge name

Description Stops the flow of messages through a bridge.

bridge suspend

Synopsis bridge suspend bridge name

Description Suspends the flow of messages through a bridge.

endpoint_admin show

Synopsis endpoint_admin show [IOR | INIT_REF_KEY]

Description Displays a bridge's endpoint admin's name and the type of endpoints it supports.

endpoint destroy

 $\textbf{Synopsis} \hspace{1.5cm} \textbf{endpoint destroy [-source | -sink] [-admin \textit{IOR | INIT_REF_KEY] bridge}} \\$

name

Description Destroys an endpoint.

Arguments

-source | -sink Specify whether the endpoint is a message source or a

message sink.

-admin Specify what type of admin object with which it is

associated.

endpoint list

Synopsis endpoint list [-source | -sink] [-admin IOR | INIT_REF_KEY]

Description Lists the endpoints associated with an endpoint admin.

Arguments

-source | -sink Specify whether the endpoint is a message source or a

message sink.

-admin Specify what type of admin object with which it is

associated.

endpoint show

Synopsis endpoint show [-source | -sink] [-admin IOR | INIT_REF_KEY] bridge

name

Description Display the status and attributes of a particular endpoint for the specified bridge.

Arguments

–source \mid –sink $\;$ Specify whether the endpoint is a message source or a

message sink.

-admin Specify what type of admin object with which it is

associated.

JMS Broker

Overview

The Java Messaging Service (JMS) provides a native mechanism for Java applications to participate in messaging systems.

itadmin provides a set of commands for managing the JMS broker:

Table 12: *JMS Broker Commands*

jms start	Starts the JMS broker.
jms stop	Shuts down the JMS broker.

jms start

Synopsis jms start

Description Starts the JMS broker.

jms stop

Synopsis jms stop

Description Shuts down the JMS broker.

Configuration Domain

Overview

A subset of itadmin commands let you manage a configuration domain, both file-based and configuration repository-based. These commands manage the following components of a configuration domain:

Configuration Repository	page 262
Namespaces	page 266
Scopes	page 269
Variables	page 271

Note: To use itadmin in a repository-based configuration domain, the configuration repository must be running (see "Starting Orbix Services" on page 233).

Configuration Repository

Overview

The following commands enable you to manage the configuration repository (CFR):

 Table 13:
 Configuration Repository Commands

config dump	Displays the entire contents of the configuration domain.
config list_servers	Shows all deployed replicas of the configuration repository.
config stop	Stops the configuration repository.
file_to_cfr.tcl	Converts from a file-based to a CFR-based configuration.

Note: For details on using a secure configuration repository-based domain, see the *Orbix Security Guide*.

config dump

Synopsis

config dump [-compatible]

-compatible

Formats the CFR configuration so that it can be used in a file-based configuration. You can copy the output into a configuration file.

Description

Outputs the entire contents of the configuration domain to stdout in a form similar to a configuration file.

Examples

The following extract shows the values of some initial object references and plug-ins in the initial_references configuration namespace:

config list_servers

Synopsis config list_servers [-active]

Description Shows all active deployed replicas of the configuration repository.

Arguments

-active Displays the total number of active deployed replicas.

config show_server

Synopsis config show_server cfr replica name

Description Displays runtime information about the specified CFR server.

config stop

Synopsis config stop [replica-name | -ior replica-ior]

Description Stops the configuration repository. An unqualified config stop command stops

all running replicas of the configuration repository.

Arguments

replica-name Stops the specified replica of the configuration repository.

You can obtain the replica's name with itadmin config

list.

-ior replica-ior Stops the specified replica, as specified by its IOR.

file to cfr.tcl

Synopsis file_to_cfr.tcl [-scope scope] [-output_to_file file]

Description Converts from a file-based configuration to a CFR-based configuration. Running this script creates itadmin variable create arguments in the output file, which

you can then run against a CFR.

Examples The recommended way to run this is to set \$IT_DOMAIN_NAME to your file-based domain name, and execute the script. Then set \$IT_DOMAIN_NAME to your CFR domain name, and finally run the generated output script.

> Because a file-based configuration contains no data type information, the file_to_cfr.tcl script must make educated guesses about the types being processed. However, you can edit the generated script to ensure that the correct data types were chosen before running it against your CFR.

Note: Because this tcl script creates a temporary file, the user will need write access to the current directory.

264

Arguments

-scope Processes configuration in the specified scope only.

-output_to_file <filename>Specifies the newly generated script used to populate a CFR.

If the -scope argument is omitted, the script processes the whole configuration. If the -output_to_file argument is omitted, the output goes to stdout instead.

Namespaces

Overview

The following commands let you manage configuration namespaces:

Table 14: Configuration Namespace Commands

namespace create	Creates namespaces in the specified scope.
namespace list	Lists the namespaces in the given namespace or configuration scope.
namespace remove	Removes a namespace and all its contained namespaces and variables from the configuration domain.
namespace show	Displays all sub-namespaces, variables and their values contained within a namespace.

namespace create

Synopsis namespace create [-scope scoped-name] namespace

Description Creates a namespace and any intermediate namespaces, if they do not already

exist.

Arguments

Examples

-scope Creates the namespace in the specified scope. If you omit

this argument, the namespace is created in the root scope.

The following example creates the plugins:local_log_stream namespace within the node_daemon configuration scope:

itadmin namespace create -scope node_daemon
 plugins:local_log_stream

namespace list

Synopsis

namespace list [-scope scoped-name] [namespace]

Description

Lists the namespaces in the specified namespace or configuration scope. If you specify a namespace, itadmin lists only the namespaces nested within it; otherwise, it shows all namespaces within the specified or root scope.

Arguments

-scope

Narrows the namespaces to a specific configuration scope. If you omit this argument, namespaces in the root scope are listed.

Examples

The following example lists namespaces in the root configuration scope:

itadmin namespace list

binding
plugins
url_protocols
url_resolvers
domain_plugins
initial_references

The following example lists namespaces nested within the initial_references namespace:

itadmin namespace list initial_references

PICurrent
IT_Locator
POACurrent
NameService
XAConnector
EventService
IT_Activator
DynAnyFactory
IT_NodeDaemon

PSS RootPOA

IT_MulticastReliabilityProtocol

namespace remove

Synopsis namespace remove [-scope scoped-name] namespace

Description Removes a namespace.

Arguments

-scope Removes the namespace from the specified scope. If you

omit this argument, the namespace is removed from the root

scope.

namespace show

Synopsis namespace show [-scope scoped-name] namespace

Description Displays all namespaces, variables and their values within the specified

namespace.

Arguments

-scope Narrows the namespaces to a specific scope. If you omit this

argument, namespaces and their contents in the root scope

are displayed.

itadmin namespace show initial references

Examples

The following example shows the contents of the initial_references namespace in the root configuration scope:

```
initial_references:RootPOA:plugin = "poa";
initial_references:POACurrent:plugin = "poa";
initial_references:DynAnyFactory:plugin = "it_dynany";
initial_references:TransactionCurrent:plugin = "ots_lite";
initial_references:TransactionFactory:plugin = "ots_lite";
initial_references:PSS:plugin = "pss_db";
initial_references:NameService:reference = "IOR:0100...00900";
```

initial_references:IT_Locator:reference = "IOR:0100...00900";

initial_references:ConfigRepository:reference="IOR:0100...00900"

Scopes

Overview

The following commands let you manage configuration scopes:

Table 15: Configuration Scope Commands

scope create	Creates a configuration scope.
scope list	Displays all sub-scopes defined within a scope.
scope remove	Removes a configuration scope and all its contained namespaces, variables, and scopes.
scope show	Displays all namespaces, variables, and their values defined within a scope.

scope create

Synopsis scope create scoped-name

Description Creates a configuration scope. Unless qualified by higher-level scope names, the

scope is created in the root configuration scope. To create a scope in a scope other

than the root, specify its fully qualified name.

Examples For example, the following command creates the test scope within

company.production:

itadmin scope create company.production.test

After you create the scope, add the desired namespaces and variables within it with itadmin variable create and itadmin namespace create.

scope list

Synopsis scope list [scoped-name]

Description Lists all the sub-scopes in the specified configuration scope. If no scope is

specified, this command lists the sub-scopes in the root scope.

Examples

The following command lists all the sub-scopes defined within the node_daemon configuration scope:

itadmin scope list node_daemon

node_daemon2 node_daemon3

scope remove

Synopsis

scope remove scoped-name

Description

Removes the specified scope from the configuration. This includes all its contained namespaces, variables, and configuration scopes.

scope show

Synopsis

scope show [scoped-name] [-compatible] [-output_to_file filename]

Description

Displays all sub-namespaces, variables, and their values in the specified configuration scope. If no scope is specified, this command displays the contents of the root scope.

Arguments

-compatible

Formats the displayed configuration so that it can be used in a file-based configuration. This enables you to produce file-based configuration segments from a scope (rather than the entire CFR).

-output_to_file <filename>Directs the output to the specified file.

Examples

The following command displays the contents of the node_daemon configuration scope:

itadmin scope show node daemon

```
orb_plugins = local_log_stream, iiop_profile, giop, iiop;
event_log:filters=IT_NODE_DAEMON=INFO_ALL+WARN+ERROR+FATAL;
plugins:node_daemon:shlib_name = "it_node_daemon_svr";
plugins:node_daemon:nt_service_dependencies = "IT locator
    orbix2000";
plugins:node_daemon:name = "it_node_daemon";
```

Variables

Overview

The following commands let you manage configuration variables:

Table 16: Configuration Variable Commands

variable create	Creates a variable or namespace within the configuration domain.
variable modify	Changes one or more variable values.
variable remove	Removes a variable from the configuration domain.
variable show	Displays a variable and its value.

variable create

Synopsis

variable create [-scope scoped-name] -type long|bool|list|string -value value var-name

Description

Creates the specified variable in the configuration domain. Any configuration namespaces specified in the variable name that do not exist are also created.

Arguments

The following arguments are supported:

-scope scoped-name

The configuration scope in which to define the variable. If you omit this argument, the variable is created in the root configuration scope.

-type type

The type of the variable. Supply one of the following types:

- long
- bool
- list (a comma-separated list of strings)
- string

For more about variable types, see "Data types" on page 45.

-value value

The variable's value. The value must match the type specified by the -type switch.

The following values are valid for the specified type:

long: any signed long value

bool: true or false

list: list items must be separated by commas. Empty elements or list items containing spaces must be quoted—for example:

foo, "bar none", baz

See "Specifying lists" on page 251 for more details.

string: Enclose values in double quotes.

Examples

The following example creates a variable named orb_plugins in the root configuration scope:

```
itadmin variable create -type list -value IIOP,GIOP,PSS
    orb_plugins
```

The following example creates variable service_name in scope IFR:

```
itadmin variable create -scope IFR -type string -value "ARTIFR" service name
```

The following example creates a namespace in the root configuration scope:

```
itadmin variable create -type string -value
  "IOR:004332434235234235933..."
  initial_references:IntefaceRepository:reference
```

Note: In shell mode, do not specify IORs to the -value argument. Specify IORs in command-line and script modes only.

variable modify

Synopsis variable modify [-scope scoped-name] -type long|bool|list|string

-value value var-name

Description Modifies the value of a variable or namespace in the configuration domain in the

specified scope.

The following arguments are supported:

The configuration scope in which to modify the -scope scoped-name

variable or namespace. The default is the root

configuration scope.

-type type The type of the variable. Supply one of the following

types:

long

bool

list (a comma-separated list of strings)

string

-value value The variable's value. The value must match the type specified by the -type switch.

The following values are valid for the specified type:

long: any signed long value

bool: true or false

list: list items must be separated by commas. Empty elements or list items containing spaces must be quoted—for example:

foo, "bar none", baz

See "Specifying lists" on page 251 for more details.

string: Enclose values in double quotes.

The following example modifies the event log filters for the naming service:

itadmin variable modify -scope naming -type list -value IT_NAMING=ERR+FATAL event_log:filters

Arguments

Examples

variable remove

Synopsis variable remove [-scope scoped-name] var-name

Description Removes the specified variable from the configuration domain. This operation

does not remove a configuration namespace.

Arguments

-scope scoped-name The configuration scope from which to remove the

variable. If you omit this argument, the variable is

removed from the root scope.

variable show

Synopsis variable show [-scope scoped-name] var-name

Description Displays the specified variable and its value, within the specified scope. The

default is the root configuration scope.

Arguments

-scope Narrows the displayed variable to a specific configuration

scope.

Examples The following example shows a variable in the default root configuration scope:

```
itadmin variable show orb_plugins
orb_plugins = iiop_profile, giop, iiop
```

The following example shows the same variable as it is set for the event service in the configuration scope event:

itadmin variable show -scope iona_services.event orb_plugins
orb_plugins = iiop_profile, giop, iiop

Event Service

Overview

The event service is a CORBA service that enables applications to send events that can be received by any number of objects. For more about the event service, see the *CORBA Programmer's Guide*.

itadmin commands let you manage the following event service components:

Event Service Management	page 276
Event Channel	page 278

Event Service Management

Overview

The following commands let you manage an event service instance:

Table 17: Event Service Commands

event show	Displays the attributes of the specified event service.
event stop	Stops an instance of the event service.

event show

Synopsis

event show

Description

Displays the attributes of the default event service.

Multiple instances of the event service are also supported. To show the attributes of a non-default event service, specify the ORB name used to start the event service (using the -ORBname parameter to itadmin).

Examples

The following command shows the attributes of a default event service:

```
itadmin event show
Event Service Name: IT_EventNamedRoot
  Host Name: podge
  Event Channel Name List:
    my_channel
```

The following command shows the attributes of a non-default event service:

```
itadmin -ORBname event.event2 event show
Event Service Name: IT_EventNamedRoot2
Host Name: rodge
Event Channel Name List:
   my_channel
   my_channel2
```

Each event service instance must have a unique name. You can specify this is in your configuration, using the plugins:poa:root_name variable. The event service uses named roots to support multiple instances.

In this example, the plugins:poa:root_name variable is set to IT_EventNamedRoot2 in the event.event2 configuration scope:

```
event{
    plugins:poa:root_name = "IT_EventNamedRoot";
    ...

    event2
    {
        plugins:poa:root_name = "IT_EventNamedRoot2";
        };
}
```

event stop

Synopsis

event stop

Description

Stops the default event service.

Multiple instances of the event service are also supported. To stop a non-default event service, qualify the $itadmin\ command\ with\ the\ -ORBname\ argument\ and\ supply the\ ORB\ name\ used\ to\ start\ the\ event\ service.$

To start the event service, use the itevent command. You can also use the start_domain-name_services command. For more information, see "Starting Orbix Services" on page 233.

Examples

The following command stops the default event service.

```
itadmin event stop
```

The following command stops the event service that was started with ORB name event.event2:

```
itadmin -ORBname event.event2 event stop
```

Event Channel

The following commands let you manage an event channel:

 Table 18:
 Event Channel Commands

ec create	Creates an untyped event channel with the specified name.
ec create_typed	Creates a typed event channel with the specified name.
ec list	Displays all untyped event channels managed by the event service.
ec remove	Removes the specified untyped event channel.
ec remove_typed	Removes the specified typed event channel.
ec show	Displays all attributes of the specified untyped event channel.
ec show_typed	Displays all attributes of the specified typed event channel.

ec create

Synopsis ec create channel-name

Description Creates an untyped event channel with the specified name. If specified with an

unqualified itadmin command, the event channel is created in the default event service. You can create an event channel in another (non-default) event service by qualifying the <code>itadmin</code> command with the <code>-ORBname</code> argument and supplying

the ORB name used to start the service.

Examples The following command creates an untyped event channel, my channel:

itadmin ec create my_channel

The following command creates an untyped event channel (for a non-default event service) named my_channel2:

itadmin -ORBname event.event2 ec create my_channel2

ec create_typed

Synopsis ec create_typed channel_name

Description Creates a typed event channel with the specified name.

ec list

Synopsis ec list [-count]

Description Displays all the untyped event channels managed by an event service.

Arguments

-count Displays the total number of untyped event channels.

ExamplesThe following example displays the untyped event channels that are in the default

event service:

itadmin ec list

my_channel mkt_channel eng_channel The following example displays the untyped event channels that are in a non-default event service:

```
itadmin -ORBname event.event2 ec list
my_channel
my_channel2
mkt_channel
eng_channel
```

The following example displays the number of untyped event channels managed by an event service:

```
itadmin ec list -count
3
```

ec remove

Synopsis ec remove channel-name

Description Removes the specified untyped event channel.

Examples The following command removes untyped event channel my_channel:

```
itadmin ec remove my_channel
```

The following command removes untyped event channel my_channel2 from a non-default event service:

itadmin -ORBname event.event2 ec remove my_channel2

ec remove_typed

Synopsis ec remove_typed channel_name

Description Removes the specified typed event channel.

ec show

Synopsis ec show channel-name

Description Displays all attributes of the specified untyped event channel.

Examples The following command displays the attributes of my_channel:

itadmin ec show my_channel

Channel Name: my_channel

Channel ID: 1

Event Communication: Untyped

The following command displays the attributes of $my_channel2$ from a non-default event service:

itadmin -ORBname event.event2 ec show my_channel2

Channel Name: my_channel2

Channel ID: 2

Event Communication: Untyped

Note: For information about event service configuration variables, see the section on the plugins:notification namespace in the *Orbix Configuration Reference*.

ec show_typed

Synopsis ec show_typed channel_name

Description Displays all attributes of the specified typed event channel.

CHAPTER 21 | Event Service

Interface Repository

Overview

A subset of itadmin commands let you create, browse, and remove IDL definitions from the interface repository. You can manage the following interface repository components:

IDL Definitions	page 284
Repository Management	page 285

IDL Definitions

Overview

itadmin provides a single itadmin idl command, which lets you modify the contents of an interface repository with new IDL definitions.

idl - R = -v

Synopsis

idl -R=-v idl-filename

Description

Writes IDL definitions from a single IDL source file into the interface repository. The -R=-v argument setting causes the interface repository to use verbose mode to indicate command progress. The <code>idl-filename</code> argument names the IDL file. You must execute the <code>idl</code> command from the command line.

Examples

The following example writes the IDL definitions in the foo.idl file to the interface repository:

bash \$ idl -R=-v foo.idl
Created Alias MyLong.
Created Operation opl.
Created Operation op2.
Created Interface Foo.

Note: The idl -R=-v command does not require the itadmin command.

Repository Management

Overview

The following commands let you browse and modify the contents of an interface repository:

Table 19: Interface Repository Commands

ifr cd	Changes the current container (in shell mode).
ifr destroy_contents	Destroys the contents of the interface repository.
ifr ifr2idl	Outputs the contents of the interface repository to the specified file.
ifr list	Lists the contents of the current container.
ifr pwd	Prints the name of the current container (in shell mode).
ifr remove	Removes an IDL definition from the interface repository.
ifr show	Prints specified IDL definitions contained in the interface repository.
ifr stop	Stops the interface repository.

ifr cd

Synopsis

ifr cd [scoped-name | ..]

Description

Changes the current container to the specified scoped name. Using the argument ".." changes the current container to the next outermost container. If no arguments are given, ifr cd changes the current container to the interface repository. Use ifr cd in command shell mode only.

Examples

The following command changes to the specified scoped name:

itadmin ifr cd MYCO.PRODUCTION.TOOLS

ifr destroy_contents

Synopsis ifr destroy_contents

Description Destroys the entire contents of the interface repository, leaving the repository itself

intact.

ifr ifr2idl

Synopsis ifr ifr2idl filename

Description Converts the entire contents of the interface repository to text and writes it to the

specified filename.

ifr list

Synopsis ifr list [-1] [scoped-name | .]

Description Lists the contents of the specified container. If no container name is provided, this

command lists the contents of the current container.

Arguments

-1 Lists the contents in long form: absolute name, kind,

repository ID.

scoped-name Specifies the container to list the contents of. The default is

the root name.

. (dot) Specifies the current container.

ifr pwd

Synopsis ifr pwd

Description Displays the name of the current container. Use if r pwd in command shell mode

only. Command-line mode does not store persistent state.

ifr remove

Synopsis ifr remove scoped-name

Description Removes the scoped name by invoking the function IRObject::destroy() on

the scoped name. The *scoped-name* argument is the name of the interface repository entry to be removed, and is relative to the current container.

ifr show

Synopsis ifr show scoped-name

Description Displays the scoped name in IDL format. The scoped-name argument is relative

to the current container.

ifr stop

Synopsis ifr stop

Description Stops the interface repository.

CHAPTER 22 | Interface Repository

Location Domain

Overview

This section describes itadmin commands that manage a location domain and its components. Some commands modify static information in the implementation repository; others affect runtime components.

itadmin commands let you manage the following location domain components:

Locator Daemon	page 290
Named Key	page 293
Node Daemon	page 296
ORB Name	page 300
POA	page 304
Server Process	page 311

Locator Daemon

Overview

The following commands manage locator daemons:

Table 20: Locator Daemon Commands

locator heartbeat_daemons	Pings all the of the node daemons known to the specified locator, removing those that are no longer active.
locator list	Displays all locators in the location domain.
locator show	Displays all attributes of the specified locator daemon.
locator stop	Stops the locator daemon.

Locator daemon name

Most commands require you to supply the locator daemon name. The default name has the following format:

iona_services.locator_daemon.unqualified-hostname

For example:

iona_services.locator_daemon.oregon

locator heartbeat_daemons

locator heartbeat_daemons locator_name

Description

Synopsis

Pings all the of the node daemons known to the specified locator, removing those that are no longer active.

locator list

Synopsis locator list [-count] [-active]

Description Displays all locators in the location domain.

Arguments

-count Displays the number of locators in the location domain.

-active Displays all active locators in the location domain.

locator show

Synopsis locator show [-ior] locator-name

Description Displays all attributes of the specified locator.

Arguments

-ior Indicates that the target is an IOR, rather than the name of the Locator.

Examples

The following example shows the attributes displayed for a default locator:

itadmin locator show iona_services.locator.wicklow

Locator Name: iona_services.locator

Domain name: enterprise_services

Host name: wicklow

Start time: Sun, 05 Aug 2001 07:55:59.5380000 +0500

Replica type: Master

The following example shows the attributes for a locator running on wicklow, port 3076.

itadmin locator show -ior corbaloc::1.2@wicklow:3076/IT_Locator

Locator Name: iona_services.locator
Domain name: enterprise_services

Host name: wicklow

Start time: Sun, 05 Aug 2001 07:55:59.5380000 +0500

Replica type: Master

locator stop

Synopsis locator stop [-alldomain] [-ior] locator-name

Description Stops the specified locator daemon.

Arguments

-alldomain Stops the locator, all registered node daemons, and monitored

processes running in a location domain.

-ior Indicates that the target is an IOR, rather than the name of the

Locator.

Named Key

Overview

Named keys allow users to specify human readable URLs in place of a server's IOR. Named keys work best when used with persistent objects. If the object's IOR changes, the named key will need to recreated.

To pass the IOR of a server to a client using a named key, the user will need to supply an address is the following format:

corbaloc:iiop:ver@host:port/named_key

ver The IIOP version the server uses to communicate.

host The hostname for the machine running the locator daemon.

port The port used by the locator.

named_key The named key created for the server.

For example, the corbaloc reference for a replicated locator daemon would look like:

```
corbaloc:iiop:1.2@fox:8035,iiop:1.2@hound:8035/hunter
```

One instance of the locator daemon is hosted on fox and listens on port 8035. The other instance is hosted on hound and also listens on port 8035. The named key associated with this replicated locator daemon's IOR is hunter.

For more information on corbaloc references read section 13.6.10, "Object URLs," of the OMG CORBA specification.

The following commands let you manage named keys:

Commands

Table 21: Named Key Commands

named_key create	Creates an association between a specified well-known object key and a specified object reference.
named_key list	Lists all well known object keys that are registered with the locator daemon.

Table 21: Named Key Commands

named_key remove	Removes the specified <i>object-key</i> from the location domain.
named_key show	Displays the object reference associated with the given key.

named_key create

Synopsis named_key create -key object-reference

DescriptionAssociates a well-known object key name with an object reference. The -key argument specifies the human-readable string name of the key to use when

referring to the specified object-reference.

After entering this command, object requests destined for the specified object

key are forwarded to the specified object reference.

Use named_key create in command-line mode only.

Examples The following example shows the named key created for the default naming

service when Orbix is installed:

itadmin named_key create -key NameService IOR:010000002...003500

named_key list

Synopsis named_key list [-count]

Description Lists all well-known object keys registered in the location domain.

Arguments

-count Displays the number of well-known object keys in the location domain.

Examples The following

The following command lists the named keys that are created in a default Orbix environment:

itadmin named key list

NameService

InterfaceRepository

named_key remove

Synopsis named_key remove object-key

Description Removes the specified human-readable *object-key* from the location domain.

named_key show

Synopsis named_key show object-key

Description Displays the object reference associated with the specified human-readable

object-key.

Examples

itadmin named_key show NameService

Named Object Key : NameService

Associated Object Reference:

IOR01000002f0000004944...00100003500

Node Daemon

Overview

The following commands manage node daemons:

 Table 22:
 Node Daemon Commands

node_daemon list	Displays all node daemon names implicitly registered with the locator daemon.
node_daemon remove	Removes a node daemon from the location domain that is created implicitly when the specified node daemon starts.
node_daemon show	Displays all attributes of the specified node daemon.
.node_daemon stop	Stops the node daemon.
add_node_daemon.tcl	Adds node daemons to a host.

Node daemon name

Most commands require you to supply the node daemon name. The default name has the following format:

iona_services.node_daemon.unqualified-hostname

For example:

iona_services.node_daemon.oregon

node daemon list

Synopsis node_daemon list [-count]

Description Displays all node daemon names implicitly registered with the locator daemon.

Node daemon entries are implicitly created in the implementation repository

(IMR) when the specified node daemon starts.

Arguments

-count Displays the total node daemon count.

node daemon remove

Synopsis node_daemon remove node-daemon-name

Description Removes a node daemon entry from the implementation repository. Node daemon

entries are created implicitly when the specified node daemon starts.

Use this command only when the specified node daemon shuts down

prematurely due to a host crash or termination signal.

WARNING: Do not use node_daemon remove on a running node daemon.

node_daemon show

Synopsis node_daemon show node-daemon-name

Description Displays the attributes for the specified node daemon.

Examples The following example shows the attributes displayed for the node daemon on

host dali:

itadmin node_daemon show dali

Node Daemon Name: dali

Host Name: dali

File Access Permissions:

User: mstephens Group: o2kadm

Start time: Mon, 06 Aug 2001 06:55:53.4480000 +0500

The default node name is *host*. To change the default name, modify plugins:node_daemon:name, using itadmin variable modify. In a file-based configuration domain, you can also edit this variable in your configuration file

.node_daemon stop

Synopsis

node_daemon stop node-daemon-name

Description

Stops the specified node daemon. This command also stops all the processes monitored by that node daemon.

To view all processes monitored by the specified node daemon, use process list -node_daemon.

add_node_daemon.tcl

Synopsis

itadmin add_node_daemon.tcl -number<add> -port <base_port>
-script_dir <script_dir> [-host <cluster>] [-out <IOR_file>]

Arguments

add The number of node daemons to add to the host.

base_port The port number to be used by the first new node daemon. Each additional node daemon will be assigned a port numbers incrementing upward by one.

script_dirThe directory where the domain's start and stop scripts reside. This
 is typically, <install_dir>\etc\bin.

cluster Indicates the name of the cluster or federated name of which the host is associated. This parameter is optional.

IOR_file The full path name of the file store the IORs of the new node daemons. This parameter is optional and the default location is <current_working_dir>\node_daemons.ior.

To add node daemons to a host:

- 1. Ensure that the domain to which additional node daemons are to be added is running.
- Source the <domain>_env file to set the configuration environment variables.
- Run the command. It silently configures and deploys the new node daemons into the running configuration. The domain start and stop scripts will be modified to include the new node daemons.
- 4. Once the command finishes, stop the domain's services using the domain's stop script, stop_<domain>_services.
- 5. Manually modify the value of initial_references:IT_NodeDaemon:reference for the CORBA servers you want to use the additional node daemons so that it contains a reference to the new node daemon.
- If the servers are started on demand, you must also modify their process information to reflect the server's new node daemon.
- 7. Restart the domain using its start script, start_<domain>_services.

ORB Name

Overview

The following commands manage ORB names:

Table 23: ORB Name Commands

orbname create	Creates an ORB name in the location domain.
orbname list	Displays all ORB names in the location domain.
orbname modify	Modifies the specified ORB name entry either by associating it with another process entry, or by disassociating it from any process.
orbname remove	Removes an ORB name from the location domain.
orbname show	Displays attributes for the specified ORB name.

orbname create

Synopsis

orbname create [-process process-name] ORB-name

Description

Creates the specified ORB name in the location domain. This designates a server-side ORB that is subject to POA or process activation. In the location domain, the ORB name is associated with a POA name and is used for process activation.

Arguments

-process

Associates the ORB name with the specified process. The process name must previously be registered with the locator daemon (see "process create" on page 311).

Examples

The following command creates a scoped ORB name:

itadmin orbname create MutualFunds.Tracking.GroInc.Stocks

orbname list

Synopsis

orbname list [-active] [-count] [-process process-name]

Description

Lists all ORB names in the location domain.

Arguments

-active Lists only the name in the locator's active ORB table.

-count Lists the total number of ORB names in the location domain.

-process Lists only the ORB name entries that are associated with

process-name.

Examples

The following example lists all registered ORB names in the location domain:

itadmin orbname list

ifr

naming

production.test.testmgr
production.server

orbname modify

Synopsis orbname modify [-process process-name] ORB-name

Description Modifies the specified ORB name entry by associating it with the specified process

name. If the process name is omitted, the ORB name is disassociated from any

process.

Arguments

process-name The name of the process to which the ORB name will be

associated.

orbname remove

Synopsis

orbname remove [-active|-deep|-force] ORB-name

Description

Removes an ORB name from the location domain. You might need to remove an ORB name, if its application is removed from the environment, or if the ORB name has changed, or to prevent process activation.

If there is an active ORB entry for the ORB name in the locator's active ORB table, this is also removed.

An ORB name can be the same as the ORB_id (used to identify an ORB within a process) and has the following syntax:

ORBNameSegment.ORBNameSegment.ORBNameSegment

Arguments

The following arguments are mutually exclusive:

-active Removes only the active ORB entry from the locator's active ORB table, and does not remove the ORB name.

-deep Removes the ORB name and all POA names in the location domain

that refer to it.

-force Forces ORB name removal, even though some POA names in the

location domain might have references to it.

Examples

The following example removes the production. test ORB name:

itadmin orbname list

ifr naming

 $\verb"production.test.testmg" \\$

production.server

itadmin orbname remove -active production.test.testmgr

itadmin orbname list

ifr

naming

production.server

orbname show

Synopsis orbname show ORB-name

Description Displays all the attributes for the specified ORB name.

Examples The following example displays the attributes for the company. sales ORB name:

itadmin orbname show company.sales

ORB Name: company.sales
Process Name: sales_process

Active: yes

POA

Overview

The following commands manage POA entries:

Table 24: POA Commands

poa create	Creates a POA name in the location domain.
poa list	Displays POA names in the location domain.
poa modify	Modifies the indicated POA name as specified.
poa remove	Removes a POA name from the location domain.
poa show	Displays all data that is entered for POA-name.

poa create

Synopsis

Registers a POA in the location domain. The required FQPN argument is the fully-qualified POA name. An FQPN has the following syntax:

FQPNsegment/FQPNsegment/FQPNsegment

Arguments

-orbname ORB-name Associates an ORB name with the specified POA. This argument requires an ORB-name argument with the following syntax:

 $\label{lem:orbname} \mbox{ORBNameSegment.ORBNameSegment} \mbox{-} \mbox{orbname cannot be combined with -persistent,} \\ \mbox{-replicas, or -transient}$

-replicas

replica-list

Associates the specified POA with multiple ORBs specified in replica-list, where replica-list is a

comma-delimited list of ORBs:

orb[,orb]...

-replicas cannot be combined with -persistent,

-orbname, or -transient.

-persistent

Marks the POA as persistent without associating it with an

ORB.

-persistent cannot be combined with -replicas,

-orbname, or -transient.

-transient

Marks the POA as transient.

-transient cannot be combined with -replicas,

-orbname, or -persistent

-allowdynamic

Enables dynamic registration of a POA in the location domain. The default is no dynamic registration. Enabling dynamic creation allows servers to register information (although administrators must create the top-level name

manually).

-allowdynreplicas Must be set to yes or no:

- yes: (default) Any ORB creating the POA is automatically added to the POA's replica list.
- no: Only those ORBs that are configured in the cluster through replicas are allowed to create the POA.

-load_balancer

1b-name

Determines the load balancer used to select a replica response to client requests. If a load balancer is not specified, requests will be routed to the first server that creates the POA.

The Orbix distribution provides support for the following algorithms:

- round_robin: the locator uses a round-robin algorithm to select from the list of active servers that is, the first client is sent to the first server, the second client to the second server, and so on.
- random: the locator randomly selects an active server to handle the client.
- prefer_local: the locator tries to use a server whose
 IP address matches that of the client.

The following command creates a transient POA name in the location domain:

itadmin poa create -transient banking_service

The following command creates a persistent POA name in the location domain:

itadmin poa create -orbname banking_services_app
banking service/account

The following command creates a persistent POA name associated with multiple ORBs:

itadmin poa create -replicas bank_server_1,bank_server_2
 -load_balancer round_robin banking_service/account

Examples

poa list

Synopsis poa list [-active] [-children FQPN] [-count] [-persistent]

[-transient]

Description Shows all POA names in the location domain.

Arguments

-active Lists only entries for POAs that are currently active.

-active and -transient parameters are mutually

exclusive.

-children FQPN Lists only entries for child POAs of the specified parent

POA

-count Lists the total number of POA names in the location

domain.

-persistent Lists only POA names for persistent POAs.

-transient Lists only POA names for transient POAs. -transient

and -active arguments are mutually exclusive.

Examples

itadmin poa list

banking_service

banking_service/account

banking_service/account/checking

banking_service/account/checking/deposit

poa modify

Synopsis poa modify [-orbname ORB-name]

 $[-{\tt replicas}\ {\tt replica-list}]$

[-clear_replicas]

[-augment_replicas replica-list]
[-remove_replicas replica-list]

[-allowdynamic]
[-allowdynreplicas]

[-load_balancer lb-name] FQPN

Description

Modifies the specified POA name. The required FOPN argument is the fully-qualified POA name. A FOPN has the following syntax:

FQPNsegment/FQPNsegment/FQPNsegment

Arguments

-orbname ORB-name Associates the specified ORB name with the specified POA. This argument requires an ORB-name argument with the following syntax:

ORBNameSegment.ORBNameSegment.ORBNameSegment

-replicas replica-list

Associates the specified POA with multiple ORBs specified in replica-list, where replica-list is a

comma-delimited list of ORBs:

orb[,orb]...

-replicas cannot be combined with -orbname.

-clear_replicas replica-list Disassociates the POA from any ORBs.

-augment_replicas Enables you to add replicas without having to redefine the complete list. replica-list is a comma-delimited list of additional ORBs:

orb[,orb]...

-remove replicas replica-list

Enables you to remove replicas without having to redefine the complete list. replica-list is a comma-delimited list of ORBs to be removed:

orb[,orb]...

-allowdynamic

Enables dynamic registration of a POA in the location domain. The default is no dynamic registration. Enabling dynamic creation allows servers to register information (although administrators must create the top-level name manually).

-allowdynreplicas Must be set to yes or no:

- yes: (default) Any ORB creating the POA is automatically added to the POA's replica list.
- no: Only those ORBs that are explicitly configured in the cluster through replicas are allowed to create the POA.

-load balancer

Determines the load balancer used to select a replica response to client requests. If a load balancer is not specified, requests will be routed to the first server that creates the POA.

The Orbix distribution provides support for the following algorithms:

- round_robin: the locator uses a round-robin algorithm to select from the list of active servers that is, the first client is sent to the first server, the second client to the second server, and so on.
- random: the locator randomly selects an active server to handle the client.
- prefer_local: the locator tries to use a server whose
 IP address matches that of the client.

poa remove

Synopsis

poa remove [-active|-allactive] FQPN

Description

Removes the entry for the specified POA and its descendants from the location domain. By default, all active entries for the POA and its children are also removed. Use the -active argument to remove only the active entry for the specified POA.

Arguments

-active Removes currently active entries for the specified POA only.
-active and -allactive arguments are mutually exclusive.
-allactive Removes only active entries for the specified POA and all its

children.

Examples

The following example removes the specified POA and its children:

itadmin

% poa list

banking_service

banking_service/account

banking service/account/checking

banking_service/account/checking/deposit

% poa remove banking_service/account/checking

% poa list

banking_service

banking_service/account

poa show

Synopsis

poa show FOPN

Description

Displays all the attributes for the specified POA name. A FQPN (fully-qualified POA name) has the following syntax:

FQPNsegment/FQPNsegment/FQPNsegment

Examples

The following example shows the attributes for the IFR POA name:

itadmin poa show IFR

FQPN: IFR

Active: no

Lifespan: persistent

ORB Names:

iona_services.ifr

Allow Replicas outside this list: no Load Balancing Algorithm: <NONE> Allow Dynamic Registration: no

Parent FQPN: <NONE> Children FQPN: <NONE>

310

Server Process

Overview

The following commands let you manage server process entries:

Table 25: Server Process Commands

process create	Creates a server process name in the location domain.
process disable	Disables the specified server process for process activation, using the node daemon.
process enable	Enables a target server process for on-demand activation by the node daemon.
process kill	Kills the specified process that was started by its associated node daemon.
process list	Lists names of server processes in the location domain.
process modify	Modifies the process as specified.
process remove	Removes a server process name from the location domain.
process show	Displays a complete server process entry.
process start	Starts a registered server process.
process stop	Stops a registered server process.

process create

Synopsis

process create -args "-ORBname orb-name [arg-list]"

[-description] [-startupmode mode]

[-node_daemon node-daemon-name] [-pathname pathname]

[-directory dir] [-env env] [-group group] [-user user]

[-umask umask] process-name

Description

Registers a server process in a location domain's implementation's repository.

Arguments

The following arguments apply to all platforms.

-args

Arguments supplied to the process when it starts. At a minimum, supply the -ORBname argument with the name of the ORB associated with this server process.

Enclose all arguments within quotation marks, and separate multiple arguments with spaces. For example:

```
itadmin process create -args "-ORBname
    company.production.sver1" my_app
```

If you are registering a Java server, the argument list generally includes the class path.

If the process start-up mode is per_client, the locator creates a new ORB name and a new process entry for each request from a client to the persistent POA associated with this process. In this case, the %o and %p strings in the process's arguments are substituted with the new ORB name and the new process name respectively. For example:

```
-args "--ORBname %o"
```

For more details, see "Per-client activation" on page 54.

-description

A brief description of the target process. Enclose the description in double quotes.

-startupmode

Specifies the start-up mode of the target process:

- on_demand (default) starts the process when requested by a client.
- per_client starts a new process for each client.
- disable disables automatic startup.

-node_daemon

The name of the node daemon that starts or modifies this process.

-pathname

The full pathname of the executable to start when the process is activated.

On Windows platforms, specify a drive letter if not the current drive of the node daemon. Windows paths can be expressed with one forward slash separator or two backward slashes. -directory

Specifies the working directory to which the target process writes output files, error logs, and so on.

On UNIX the default current working directory is set to the root file system. On Windows, the default current drive is the node daemon's drive, and the current directory is set to the root directory.

On Windows, specify a drive letter if the working directory drive differs from the node daemon's current drive. Windows paths can be expressed with one forward slash separator or two backward slashes.

On UNIX, if the current working directory path does not exist, it is created automatically with permissions drwx-----.

Use this argument in order to:

- Ensure that the server runs in a directory that is in the root file system. This avoids problems with running servers in mounted file systems.
- Use relative path names. This means that administrators can set the working directory for the activated server, without having to define other paths and directories.
- Ensure that core files cannot overwrite each other if the server is configured to run somewhere other than the root directory.

-env

Explicitly sets the process environment. This argument takes an list of space-delimited *variable=value* pairs, enclosed in quotation marks:

env "DISPLAY=circus: 0.0 CLOWN=Bozo HOME=/tent"

This option overrides any environment variables set by the node daemon. By default, the server inherits its environment from the node daemon. If you use this option, you must specify all environment variables that the server requires.

For more information about environment settings, see "Server Environment Settings" on page 56.

-group

Group name that starts the target process. The default is nobody. For more information, see page 58.

-user

User name that starts the target process. The default is nobody. For more information, see page 58.

-umask File mode creation mask for the activated target process.

Specify as three octal digits ranging from 000 to 777. The

default is 022 (maximum file permissions: 755, or rwxr-xr-x).

process disable

Synopsis process disable process-name

Description Disables on-demand activation of the specified server *process-name*.

process enable

Synopsis process enable process-name

Description Enables on-demand activation of the specified server *process-name*.

process kill

Synopsis process kill [-signal signal_number] [-force] process_name

Description Kills the specified process that was started by its associated node daemon. The

-signal argument specifies the UNIX signal number to kill the process. This

command has the following effects:

UNIX Sends a signal to the process. The default is 9.

Windows Calls TerminateProcess().

This command only works for processes activated by the node daemon. For

manually launched processes, it has no effect.

Arguments

 $\hbox{-signal} \qquad \hbox{Specifies the UNIX signal number to kill a process. The default} \\$

is 9.

-force

Forces the removal of the persistent data for the specified process from the implementation repository (IMR). This can be used when a previously active process has died or been killed, and the persistent data in the IMR was not cleaned up correctly. If the persistent data held by the locator and node daemon was not correctly cleaned up, there may be issues when trying to restart the process.

Note: This command should be used with caution, and only if the normal cleanup mechanisms have failed for some unknown reason.

process list

Synopsis

process list [-count] [-node_daemon node-daemon-name] [-active]

Description

Lists the target process names of all processes registered in the location domain. Listing process names is useful for verifying a target process name or its status.

Arguments

-count Displays the total number of process names in the location

domain.

-node_daemon Lists all monitored processes for a given node daemon. This is

useful if you want to perform the .node_daemon stop

command.

-active Lists all currently active processes.

Examples

The following example lists all registered process names in a location domain

itadmin process list

if

naming

my_app

process modify

Synopsis

process modify -args '-ORBname orb-name [arg-list]"

[-description] [-startupmode mode]

[-node_daemon node-daemon-name]

[-pathname pathname] [-directory dir]

[-env env] [-group group] [-user user]

[-umask umask] process-name

Description

Modifies the specified process entry in the implementation repository.

Arguments

-args

Arguments supplied to the process when it starts. At a minimum, supply the -ORBname argument with the name of the ORB associated with this server process.

Enclose all arguments with quotation marks, and separate multiple arguments with spaces. For example:

```
itadmin process create -args "-ORBname
    company.production.sver1" my_app
```

If you are registering a Java server, the argument list generally includes the class path.

If the start-up mode of the process is per_client, the locator creates a new ORB name and a new process entry for each request from a client to the persistent POA associated with this process. In this case, the %o and %p strings in the process's arguments are substituted with the new ORB name and the new process name respectively. For example:

```
-args "--ORBname %o"
```

For more details, see "Per-client activation" on page 54.

-description

A brief description of the target process.

-startupmode

Specifies the start-up mode of the target process:

- on_demand starts the process when requested by a client.
- per_client starts a new process for each client.
- disable disables automatic startup.

-node daemon

The name of the node daemon that will start or modify this process.

-pathname

The complete pathname of the executable that will be started when the process is activated.

For Windows platforms, specify a drive letter if the executable is not the same as the current drive of the node daemon. Windows paths can be expressed with one forward slash separator or two backward slashes.

-directory

Specifies the working directory where the target process writes output files, error logs, and so on.

On UNIX the default current working directory is set to the root file system. On Windows, the default current drive is the node daemon's drive, and the current directory is set to the root directory.

On Windows, specify a drive letter if the working directory drive differs from the node daemon's current drive. Windows paths can be expressed with one forward slash separator or two backward slashes.

On UNIX, if the current working directory path does not exist, it is created automatically with permissions drwx-----.

Use this argument in order to:

- Ensure that the server runs in a directory that is in the root file system. This avoids problems with running servers in mounted file systems.
- Use relative path names. This means that administrators can set the working directory for the activated server without having to define other paths and directories.
- Ensure that core files cannot overwrite each other if the server is configured to run somewhere other than the root directory.

-env Explicitly sets the process environment. This argument takes a list of space-delimited *variable=value* pairs, enclosed in

quotation marks:

env "DISPLAY=circus:0.0 CLOWN=Bozo HOME=/tent"

This option overrides any environment variables set by the node daemon. By default, the server inherits its environment from the node daemon. If you use this option, you must specify all environment variables that the server requires.

For more information about environment settings, see

"Server Environment Settings" on page 56.

-group Group name that starts the target process. The default is

nobody. For more information, see page 58.

-user User name that starts the target process. The default is

nobody. For more information, see "File access permissions"

on page 58.

-umask File mode creation mask for the activated target process.

Specify as three octal digits, ranging from 000 to 777. The default is 022 (maximum file permissions: 755, or

rwxr-xr-x).

process remove

Synopsis

process remove [-force|-deep|-active] process-name

Description

Removes a process implementation repository entry created using process create. If you omit the -force or -deep switch, POA entries that reference this process are not removed and an error is reported.

Removing a process also removes the active process entry from the locator's active process table. The -active argument removes only an active process entry from the locator's active process table; the process remains registered with the implementation repository.

Arguments

The following arguments are mutually exclusive. Choose one:

-active Removes only the active process entry from the locator's active

process table.

-deep Removes the process entry and all object adapter implementation

repository entries that refer to it.

-force

Forces process removal even if other implementation repository entities have references to it.

Examples

The following example removes the my_app server process name:

itadmin process list

ifr

naming

my_app

itadmin process remove -force my_app

itadmin process list

ifr naming

process show

Synopsis

process show process-name

Description

Displays all process data entered for the specified *process-name*. If the process is active, process show displays the active node daemon name. Viewing a target process is useful for verifying whether a process name is registered and has the appropriate settings.

Examples

The following example shows the information registered with the locator daemon for a target process:

```
itadmin process show my_app
Process Name: my_app
Description: Unknown services provided.
Startup Mode: on_demand
Node Daemon List:
 Node Daemon Name: oregon
   Host Name: oregon
   Max. Retries: 3
   Retry Interval: 2
   Path Name: c:\Program Files\Acme\bin\my_app.exe
   Arguments: -safe -sane
    Environment Variables: Inherited from node daemon
   File Access Permissions:
     User: mstephen
     Group: PC-GROUP
    File Creation Permissions:
     Umask: 022
    Current Directory: /
    Resource Limits: Inherited from node daemon
```

process start

Synopsis

process start process-name

Description

Starts a target process on the host where the node daemon configured for the process resides.

process stop

Synopsis process stop [-signal number] process-name

Arguments Stops the specified process that was started by its associated node daemon.

Depending on the environment used, this command has the following effect:

UNIX/C++ Sends a SIGINT (2) signal to the process.

Windows/C++ Calls GenerateConsoleCtrlEvent (CTRL_BREAK_EVENT, 0).

Java Calls System.exit(0).

Arguments

-signal Specifies the UNIX signal number to stop a process.

WARNING: The signal number is ignored for a Windows NT process.

CHAPTER 23 | Location Domain

Mainframe Adapter

Overview

The following itadmin commands enable you to use the mapping gateway interface of the Orbix Mainframe Adapter (MFA).

These commands enable you to list transaction mappings supported by your CICS or IMS server adapter, add or delete interfaces and operations, and change transactions that operations are mapped to. A new mapping file can be read, or the existing mappings can be written to a new file.

 Table 26:
 Mainframe Adapter itadmin Commands

mfa add	Adds a new mapping.
mfa change	Changes the transaction to which an existing operation is mapped.
mfa delete	Causes the server adapter to stop exporting a specified operation.
mfa -help	Prints a list of the operations that the mfa plugin supports.
mfa list	Prints a list of the mappings (interface, operation, and name) that the server adapter supports.
mfa refresh	Causes the server adapter to obtain up-to-date type information for the specified operation.
mfa reload	Causes the server adapter to reload the list of mappings from its mapping file.
mfa resetcon	If the IMS server adapter is using OTMA to communicate with IMS, this command causes the server adapter to close its connection and to reconnect. Has no effect on the CICS server adapter.
mfa resolve	Prints a stringified IOR for the object in the server adapter that supports the specified interface.

 Table 26:
 Mainframe Adapter itadmin Commands

mfa save	Causes the server adapter to save its current mappings to either its current mapping file or to a filename that you provide.
mfa stats	Causes the server adapter to switch over to a new mapping file, and to export only the mappings contained within it.
mfa stats	Displays statistical information on the running server adapter.
mfa stop	Instructs the server adapter to shut down.

Note: The add, change, and delete operations only update the CICS or IMS server adapter internal information. If, however, you use the save operation the new details are written to the server adapter mapping file.

mfa add

Synopsis mfa add -interface <name> -operation <name> <mapped value>

Description Adds a new mapping.

Parameters You must supply the name of the interface, name of the operation and the mapped

value that you want added. Module names form part of the interface name and are

separated from the interface name with a / character.

Examples For example, to add a new Simple/SimpleObject mapping, use the following

command:

itadmin mfa add -interface Simple/SimpleObject -operation
 call_me SIMPLESV

mfa change

Synopsis mfa change -interface <name> -operation <name> <mapped value>

Description Changes the transaction to which an existing operation is mapped.

Parameters You must supply the name of the interface, name of the operation and the mapped

value that you want added. Module names form part of the interface name and are

separated from the interface name with a / character.

Examples For example, to change the transaction to which the call_me operation is mapped

to SIMPLESV, use the following command:

itadmin mfa change -interface Simple/SimpleObject -operation
 call_me SIMPLESV

mfa delete

Synopsis mfa delete -interface <name> -operation <name>

Description Stops the server adapter exporting the specified operation.

Parameters You must supply the interface name and the operation name that you want the

server adapter to stop exporting. Module names form part of the interface name

and are separated from the interface name with a / character.

Examples For example, to stop the server adapter exporting the call_me operation, use the

following command:

itadmin mfa delete -interface Simple/SimpleObject -operation

call_me

mfa -help

Synopsis mfa -help

Description Lists all the operations provided by the mfa itadmin plugin.

mfa list

Synopsis mfa list

Description Prints a list of the mappings (interface, operation and name) that the adapter server

supports.

Parameters You must supply the interface name. Module names form part of the interface

name and are separated from the interface name with a / character.

mfa refresh

Synopsis mfa refresh [-operation <name>] <interface name>

Description Causes the server adapter to obtain up-to-date type information for the specified

interface.

Parameters You must supply the interface name. Module names form part of the interface

name and are separated from the interface name with a / character. The

-operation $\mbox{-name}\mbox{-}$ argument is optional. If you omit the -operation $\mbox{-}$ name>

argument, all operations mapped in the specified interface are refreshed.

Examples For example, to cause the server adapter to get up-to-date type information for the

Simple interface, use the following command:

itadmin mfa refresh Simple/SimpleObject

mfa reload

Synopsis mfa reload

Description Causes the server adapter to reload the list of mappings from its mapping file.

mfa resetcon

Synopsis mfa resetcon

Description

If the IMS server adapter is using OTMA to communicate with IMS, when this operation is called on the Mapping Gateway interface, the server adapter closes its connection with OTMA and reconnects. This is done in such a way that it does not affect any clients connected to the server adapter by briefly queueing client requests in the server adapter until the connection is re-established. The purpose of this operation is to free any cached security ACEE's on the OTMA connection. You should, therefore, use this operation after changes that affect users access to IMS have been made to user security profiles in the OS/390 security package; for example, RACF.

Note: This command has no effect on the CICS server adapter.

mfa resolve

Synopsis mfa resolve <interface name>

Description Prints a stringified IOR for the object in the server adapter that supports the

specified interface. This IOR string can then be given to clients of that interface, or stored in an Orbix naming service. The IOR produced contains the TCP/IP port number for the locator if the server adapter is running with direct persistence set

to no. Otherwise, it contains the server adapter's port number.

Examples For example, to retrieve an IOR for Simple IDL, use the following command:

itadmin mfa resolve Simple/SimpleObject

Once retrieved, the IOR can be distributed to the client and used to invoke on the

target server running inside CICS or IMS.

mfa save

Description Causes the server adapter to save its current mappings to either its current mapping

file, or to a file name that you provide.

Parameters The [<mapping_file name>] argument is optional. You need only provide it if

you want the server adapter to save its current mappings to a specified file.

Examples For example, to get the server adapter to save its current mappings to a

myMappings.map file, use the following command:

itadmin mfa save "C:\myMappings.map"

mfa stats

Synopsis mfa stats

Description Displays some statistical information on the running server adapter. Information

includes the current time according to the server adapter, the pending request queue length, the total number of worker threads, worker threads currently active, total number of requests processed by the server adapter since startup and the

server adapter startup time.

mfa stop

Synopsis mfa stop

Description Causes the server adapter to shut down.

mfa switch

Synopsis mfa switch <mapping_file name>

Description Causes the server adapter to switch over to a new mapping file, and to export only

the mappings contained in it.

Parameters You must provide the name of the mapping file that you want the server adapter

to switch over to.

Examples For example, to get the server adapter to switch over to a myMappings.map

mapping file, use the following command:

itadmin mfa switch "c:\myMappings.map"

CHAPTER 24 | Mainframe Adapter

Naming Service

Overview

A subset of itadmin commands let you manage the naming service and its contents. You can use these commands to create, list, and remove naming contexts, objects, and object groups from the naming service.

All paths and compound names in the naming service conform to the CORBA Interoperable Naming Service (INS) string name format.

Naming service commands operate on two components:

Names	page 332
Object Groups	page 336

Names

Overview

The following ns commands let you manage and browse the naming service:

Table 27: Naming Service Commands

ns bind	Creates an association between a context or object reference and the specified compound name.
ns list	Lists the contents of the specified path.
ns list_servers	Lists all active naming servers.
ns newnc	Creates a new naming context or object and binds it to the specified path.
ns remove	Removes the specified context or object.
ns resolve	Displays a resolved string name form of the IOR for a specified path.
ns show_server	Displays the naming server details for the server name specified.
ns stop	Stops the naming service.
ns unbind	Unbinds the path-specified context or object.

ns bind

Synopsis

ns bind {-context | -object} -path path IOR

Description

Creates an association between a context or object reference and the path-specified compound name. Use this command in command-line mode only.

Arguments

-context-objectBinds a contextBinds an object.

-path Specifies an INS string name as the path to the new binding.

Examples

The following example binds an object to the name james.person, in the company/staff naming context:

itadmin ns bind -o -path company/staff/james.person "TOR:0000000037e276f47a4b94874c64648e949..."

ns list

Synopsis ns list [path]

Description Displays the contents of

Displays the contents of the specified path. If path resolves to a context, its contents are displayed. If path resolves to an object, the object is displayed. If no path is specified, the contents of the initial naming context are displayed. The path argument takes the form of an INS string name.

The type of the binding is also listed. A binding of type Object names an object. A binding of type Context names a naming context.

Examples

The following command lists the bindings in company/engineering in the naming service:

itadmin ns list company/engineering

paula (Object)
production (Context)
john (Object)
manager (Object)

ns list_servers

Synopsis ns list_servers [-active]

Description Lists all the active servers.

Arguments

-active Displays all active naming servers.

ns newnc

Synopsis ns newnc [path]

Description

Creates a naming context or object and binds it to the specified path. If path is not specified, ns newno prints the IOR to standard out. The path argument takes the form of an INS string name.

Examples

itadmin
% ns newnc foo.bar/foo3.bar3
% ns list foo.bar

/foo2.bar2 Context /foo3.bar3 Context

ns remove

Synopsis ns remove [-recursive] path

Description

Unbinds the specified context or object. If <code>path</code> is a context, the context is also destroyed. The ns remove command checks whether a context is empty before destroying it. If the context is empty, ns remove destroys it and then unbinds it. If the context is not empty and you omit the -recursive argument, ns remove displays an error message. The required <code>path</code> argument specifies an INS string name.

Arguments

-recursive Recursively destroys and unbinds a context or object if the context is not empty.

Examples

For example, the following commands destroy the manager bindings:

itadmin ns remove company/engineering/manager.person
itadmin ns remove company/engineering/support/manager.person

ns resolve

Synopsis ns resolve path

Description

Prints the resolved string form of the IOR for a given path specified by an INS string name. If a path is not specified, the string form of the root naming context is displayed. The *path* argument takes the form of an INS string name.

For example:

itadmin ns resolve company/engineering

"IOR:0003032272d9218a35d9614357f87c93800d7...6f3"

Examples

The following examples show that the names company/staff/paula.person and company/engineering/manager.person resolve to the same object:

itadmin ns resolve company/staff/paula.person

"IOR:0000000569a2e8034b94874d6583f09e24..."

itadmin ns resolve company/engineering/manager.person

"IOR:0000000569a2e8034b94874d6583f09e24..."

ns show_server

Synopsis ns show_server server_name

Description Displays the naming server details for the server name specified.

Stops the naming service.

ns stop

Description

Synopsis ns stop server_name

ns unbind

Synopsis ns unbind path

Description Unbinds the context or object specified by path. The path argument takes the

form of an INS string name.

Object Groups

Overview

The following nsog commands let you manage object groups:

 Table 28:
 Object Group Commands

nsog add_member	Adds the specified member object to the specified object group.
nsog bind	Binds the specified object group to the specified path.
nsog create	Creates the specified object group, with the specified selection policy.
nsog list	Lists all object groups currently existing in the naming service.
nsog list_members	Lists the names of members belonging to the specified object group.
nsog modify	Modifies the selection policy for the specified object group.
nsog remove	Removes the specified object group from the naming service.
nsog remove_member	Removes the specified member object from the specified object group.
nsog set_member_timeout	Sets the load timeout period for a member of an active object group.
nsog show_member	Displays the object reference that corresponds to the specified member of an object group.
nsog update_member_load	Updates the load value of a member of an active object group.

nsog add_member

Synopsis nsog add_member -og_name group-name -member_name member-name IOR

Description Adds an object to the specified object group. After being added, the object is

available for selection.

Arguments The following arguments are all required:

-og_name Specifies the object group to which the member is added.

group-name

-member_name Specifies a unique group member name.

member-name

IOR Specifies the member's object reference.

Examples The following command adds a member, paula, to the engineers object group

with an object reference of IOR:0001def...:

nsog bind

Synopsis nsog bind -og_name group-name path

DescriptionBinds the specified object group to the specified path in the naming service. When

clients resolve that path, they transparently obtain a member of the specified object

group.

Arguments

-og_name Specifies the name of the object group to bind.

group-name

path SPecifies the INS path to bind the object group.

Examples The following example binds the engineers object group to the path

company/engineering/engineers.pool:

itadmin nsog bind -og_name engineers
company/engineering/engineers.pool

The company/engineering context must be already created.

nsog create

Synopsis nsog create -type selection-policy group-name

Description Adds the named object group group-name to the naming service with the specified

selection policy. On creation, an object group contains no member objects.

The naming service directs client requests to object group members according to

the specified selection algorithm. For more about active load balancing, see

"Active load balancing" on page 120.

Arguments

-type Specifies the object group's selection algorithm with

selection-policy one of the following values:

rr: round-robin rand: random

active: active load balancing

group-name Specifies the name of the new object group.

Examples The following example creates an object group, engineers, with a random

selection policy:

itadmin nsog create -type rand engineers

nsog list

Synopsis nsog list

Description Displays all object groups that currently exist in the naming service.

Examples

itadmin nsog list

Random Groups: engineers

 $nsog\ list_members$

Synopsis nsog list_members -og_name group-name

Description Lists the members of the specified object group.

Arguments

-og_name Specifies the target object group.

group-name

Examples The following example lists the members of the engineers object group:

itadmin nsog list_members engineers

nsog modify

Synopsis nsog modify -type selection-policy group-name

Description Changes the selection algorithm for the specified object group. An object group's

selection algorithm determines how the naming service directs client requests to

object group members (see "Selection algorithms" on page 120).

Arguments

-type Specifies the object group's selection algorithm with one of

selection-po the following values:

licy rr: round-robin

rand: random

active: active load balancing (see "Active load balancing"

on page 120).

group-name Specifies the object group to modify.

Examples The following command changes the object group engineers's selection

algorithm:

itadmin nsog modify -type rr engineers

nsog remove

Synopsis nsog remove group-name

Description Removes the specified object group from the naming service.

Examples

The following example removes and unbinds the engineers object group:

itadmin nsog remove engineers

itadmin unbind company/engineering/engineers.pool

Note: If the object group is bound in a naming graph, you must also unbind it, as shown in this previous example.

nsog remove_member

Synopsis

nsog remove_member -og_name group-name member-name

Description

Removes an object group member. You might wish to remove a member of an object group if it no longer participates in the group—for example, the service it references is inaccessible.

Arguments

-og_name The target object group.

group-name

member-name The member to remove from group-name.

Examples

The following example removes paula from the engineers object group:

itadmin nsog remove_member -og_name engineers paula

nsog set_member_timeout

Synopsis

nsog set_member_timeout -og_name group-name -member_name member timeout-value

Description

Specifies how long an object group member is eligible for load updates, in an object group that has active load balancing. If the member's load value is not updated before <code>timeout-value</code> elapses, the member is removed from the object group's selection pool.

This command has no effect on round-robin and random groups. However, the member timeout is stored and put to use if the object group's selection algorithm is modified to active load balancing (see "nsog modify" on page 339).

Arguments

-og_name Specifies the target object group.

group_name

-member_name Specifies the target object.

member

timeout-value Specifies the timeout value in seconds. A value of -1 sets an

infinite timeout value.

Examples The following command sets the load timeout period to 30 seconds for member

gate3 in the gateway active object group:

nsog set_member_timeout -og_name gateway -member_name gate3 30

nsog show_member

Synopsis nsog show_member -og_name group-name member-name

Description Displays the object reference that corresponds to the specified member of the

specified object group.

Examples For example, to display the IOR of member paula in the object group engineers:

itadmin nsog show_member -og_name engineers paula

"IOR:0000000569a2e8034b94874d6583f09e24..."

nsog update_member_load

Synopsis nsog update_member_load -og_name group_name -member_name member name load value

> Updates the load value for the specified member of an active object group. This load value is valid for a period of time specified by the timeout assigned to that member (see "nsog set member timeout" on page 340). In an active selection policy, the naming service selects the group member with the lowest load value.

This command has no effect on round-robin and random object groups. The naming service makes no interpretation of a member's load value, and only uses this information to select the lowest loaded member.

The following command updates the load value to 2.0 for member1 in the webrouter active object group:

nsog update_member_load -og_name webrouter -member_name member1 2.0

Description

Examples

Notification Service

Overview

The CORBA notification service enables applications to send events to any number of objects. For more details, see the *Orbix Enterprise Messaging Guide*. Orbix itadmin commands enable you to manage the following components of a notification service:

Notification Service Management	page 344
Event Channel	page 348

Notification Service Management

The following commands let you manage an notification service instance.

Table 29: Notification Service Commands

notify checkpoint	Performs checkpoint operations on the notification service's Berkeley DB database.
notify post_backup	Performs post-backup operations on the notification service database.
notify pre_backup	Performs pre-backup operations on the notification service database.
notify show	Displays the attributes of the specified notification service.
notify stop	Stops a notification service.

notify checkpoint

Synopsis

Description

notify checkpoint

Performs checkpoint operations on the notification service's Berkeley DB database.

When using transactions, Berkeley DB maintains transaction log files. Each time a transaction commits, data is appended to the transaction log files, and the database files are not modified. Data in transaction log files is then transferred periodically to the database files. This transfer is called a *checkpoint*. You can specify the checkpoint interval with the following configuration variable:

plugins:notify:database:checkpoint_interval

The checkpoint operation performs a Berkeley DB checkpoint. The following configuration variable determines whether to delete the old log files, or move them to another directory:

plugins:notify:database:checkpoint_deletes_old_logs

The following configuration variable specifies the directory to which log files should be moved:

plugins:notify:database:old_log_dir

notify post_backup

Synopsis notify post_backup

Description Performs post-backup operations on the notification service database.

When backing up data files, it is important that no checkpoint occurs during the backup. The pre-backup operations force a checkpoint and then suspend checkpointing. The post-backup operations resume checkpointing.

notify pre_backup

Synopsis notify pre_backup

Description Performs pre-backup operations on the notification service database.

When backing up data files, it is important that no checkpoint occurs during the backup. The pre-backup operations force a checkpoint and then suspend checkpointing. The post-backup operations resume checkpointing.

notify show

Synopsis notify show

Description Displays the attributes of the default notification service.

Multiple instances of the notification service are also supported. To show the attributes of a non-default notification service, specify the ORB name used to start the notification service (using the -ORBname parameter to itadmin).

Examples The following command shows the attributes of a default notification service:

itadmin notify show

Notification Service Name: IT_NotifyNamedRoot

Host Name: podge

Notification Channel Name List:

my_channel

The following command shows the attributes of the specified non-default notification service:

```
itadmin -ORBname notify.notify2 notify show
Notification Service Name: IT_NotifyNamedRoot2
Host Name: rodge
Notification Channel Name List:
   my_channel
   my_channel2
```

The notification service name must be unique for each notification service instance. You can specify this is in your configuration, by setting plugins:poa:root_name. The notification service uses named roots to support multiple instances.

In the following example, plugins:poa:root_name is set to IT_NotifyNamedRoot2 in the notify.notify2 configuration scope:

```
event{
    plugins:poa:root_name = "IT_NotifyNamedRoot";
    ...
    notify2
    {
        plugins:poa:root_name = "IT_NotifyNamedRoot2";
        };
}
```

notify stop

Synopsis notify stop

Description Stops the default notification service.

Multiple instances of the notification service are also supported. To stop a non-default notification service, specify the ORB name used to start the notification service (using the -ORBname parameter to itadmin).

To start the notification service, use the itnotify run command. You can also use the start_domain-name_services command. For more information, see "Starting Orbix Services" on page 233.

Examples The following command stops the default notification service:

itadmin notify stop

The following command stops a notification service that was started with an ORB name of notify.notify2:

itadmin -ORBname notify.notify2 notify stop

Event Channel

The following commands enable you to manage a notification service's event channel:

Table 30: Event Channel Commands

nc create	Creates an untyped event channel with the specified name.
nc list	Displays all untyped event channels managed by the notification service.
nc remove	Removes the specified untyped event channel.
nc show	Displays all attributes of the specified untyped event channel.
nc set_qos	Specifies qualities of service for the specified event channel.

nc create

Synopsis

nc create -event_reliability -connection_reliability *channel-name* Creates an untyped event channel, in the default notification service, with the specified name.

Arguments

-event_reliability

Specifies the level of guarantee given on the delivery of individual events. Possible values are best_effort or persistent.

-connection_reliability

Specifies the level of guarantee given on the persistence of a clients connection to its notification channel. Possible values are best_effort or persistent.

Examples

The following command creates an untyped event channel named my_channel:

```
itadmin nc create -event_reliability persistent
-connection_reliability persistent my_channel
```

The following command creates an untyped event channel named my_channel2 in the notify.notify2 notification service:

```
itadmin -ORBname notify.notify2 nc create -event_reliability
   persistent -connection_reliability persistent my_channel2
```

The event reliability and connection reliability must be set at the time of creation. When these values are set, they cannot be changed.

nc list

Synopsis

nc list -count

Description

Displays all the untyped event channels managed by the notification service.

To display the total number of untyped event channels, specify the -count argument. No value argument is required.

Examples

The following command displays the untyped event channels managed by a default notification service:

itadmin nc list

my_channel mkt_channel eng_channel The following command displays the untyped event channels managed by a non-default notification service:

itadmin -ORBname notify.notify2 nc list

my_channel my_channel2 mkt_channel eng_channel

The following command displays the number of untyped event channels managed by a notification service:

itadmin nc list -count 3

nc remove

Synopsis nc remove channel-name

Description Removes the specified untyped event channel.

Examples The following command removes an untyped event channel named my_channel:

```
itadmin nc remove my_channel
```

The following command removes an untyped event channel (from a non-default notification service) named my_channel2:

itadmin -ORBname notify.notify2 nc remove my_channel2

nc show

Synopsis nc show channel-name

Description Displays all attributes of the specified untyped event channel.

Examples The following command displays all the attributes of an event channel named my_channel:

itadmin nc show my_channel Channel Name: my_channel

Channel ID: 1

Event Communication: Untyped

The following command displays the attributes of an event channel (from a non-default notification service) named my channel 2:

itadmin -ORBname notify.notify2 nc show my_channel2

Channel Name: my_channel2

Channel ID: 2

Event Communication: Untyped

Note: For information about notification service configuration variables, see the section discussing the plugins:notification namespace in the *Orbix Configuration Reference*.

nc set_qos

Synopsis

nc set_qos

[-priority] [-order_policy] [-discard_policy]
[-start_time_supported] [-stop_time_supported]
[-max_events_per_consumer] [-max_batch_size] [-max_retries]
[-pacing_interval] [-timeout] [-pull_interval] [-retry_timeout]
[-max_retry_timeout] [-request_timeout] [-retry_multiplier]
channel name

Specifies various qualities of service (QoS) for the specified event channel name. Values of existing QoS properties can be changed, and new QoS properties can be added. All set_qos arguments are optional.

Arguments

-priority

Specifies the order that events are delivered to a consumer whose -order_policy is set to priority_order. It also affects the order that events are dequeued for consumers whose -discard_policy is set to priority_order.

The -priority indicates the relative priority of the event compared to other events in the channel. Values can be in the range of -32,767 and 32,767. Higher priority events are delivered before lower. The default is 0.

-order_policy Specifies the order to queue events for delivery.

Possible values are:

any_order fifo_order priority_order deadline_order

-discard_policy Specifies the order that events are discarded

when -max events per consumer has been

reached. Possible values are:

any_order fifo_order priority_order deadline_order

-start_time_supported Specifies whether start time is supported. This is

an absolute time (e.g., 20/12/04 at 11:15) that determines the earliest time a channel can deliver the event. If set to true, the event is held until the

specified time is reached.

-stop_time_supported Specifies whether stop time is supported. This is

an absolute time (e.g., 20/12/04 at 11:15) that determines the latest time a channel can deliver the event. If set to true, events later than the

specified stop time are not sent.

-max_events_per_consumer Specifies the maximum number of events that a

channel queues for a consumer before it starts discarding them. Events are discarded in the order specified by <code>-discard_policy</code>. A setting of 0 specifies the channel to queue an unlimited

number of events.

-max_batch_size Specifies the maximum number of structured

events sent in a sequence to consumers.

-max_retries Specifies the maximum number of times that a

proxy push supplier calls push() on its

consumer before it gives up. The default value is 0, which means an infinite number of retries.

-pacing_interval Specifies the maximum amount of time that a

channel is given to assemble structured events in a sequence, before delivering the sequence to

consumers.

The default value is 0, which specifies an

unlimited time.

-timeout Specifies how long an event remains viable after

the channel receives it. After the -timeout value expires, the event is discarded. The default is 0, which means that events have an infinite lifetime.

-pull_interval Specifies how much time elapses between

attempts by a proxy pull consumer to call pull() or try_pull() on its supplier. The default value

is 1 second.

-retry_timeout Specifies how much time elapses between

attempts by a proxy push supplier to call push()

on its consumer. The default is 1 second.

-max_retry_timeout Specifies the ceiling for -retry_timeout. This

applies to timeouts directly assigned by developers as well as values reached by the multiplication of -retry_multiplier and-retry_timeout. The default value is 60

seconds.

-request_timeout Specifies how much time is permitted to a

channel object to perform an operation on a

client.

If the operation does not return within the specified limit, the operation throws a

CORBA::TRANSIENT system exception.

-retry_multiplier Specifies the number by which the current value

of -retry timeout is multiplied to determine

the next -retry_timeout value. The

-retry_multiplier value is applied until either

the ${\tt push}$ () is ${\tt successful}$ or ${\tt -max_retry_timeout}$

is reached. The default value is 1.0. $\,$

Examples

The following simple example sets the order and discard policies for an event channel named my_channel:

```
itadmin nc set_qos -order_policy fifo_order -discard_policy
fifo_order my_channel
```

The following example sets the order policy and the priority for an event channel named sales_channel.

```
itadmin nc set_qos -order_policy priority_order sales_channel
itadmin nc set_qos -priority 3 sales_channel
```

The following enables start time for an event channel named production_channel:

itadmin nc set_qos -start_time_supported true production_channel

Object Transaction Service

Overview

itadmin supports the object transaction service (OTS). Using itadmin commands in transactional mode ensures consistency and reliability in a distributed environment.

With itadmin, you can start, commit, rollback, suspend, and resume transactions. This lets you use other itadmin commands in transactional mode—for example, process create, or orbname modify.

A service can have several readers but only one writer. A transaction takes the writer thread. So, if you start a transaction in a service and then do not commit, roll back, or suspend the transaction, the service blocks until the timeout period expires (30 seconds). The transaction is then rolled back.

Similarly, if a transaction involving a service and the client (itadmin in this case) is terminated, the service is unaware of this and must be terminated.

You can manage transactions with the following itadmin commands:

Table 31: Object Transaction Service Commands

tx begin	Starts a transaction.
tx commit	Commits a transaction.
tx resume	Resumes a transaction.
tx rollback	Rolls back a transaction.
tx suspend	Suspends a transaction.

tx begin

Synopsis

Description

tx begin

Starts a transaction. To use itadmin commands in a transaction, call tx begin followed by the other itadmin commands you wish to execute (for example, orbname create).

You must finalize the execution of these commands, using tx commit, or undo them, using tx rollback.

Examples

The following example starts a transaction, and then creates an ORB name:

itadmin
% tx begin
% orbname create MutualFunds.Tracking.GroInc.Stocks

tx commit

Synopsis tx commit

DescriptionCommits a transaction. The commands executed after the transaction started using tx begin are finalized.

Examples

The following example commits the transaction:

```
itadmin
% tx begin
% orbname create MutualFunds.Tracking.GroInc.Stocks
% tx commit
```

tx resume

Synopsis tx resume

Description

Resumes a suspended transaction. Commands that occur after tx resume are part of the context of the transaction and are committed or rolled back at the conclusion of the transaction.

Examples

The following example resumes the transaction:

```
itadmin
% tx begin
% orbname create MutualFunds.Tracking.GroInc.Stocks
% tx suspend
% tx resume
```

Note: You can not use more than one transaction at a time. You can not begin a transaction, suspend it and then begin another transaction. The tx suspend command should be only used to do non-transactional work before a subsequent tx resume command.

tx rollback

Synopsis tx rollback

Description Rolls back a transaction. The effects of commands executed after the transaction

started using tx begin are undone.

Examples The following example rolls back the transaction:

itadmin

% tx begin

% orbname create MutualFunds.Tracking.GroInc.Stocks

% tx rollback

tx suspend

Synopsis tx suspend

Description Suspends a transaction. Commands that occur between tx suspend and tx resume

are not part of the transaction, and are not committed or rolled back at the end of

the transaction.

Examples The following example suspends the transaction:

itadmin

% tx begin

% orbname create MutualFunds.Tracking.GroInc.Stocks

% tx suspend

CHAPTER 27 | Object Transaction Service

Object Transaction Service Encina

Overview

A subset of itadmin commands support the object transaction service (OTS) Encina plug-in.

In order to support the two-phase commit (2PC) protocol, an Encina OTS server needs a medium to log information about transactions—for example, IORs of the resources participating in a transaction. This medium is the *transaction log*, a logical entity consisting of or mirrored by one or more (physical) Encina volumes. Each volume in turn consists of one or more files or raw disks, which are said to back up the volume. Each of these volumes, or *mirrors*, contain the same information. This ensures recovery in case of failure of a machine that hosts some or all of a volume's constituent files/raw disks.

Transaction logs contain metadata, such as number and location of files or raw disks backing up the physical volumes that mirror the transaction log. Two files maintain this information:

- Restart file identifies an initialized transaction log.
- Backup restart file provides a backup to the restart file in case it is lost or corrupted by hardware failure.

For full information about two-phase commit and the Encina plug-in, see the CORBA OTS Guide.

You can manage the OTS Encina plug-in with the following itadmin commands:

encinalog add	Adds a file/raw disk to the list of files/raw disks backing up a physical volume of an Encina transaction log.
encinalog add_mirror	Creates a new physical volume and adds this to the list of volumes mirroring an Encina transaction log.
encinalog create	Creates a file for use in a transaction log—that is, a file that can be used to back up a physical volume mirroring an Encina transaction log.
encinalog display	Displays information about the physical volumes of an Encina transaction log.
encinalog expand	Expands an Encina transaction log.

encinalog init Initializes an Encina transaction log, thereby creating

restart and backup restart files.

encinalog Removes a physical volume from an Encina transaction

remove_mirror lo

otstm stop Stops the otstm service.

Note: The commands described in this chapter assume the use of the itadmin command shell unless stated otherwise.

encinalog add

Synopsis

encinalog add -restart restart-file [-backup backup-file] [-vol
vol-spec] [-silent] file-spec

Description

Adds a file/raw disk to the list of files/raw disks that back up the physical volume vol-spec, thereby increasing the total size of this volume.

If you omit the -vol argument, the file/raw disk is added to the list of files/raw disks backing up volume logVol_physicalVol1.

Arguments

-restart restart-file Identifies the target transaction log.

-backup backup-file Optionally identifies the target transaction log. If no

backup restart file is specified, the default path is

derived from restart-file.bak.

-vol vol-spec Specifies a physical volume other than the default

one.

-silent Suppresses the display of the completion status.

file-spec The path to an existing file (created with encinalog

create) or raw disk.

Examples

The following example adds the file ots2.log to the physical volume logVol_physicalVol2 which mirrors the transaction log identified by restart file ots.restart and backup restart file ots.backup:

itadmin encinalog add -restart ots.restart -backup ots.backup vol logVol_physicalVol2 ots2.log

Note: Use the encinalog display command to list the named of the individual physical volumes mirroring the transaction log.

encinalog add_mirror

Synopsis encinalog add_mirror -restart restart-file -backup backup-file

[-silent] file-spec

Description Creates a physical volume backed up by file-spec, and adds it to the list of

physical volumes mirroring the transaction log.

The new physical volume is named logVol_physicalVoln, where n is the lowest number for which there is no physical volume mirroring the transaction

log.

Arguments

-restart Identifies the target transaction log.

restart-file

-backup Optionally identifies the target transaction log. If no

backup-file backup restart file is specified, the default path is derived

from restart-file.bak.

-silent Suppresses the display of the completion status.

file-spec The path name of a file or raw disk created with encinalog

create.

Examples The following example adds a physical volume backed up by file otsmirror.log

to the to the list of volumes mirroring the transaction log identified by restart file

ots.restart and backup restart file ots.backup:

itadmin encinalog add_mirror -restart ots.restart -backup

ots.backup otsmirror.log

encinalog create

Synopsis encinalog create [-size-type file-size] [-replace] [-silent]

file-spec

Description Creates a file, file-spec, which can be used to back up a physical volume of an

Encina transaction log. The default size is 4 megabytes.

Arguments

-size-type file-size Specifies a non-default size, where -size-type is one of the following literals:

- -msize specifies the size in megabytes.
- -ksize specifies the size in kilobytes.
- -size specifies the size in bytes.

The minimum size is 1 megabyte; the maximum size is 16 megabytes.

-replace

Overwrites an existing file.

-silent

Suppresses the display of the completion status.

Examples

The following example creates a file of size 2 megabytes and overwrites an existing file of the same name:

itadmin encinalog create -msize 2 -replace ots.log

encinalog display

Synopsis

encinalog display -restart restart-file [-backup backup-file]

Description

Displays information on the physical volumes mirroring the transaction log.

Arguments

-restart restart-file Identifies the target transaction log.

-backup

backup-file

Optionally identifies the target transaction log. If no backup restart file is specified, the default path is derived

from restart-file.bak.

Examples

The following example displays information on the physical volumes of a transaction log identified by ots.restart and the backup restart file ots.backup:

itadmin encinalog display -restart ots.restart -backup ots.backup

Logical Volume: logVol Free Pages: 960 Total Number of Pages: 1016

Physical Volume: logVol_physicalVol1 File Name: /tmp/ots.log Physical Volume: logVol_physicalVol2 File Name: /tmp/otsmirror.log

encinalog expand

Synopsis

encinalog expand -restart restart-file [-backup backup-file] [-silent]

Description

Expands the transaction log to its maximum size, which is the minimum of the individual physical volume sizes. These, in turn, are the accumulated sizes of the files/raw disks backing up the individual physical volumes. The operation is necessary after the size of all physical volumes has been increased by adding files/raw disks to the volumes.

Arguments

-restart Identifies the transaction log to expand

restart-file

-backup Optionally identifies the transaction log to expand. If no backup-file

backup restart file is specified, the default path is derived

from restart-file.bak.

-silent Suppresses the display of the completion status.

Examples

The following example expands the logical volume associated with ots.restart and the backup restart file ots.backup:

itadmin encinalog expand -restart ots.restart -mirror ots.backup

encinalog init

Synopsis encinalog init [-replace] [-restart restart-file] [-backup

backup-file] [-silent] file-spec

Description Initializes an Encina transaction log, mirrored by one physical volume

logVol_physicalVol1, and backed up by the file/raw disk file-spec.

The command also creates restart and backup files. You can explicitly name these files; otherwise, the default restart file and backup restart file names are

file-spec_restart and file-spec_restart.bak, respectively.

Arguments

-restart Specifies the restart file name.

restart-file

-backup Optionally identifies the transaction log to initialize. If no

backup-file backup restart file is specified, the default path is derived

from restart-file.bak.

-replace Overwrites the existing restart files.

-silent Suppresses the display of the completion status.

Examples The following example initializes a transaction log using alternative names for

the restart and backup restart files:

itadmin encinalog init -restart ots.restart -backup ots.backup
 ots.log

encinalog remove_mirror

Synopsis encinalog remove_mirror -restart restart-file [-backup

backup-file] [-silent] vol-spec

Description Removes the physical volume *vol-spec* from the list of volumes mirroring the

transaction log.

Arguments

-restart Identifies the target transaction log.

restart-file

-backup Optionally identifies the target transaction log. If no backup-file

backup restart file is specified, the default path is derived

from restart-file.bak.

-silent Suppresses the display of the completion status.

The following example removes the physical volume logVol_physicalVol1 from the transaction log identified by ots.restart and backup restart file ots.backup:

itadmin encinalog remove mirror -restart ots.restart -backup ots.backup logVol_physicalVol1

Note: See encinalog init and encinalog add_mirror for the possible names of a physical volume, or use the encinalog display command to get the names of the physical volumes mirroring a transaction log. Because a transaction log needs at least one mirror, remove_mirror will not allow you to remove a physical volume if it is the only volume.

otstm stop

Examples

Synopsis otstm stop

Description Stops the otstm service. CHAPTER 28 | Object Transaction Service Encina

Persistent State Service

Overview

A subset of itadmin commands let you manage the persistent state service (PSS). PSS is a CORBA service for building CORBA servers that access persistent data and include transactional support. PSS is for use with C++ applications only. For more details about PSS, see the *CORBA Programmer's Guide*.

You can manage a PSS database using the following commands:

 Table 32: Persistent State Service Commands

pss_db archive_old_logs	Archives old log files for the specified IOR.
pss_db checkpoint	Performs checkpoint operations on the database referenced in the specified file.
pss_db delete_old_logs	Deletes old log files for specified IOR.
pss_db list_replicas	Lists the replicas for the specified IOR.
pss_db name	Returns the name of the object reference to the database.
pss_db post_backup	Performs post-backup operations on the database referenced in the specified file.
pss_db pre_backup	Performs pre-backup operations on the database referenced in the specified file.
pss_db remove_replica	Removes a replica from the database's replica group.
pss_db show	Returns replication related information for the specified IOR.

pss_db archive_old_logs

Synopsis

pss_db archive_old_logs IOR-file

Description

Archives old log files for the specified IOR. The IOR-file argument specifies the full pathname to the file that contains the object reference.

pss_db checkpoint

Synopsis

pss_db checkpoint IOR-file

Description

Performs checkpoint operations on the database referenced in the file. The *IOR-file* argument specifies the full pathname to the file that contains the object reference.

When using transactions, Berkeley DB maintains transaction log files. Each time a transaction commits, data is appended to the transaction log files, and the database files are not modified. Data in transaction log files is then transferred periodically to the database files. This transfer is called a *checkpoint*. You can specify the checkpoint interval, using the following configuration variable:

plugins:pss_db:envs:env_name:checkpoint_interval

For example, plugins:pss_db:envs:locator:checkpoint_interval.

The checkpoint operation performs a Berkeley DB checkpoint. The following configuration variable specifies whether to delete the old log files, or move them to another directory:

plugins:pss_db:envs:env_name:checkpoint_deletes_old_logs

The following configuration variable specifies the directory to which log files should be moved:

plugins:pss_db:envs:env_name:old_log_dir

For more details on these configuration variables, see the section discussing the plugins:pss_db namespace in the *Orbix Configuration Reference*.

pss_db delete_old_logs

Synopsis pss_db delete_old_logs IOR-file

Description Deletes old log files for specified IOR. The IOR-file argument specifies the full

pathname to the file that contains the object reference.

pss_db list_replicas

Synopsis pss_db list_replicas [-active] IOR-file

Returns the names of all replicas for the database specified in the file containing

the object reference.

Arguments

-active List only active replicas.

IOR-file Specifies the full pathname to file that contains the

object reference.

pss_db name

Synopsis pss_db name IOR-file

Description Returns the name of the object reference to the persistent state database.

The IOR-file argument specifies the full pathname to the file that contains the

object reference.

pss_db post_backup

Synopsis pss_db post_backup IOR-file

Description Performs post-backup operations on the database referenced in the file. The

IOR-file argument specifies the full pathname to the file that contains the object

reference.

When backing up data files, it is important that no checkpoint occurs during the backup. The pre-backup operations force a checkpoint and then suspend checkpointing. The post-backup operations resume checkpointing.

pss_db pre_backup

Synopsis

pss_db pre_backup IOR-file

Description

Performs pre-backup operations on the database referenced in the file. The *IOR-file* argument specifies the full pathname to file that contains the object reference.

When backing up data files, it is important that no checkpoint occurs during the backup. The pre-backup operations force a checkpoint and then suspend checkpointing. The post-backup operations resume checkpointing.

pss_db remove_replica

Synopsis

pss_db remove_replica [-iorfile IOR-file] [-envhome env-dir]
replica-name

Description

Removes the replica specified replica-name from the replica group. The -iorfile or envhome argument must be specified, depending on whether the service containing the database is running or not.

The remove_replica command should only be used when removing a service's replica. See the *Orbix Deployment Guide* for more details.

Arguments

-iorfile Specifies the path to the file containing the databases

reference. This argument is used to remove a replica

when the replica group is running.

-envhome

Specifies the path to the database root directory. This argument is used when the service containing the database is not running. It only removes the replica

from the local database.

pss_db show

Synopsis

pss_db show IOR-file

Description

Returns information about the specified database. This includes:

- database name
- whether the database is replicated
- database replica name
- whether the database is a master or slave.

The ${\it IOR-file}$ argument specifies the full pathname to file that contains the object reference.

CHAPTER 29 | Persistent State Service

Security Service

Overview

The itadmin tool supports security commands to administer the key distribution management (KDM) database, which is part of SSL/TLS for CORBA. The KDM is a security feature that enables automatic activation of secure Orbix servers—see the *CORBA SSL/TLS Guide* for details.

Key distribution management

Key distribution management (KDM) is a mechanism that distributes pass phrases to a secure server during automatic activation. Without the KDM, it is impossible to activate a secure server automatically because pass phrases must be supplied manually when the server starts up.

The KDM also protects a server's implementation repository (IMR) entry from unauthorized tampering. Whenever a *process IMR entry* is updated, the KDM requires a security checksum to be generated (using the checksum create command). The process IMR entry is the part of an IMR record that stores the server executable location. Before activating a secure server, the KDM checks that the stored checksum matches the current checksum for the process IMR entry.

The KDM framework consists of the following elements:

- A KDM server provides security attributes to the locator on request.
- A *KDM database* is used by the KDM server to store security attributes.
- A KDM administration plug-in provides the security commands described in this section and communicates directly with the KDM server. SSL/TLS installs a secure KDM administration plug-in the itadmin utility.

KDM database

The KDM database stores the following kinds of security attributes:

- Pass phrases are associated with an ORB name and stored as a security attribute in the KDM database. The pass phrases are supplied to a secure server during automatic activation.
- Checksums are associated with a process name and stored as a security attribute in the KDM database. The checksum is tested against the current process IMR record before a server is automatically activated.

The process IMR record used by the checksum algorithm includes all of the fields associated with the itadmin process command except the process description.

The security commands are mainly concerned with managing the entries in the KDM database—creating, updating, and removing security attributes.

All of these commands require a secure connection to the KDM database. It is therefore necessary to log on to the KDM server, using admin_logon, prior to issuing any of the security commands.

Commands

itadmin commands let you manage the following security service activities:

Logging On	page 375
Managing Checksum Entries	page 376
Managing Pass Phrases	page 379

Logging On

Overview

You log on to the KDM server with the itadmin admin logon command.

admin_logon

Synopsis

admin_logon login [-password pass-phrase] identity

Description

Logs an administrator on to the KDM server. This command must be issued prior to any of the other secure commands (kdm_adm or checksum).

Arguments

login

This argument specifies the name of an X.509 certificate that

identifies the administrator.

The *identity* parameter specifies the name of a PKCS#12 certificate file, *identity*.p12, located in the directory specified by the itadmin_x509_cert_root configuration variable.

-password

This argument lets you specify the pass phrase for the *identity*.p12 certificate on the same line as the command,

instead of being prompted for it.

This argument is provided for scripting in a development

environment and should not be used in a live system.

Examples

To log on to the KDM server, before issuing any secure commands, enter the following at the command line:

itadmin

% admin_logon login my_admin_id

Please enter password for identity my_admin_id:

The Enter password prompt lets you enter the pass phrase for the my_admin_id.p12 certificate without echoing to the screen.

Managing Checksum Entries

Overview

The following itadmin commands let you manage checksum entries:

 Table 33:
 Checksum Entry Commands

checksum confirm	Confirms that the process IMR entry for the specified process has not been changed since the checksum was created.
checksum create	Creates a checksum for the specified process IMR entry and store the checksum in the KDM database.
checksum list	Lists process names that have security checksum information in the KDM database.
checksum remove	Removes a security checksum entry from the KDM database.

checksum confirm

Synopsis checksum confirm -process process-name

Description Confirms that the process IMR entry for *process-name* has not been modified

since the checksum entry in the KDM database was created.

Arguments

-process Specifies the name, process-name, of a process IMR entry.

Examples

To confirm that the checksum previously stored for the $my_process_name$ process agrees with the checksum for the current $my_process_name$ IMR entry, enter the following at the command line:

```
itadmin
% admin_logon login my_admin_id
Please enter password for identity my_admin_id:
% checksum confirm -process my_process_name
The checksum is valid.
%
```

checksum create

Synopsis checksum create -process process-name

Description Creates a checksum entry in the KDM database for the process process-name.

The checksum must be recreated whenever the process IMR entry for the specified

process is modified.

Arguments

-process Specifies the name, *process-name*, of a process IMR entry.

Examples

To create a checksum entry in the KDM database for my_process_name, enter the following at the command line:

```
itadmin
% admin_logon login my_admin_id
Please enter password for identity my_admin_id:
% checksum create -process my_process_name
%
```

checksum list

Synopsis checksum list [-count]

Description Lists the names of all processes that have checksum entries in the KDM database.

Arguments

-count Returns a count of the number of checksum entries, instead of listing them.

Examples

To list all process names with checksum entries in the KDM database, enter the following at the command line:

```
itadmin
% admin_logon login my_admin_id
Please enter password for identity my_admin_id:
% checksum list
simple_process
%
```

checksum new_pw

Synopsis checksum new_pw

Description Password protects the checksum entry in the KDM database.

checksum remove

Synopsis checksum remove -process process-name

Description Removes the checksum entry associated with the *process-name* process name

from the KDM database.

Arguments

-process Specifies the name, process-name, of a process IMR entry.

Examples

To remove the checksum entry associated with $my_process_name$ from the KDM database, enter the following at the command line:

```
itadmin
% admin_logon login my_admin_id
Please enter password for identity my_admin_id:
% checksum remove -process my_process_name
Security checksum associated with process my_process_name has been removed.
%
```

Managing Pass Phrases

Overview

The following itadmin commands let you manage pass phrases:

Table 34: Pass Phrase Commands

kdm_adm change_pw	Changes the pass phrase for encrypting the KDM database.
kdm_adm confirm	Confirms that the pass phrase associated with the specified ORB name has the value you expect.
kdm_adm create	Creates an entry in the KDM database that associates a pass phrase with the specified ORB name.
kdm_adm list	Lists the ORB names that have pass phrase information in the KDM database.
kdm_adm new_pw	Creates a new pass phrase for encrypting the KDM database.
kdm_adm remove	Removes an entry from the KDM database associated with the specified ORB name.

kdm_adm change_pw

Synopsis

kdm_adm change_pw

Description

Changes the pass phrase used to encrypt the KDM database. The command prompts you for the current pass phrase and then prompts you twice for the new pass phrase (to ensure it was entered correctly).

Examples

To change the KDM database pass phrase, enter the following at the command line:

```
itadmin
% admin_logon login my_admin_id
Please enter password for identity my_admin_id:
% kdm_adm change_pw
Please enter the current KDM password:
Please enter the new KDM password:
Please confirm the new KDM password:
%
```

After entering the admin_logon command, you are prompted for the my_admin_id.p12 certificate pass phrase.

After entering the kdm_adm change_pw command, you are prompted three times for pass phrases. In response to the first Enter password prompt, enter the current KDM database pass phrase. In response to the second and third Enter password prompts, enter the new KDM database pass phrase.

kdm_adm confirm

Synopsis

kdm adm confirm -orbname ORB-name

Description

Confirms the pass phrase associated with the specified ORB name, ORB-name. The command prompts you for the pass phrase associated with ORB-name and tells you whether or not you entered the correct pass phrase.

Examples

To confirm the pass phrase associated with the my_orb_name ORB name, enter the following at the command line:

```
itadmin
% admin_logon login my_admin_id
Please enter password for identity my_admin_id:
% kdm_adm confirm -orbname my_orb_name
Please enter password for orb my_orb_name :
The password is correct.
%
```

kdm_adm create

Synopsis

kdm_adm create -orbname ORB-name [-password pass-phrase]

Description

Creates an entry in the KDM database to associate a pass phrase with the specified ORB name, <code>ORB-name</code>. Just one pass phrase can be associated with an ORB name. If the <code>-password</code> argument is omitted, the command prompts you for a pass phrase which is not echoed to the screen.

Arguments

-orbname Specifies the ORB name, ORB-name, with which the new pass

phrase is associated.

-password Lets you specify a new pass phrase. This argument is provided for

scripting purposes during development and should not be used in

a live system.

Examples

To associate a pass phrase with the my_orb_name ORB name and store the association in the KDM database, enter the following at the command line:

itadmin

% admin_logon login my_admin_id

Please enter password for identity my_admin_id:

% kdm_adm create -orbname my_orb_name

Please enter password for orb my_orb_name :

욹

kdm_adm list

Synopsis

kdm_adm list [-count]

Lists all ORB names that have associated pass phrases stored in the KDM database.

Arguments

-count

Returns a count of the number of ORB name entries instead of listing them.

Examples

To list all ORB names that have associated pass phrases, enter the following at the command line:

```
itadmin
% admin_logon login my_admin_id
Please enter password for identity my_admin_id:
% kdm_adm list
my_orb_name
%
```

kdm_adm new_pw

Synopsis kdm_adm new_pw

Description Creates a new pass phrase for encrypting the KDM database.

kdm_adm remove

Synopsis kdm_adm remove -orbname ORB-name

DescriptionRemoves the security entry in the KDM database associated with the ORB-name ORB name.

ExamplesTo remove the security entry associated with the my_orb_name ORB name, enter the following at the command line:

itadmin

% admin logon login my admin id

Please enter password for identity my_admin_id:

% kdm_adm remove -orbname my_orb_name

Security attributes associated with orbname my_orb_n ame have been removed.

용

Trading Service

Overview

 $\verb|itadmin| provides a set of commands for managing the following trading service components:$

Trading Service Administrative Settings	page 384
Federation Links	page 389
Regular Offers	page 393
Proxy Offers	page 395
Type Repository	page 397

Trading Service Administrative Settings

Overview

The following commands let you mange trading service administrative settings:

Table 35: Trading Service Commands

trd_admin get	Displays administrative settings.
trd_admin set	Modifies administrative settings.
trd_admin stop	Stops the trading service.

trd_admin get

Synopsis trd_admin get arg

Description Displays administrative settings.

Arguments Supply one of the following arguments:

-request_id_stem	Displays the request id stem assigned to this instance of the trading service.
-def_search_card	Displays the default search cardinality-the default upper bound of offers to be searched.
-max_search_card	Displays the maximum search cardinality-maximum upper bound of offers to be searched.
-def_match_card	Displays the default match cardinality-default upper bound of matched offers to be ordered.
-max_match_card	Displays the maximum match cardinality-maximum upper bound of matched offers to be ordered.
-def_return_card	Displays the default return cardinality-default upper bound of ordered offers to be returned.
-max_return_card	Displays the maximum return cardinality-maximum upper bound of ordered offers to be returned.

-max_list	Displays the upper bound on the size of any list returned by the trading service, namely the returned offers parameter in query, and the next_n operations in OfferIterator and OfferIdIterator.
-modifiable_properties	Displays whether the trading service supports properties modification.
-dynamic_properties	Displays whether the trading service supports dynamic properties.
-proxy_offers	Displays whether the trading service supports proxy offers.
-def_hop_count	Displays the default hop count-default upper bound of depth of links to be traversed in a federated query.
-max_hop_count	Displays the maximum hop count-maximum upper bound of depth of links to be traversed in a federated query.
-def_follow_policy	Displays the default federation link follow policy.
-max_follow_policy	Displays the limiting link follow policy for all links of the trader. This setting overrides both link and importer policies.
-max_link_follow_policy	Displays the most permissive follow policy allowed when creating new links.
-type_repos	Displays the stringified IOR of the service type type repository.

Examples

```
>itadmin trd_admin get -type_repos
IOR:0000000000000036494....
> itadmin trd_admin get -proxy_offers
yes
>itadmin trd_admin get -def_follow_policy
always
>itadmin trd_admin get -max_list
2147483647
```

trd admin set

Synopsis trd_admin set arg

Description Modifies administrative settings.

Arguments Supply one of the following arguments:

-request_id_stem id_stem Modifies the request id stem of this instance

of the trading service.

-def_search_card value Modifies the default search cardinality-the

default upper bound of offers to be searched. The value must be a positive integer.

-max_search_card value Modifies the maximum search

cardinality-the maximum upper bound of offers to be searched. The value must be a

positive integer.

-def_match_card value Modifies the default match cardinality-the

default upper bound of matched offers to be ordered. The value must be a positive

integer.

-max_match_card value Modifies the maximum match

cardinality-the maximum upper bound of matched offers to be ordered. The value

must be a positive integer.

-def_return_card value Modifies the default return cardinality-the

default upper bound of ordered offers to be returned. The value must be a positive

integer.

-max_return_card value Modifies the maximum return

cardinality-the maximum upper bound of ordered offers to be returned. The value

must be a positive integer.

-max_list value Modifies the upper bound on the size of any

list returned by the trading service, namely the returned offers parameter in query, and the next_n operations in OfferIterator and OfferIdIterator. The value must be a

positive integer.

-modifiable properties Specifies whether to enable support of boolean-value modifiable properties. -dynamic properties Specifies whether to enable support of boolean-value dynamic properties. -proxy_offers boolean-value Specifies whether to enable support of proxy offers. -def hop count value Sets the default hop count-the default upper bound of depth of links to be traversed in a federated query. The value must be a positive integer. -max_hop_count Sets the maximum hop count-the maximum upper bound of depth of links to be traversed in a federated query. -def_follow_policy policy Sets the default federation link follow policy with one of the following values: local_only if no local alwavs -max_follow_policy policy Sets the limiting link follow policy for all links of the trader. This setting overrides both link and importer policies. Supply one of the following values: local_only if no local always -max_link_follow_policy Specifies the most permissive follow policy policy allowed when creating new links with one of the following values: local_only if_no_local always Sets the IOR, in string format, of the service -type_repos IOR

type repository.

Examples

>itadmin trd_admin set -def_search_card 12
def_search_card set to 12

trd_admin stop

Stops the trading service.

Federation Links

Overview

The following commands let you mange federation links:

 Table 36:
 Federation Link Commands

trd_link create	Creates a federation link.
trd_link list	Lists all federation links.
trd_link modify	Modifies a federation link.
trd_link remove	Removes a federation link.
trd_link show	Displays the details on a federation link.

trd link create

Synopsis

trd_link create

-target IOR

-def_pass_on_follow_rule rule

-limiting_follow_rule rule

link-name

Description

Creates a federation link.

Arguments

-target IOR

Defines the trading service instance the link points to. An IOR to a CosTrading: :Lookup interface is expected.

-def_pass_on_follow_rule rule

Defines default link-follow behavior to pass on for a particular link, if an importer does not specify its link_follow_rule; it must not exceed limiting_follow_rule. Supply one of the following values for rule:

- local_only
- if_no_local
- always

-limiting_follow_rule rule Defines limiting link follow behavior for a particular link. Supply one of the following values for rule:

- local_only
- if_no_local
- always

link-name

A string that uniquely identifies the new link in the trading service instance.

Examples

>itadmin trd link create -target 'cat ./trader B lookup.ior' -def_pass_on_follow_rule always -limiting_follow_rule always Link_to_Trader_B

created link Link_to_Trader_B

trd_link list

Synopsis trd link list

Description Lists names of all federation links in the trading service instance.

Examples

>itadmin trd link list

Link_to_Trader_B

trd_link modify

Synopsis trd_link modify

> -def_pass_on_follow_rule rule -limiting_follow_rule rule

link-name

Description Modifies an existing federation link.

Arguments

nıle

-def_pass_on_follow_rule Defines the default link-follow behavior to be passed on for a particular link if an importer does not specify its link_follow_rule; it must not exceed limiting_follow_rule. Supply one of the following values for rule:

- local_only
- if no local
- always
- -limiting_follow_rule ruleDefines limiting link follow behavior for a particular link. Supply one of the following values for rule:
 - local_only
 - if_no_local
 - always

link-name

A string that uniquely identifies the new link in the trading service instance.

Examples

>itadmin trd_link modify -def_pass_on_follow_rule if_no_local -limiting_follow_rule always Link_to_Trader_B

modified link Link to Trader B

trd link remove

Synopsis

trd link remove link-name

Description

Removes the specified federation link.

Arguments

link-name

A string that uniquely identifies the link to be removed from the trading service instance.

Examples

>itadmin trd_link remove Link_to_Trader_B

removed link Link_to_Trader_B

trd_link show

Synopsis trd_link show link-name

Description Displays details on the specified federation link.

Arguments

link-name A string that uniquely identifies the link whose details are to be

displayed.

Examples

>itadmin trd_link show Link_to_Trader_B

name:

Link_to_Trader_B

def_pass_on_follow_rule:

if_no_local

limiting_follow_rule:

always

target:

limiting_follow_rule:

IOR:000000000000002249...

Regular Offers

Overview

The following commands let you mange regular offers:

 Table 37:
 Regular Offer Commands

trd_offer list	Lists all regular offers.
trd_offer remove	Removes a regular offer.
trd_offer show	Displays details on a regular offer.

trd_offer list

Synopsis trd_offer list

Description Lists the offer IDs of all regular (non-proxy) offers.

Examples

>itadmin trd_offer list
Printer~1~0

trd_offer remove

Synopsis trd_offer remove offer-id

Description Removes (withdraws) the specified offer.

Arguments

offer-id Offer ID of an existing offer.

Examples

>itadmin trd_offer remove Printer~1~0

offer Printer~1~0 removed

trd_offer show

Synopsis trd_offer show offer-id

Description Displays details on the specified offer.

Arguments

offer-id Offer ID of an existing offer.

Examples

>itadmin trd_offer show Printer~1~0

offer id:

Printer~1~0

object:

IOR:00000000000000224...

service type:

Printer

properties:

boolean color TRUE long dpi 3200 short ppm 30

Proxy Offers

Overview

The following commands let you manage proxy offers:

Table 38: Proxy Offer Commands

trd_proxy list	Lists all proxy offers.
trd_proxy remove	Removes a proxy offer.
trd_proxy show	Displays details on a proxy offer.

trd_proxy list

Synopsis trd_proxy list

Description Lists the offer IDs of all proxy offers

Examples

>itadmin trd_proxy list
Printer~2~0

trd_proxy remove

Synopsis trd_proxy remove offer-id

Description Removes (withdraws) the specified proxy offer.

Arguments

offer-id Offer ID of an existing proxy offer

Examples

>itadmin trd_proxy remove Printer~2~0

proxy offer Printer~2~0 removed

trd_proxy show

Parameters trd_proxy show offer-id

Description Displays details on the specified proxy offer.

Arguments

offer ID of an existing proxy offer

Examples

```
>itadmin trd_proxy show Printer~2~0
offer id:
        Printer~2~0
service type:
        Printer
target:
        IOR:00000000000000224...
if match all:
        TRUE
constraint recipe:
        ppm > 20
policies to pass on:
        boolean bool_policy FALSE
properties:
        boolean color FALSE
        long dpi 3200
        short ppm 12
```

Type Repository

Overview

They following commands effect the server type repository:

Table 39: Server Type Repository Commands

trd_type list	Lists all service types in the service type repository.
trd_type mask	Masks a service type.
trd_type remove	Removes a service type from the service type repository.
trd_type show	Displays details on a given service type.
trd_type unmask	Unmasks a service type.

trd_type list

Synopsis trd_type list

Description Lists all service types in the service type repository.

Examples

>itadmin trd_type list

Printer

trd_type mask

Synopsis trd_type mask service-type-name

Description Masks a service type.

Examples

>itadmin trd_type mask Printer
service type Printer masked

trd_type remove

Synopsis trd_type remove service-type-name

Description Removes a service type from the service type repository.

Examples

>itadmin trd_type remove Printer
service type Printer removed

trd_type show

Synopsis trd_type show service-type-name

Description Displays details on a given service type.

Examples

>itadmin trd_type show Printer

name:

Printer

interface:

IDL:PrintServer:1.0

masked:

no

incarnation number:

{0,1}

super types:

none

properties:

mandatory read-only boolean color

mandatory long dpi

mandatory read-only short ppm

trd_type unmask

Synopsis trd_type unmask service-type-name

Description Unmasks a service type.

Examples

>itadmin trd_type unmask Printer
service type Printer unmasked

Part V

Appendices

In this part

This part contains the following:

Orbix Windows Services	page 403
Run Control Scripts for Unix Platforms	page 415
ORB Initialization Settings	page 435
Development Environment Variables	page 441
Debugging IOR Data	page 213

Orbix Windows Services

During configuration, Orbix services are installed as Windows services that start up automatically at system startup.

This appendix describes how you can manage Orbix services as Windows services, and offers solution to typical problems. These services include:

- Configuration repository
- Locator daemon
- Node daemon
- Naming service
- Interface repository
- Event and notification services
- JMS
- Object transaction service

In this appendix

This appendix discusses the following topics:

Managing Orbix Services on Windows	page 405
Orbix Windows Service Commands	page 406
Orbix Windows Service Accounts	page 409
Running Orbix Windows Services	page 411

Logging Orbix Windows Services	page 412
Uninstalling Orbix Windows Services	page 413
Troubleshooting Orbix/Windows Services	page 414

Managing Orbix Services on Windows

Overview

If you choose to install Orbix services as Windows services, you can use the control panel's **Services** dialog to start, pause, continue, and stop any of the installed services. Equivalent functionality is provided through Orbix commands (see "Orbix Windows Service Commands").

Note: To install and uninstall Orbix services as Windows services, you must execute the <u>install</u> and <u>uninstall</u> commands.

Identifying Orbix services as Windows services

Each installed Orbix service executable name has a Windows service name. This is a unique identifier for each service used by the Windows Service control manager. By default, a Windows service name has the following format:

IT ORB-name domain-name

Each service can create sub-keys under the following registry key:

HKEY_LOCAL_MACHINE/SYSTEM/CurrentControlSet/Services

A Windows service name is used internally and must be unique. A Windows display name is shown in the Services dialog only. By default, the Windows service name and display name are the same.

Orbix Windows Service Commands

Overview

You can manage Orbix services from the command-line. Service commands have the following syntax:

```
exec-name [ORB-arguments] [exec-arguments] Win-service-command
[Win-service-arguments]
```

ORB-arguments can be any of the ORB initialization parameters that are documented in Appendix C on page 435. In general, ORB-arguments is required only for the configuration repository. Because the configuration repository has its own domain, any service command that applies to the configuration repository must supply the -ORBname argument.

For example, the following command installs the configuration repository as a Windows service in the cfr-AcmeProducts configuration repository domain:

```
itconfig_rep -ORBname iona_services.config_rep -ORBdomain_name
    cfr-AcmeProducts install
```

You can execute the following commands on any Orbix Windows service:

continue
help
install
pause
prepare
query
rum
stop
uninstall

continue

Synopsis

executable-name continue

Description

Resumes execution of the background service from its paused state.

help

Synopsis executable-name help

Description Prints a description message for the specified service.

install

Synopsis executable-name install [-description=service-description]

Description

Installs the specified Orbix service as a Windows service. Because the Orbix configuration tool automatically installs the desired services as Windows services, you should rarely need to use this command to install a service manually.

The Windows service control manager starts installed Orbix services automatically during system startup. The install command specifies a Windows 32-bit service that runs in its own process.

Use the -description argument to change a display name for each service used by the Windows Service control manager. This leaves unchanged the internal service name used in the Windows registry key.

Note: In general, it is recommended that you always install Orbix Windows services by running the Orbix configuration tool.

pause

Synopsis executable-name pause

Description Pauses execution of the specified background service.

prepare

Synopsis executable-name prepare [-publish_to_file=name]

Description Prepares the specified Orbix service for running, creating databases and initial object references. Use the -publish_to_file argument to write object references to a specified file; otherwise, stdout is used. This command is implicitly

performed when Orbix is configured.

query

Synopsis executable-name query

Description For the specified service, outputs current status, configuration parameters, and

dependencies on other services.

run

Synopsis executable-name run -service

Description Runs the specified Orbix service as a Windows service. The specified service must

already be installed.

stop

Synopsis executable-name stop

Description Stops execution of the specified service. You must stop a service before you can

uninstall it.

uninstall

Synopsis executable-name uninstall -ORBname name

Description Uninstalls the specified Orbix service as a Windows service. You must specify an

ORB name. See "Uninstalling Orbix Windows Services" on page 413 for more

details.

Orbix Windows Service Accounts

Overview

By default, Orbix installs services on Windows under a LocalSystem account that has no interaction with the desktop. You can change the domain/user/passwd with the Windows service control manager.

To change this password, use the **Services** options in the Windows **Control Panel**. You can also enable interaction with the desktop for a LocalSystem account only. Figure 16 shows details displayed for the locator service on Windows 2000.




Figure 16: Locator Service Details

Setting service security

A service running under the LocalSystem account has no user account information associated with it. As a result, the service might have limited access to network resources. If this is not desired, use the **Services** options available in the Windows **Control Panel** to change the user/group and passwd for the service.

Orbix node daemons run under the LocalSystem account and activate other processes as the LocalSystem account. If this is not desired, use the **Services** options available in the Windows **Control Panel** to change the user/group and passwd for this service.

Running Orbix Windows Services

Overview

Before you can run an Orbix Windows service, the specified service must already be installed. You must supply the -service parameter to run as a Windows service.

When Orbix Windows services are installed, the order in which they must be run depends on whether your configuration domain is configuration repository-based or file-based.

Running in a configuration repository domain

When running Orbix Windows services in a configuration repository domain, run the services in the following order:

1. Configuration repository. For example:

itconfig_rep -ORBdomain_name cfr-AcmeProducts run -service

2. Locator daemon. For example:

itlocator run -service

3. Any other persistent service—interface repository, node daemon, naming service. For example:

itifr run -service

Running in a file-based domain

When running Orbix services as Windows services in a file-based domain, run Orbix services in the following order:

1. Locator daemon. For example:

itlocator run -service

Any other persistent service—interface repository, node daemon, naming service. For example:

itnode_daemon run -service

Logging Orbix Windows Services

Overview

In a configuration domain, logging is written to a file located in the same directory as the services, by default. By default, logging shows all informational messages, warnings, errors, and fatal errors.

The default log file name has the following format:

```
service-name.log.timestamp
```

For example, the locator's log file might have the following name:

```
locator.log.18012000
```

Setting user-defined logging

To change the logging output stream to a different file, set the following configuration variable in the configuration scope for each service:

```
plugins:local_log_stream:filename=filename
```

To add this variable to your configuration domain, use the itadmin variable create command. You must set this variable in the configuration scope for each service; for example, in the locator configuration scope:

```
itadmin variable create -scope iona_services.locator
  -type string -value "c:temp\it_locator.log"
  plugins:local_log_stream:filename
```

If your configuration domain is file based, you can manually add variables to your configuration file in the appropriate configuration scope. For example, to set logging for the node daemon, add the following in the node_daemon scope:

```
plugins:local_log_stream:filename="c:\temp\it_node_daemon.log";
```

See Chapter 13 on page 187 for more information on Orbix logging.

Uninstalling Orbix Windows Services

Overview

To cleanly remove any version of Orbix from your system, you should first uninstall all Orbix services from the Windows host.

In a configuration repository-based domain, complete the following procedure:

- Stop and uninstall all services while the configuration repository and locator daemon are still running.
- 2. Stop and uninstall the locator daemon.
- 3. Stop and uninstall the configuration repository.

Commands for uninstalling services

The following series of commands show how you should stop and uninstall Orbix Windows services:

```
itnode_daemon -ORBname iona_services.node_daemon.test stop
itnode_daemon -ORBname iona_services.node_daemon.test uninstall

itifr -ORBname iona_services.ifr.test stop
itifr -ORBname iona_services.ifr.test uninstall

itnaming -ORBname iona_services.naming.test stop
itnaming -ORBname iona_services.naming.test uninstall

itevent -ORBname iona_services.event.test stop
itevent -ORBname iona_services.event.test uninstall

itlocator -ORBname iona_services.locator.test stop
itlocator -ORBname iona_services.locator.test uninstall

itconfig_rep -ORBname iona_services.config_rep.test
    -ORBdomain_name cfr-AcmeProducts stop
itconfig_rep -ORBname iona_services.config_rep.test
    -ORBdomain_name cfr-AcmeProducts uninstall
```

Troubleshooting Orbix/Windows Services

The following sections describe several common problems related to Orbix/Windows services, and how to resolve them.

Handling log-off events in activated servers

A node daemon that is installed as a Windows service continues to run in the background after users log off. It also activates server processes under the LocalSystem account. In order to shield these processes from log-off events (CTRL_LOGOFF_EVENT), the activated processes must have control handlers; otherwise, the logoff causes them to shut down.

Configuring for slow service startup

Occasionally, Windows services might require extra time to restart after system reboot. This might be due to a slow system, or to recovery of service-related databases.

Two changes in the configuration can help resolve this problem:

 Reduce the value set for max_binding_iterations, as in the following example:

```
policies:binding_establishment:max_binding_iterations = "1";
```

 Increase the wait time for a service's pending operations (for example, start, pause, resume). The default wait time for all services is set to 900 seconds (15 minutes):

```
plugins:plugin-name:nt_service_pending_op_wait = "900";
```

Reset this variable for services, as necessary. For example, the following variable increases the locator's wait time to 20 minutes:

```
plugins:locator:nt_service_pending_op_wait = "1200";
```

Run Control Scripts for Unix Platforms

Orbix services can be configured to start when the operating system enters the default run level and to shut down when the operating system leaves the default run level.

Overview

This appendix provides details on how Orbix registers its services with the operating system for automated startup and shutdown. Procedures for disabling, enabling and removal of automated startup registration are also covered.

Sometimes UNIX system administrators choose to customize run levels and run control scripts of their operating systems. If your run levels are customized, the details in this appendix will help you manually register your Orbix services for automated startup and shutdown or to use run control scripts generated by Orbix as a starting point for customization.

Note: For reliable startup and shutdown of Orbix services, it is recommended that you install the Java runtime, the Orbix components, the license file, the domain configuration files, the service databases and the log files on locally mounted filesystems.

You must have root privileges to perform tasks described in this appendix.

Operating Systems

Follow the links below for details on your operating system:

Solaris	page 417
AIX	page 420
HP-UX	page 424
IRIX	page 428
Red Hat Linux	page 431

For additional details on run levels and run control scripts refer to your operating system's documentation.

Solaris

Run level

The default run level is 3; this includes all services from run level 2.

Run control scripts

For a domain, <domain>, the following run control scripts are generated:

```
/etc/init.d/itsvs_<domain>
/etc/rc0.d/K27itsvs_<domain> -> /etc/init.d/itsvs_<domain>
/etc/rc1.d/K27itsvs_<domain> -> /etc/init.d/itsvs_<domain>
/etc/rc2.d/S97itsvs_<domain> -> /etc/init.d/itsvs_<domain>
/etc/rcS.d/K27itsvs_<domain> -> /etc/init.d/itsvs_<domain>
```

/etc/init.d/itsvs_<domain> contains the following:

```
rval=0
case "$1" in
   'start')
if [ -x ${DOMAIN_START_SCRIPT} ]; then
         echo "Starting IONA Orbix services for domain ${DOMAIN}"
         ${DOMAIN_START_SCRIPT}
else
echo "ERROR: Failed to start IONA Orbix services for domain
   ${DOMAIN} - \
          domain start script ${DOMAIN_START_SCRIPT} does not
   exist or is not executable"
rva1=1
fi
   ;;
   'stop')
if [ -x ${DOMAIN_STOP_SCRIPT} ]; then
         echo "Stopping IONA Orbix services for domain ${DOMAIN}"
         ${DOMAIN_STOP_SCRIPT}
else
echo "ERROR: Failed to stop IONA Orbix services for domain
   ${DOMAIN} - \
         domain stop script ${DOMAIN_STOP_SCRIPT} does not exist
   or is not executable"
rval=1
fi
   ;;
   echo "IONA Orbix run control script for domain ${DOMAIN}"
echo "Usage: $0 { start | stop }"
  rval=1
   ;;
   esac
   exit $rval
```

Disabling automatic services

To temporarily disable automatic startup and shutdown for domain <domain>:

1. Stop <domain> services by running

```
> stop_<domain>_services
```

2. Rename the following symbolic links by prepending a _ to their names:

```
/etc/rc0.d/K27itsvs_<domain>
/etc/rc1.d/K27itsvs_<domain>
/etc/rc2.d/S97itsvs_<domain>
/etc/rcS.d/K27itsvs_<domain>
```

Enabling automatic service

To enable automatic startup and shutdown for <domain>:

 Rename the following symbolic links by removing leading _ from their names:

```
/etc/rc0.d/_K27itsvs_<domain>
/etc/rc1.d/_K27itsvs_<domain>
/etc/rc2.d/_S97itsvs_<domain>
/etc/rcS.d/_K27itsvs_<domain>
```

2. Start domain services by running:

```
> start_<domain>_services
```

Unregistering automatic services

To unregister automatic startup and shutdown for <domain>:

1. Stop <domain> services by running:

```
> stop_<domain>_services
```

2. Remove the following files:

```
/etc/rc0.d/K27itsvs_<domain>
/etc/rc1.d/K27itsvs_<domain>
/etc/rc2.d/S97itsvs_<domain>
/etc/rcS.d/K27itsvs_<domain>
/etc/init.d/itsvs_<domain>
```



Run level

The default run level is 2.

Actions

For a domain named <domain>, Orbix performs the following actions:

Makes an entry in /etc/inittab with /usr/sbin/mkitab:

 Creates a run control script /etc/rc.itsvs_<domain> that contains the following:

```
rval=0
case "$1" in
'start')
if [ -x ${DOMAIN_START_SCRIPT} ] ; then
echo "Starting IONA Orbix services for domain ${DOMAIN}"
${DOMAIN_START_SCRIPT}
echo " ERROR: Failed to start IONA Orbix services for domain
   ${DOMAIN} - \
                       domain start script
   ${DOMAIN_START_SCRIPT} does not exist or is not
   executable"
rval=1
fi
;;
if [ -x ${DOMAIN_STOP_SCRIPT} ] ; then
echo "Stopping IONA Orbix services for domain <domain>"
${DOMAIN_STOP_SCRIPT}
else
echo "Can not stop IONA Orbix servies for domain <domain> -
          domain stop script ${DOMAIN_STOP_SCRIPT} does not
  exist or is not executable"
rval=1
fi
;;
*)
echo "IONA Orbix run control script for domain ${DOMAIN}"
echo "Usage: $0 { start | stop }"
rval=1
;;
esac
exit $rval
```

 Creates /etc/rc.shutdown if it does not exist, and adds the following code:

Note: /etc/rc.shutdown *must* return 0, otherwise the AIX shutdown sequence is interrupted.

Disable automatic services

To temporarily disable automatic startup and shutdown for <domain>:

1. Stop domain services by running

```
> stop_<domain>_services
```

- 2. Comment out the itsvs_<domain>entry in /etc/inittab.
- Comment out the code between <IONA Orbix <domain> > and </IONA
 Orbix <domain> > tags in /etc/rc.shutdown.

Enable automatic services

To enable automatic startup and shutdown for <domain>:

- Uncomment the code between <IONA Orbix <domain> > and </IONA
 Orbix <domain> > tags in /etc/rc.shutdown.
- 2. Uncomment the itsvs_<domain> entry in /etc/inittab.
- 3. Start domain services by running

```
> start_<domain>_services
```

Unregister automatic services

To unregister automatic startup and shutdown for <domain>:

- 1. Remove the itsvs_<domain> entry from /etc/inittab by running
 - > rmitab itsvs_<domain>
- If <domain> is the only Orbix domain registered for automatic startup and shutdown, remove file /etc/rc.shutdown. Otherwise, remove the code between <IONA Orbix <domain> > and </IONA Orbix <domain> > tags in/etc/rc.shutdown.
- 3. Remove /etc/rc.itsvs_<domain>.

HP-UX

Run level

The default run level is 3. See the output of run control scripts for the last boot of the machine in /etc/rc.log. The previous boot log is in /etc/rc.log.old.

Run control scripts

For a domain, <domain>, the following files are generated:

```
/sbin/rc2.d/K270itsvs_<domain> -> /sbin/init.d/itsvs_<domain> /sbin/rc3.d/S970itsvs_<domain> -> /sbin/init.d/itsvs_<domain> /sbin/init.d/itsvs_<domain> /etc/rc.config.d/itsvs_<domain>
```

The contents of /sbin/init.d/itsvs_<domain> is as follows:

```
#!/bin/sh
          Copyright (c) 1993-2002 IONA Technologies PLC.
          All Rights Reserved
# <deployment-specific portion>
DOMAIN=boot
DOMAINS_ETC_DIR=/etc/opt/iona
DOMAINS_VAR_DIR=/var/opt/iona
# </deployment-specific portion>
DOMAIN_START_SCRIPT=
   ${DOMAINS_ETC_DIR}/bin/start_${DOMAIN}_services
DOMAIN_STOP_SCRIPT=
   ${DOMAINS_ETC_DIR}/bin/stop_${DOMAIN}_services
if [ -r /etc/rc.config.d/itsvs_ ${DOMAIN} ] ;
  then . /etc/rc.config.d/itsvs_${DOMAIN}
  echo "WARNING: /etc/rc.config.d/itsvs_${DOMAIN} configuration
   file is missing or is not readable"
fi
```

```
rval=0
case "$1" in
  'start_msg')
   echo "Starting IONA Orbix services for domain ${DOMAIN}"
  'stop msq')
   echo "Stopping IONA Orbix services for domain ${DOMAIN}"
  ;;
   'start')
if [ "ITSVS_${DOMAIN}" -eq 1 ]; then
  if [ -x ${DOMAIN_START_SCRIPT} ]; then
    echo "Starting IONA Orbix services for domain ${DOMAIN}"
   ${DOMAIN_START_SCRIPT}
   rval=4
  else
   echo "ERROR: Failed to start IONA Orbix services for domain
   ${DOMAIN} - \ domain start script ${DOMAIN_START_SCRIPT} does
   not exist or is not executable"
   rval=1
  fi
else
  # domain is disabled
  rval=2
fi
  ;;
  'stop')
if [ "ITSVS_${DOMAIN}" -eq 1 ]; then
 if [ -x ${DOMAIN_STOP_SCRIPT} ]; then
    echo "Stopping Orbix services for the ${DOMAIN} domain"
   ${DOMAIN_STOP_SCRIPT}
   rval=4
  else
   echo "ERROR: Failed to start IONA Orbix services for domain
   ${DOMAIN} - \ domain stop script ${DOMAIN_STOP_SCRIPT} does
   not exist or is not executable"
   rval=1
  fi
else
  # domain is disabled
 rval=2
fi
   ;;
```

```
*)
echo "IONA Orbix run control script for domain ${DOMAIN}"
echo "Usage: $0 { start | stop }"
rval=1
;;
esac
exit $rval
```

/etc/rc.config.d/itsvs_<domain> contains the following:

```
#
# Copyright (c) 1993-2002 IONA Technologies PLC.
# All Rights Reserved
#
# IONA Orbix services, domain <domain> configuration
# ITSVS_<DOMAIN>: set to 1 to enable Orbix services for domain <domain>
ITSVS_<DOMAIN>=1
```

Disable automatic services

To temporarily disable automatic startup and shutdown for <domain>:

1. Stop domain services by running

```
> stop_<domain>_services
```

2. Set ITSVS_<DOMAIN> to 0 in /etc/rc.config.d/itsvs_<domain>.

Enable automatic services

To enable automatic startup and shutdown for <domain>:

- 1. Set ITSVS_<DOMAIN> to 1 in /etc/rc.config.d/itsvs_<domain>.
- 2. Start domain services by running

```
> start_<domain>_services
```

Unregister automatic services

To unregister automatic startup and shutdown for *<domain>*:

1. Stop domain services by running

> stop_<domain>_services

2. Remove the following files:

/sbin/rc2.d/K270itsvs_<domain> /sbin/rc3.d/S970itsvs_<domain> /sbin/init.d/itsvs_<domain> /etc/rc.config.d/itsvs_<domain>

IRIX

Run level

The default run level is 2.

Run control scripts

For a domain, <domain>, the following files are generated:

```
/etc/init.d/itsvs_<domain>
/etc/r0.d/K27itsvs_<domain> -> /etc/init.d/itsvs_<domain>
/etc/r2.d/S97itsvs_<domain> -> /etc/init.d/itsvs_<domain>
/var/config/itsvs_<domain>
```

/etc/init.d/itsvs_<domain> contains the following:

```
#!/bin/sh
          Copyright (c) 1993-2002 IONA Technologies PLC.
          All Rights Reserved.
# <deployment-specific portion>
DOMAIN=boot
DOMAINS_ETC_DIR=/etc/opt/iona
DOMAINS_VAR_DIR=/var/opt/iona
# </deployment-specific portion>
DOMAIN_START_SCRIPT=
   ${DOMAINS_ETC_DIR}/bin/start_${DOMAIN}_services
DOMAIN_STOP_SCRIPT=
   ${DOMAINS_ETC_DIR}/bin/stop_${DOMAIN}_services
rval=0
if [ ! /sbin/chkconfig itsvs_${DOMAIN} ]; then
# domain is disabled
  exit $rval
fi
```

```
case "$1" in
   'start')
if [ -x ${DOMAIN_START_SCRIPT} ]; then
  echo "Starting Orbix services for domain ${DOMAIN}"
  ${DOMAIN START SCRIPT}
else
  echo "ERROR: Failed to start IONA Orbix services for domain
   ${DOMAIN} - "
 echo "domain start script ${DOMAIN START SCRIPT} does not exist
   or is not executable"
  rval=1
;;
   'stop')
if [ -x ${DOMAIN_STOP_SCRIPT} ]; then
  echo "Stopping IONA Orbix services for domain ${DOMAIN}"
  ${DOMAIN STOP SCRIPT}
else
  echo "ERROR: Failed to stop IONA Orbix servies for domain
  echo "domain stop script ${DOMAIN_STOP_SCRIPT} does not exist
   or is not executable"
  rval=1
fi
;;
   *)
   echo "IONA Orbix run control script for domain ${DOMAIN}"
   echo "Usage: $0 { start | stop }"
   rval=1
   ;;
   esac
   exit $rval
```

Disable automatic services

To temporarily disable automatic startup and shutdown for <domain>:

1. Stop domain services by running

```
> stop_<domain>_services
```

2. Run

```
> /sbin/chkconfig itsvs_<domain> off
```

Enable automatic services

To enable automatic startup and shutdown for <domain>:

- 1. Rui
 - > /sbin/chkconfig itsvs_<domain> on
- 2. Start domain services by running
 - > start_<domain>_services

Unregister automatic services

To unregister automatic startup and shutdown for <domain>:

- 1. Stop domain services by running
 - > stop_<domain>_services
- 2. Remove the following files:

/var/config/itsvs_<domain>
/etc/r0.d/K27itsvs_<domain>
/etc/r2.d/S97itsvs_<domain>
/etc/init.d/itsvs_<domain>

Red Hat Linux

Run level

The default run level is either 3 or 5. Orbix determines the default run level.

Run control scripts

Run control scripts generated by the Orbix configuration tool are compatible with chkconfig(8) and linuxconf.

For a domain named *<domain>*, the following files are generated by the Orbix configuration tool:

```
/etc/rc0.d/K27itsvs_<domain> -> /etc/rc.d/init.d/itsvs_<domain>
/etc/rc1.d/K27itsvs_<domain> -> /etc/rc.d/init.d/itsvs_<domain>
/etc/rc2.d/K27itsvs_<domain> -> /etc/rc.d/init.d/itsvs_<domain>
/etc/rc[3|5].d/S97itsvs_<domain> ->
/etc/rc.d/init.d/itsvs_<domain>
/etc/rc.d/init.d/itsvs_<domain>
```

/etc/rc.d/init.d/itsvs_<domain> contains the following:

```
#!/bin/bash
          Copyright (c) 1993-2002 IONA Technologies PLC.
          All Rights Reserved
# chkconfig:
               [3|5] 27 97
 description: IONA Orbix services, domain <domain>
# <deployment-specific portion>
DOMAIN=boot
DOMAINS_ETC_DIR=/etc/opt/iona
DOMAINS_VAR_DIR=/var/opt/iona
# </deployment-specific portion>
DOMAIN_START_SCRIPT=
   ${DOMAINS_ETC_DIR}/bin/start_${DOMAIN}_services
DOMAIN_STOP_SCRIPT=
   ${DOMAINS_ETC_DIR}/bin/stop_${DOMAIN}_services
DOMAIN_LOCK_FILE=/var/lock/subsys/itsvs_${DOMAIN}
```

```
rval=0
case "$1" in
   'start')
# check if the domain is running
[ -f "${DOMAIN_LOCK_FILE}" ] && exit $rval
if [ -x ${DOMAIN_START_SCRIPT} ]; then
  echo "Starting IONA Orbix services for domain <domain>"
  ${DOMAIN START SCRIPT}
  touch ${DOMAIN_LOCK_FILE}
else
  echo "ERROR: Failed to start IONA Orbix services for domain
   <domain> - "
 echo "domain start script ${DOMAIN_START_SCRIPT} does not exist
   or is not executable"
 rval=1
fi
   ;;
   'stop')
# check if the domain is not running
[ ! -f "${DOMAIN_LOCK_FILE}" ] && exit $rval
if [ -x ${DOMAIN_STOP_SCRIPT} ]; then
  echo "Stopping IONA Orbix services for domain <domain>"
  ${DOMAIN_STOP_SCRIPT}
else
  echo "ERROR: Failed to stop IONA Orbix services for domain
   <domain> - "
  echo "domain stop script ${DOMAIN_STOP_SCRIPT} does not exist
   or is not executable"
fi
rm -f ${DOMAIN_LOCK_FILE}
  ;;
   echo "IONA Orbix run control script for domain ${DOMAIN}"
   echo "Usage: $0 { start | stop }"
  rval=1
;;
   esac
   exit $rval
```

Disable automatic services

To temporarily disable automatic startup and shutdown for <domain>:

- 1. Stop domain services by running
 - > stop_<domain>_services
- 2. Run
 - > chkconfig -del itsvs_<domain>

Enable automatic services

To enable automatic startup and shutdown for <domain>:

- 1. Run
 - > chkconfig -add itsvs_<domain>
- 2. Start domain services by running
 - > start_<domain>_services

Unregister automatic services

To unregister automatic startup and shutdown for <domain>:

- 1. Stop domain services by running
 - > stop_<domain>_services
- 2. Run
 - > chkconfig -del itsvs_<domain>
- 3. Remove the following files:

/etc/rc.d/init.d/itsvs_<domain>
/var/lock/subsys/itsvs_<domain>

APPENDIX B | Run Control Scripts for Unix Platforms

ORB Initialization Settings

Initialization settings can be set for an ORB through command-line arguments, which are passed to the initializing ORB.

In most cases, equivalent environment variables or Java properties are available. In the absence of command-line arguments, these are used by the initializing ORB.

Initialization parameters pertain to the immediate requirements of the initializing ORB; for example, the name of its configuration domain and location, and the naming scope in which to find the ORB's configuration. The ORB's behavior is further defined by its configuration, as set by configuration variables. For more information about these, refer to the *Configuration Reference*.

Precedence of settings

Most initialization parameters can be set in one of the following ways, in descending order of precedence:

- Command-line arguments.
- Environment variables or Java properties.
- Default values.

Java properties

Java properties can be set for an initializing ORB in two ways, in descending order of precedence:

Set as system properties. For example:

java -DORBdomain_name finance corporate.finance_app

Set in the properties file iona.properties.

An initializing ORB searches for the properties file in the following locations, in this order:

- 1. Current directory.
- 2. Directories on the classpath.
- 3. Jars on the classpath.

Domains directory

The directory that contains the target configuration file; set with:

Command-line argument: -ORBconfig_domains_dir
Environment variable: IT_CONFIG_DOMAINS_DIR
Java property: ORBconfig_domains_dir

This directory typically stores a file for each accessible configuration domain name.

For example:

```
my_app -ORBconfig_domains_dir c:\iona\etc\domains
```

Nothing else should be stored in this directory. This enables tools to easily enumerate the list of available domains.

The configuration domains directory defaults to <code>ORBconfig_dir/domains</code> on UNIX, and <code>ORBconfig_dir/domains</code> on Windows.

Domain name

The name of the configuration domain to use; set with:

Command-line argument: -ORBdomain_name
Environment variable: IT_DOMAIN_NAME
Java property: ORBdomain_name

For example:

my_app -ORBdomain_name my_domain

Configuration directory

The root configuration directory; set with:

Command-line argument: -ORBconfig_dir
Environment variable: IT_CONFIG_DIR
Java property: ORBconfig_dir

Specifies the root configuration directory. The default root configuration directory is /etc/opt/iona on UNIX, and product-dir\etc on Windows.

ORB name

The ORB name, which specifies the configuration scope for this ORB; set with:

Command-line argument only: -ORBname

The following application takes it configuration from the my_orb scope:

```
my_app -ORBname my_orb
```

You can also use the -ORBname parameter to specify non-default configuration scopes for Orbix services. For example:

itconfig_rep -ORBname config_rep.config2 run

Initial reference

An initial object reference for a service using the interoperable naming service format; set with:

Command-line argument only: -ORBInitRef

For example:

```
-ORBInitRef NameService=IOR00023445AB...
-ORBInitRef
NotificationService=corbaloc:555objs.com/NotificationService
-ORBInitRef TradingService=corbaname:555objs.com/Dev/Trader
```

Default initial reference

An initial object reference to a service if none is explicitly specified by -ORBInitRef; set with:.

Command-line argument only: -ORBDefaultInitRef

This parameter takes a URL, which forms a new URL identifying an initial object reference. For example:

```
my_app -ORBDefaultInitRef corbaloc:555objs.com
```

A call to resolve_initial_references("NotificationService") with the following argument results in a new URL:

```
corbaloc:555.objs.com/NotificationService
```

The new URL has a '/' character and a stringified object key appended.

Product directory

The directory in which IONA products are installed, set with:

Command-line argument: -ORBproduct_dir
Environment variable: IT_PRODUCT_DIR
Java property: ORBproduct_dir

For example:

```
my_app -ORBproduct_dir c:\iona
```

This directory is read-only and location independent. This enables it to be shared across systems even if mounted at different locations.

The directory in which products are installed defaults to /opt/iona on UNIX, and %SystemDrive%\Program Files\IONA on Windows.

APPENDIX C | ORB Initialization Settings

Development Environment Variables

For C++ installations, you can specify several environment variables that pertain to development environments only.

IT_IDL_CONFIG_FILE

Specifies the configuration file for the IDL compiler.

UNIX

Defaults to \$IT INSTALL DIR/asp/version/etc/idl.cfg.

Windows

Defaults to %IT_INSTALL_DIR%\asp\version\etc\idl.cfg.

Note: Do not modify the default IDL configuration file. This affects demo programs and other applications. Instead, use this variable to point the IDL compiler to a customized file if necessary.

IT_IDLGEN_CONFIG_FILE

Specifies the configuration file for the Orbix code generation toolkit.

UNIX

Defaults to \$IT_INSTALL_DIR/asp/version/etc/idlgen.cfg.

Windows

 $Defaults \ to \ \texttt{`IT_INSTALL_DIR'`asp'} version \ \texttt{`etc'idlgen.cfg}.$

Named Keys for Orbix Services

This appendix lists the named keys for the Orbix services and associated configuration variables.

In this appendix

This appendix includes the following sections:

Orbix Service Named Key Strings	page 444
Configuration for Advertising Services	page 447

Orbix Service Named Key Strings

Table 40 shows the key strings used by each service.

 Table 40:
 Orbix Service Key Strings

Service	Plain Text Forwarder Key	IMR Key	IOR Prefix	Initial Reference
Security	IT_SecurityService	n/a	IT_SecurityService	IT_SecurityService
	IT_Login	n/a	IT_Login	IT_Login
Configuratio n Repository (CFR)	ConfigRepository	n/a	ConfigRepository	ConfigRepository
	IT_ConfigRepositoryRep lica	n/a	IT_SingleConfigRepositor y	n/a
Firewall Proxy Service (FPS)	IT_FPS_Registry	n/a	IT_FPS_Registry	IT_FPS_Registry
	IT_FPS_Manager	n/a	IT_FPS_Manager	IT_FPS_Manager
Management	IT_ManagementService. User	n/a	IT_MgmtServiceUser	IT_MgmtServiceUse r
	IT_ManagementService. Registration	n/a	IT_MgmtService	IT_MgmtService
	IT_ManagementService. Security	n/a	IT_MgmtServiceSec	IT_MgmtServiceSec
Locator	IT_Locator	n/a	IT_Locator	IT_Locator
	IT_LocatorReplica	n/a	IT_SingleLocator	n/a
Node daemon	IT_NodeDaemon	n/a	IT_NodeDaemon	n/a
Transaction monitor	TransactionServiceAdmi n	TransactionServic eAdmin	TransactionServiceAdmin	TransactionServiceA dmin

Service	Plain Text Forwarder Key	IMR Key	IOR Prefix	Initial Reference
	TransactionFactory	TransactionFactor y	TransactionFactory	TransactionFactory
Interface Repository	InterfaceRepository	InterfaceRepositor y	InterfaceRepository	InterfaceRepository
Naming	NameService	NameService	NameService	NameService
	IT_NameServiceReplica	n/a	IT_SingleNameService	n/a
Trader	TradingService	TradingService	TradingService	TradingService
	TradingServiceNR	n/a	n/a	n/a
	Replicator	n/a	n/a	n/a
Basic Log	DefaultBasicLogFactory	BasicLoggingServ ice	BasicLoggingService	BasicLoggingService
Event Log	DefaultEventLogFactory	EventLoggingServ ice	EventLoggingService	EventLoggingServic e
Notification Log	DefaultNotifyLogFactory	NotifyLoggingSer vice	NotifyLoggingService	NotifyLoggingServic e
Notification	DefaultEventChannelFact ory	NotificationServic e	NotificationService	NotificationService
	DefaultEndpointAdmin	n/a	IT_NotificationEndpointA dmin	IT_NotificationEndp ointAdmin
Event	DefaultEventChannelFact ory	EventService	EventService	EventService
	DefaultTypesEventChann elFactory	n/a	n/a	n/a
JMS	MessageBroker	IT_JMSMessageB roker	IT_JMSMessageBroker	IT_JMSMessageBro ker
	ServerContext	n/a	IT_JMSServerContext	IT_JMSServerConte xt
	MessagingBridge	n/a	IT_MessagingBridge	IT_MessagingBridge

APPENDIX E | Named Keys for Orbix Services

Service	Plain Text Forwarder Key	IMR Key	IOR Prefix	Initial Reference
	EndpointAdmin	n/a	IT_JMSEndpointAdmin	IT_JMSEndpointAd min

Configuration for Advertising Services

Table 41 shows the configuration variables for each service (where applicable). Setting one of these variables to true prevents registration of a key with the plain text key forwarder for that service.

 Table 41: Advertise Service Configuration Variables

Service	Configuration Variable Name
Firewall Proxy Service (FPS)	fps:advertise_services
Transaction monitor	plugins:ots:advertise_services
Interface Repository	plugins:ifr:advertise_services
Naming	plugins:naming:advertise_services
Trader	trader:advertise_services
Basic Log	plugins:basic_log:advertise_services
Event Log	plugins:event_log:advertise_services
Notification Log	plugins:notify_log:advertise_services
Notification	plugins:notify:advertise_services
Event	plugins:event:advertise_services

APPENDIX E | Named Keys for Orbix Services

Glossary

A

C

administration

All aspects of installing, configuring, deploying, monitoring, and managing a system.

ART

Adaptive Runtime Technology. IONA's modular, distributed object architecture, which supports dynamic deployment and configuration of services and application code. ART provides the foundation for IONA software products.

ATLI2

Abstract Transpot Layer Interface, version 2. IONA's current transport layer implementation.

Certificate Authority

Certificate Authority (CA). A trusted third-party organization or company that issues digital certificates used to create digital signatures and public-private key pairs. The role of the CA in this process is to guarantee that the individual granted the unique certificate is, in fact, who he or she claims to be. CAs are a crucial component in data security and electronic commerce because they guarantee that the two parties exchanging information are really who they claim to be.

CFR

See configuration repository.

client

An application (process) that typically runs on a desktop and requests services from other applications that often run on different machines (known as server processes). In CORBA, a client is a program that requests services from CORBA objects.

configuration

A specific arrangement of system elements and settings.

configuration domain

Contains all the configuration information that Orbix ORBs, services and applications use. Defines a set of common configuration settings that specify available services and control ORB behavior. This information consists of configuration variables and their values. Configuration domain data can be implemented and maintained in a centralized Orbix configuration repository or as a set of files distributed among domain hosts. Configuration domains let you organize ORBs into manageable groups, thereby bringing scalability and ease of use to the largest environments. See also configuration file and configuration repository.

configuration file

A file that contains configuration information for Orbix components within a specific configuration domain. See also configuration domain.

configuration repository

A centralized store of configuration information for all Orbix components within a specific configuration domain. See also configuration domain.

configuration scope

Orbix configuration is divided into scopes. These are typically organized into a root scope and a hierarchy of nested scopes, the fully-qualified names of which map directly to ORB names. By organizing configuration properties into various scopes, different settings can be provided for individual ORBs, or common settings for groups of ORB. Orbix services, such as the naming service, have their own configuration scopes.

CORBA

Common Object Request Broker Architecture. An open standard that enables objects to communicate with one another regardless of what programming language they are written in, or what operating system they run on. The CORBA specification is produced and maintained by the OMG. See also OMG.

CORBA naming service

An implementation of the OMG Naming Service Specification. Describes how applications can map object references to names. Servers can register object references by name with a naming service repository, and can advertise those

names to clients. Clients, in turn, can resolve the desired objects in the naming service by supplying the appropriate name. The Orbix naming service is an example.

CORBA objects

Self-contained software entities that consist of both data and the procedures to manipulate that data. Can be implemented in any programming language that CORBA supports, such as C++ and Java.

CORBA transaction service

An implementation of the OMG Transaction Service Specification. Provides interfaces to manage the demarcation of transactions and the propagation of transaction contexts. Orbix OTS is such as service.

CSIv2

The OMG Common Secure Interoperability protocol v2.0, which can be used to provide the basis for application-level security in both CORBA and J2EE applications. The IONA Security Framework implements CSIv2 to transmit usernames and passwords, and to assert identities between applications.

deployment

The process of distributing a configuration or system element into an environment.

HTTP

HyperText Transfer Protocol. The underlying protocol used by the World Wide Web. It defines how files (text, graphic images, video, and other multimedia files) are formatted and transmitted. Also defines what actions Web servers and browsers should take in response to various commands. HTTP runs on top of TCP/IP.

IDL

Interface Definition Language. The CORBA standard declarative language that allows a programmer to define interfaces to CORBA objects. An IDL file defines the public API that CORBA objects expose in a server application. Clients use these interfaces to access server objects across a network. IDL interfaces are independent of operating systems and programming languages.

H

I

IFR

See interface repository.

HOP

Internet Inter-ORB Protocol. The CORBA standard messaging protocol, defined by the OMG, for communications between ORBs and distributed applications. IIOP is defined as a protocol layer above the transport layer, TCP/IP.

implementation repository

A database of available servers, it dynamically maps persistent objects to their server's actual address. Keeps track of the servers available in a system and the hosts they run on. Also provides a central forwarding point for client requests. See also location domain and locator daemon.

IMR

See implementation repository.

installation

The placement of software on a computer. Installation does not include configuration unless a default configuration is supplied.

Interface Definition Language

See IDL.

interface repository

Provides centralized persistent storage of IDL interfaces. An Orbix client can query this repository at runtime to determine information about an object's interface, and then use the Dynamic Invocation Interface (DII) to make calls to the object. Enables Orbix clients to call operations on IDL interfaces that are unknown at compile time.

invocation

A request issued on an already active software component.

IOR

Interoperable Object Reference. See object reference.

L

location domain

A collection of servers under the control of a single locator daemon. Can span any number of hosts across a network, and can be dynamically extended with new hosts. See also locator daemon and node daemon.

locator daemon

A server host facility that manages an implementation repository and acts as a control center for a location domain. Orbix clients use the locator daemon, often in conjunction with a naming service, to locate the objects they seek. Together with the implementation repository, it also stores server process data for activating servers and objects. When a client invokes on an object, the client ORB sends this invocation to the locator daemon, and the locator daemon searches the implementation repository for the address of the server object. In addition, enables servers to be moved from one host to another without disrupting client request processing. Redirects requests to the new location and transparently reconnects clients to the new server instance. See also location domain, node daemon, and implementation repository.

N

naming service

See CORBA naming service.

node daemon

Starts, monitors, and manages servers on a host machine. Every machine that runs a server must run a node daemon.

O

object reference

Uniquely identifies a local or remote object instance. Can be stored in a CORBA naming service, in a file or in a URL. The contact details that a client application uses to communicate with a CORBA object. Also known as interoperable object reference (IOR) or proxy.

OMG

Object Management Group. An open membership, not-for-profit consortium that produces and maintains computer industry specifications for interoperable enterprise applications, including CORBA. See www.omg.com.

ORB

Object Request Broker. Manages the interaction between clients and servers, using the Internet Inter-ORB Protocol (IIOP). Enables clients to make requests and receive replies from servers in a distributed computer environment. Key component in CORBA.

OTS

See CORBA transaction service.

POA

Portable Object Adapter. Maps object references to their concrete implementations in a server. Creates and manages object references to all objects used by an application, manages object state, and provides the infrastructure to support persistent objects and the portability of object implementations between different ORB products. Can be transient or persistent.

protocol

Format for the layout of messages sent over a network.

server

A program that provides services to clients. CORBA servers act as containers for CORBA objects, allowing clients to access those objects using IDL interfaces.

SSL

Secure Sockets Layer protocol. Provides transport layer security—authenticity, integrity, and confidentiality—for authenticated and encrypted communications between clients and servers. Runs above TCP/IP and below application protocols such as HTTP and IIOP.

SSL handshake

An SSL session begins with an exchange of messages known as the SSL handshake. Allows a server to authenticate itself to the client using public-key encryption. Enables the client and the server to co-operate in the creation of symmetric keys that are used for rapid encryption, decryption, and tamper

P

S

detection during the session that follows. Optionally, the handshake also allows the client to authenticate itself to the server. This is known as mutual authentication.

TCP/IP

Transmission Control Protocol/Internet Protocol. The basic suite of protocols used to connect hosts to the Internet, intranets, and extranets.

TLS

Transport Layer Security. An IETF open standard that is based on, and is the successor to, SSL. Provides transport-layer security for secure communications. See also SSL.

T

Index

\mathbf{A}	C++ request logging 196
active connection management 103	catastrophic recovery 142
client-side configuration 104	checkpoints
server-side configuration 103	Berkeley DB 139
active load balancing 120	checksum 373
admin_logon 375	confirm 376
algorithms, compression 151	create 377
-args 54	list 377
ATLI2 160	list all processes 377
	manage 376
В	remove 378
backups	cicsraw operations 196
full 142	CICS server adapter
incremental 144	Mapping Gateway interface 177
bandwidth 149	client_binding_list 167
Berkeley DB environment 138	cluster.properties file 97
checkpoints 139	command-line parameters
data files 138	-ORBadmin_config_domains_dir 48
file types 138	-ORBadmin_domain_name 48
recovery 142	-ORBconfig_domain 36
store environment files 138	-ORBdomain_name 48
transaction log files 138	compression plug-in 149
archive 140	config dump 262
delete 140	ConfigList 45
size 140	config list 263
bidirectional GIOP 168	config stop 264
BiDir Gen3 173	configuration
BiDir_GIOP 171	convert from file to CFR 264
BiDirIdGenerationPolicy 169	default directory 36
BiDirPolicy::ALLOW 169	file-based 23
BiDirPolicy::BiDirAcceptPolicy 170	itadmin commands 261
BiDirPolicy::BidirectionalAcceptPolicy 173	namespace management 266
BiDirPolicy::BiDirExportPolicy 169	repository-based 24
BiDirPolicy::BiDirOfferPolicy 170	scope management 269
binding:client_binding_list 153, 167, 171	variable management 271 configuration domain
binding:server_binding_list 197	obtain for ORB 34
boolean 45	C++ applications 36
buffered logging 195	Java applications 36
bzip2 151	troubleshoot 48
	configuration repository 24
C	converting from file to 264
C++ management agent registration 198	dump contents 262
C Indiagonicii agoni registration 170	dump contents 202

list replicas 263	expand 363
manage 262	init 364
start 236	remove_mirror 364
stop 264	Encina transactions
configuration scope 38	add backup files 360
define 40	add mirror volume 361
file-based configuration 40	create log backup 361
itadmin commands 41	display mirror volume data 362
map to ORB name 39	expand transaction log 363
name 39	initialize transaction log 364
share 44	remove mirror 364
configuration variables	stop service 365
components 45	environment variables
data type 45	development 442
constructed 45	ORB initialization 435
namespace 45	event
	show 276
precedence of settings 42 set value 46	
	stop 277 event channel
constructed types 45	
corbaloc URL 165	create 279, 348, 351
CREATE_DEFAULT_ERROR_MODE 57	list all 279, 349
CREATE_NEW_PROCESS_GROUP 57	manage 278, 348
	remove 280, 350
D	show attributes 281, 350
data files	event log 245
Berkeley DB 138	event_log:filters 167, 170
decompression 150	event service
default-domain.cfg 36	itadmin commands 275
DETACHED_PROCESS 57	manage 276
direct persistence 165	show attributes 276
failover 86	start 242
double 45	stop 277
dual-stack host 164	export policy 169
dynamic logging 198	
	F
E	failover 81, 85
E	direct persistence 86
ec	federation links,manage 389
create 279	file-based configuration 23
list 279	filename 194
remove 280	file_to_cfr.tcl 264
show 281	filters 188
EGMIOP 160	
election protocol 99	firewall proxy plug-in 133
encinalog	firewall proxy service 131
add 360	fps 133
add_mirror 361	fps:proxy_evictor:hard_limit 134
create 361	fps:proxy_evictor:soft_limit 134
display 362	fps_agent.jar 133 FOPN 6

fragmentation 158	browse contents 125
full backup 142	destroy contents 286
	display containment hierarchy 125
G	itadmin commands 283, 323
General Inter-ORB Protocol 168	list container contents 125, 286, 326
GenerateConsoleCtrlEvent() 321	list current container 286, 328
GIOP, bidirectional 168	maintain 14
GIOP::BiDirId 169	manage 283, 323
GIOP request 196	navigate to other containment levels 126, 285, 326
GIOP Snoop 151, 201	remove definitions 128, 287, 327
gzip 151	show scoped name 287, 327
gzip 131	start 123
***	start daemon 241
H	stop daemon 123, 287, 328
hard_limit	usage 14
IIOP 103, 104	write contents to file 286, 325
host, moving to a new 61	interfaces
	add to interface repository 127, 284
I	define 14
	obtain from interface repository 14
compile 14	remove definitions from interface repository 128
IDL definitions, manage 124, 284	interoperable object reference. See IOR
ifr	IOP::BI_DIR_GIOP_OFFER 170
cd 285, 326	IOP::TAG_BI_DIR_GIOP 169
destroy_contents 129, 286	IOR 8
ifr2idl 286, 325	iordump 151, 170
list 286, 326	IPv4 163
pwd 286, 328	IPv6 163
remove 128, 287, 327	is2.properties file 97
show 287, 327	IT_ACTIVATOR 190
stop 123, 287, 328	itadmin commands 248
IIOP plug-in configuration	abbreviations 253
hard connection limit	command-line usage 248
client 104	configuration domain 261
server-side 103	escape character 252
soft connection limit	event service 275
client 104	help 253
server 103	interface repository 283, 323
implementation repository 8	lists 251
imsraw operations 197	location domain 289
IMS server adapter	logging 245
Mapping Gateway interface 177	mainframe adapter 178
incremental backups 144	naming service 332
initial_references:IT_IPTransport:plugin 161	negative values 252
initial_references:IT_MFA:reference 178	nested 248
INTERDICTION policy 134	notification service 343
Interface Definition language. See IDL	object group 336
interface repository	OTS 355
add IDL definitions 127, 284	OTS Encina 359

PSS 367	itnode_daemon run 66, 238
shell usage 248	IT_NOTIFICATION 191
spaces in values 252	itnotify run 243
SSL/TLS 373	IT_OTS_LITE 191
syntax 251	IT_POA 191
Tel scripts 249	IT_POA_LOCATOR 191
trading service 245, 255, 383	IT_PRODUCT_DIR 439
undo 250	IT_PSS 191
itadmin logging set 198	IT_PSS_DB 141, 191
IT_ATLI2_IOP 190	IT_PSS_R 191
IT_ATLI2_IP 190	it_request_logger 197
IT_ATLI2_ITMP 190	IT_SCHANNEL 191
IT_ATLI2_ITRP 190	IT_TLS 191
IT_ATLI2_SHM 190	IT_TS 191
IT_ATLI_TLS 190	IT_XA 191
IT_BiDirPolicy::BidirectionalGen3AcceptPolicy 173	it_ziop 152
IT_BiDirPolicy::BiDirIdGenerationPolicy 169	
IT_ClassLoading 190	J
IT_CODESET 190	Java CIO 160
IT_CONFIG_DIR 437	Java NIO 160
IT_CONFIG_DOMAIN 36	
IT_CONFIG_DOMAINS_DIR 436	K
IT_CONFIG_REP 190	KDM 373
itconfig_rep run 236	database 373
IT_CORE 190	log on 375
IT_CSI 190	kdm_adm change_pw 379
IT_DOMAIN_NAME 436	kdm_adm confirm 380
itevent run 242	kdm_adm create 380
IT_GIOP 190	kdm_adm list 381
IT_GSP 190 IT_IDL_CONFIG_FILE 441	kdm_adm remove 382
IT_IDLGEN_CONFIG_FILE 442	<u>-</u>
IT_IFR 190	L
itifr run 123, 241	
IT_IIOP 190	load balancing 81, 94
IT_IIOP_PROFILE 190	active selection 120
IT_IIOP_TLS 191	replicated servers 81
IT_JAVA_SERVER 191	selection strategies 120, 338, 339 LocateReply 206
IT_LEASE 191	LocateRequest 206
IT_LOCATOR 191	location domain
itlocator run 62, 237	daemon. See locator daemon
itmfaloc 182	implementation repository 8
itmfaloc URL resolver 181	itadmin commands 289
IT_MGMT 191	list registered entries 68
it_mgmt_agent_reg 199	modify entries 69
IT_MGMT_SVC 191	register ORB 52
IT_NAMING 191	register POA 53
itnaming run 112, 240	register server process 52
IT_NODE_DAEMON 191	remove entries 69

locator	delete 326
list 291	list 326
show 291	refresh 327
stop 63, 292	reload 327
locator daemon 8	resetcon 327
list all 291	resolve 328
manage 290	save 328
restart 63	stats 329
show attributes 291	stop 329
start 62, 237	switch 329
stop 63, 292	MPI 202
usage 10	
locator daemon configuration	N
find persistent objects 8	N
logging	name
buffered 195	bind to object 332
configuration 194	rebind 118
dynamic 198	named_key
get 245	create 294
local file 194	list 294
message severity levels 192	remove 295
output to local file 194	show 295
output to system log 195	named keys
rolling_file 195	create 294
set 246	list all 294
set filters for subsystems 188	manage 293
and the contract of the contra	remove 295
subsystems 190	show object reference 295
logging, precision 196	namespace
long 45 low bandwidth 149	create 266
low bandwidth 149	list 267
	remove 268
M	show 268
mainframe 196	namespaces
Mainframe Adapter 175	create 266
itmfaloc URL resolver 181	list 267
Mapping Gateway interface 177	manage 266
mainframe adapter	remove from configuration 268
itadmin commands 323	show contents 268
majority rule	naming context
replicas 100	create 115
Mapping Gateway interface 177	unbound 115
IOR 180	naming graph 110
master	build 113
election protocol 99	naming service 4
master-slave replication 97	administer 109
message fragmentation 158	bind name 332
mfa 177	bind name to object 116
add 325	build naming graph 113
change 325	itadmin commands 332

list contents 333	notify
manage 332	checkpoint 344
naming context	post_backup 345
create 115	pre_backup 345
unbound 115	show 345
naming graph 110	stop 347
new context 333	ns
object groups 119, 336	bind 116, 332
rebind name 118	list 333
resolve name 334	newnc 115, 333
start 112, 240	remove 334
stop 112, 335	resolve 118, 334
unbind 334, 335	stop 112, 335
nc	unbind 118, 335
create 348, 351	nsog
list 349	add_member 337
remove 350	bind 337
set_qos 351	create 338
show 350	list 338
NegotiateSession 174	list_members 338
NIO	modify 339
new I/O 160	remove 339
-node_daemon_54	remove_member 340
node daemon 65	set_member_timeout 340
list 297	show_member 341
list active processes 67	update_member_load 342
manage 296	update_member_road 5 12
remove 297	0
run several on host 66	0
show attributes 297	object group 119
start 66, 238	active load balancing 120
stop 67, 298	add member 337
usage 10	bind 337
node_daemon	create 119, 338
list 297	identifier 119
remove 297	itadmin commands 336
show 297	list all 338
stop 67, 298	list members 338
NORMAL_PRIORITY_CLASS 57	manage 336
normal recovery 142	member identifiers 119
notification service	member IOR 341
checkpoint operations 344	member load value updates 342
itadmin commands 343	member timeout 340
manage 344	modify selection strategy 339
post-backup operations 345	remove 339
pre-backup operations 345	remove member 340
show attributes 345	selection strategies 120, 338, 339
start 243	OBJECT_NOT_EXIST exception 8
start 243 stop 347	object references 4
stop sti	client invocations on 4

map to servants 5	manage 300
object request broker. See ORB	modify 301
objects	remove 302
persistent 8	show attributes 303
transient 8	orbname
on demand 312	create 52, 300
on-demand activation 52	register replicated server 91
replicated server 90	list 300
ORB	modify 301
configuration 38	remove 302
initialization 35, 435	show 303
map name to configuration scope 39	orb_plugins 166, 203
register in location domain 52	-ORBproduct_dir 439
register root POA name 70	ORBproduct_dir Java property 439
server 2	OS/390 176
share configuration scope 44	OTS
-ORBadmin_config_domains_dir 48	itadmin commands 355
-ORBadmin_domain_name 48	manage 355
-ORBconfig_dir 437	OTS Encina
ORBconfig_dir Java property 437	itadmin commands 359
-ORBconfig_domain 36	manage 359
ORBconfig_domain Java property 36	otstm stop 365
-ORBconfig_domains_dir 436	r in the second
ORBconfig_domains_dir Java property 436	P
-ORBDefaultInitRef 438	
-ORBdomain_name 48, 436	pass phrases 373
ORBdomain_name Java property 436	change 379
ORB initialization 435	confirm 380
configuration directory 437	create 380
default initial reference 438	list 381
domain name 436	manage 379
domains directory 436	remove 382
initial reference 438	per_client 54, 312
Java properties 435	per-client activation 54
ORB name 437	persistent objects 8
precedence of settings 435	direct persistence
product directory 439	and failover 86
-ORBInitRef 438	invoke on 8
Orbix mainframe 196	locate 51
Orbix services	replicated 83
order of startup 234	PERSIST_STORE exception 141
start and stop scripts 234	pkzip 151
start commands 235	plugin:atli2_shm:shared_memory_size 167
stop commands 244	plugins:atli2_ip:ClassName 161
Orbix services, replication 95	plugins:atli2_ip_cio:ClassName 162
-ORBname 437	plugins:atli2_ip_nio:ClassName 161
ORB name 437	plugins:config_rep:refresh_master_interval 99
create 300	plugins:giop:message_server_binding_list 153, 171
list all 300	plugins:giop_snoop:ClassName 203 plugins:giop_snoop:filename 205
	piugins.giop shoop.ilielianie 203

plugins:giop_snoop:rolling_file 205	replicated POA 91
plugins:giop_snoop:shlib_name 203	poa list 307
plugins:giop_snoop:verbosity 204	poa modify 307
plugins:local_log_stream:buffer_file 195	poa remove 309
plugins:local_log_stream:filename 157, 195	poa show 310
plugins:local_log_stream:log_elements 195	policies:giop:bidirectional_accept_policy 170
plugins:local_log_stream:milliseconds_to_log 195	policies:giop:bidirectional_export_policy 169
plugins:local_log_stream:precision_logging 196	policies:giop:bidirectional_gen3_accept_policy 173
plugins:locator:allow_node_daemon_change 61	policies:giop:bidirectional_offer_policy 170
plugins:locator:refresh_master_interval 99	policies:giop:interop_policy 197
plugins:naming:refresh_master_interval 99	policies:iiop:buffer_sizes_policy:default_buffer_size 1
plugins:node_daemon:recover_processes 66	58
plugins:orb:is_managed 199	policies:network:interfaces:prefer_ipv4 163
plugins:pss_db:envs	policies:network:interfaces:prefer_ipv6 163
env-name:replica_priority 99	policies:per_request_lb 94
plugins:pss_db:envs:env-name:allow_demotion 101	policies:ziop:compression_enabled 153
plugins:pss_db:envs:env-name:allow_minority_master	policies:ziop:compression_threshold 155
100	policies:ziop:compressor:compressor_id:level 154
plugins:pss_db:envs:env-name:hearbeat_interval 101	policies:ziop:compressor_id 154
plugins:pss_db:envs:env-name:lsn_timeout 102	portable object adapter. See POA
plugins:pss_db:envs:env-name:master_heartbeat_interv	precision logging 196
al 101	prefer_local 94, 306, 309
plugins:pss_db:envs:env_name:recover_fatal 146	primitive types 45
plugins:pss_db:envs:ifr_store:lk_max 129	priorities, replica 99
plugins:pss_db:envs:it_locator:checkpoint_archives_ol	process
d_logs_144	create 52, 311
_ E	disable 314
plugins:pss_db:envs:it_locator:checkpoint_deletes_oldlogs 144	enable 314
	list 67, 315
plugins:pss_db:envs:it_locator:db_home 145	· · · · · · · · · · · · · · · · · · ·
plugins:pss_db:envs:it_locator:old_logs_dir 145	modify 316
plugins:ziop:ClassName 152	moving to a new host 61 remove 318
plugins:ziop:shlib_name 152	
POA 5	show 319
FQPN 6	start 61, 320
list 307	stop 61, 321
manage 304	process create 54
modify 307	proxy offers, manage 395
name root POA 70	PSS
names 6	checkpoint 368
persistent 51	itadmin commands 367
register in location domain 53, 304	manage 367
remove 309	obtain IOR to 369
replicas 53, 82	post-backup operations 369
show attributes 310	pre-backup operations 370
transient 53	pss_db
POA::create_POA() 169	checkpoint 368
poa:fqpn:direct_persistent 75	name 369
poa:fqpn:well_known_address 76	post_backup 143, 369
poa create 53, 304	pre_backup 145, 370

pss_db archive_old_logs 368	S
pss_db checkpoint 368	scope
pss_db delete_old_logs 369	create 269
pss_db list_replicas 369	list 269
pss_db name 369	list sub-scopes 269
pss_db post_backup 369	manage 269
pss_db pre_backup 370	remove 270
pss_db remove_replica 370	show 270
pss_db show 371	show contents 270
•	scope See configuration scope
Q	secure_directories 61
QoS 351	security service
qualities of service, event channel 351	replication 97
quanties of service, event channer 331	server process
n	disable on-demand activation 314
R	enable on-demand activation 314
random 94, 306, 309	list 315
recovery	manage 311
Berkeley DB 142	modify 316
refresh master interval 99	moving to a new host 61
regular offers, manage 393	register 311
replica failover 165	register for on-demand activation 52
replicated servers 81	on replicated server 90
add server replicas 93	remove 318
build 89	secure directories 61
deploy 82	show attributes 319
failover 85	start 320
load balancing 85	start and stop 61
specifying strategy 91	stop 321
on-demand activation 90	servers, reactivate with node daemon 10
register ORB names 91	shared memory 166
register POA 91	shmiop plugin 166
register processes 90	simple_persistent demo 76
startup 83	SIOP 202
replication Orbix services 95	soft_limit
	IIOP 103, 104
priorities 99	SSL/TLS
security service 97	itadmin commands 373
Reply 206 repository-based configuration 24	KDM 373
	manage 373
Request 206 request_logger 196	-startupmode 54
rolling_file 195	start-up mode 312
root_name 70	string 45
root POA	
register name 71	T
round_robin 94, 306, 309	TAG_BI_DIR_GIOP 170, 172
10ana_100m 77, 500, 507	Tcl scripts, itadmin commands 249
	TerminateProcess() 314

trading service	list 395
create federation link 389	remove 395
federation links 389	show 396
itadmin commands 245, 255, 383	trd_type
list federation links 390	list 397
list offer IDs 393	mask 397
list proxy offer IDs 395	remove 398
list service types 397	show 398
manage 245, 255, 383	unmask 399
mask service type 397	tx
modify administrative settings 386	begin 355
modify federation link 390	commit 356
obtain administrative settings 384	resume 356
proxy offers 395	rollback 357
regular offers 393	suspend 357
remove federation link 391	type repository, manage 397
remove offer 393	
remove proxy offer 395	U
remove service type 398	UNIX System Services 176
show federation link attributes 392	ONIX System Services 170
show offer attributes 394	*7
show proxy offer attributes 396	${f V}$
show service type attributes 398	variable
stop 388	create 271
type repositories 397	manage in configuration 271
unmask service type 399	modify 273
transaction	remove 274
begin 355	show 274
commit 356	show setting 274
resume 356	Vista 163
roll back 357	
suspend 357	\mathbf{W}
transaction log files 138	WELL_KNOWN_ADDRESSING_POLICY 73
transient objects 8	Windows NT services 403
trd_admin	accounts 409
get 384	commands 406
set 386	identify Orbix services 405
stop 388	install Orbix service 407
trd_link	logging 412
create 389	manage 405
list 390	obtain data 408
modify 390	obtain help on service 407
remove 391	pause background service 407
show 392	prepare Orbix service 407
trd_offer	run 408, 411
list 393	in file-based configuration 411
remove 393	in repository-based configuration 411
show 394	security 410
trd_proxy	stop Orbix service 408

troubleshoot 414 uninstall service 408, 413 Windows Vista 163 Windows XP 163

X XP 163

ZZIOP compression 149 ziop plug-in 152