
Liant Software Corporation

RM/InfoExpress[®]

User's Guide

Second Edition

LIANT

This manual is a user's guide for Liant Software Corporation's RM/InfoExpress file management system for Microsoft 32-bit Windows and UNIX clients communicating with UNIX and Windows servers using TCP/IP (Transmission Control Protocol/Internet Protocol) on a network. It is assumed that the reader is familiar with RM/COBOL and various local area networks (LANs) and wide area networks (WANs).

The information in this document is subject to change without prior notice. Liant Software Corporation assumes no responsibility for any errors that may appear in this document. Liant reserves the right to make improvements and/or changes in the products and programs described in this guide at any time without notice. Companies, names, and data used in examples herein are fictitious unless otherwise noted.

No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, photocopied, recorded, or otherwise, without prior written permission of Liant Software Corporation.

The software described in this document is furnished to the user under a license for a specific number of uses and may be copied (with inclusion of the copyright notice) only in accordance with the terms of such license.

Copyright © 1986-2008 by Liant Software Corporation. All rights reserved. Printed in the United States of America.

Liant Software Corporation

5914 West Courtyard Drive, Suite 100
Austin, TX 78730
U.S.A.

Phone (512) 343-1010
(800) 762-6265

Fax (512) 343-9487

Web site <http://www.liant.com>

RM, RM/COBOL, RM/COBOL-85, Relativity, Enterprise CodeBench, RM/InfoExpress, RM/Panels, VanGui Interface Builder, CodeWatch, CodeBridge, Cobol-WOW, WOW Extensions, InstantSQL, Xcentrinity, XML Extensions, Liant, and the Liant logo are trademarks or registered trademarks of Liant Software Corporation.

Microsoft, MS, MS-DOS, Windows 98, Windows Me, Windows NT, Windows 2000, Windows XP, Windows Server 2003, Windows Vista, Windows Server 2008, and Visual Basic are trademarks or registered trademarks of Microsoft Corporation in the USA and other countries.

UNIX is a registered trademark in the United States and other countries, licensed exclusively through X/Open Company Ltd.

All other products, brand, or trade names used in this publication are the trademarks or registered trademarks of their respective trademark holders, and are used only for explanation purposes.

Documentation Release History for the RM/InfoExpress User's Guide:

Document Edition Number	Applies To Product Version	Publication Date
Second	RM/InfoExpress version 12 and later	October 2008
First	RM/InfoExpress version 9 and later	January 2005
NA	RM/InfoExpress for TCP/IP version 8	March 2004

Important Liant documentation is provided in Adobe PDF. All manuals are distributed in Adobe Acrobat (.PDF) format and require the Adobe Acrobat Reader, 6.0 or higher, in order to display them. The installation program for the Adobe Acrobat Reader is available from the Adobe web site at: www.adobe.com.

Contents

Preface	1
Welcome to RM/InfoExpress	1
About Your Documentation.....	1
Related Publications	2
Conventions and Symbols.....	3
Registration.....	4
Technical Support	4
Support Guidelines	4
Test Cases	5
Chapter 1: Installation and Verification	7
System Requirements.....	7
RM/InfoExpress Server Program.....	7
Required Hardware.....	7
Required Software	8
RM/InfoExpress Client Program	8
Setup and Installation.....	9
RM/InfoExpress Servers.....	9
Setting Up the TCP/IP Package for RM/InfoExpress Servers on Windows and UNIX	9
Installing RM/InfoExpress Server on Windows	10
Installing RM/InfoExpress Server on UNIX	13
RM/InfoExpress Clients	20
Setting Up the TCP/IP Package for RM/InfoExpress Clients on Windows and UNIX	20
Installing RM/InfoExpress Clients on Windows and UNIX	20
Verification	21
Verifying the RM/InfoExpress Server	21
Windows Server	21
UNIX Server.....	22
Verifying the RM/InfoExpress Windows Client	23
Verifying RM/InfoExpress Windows Client and Server Communication.....	23
Verifying the RM/InfoExpress UNIX Client.....	26
Verifying RM/InfoExpress UNIX Client and Server Communication	26

Chapter 2: Configuring and Running the RM/InfoExpress Server....	29
Server Configuration Options	29
Starting the RM/InfoExpress UNIX Server Program	30
UNIX Server Command Line Options	30
UNIX Server Display Command Line Option.....	31
Starting and Stopping the RM/InfoExpress Windows Server Program	31
Starting the Server	32
Stopping the Server.....	33
Configuring the RM/InfoExpress Windows Server Program	33
Starting the Server Automatically.....	33
Running Under a Specific Log On Account.....	34
Windows Server Command Line Options	34
Windows Server Display Command Line Option	35
Chapter 3: Using RM/InfoExpress with RM/COBOL for Windows Programs	37
Accessing the RM/InfoExpress Windows Client Program	37
Pointing to Network Data Files.....	38
Specifying Synonyms	38
Specifying RUNPATH Environment Variables	39
Specifying Explicit Pathnames in the RM/COBOL Program.....	39
Specifying Complete Pathnames Using RM/COBOL Data-Names	40
Executing RM/COBOL Programs	40
Chapter 4: Using RM/InfoExpress with RM/COBOL for UNIX Programs	41
Accessing the RM/InfoExpress UNIX Client Program	41
Pointing to Network Data Files.....	42
Specifying Synonyms	42
Specifying RUNPATH Environment Variables	42
Specifying Explicit Pathnames in the RM/COBOL Program.....	43
Specifying Complete Pathnames Using RM/COBOL Data-Names	43
Executing RM/COBOL Programs	43
Chapter 5: RM/InfoExpress Server Operations	45
Keyboard Functions.....	45
Server Display Screen Format	46
Server Display Commands	47
Client Information	48
File Information	50
Open Log Information	51
Error Log Information	52
Termination of Communication Activity.....	53
Termination of Server Display	54
Termination of Client Communications	54
Termination of the Server.....	54

Chapter 6: File Security on the RM/InfoExpress UNIX Server	57
UNIX System Security	57
RM/InfoExpress File Security	58
RM/InfoExpress UNIX Server Security Levels.....	58
Server-User-Name	59
Default Server User	60
.rhosts File Entry	60
ixpwwfile File Entry.....	60
User Password	61
Additional Parameters Needed for Non-UNIX Clients	61
Client Validation by the Server at Different Security Levels	61
Server Compatibility with Older and Newer Clients	61
Older Clients with the New Server	61
New Clients with an Older Server	62
Setting Up the Network to Run RM/InfoExpress with Security Enabled.....	62
Setup for Running RM/InfoExpress at Server Security Level 0.....	64
Setup for Running RM/InfoExpress at Server Security Level 1.....	65
Setup for Running RM/InfoExpress at Server Security Level 2.....	66
Setup for Running RM/InfoExpress at Server Security Level 3.....	67
Setup for Running RM/InfoExpress at Server Security Level 4.....	68
Setup for Running RM/InfoExpress at Server Security Level 5.....	69
Setup Differences Between Server Security Levels	70
Appendix A: Messages.....	71
Error Message Types	71
Permanent Error Types	72
RM/InfoExpress API-Generated Error Codes	73
RM/InfoExpress-Generated Error Codes	75
RM/InfoExpress WinSock Error Codes.....	80
RM/InfoExpress Windows Sockets Interface Error Codes.....	82
RM/InfoExpress BSD Sockets Interface Error Codes	83
Appendix B: Limits and Ranges.....	85
Limits and Ranges	85
Appendix C: Troubleshooting RM/InfoExpress	87
Failure to Locate File or Path.....	87
RM/InfoExpress Client Entries Not Terminating	88
Removing IPC Objects After Server Failure	89
Appendix D: Configuring RM/InfoExpress	91
Configuration Files and Options.....	91
Sample Configuration File.....	92
Common Configuration Options.....	93
Client-Specific Configuration Options	96
Sample RM/InfoExpress Windows Client Configuration File	98
Common Server-Specific Configuration Options.....	99
UNIX Server-Specific Configuration Options.....	101
Sample RM/InfoExpress UNIX Server Configuration File	102
Windows Server-Specific Configuration Options.....	102
Sample RM/InfoExpress Windows Server Configuration File.....	104

Appendix E: RM/InfoExpress Security Parameter File Update Utility.....	105
Using the Utility.....	106
Adding a New Entry	107
Modifying an Existing Entry	108
Deleting an Existing Entry.....	109
Listing All Entries.....	110
Appendix F: Using RM/InfoExpress with Relativity	111
Changes to Relativity Configuration for 32-Bit Windows Clients	111
Create a Configuration File.....	112
Configure Relativity to Use RM/InfoExpress.....	112
Appendix G: Summary of Enhancements	115
Version 12 Enhancements.....	115
Version 11 Enhancements.....	116
Version 10 Enhancements.....	116
Version 9 Enhancements.....	116
Version 8 Enhancements.....	117
Support for Large Files	117
Atomic I/O Support for File Version Level 4.....	117
Limited Automatic Session Reconnection	118
Client Path Prefix Inclusion and Exclusion	118
Version 2.1 Enhancements.....	118
RM/InfoExpress Server Now Supported on Windows NT Version 4.0	118
File Security on the RM/InfoExpress UNIX Server	118
New Utility to Update RM/InfoExpress Parameter File	119
Improved Server Screens	119
Optional Message Compression	119
Optional Message Encoding	119
Initialization File Support	119
-m Server Option Obsolete	119
Use Count Check by the Server	120
New File Count Option.....	120
New Option to Handle the Display of Long Filenames	120
Version 2.0.2 Enhancements.....	120
New Server Option Enables the RM/plusDB Interface	120
Version 2.0 Enhancements.....	121
RM/InfoExpress UNIX Server Filename Case-Sensitivity.....	121
RM/InfoExpress UNIX Server Configuration Option	121
RM/InfoExpress UNIX Server Runs as a Daemon.....	121
RM/InfoExpress Screen Handler Program	121
Changes in the Default Behavior	122
New Screens	122
More COBOL Information Added to Existing Screens	122
Improved Error Handling.....	122
KEEPSESSION Configuration Option.....	122
Index	123

List of Figures

Figure 1: RM/InfoExpress Client WinSock Info Message Box	23
Figure 2: Server Display Screen Format	46
Figure 3: Server Display Main Screen	47
Figure 4: Client Information Screen	48
Figure 5: Client Files Screen.....	49
Figure 6: File Information Screen	50
Figure 7: File Clients Screen.....	50
Figure 8: Open Log Screen	51
Figure 9: Open Log Screen (Toggled)	52
Figure 10: Error Log Screen	52
Figure 11: Error Log Screen (Toggled)	53
Figure 12: Terminate Command Line.....	53
Figure 13: Quit Command Line	54
Figure 14: Quit in a While Command Line	55
Figure 15: Security Parameter File Update Utility Main Screen	106
Figure 16: Add Entry Screen	107
Figure 17: Modify Entry Screen	108
Figure 18: Delete Entry Screen	109
Figure 19: List Entries Screen.....	110

List of Tables

Table 1: RM/InfoExpress UNIX Server Security Levels.....	59
Table 2: Summary of Setup Differences Between Server Security Levels	70
Table 3: Error Types and Associated Error Codes.....	72
Table 4: Error Codes Generated by Windows Sockets	80
Table 5: Error Codes Generated by the RM/InfoExpress Windows Sockets Interface.....	82
Table 6: Error Codes Generated by the RM/InfoExpress BSD Windows Sockets Interface ..	83

Preface

Welcome to RM/InfoExpress

RM/InfoExpress is a file management system designed to optimize RM/COBOL data file access on various local area networks (LANs) and wide area networks (WANs). Implementation is available for TCP/IP (Transmission Control Protocol/Internet Protocol).

The *RM/InfoExpress User's Guide* is intended for commercial application developers who have a basic understanding of RM/COBOL, Microsoft Windows, UNIX, and TCP/IP. The information in this preface outlines the contents of this manual, defines typographic and programming conventions used in the documentation, and provides information about registering your product and obtaining technical support.

The new features and significant changes for the most recent release of RM/InfoExpress are described in [Appendix G: Summary of Enhancements](#) (on page 115).

Note The term “Windows” in this document refers to Microsoft 32-bit Windows operating systems, including Microsoft Windows 2000, Windows XP, Windows Server 2003, Windows Vista, or Windows Server 2008, unless specifically stated otherwise.

About Your Documentation

The RM/InfoExpress documentation consists of a user's guide, which is distributed electronically in Portable Document Format (PDF) as part of the RM/InfoExpress software distribution. It is also available on the Liant web site at <http://www.liant.com/docs>.

Note To view and print PDF files requires, you need to install Adobe Acrobat Reader, a free program available from Adobe's web site at <http://www.adobe.com>.

This user's guide is divided into the following parts:

Chapter 1—Installation and Verification lists hardware and software requirements, and provides procedures for installing RM/InfoExpress on both clients and servers for a specific LAN or WAN type. Also included are procedures for verifying that both client and server software are properly installed and communicating with one another.

Chapter 2—Configuring and Running the RM/InfoExpress Server describes the procedures required to configure and run RM/InfoExpress servers for UNIX and Windows.

Chapter 3—Using RM/InfoExpress with RM/COBOL for Windows Programs describes how to access the RM/InfoExpress Windows client program, how RM/COBOL for Windows programs point to network data files, and explains how to execute RM/COBOL for Windows programs for use with RM/InfoExpress.

Chapter 4—Using RM/InfoExpress with RM/COBOL for UNIX describes how to access the RM/InfoExpress UNIX client program, how RM/COBOL for UNIX programs point to network data files, and how to execute RM/COBOL for UNIX programs for use with RM/InfoExpress.

Chapter 5—RM/InfoExpress Server Operations describes the RM/InfoExpress server commands. This chapter also describes the information displayed by the server during RM/InfoExpress execution.

Chapter 6—File Security on the RM/InfoExpress UNIX Server describes the implementation of file security on the RM/InfoExpress UNIX server.

Appendix A—Messages lists and defines the information and error messages that may be generated during an RM/InfoExpress session.

Appendix B—Limits and Ranges lists the logical and physical limits and ranges of RM/InfoExpress.

Appendix C—Troubleshooting RM/InfoExpress describes problems that you may encounter during an RM/InfoExpress session and provides solutions.

Appendix D—Configuring RM/InfoExpress describes various configuration parameters for RM/InfoExpress client and server components.

Appendix E—RM/InfoExpress Security Parameter File Update Utility describes how to use the utility program (**ixsecure.cob**) to update the parameter file (**ixpwfile**) with security-related information that is used by the server to authenticate the clients.

Appendix F—Using RM/InfoExpress with Relativity describes how to access Relativity files using RM/InfoExpress.

Appendix G—Summary of Enhancements provides an overview of the new features in the current release, and reviews the changes and enhancements that were added to earlier releases of RM/InfoExpress.

The *RM/InfoExpress User's Guide* also includes an index.

Related Publications

The following documents contain information necessary for a complete understanding of RM/InfoExpress as used in conjunction with a specific operating system and a local area network (LAN) or wide area network (WAN):

- *RM/COBOL User's Guide*
- *Relativity Installation Guides*

Contact the appropriate vendor for other publications:

Microsoft products are available from Microsoft Corporation.

Conventions and Symbols

The following symbols and conventions are used or followed throughout this manual.

1. Text that you enter or that is displayed on your screen is indented and appears in a monospaced font. This type style is also used for sample command lines, program code and file listing examples, and sample sessions.
2. Variable information, for which you substitute a specific value, is printed in italics. For example:

```
runcobol name [options]
```

Italic type also identifies the titles of other manuals and the chapter names in this guide, and occasionally it is used for emphasis.

3. Program names, directory names, filenames, and commands appear in bold type and lowercase text. You can type program names, directory names, filenames, and commands in uppercase or lowercase letters, except where otherwise stated.

Bold type is also used for emphasis on some types of lists, and for anything you must type exactly as it appears.
4. Key combinations are connected by a plus sign (+), for example, Ctrl + X. This notation indicates that you press and hold down the first key while you press the second key. For example, “press Ctrl + X” indicates to press and hold down the Ctrl key while pressing the X key. Then release both keys.
5. RM/COBOL Compile and Runtime Command line options may be specified either with or without a hyphen. If any option on a command line is preceded by a hyphen, then a leading hyphen is required for all options. When assigning a value to an option, the equal sign is optional if leading hyphens are used.
6. Note the distinction of the following terminology:
 - The term “window” refers to a delineated area of the screen, normally smaller than the full screen.
 - In this document, the term “Windows” refers to the following Microsoft 32-bit Windows operating systems: Microsoft Windows 2000, Windows XP, Windows Server 2003, Windows Vista, or Windows Server 2008, unless specifically stated otherwise.

Note

- Beginning with version 11, RM/InfoExpress no longer supports earlier Microsoft Windows operating systems, including Microsoft Windows 98, Windows 98 SE, Windows Me, and Windows NT 4.0.

Additionally, in this document, any references to those versions, or to the shorthand notation “Windows 9x-class” or “Windows NT-class” referring to those operating systems, are included for historical purposes only.

Registration

Please take a moment register your Liant product online at: <http://www.liant.com>.

Registering your product entitles you to the following benefits:

- **Customer support.** Free 30-day telephone support, including direct access to support personnel and 24-hour message service.
- **Special upgrades.** Free media updates and upgrades within 60 days of purchase.
- **Product information.** Notification of upgrades or revisions to RM/InfoExpress when they are released.

You can also receive up-to-date information about Liant Software and all its products via our web site. Check back often for updated content.

Technical Support

Liant Software Corporation is dedicated to helping you achieve the highest possible performance from the Liant family of products. The technical support staff is committed to providing you prompt and professional service when you have problems or questions about your Liant products.

These technical support services are subject to Liant's prices, terms, and conditions in place at the time the service is requested.

While it is not possible to maintain and support specific releases of all software indefinitely, we offer priority support for the most current release of each product. For customers who elect not to upgrade to the most current release of the products, support is provided on a limited basis, as time and resources allow.

Support Guidelines

When you need assistance, you can expedite your call by having the following information available for the technical support representative:

1. Company name and contact information.
2. Liant product serial number (found in the Electronic Software Delivery email, on the media label, or in the product banner message).
3. Liant product version number.
4. Operating system and version number.
5. Hardware, related equipment, and terminal type.
6. Exact message appearing on screen.
7. Concise explanation of the problem and process involved when the problem occurred.

Test Cases

You may be asked for an example (test case) that demonstrates the problem. Please remember the following guidelines when submitting a test case:

- The smaller the test case is, the faster we will be able to isolate the cause of the problem.
- Do not send full applications.
- Reduce the test case to the smallest possible combination of components required to reproduce the problem.
- If you have very large data files, write a small program to read in your current data files and to create new data files with as few records as necessary to reproduce the problem.
- Test the test case before sending it to us to ensure that you have included all the necessary components to recompile and run the test case. You may need to include an RM/COBOL configuration file.

When submitting your test case, please include the following items:

1. **README text file that explains the problems.** This file must include information regarding the hardware, operating system, and versions of all relevant software (including the operating system and all Liant products). It must also include step-by-step instructions to reproduce the behavior.
2. **Program source files.** We require source for any program that is called during the course of the test case. Be sure to include any copy files necessary for recompilation.
3. **Data files required by the programs.** These files should be as small as possible to reproduce the problem described in the test case.

Chapter 1: Installation and Verification

This chapter lists the hardware and software required to use RM/InfoExpress for TCP/IP (Transmission Control Protocol/Internet Protocol), detailing the differences between the server and client program requirements. Chapter 1 also provides instructions for setting up and installing RM/InfoExpress on Windows and UNIX, and outlines procedures for verifying that RM/InfoExpress is properly installed.

System Requirements

This section describes the requirements necessary for installing the RM/InfoExpress server and client components. The version of RM/InfoExpress that you have purchased is for a particular combination of hardware and operating systems. Several items listed below vary depending on the actual version of the product that you have purchased.

Before you can use RM/InfoExpress, your personal computer configuration must meet or exceed the requirements set forth in this section.

RM/InfoExpress Server Program

The following sections list the minimum hardware and software requirements for running the RM/InfoExpress server program.

Required Hardware

One of the following hardware systems is required to install the RM/InfoExpress server program:

- An IBM PC or compatible machine capable of running Microsoft Windows 2000 Server (SP3 or later), Microsoft Windows Server 2003, or Microsoft Windows Server 2008.
- A machine capable of running a supported UNIX or Linux operating system.

Note Most Liant products are distributed electronically. If you elect to receive physical media, an optical drive capable of reading a CD-ROM (for the product) and a 3.5" floppy drive (for the license) are required at installation time.

Required Software

The RM/InfoExpress server program is supported on the following operating systems:

- Microsoft 32-bit Windows servers:
 - Windows 2000 Server (SP3 or later)
 - Windows Server 2003
 - Windows Server 2008
- UNIX (or UNIX-based) servers:
 - HP-UX 11
 - IBM AIX 5.2
 - Intel UNIX System V Release 4
 - Linux (2.6 kernel or later, 32-bit and 64-bit)
 - SCO OpenServer 5
 - SCO SVR5 (UnixWare 7.1.1 or later and SCO OpenServer 6)
 - Sun Solaris SPARC (2.9) and Intel x86 (2.9)

RM/InfoExpress consists of two server programs:

- The RM/InfoExpress for Microsoft 32-bit Windows server software contains the following files:
 - the main program, **rmsrvtcp.exe**
 - the server display (or screen handler) program, **rmdistcp.exe**
- The RM/InfoExpress for UNIX server software contains the following files:
 - the main program, **rmservtcp**
 - the server display (or screen handler) program, **rmdisptcp**
 - a file security parameter file update utility program, **ixsecure.cob**

RM/InfoExpress Client Program

By default, the RM/InfoExpress client program (**rmtcp32.dll** on Windows or **librminfo.so** on UNIX) is installed by the standard installation procedure for RM/COBOL for Windows and RM/COBOL for UNIX. The hardware and software system requirements for the RM/InfoExpress client program are exactly the same as the system requirements for the RM/COBOL runtime system (**runcobol**). For more information, see the appropriate chapters on installation and system considerations for UNIX and Microsoft Windows in the *RM/COBOL User's Guide*.

Setup and Installation

The section includes setup guidelines and instructions for installing the RM/InfoExpress server and client components.

The RM/InfoExpress for TCP/IP media contains a number of individual files and programs. The media contains a README file, which lists the actual files and programs delivered. For a list of known problems and recovery tips, refer to the section “Problems in This Release” in the README file.

Note The RM/InfoExpress server software should be installed only on the machine on which it is to run. If appropriately licensed, the RM/COBOL runtime system with the RM/InfoExpress client software may be installed on a UNIX server machine or a Windows server machine.

RM/InfoExpress Servers

This section describes how to set up and install the RM/InfoExpress server software on 32-bit Windows servers and UNIX server machines.

Setting Up the TCP/IP Package for RM/InfoExpress Servers on Windows and UNIX

Before you install the RM/InfoExpress server program, you must first ensure that the complete TCP/IP package has been installed and set up on your Windows and UNIX server machines.

Make certain that the **hosts** and **services** files are included. On Windows, these files are usually in the `\windows-directory\system32\drivers\` directory, where *windows-directory* is the name of the directory where Windows is installed. On UNIX, the files are usually named `/etc/hosts` and `/etc/services`.

- The **hosts** file lists the IP (Internet Protocol) addresses and host name(s) of all machines (clients and servers) that are connected to your network. As an alternative to using a **hosts** file on every machine, you can use DSN (Domain Name Service). One machine or a few machines run DNS; all of the other machines on the network access DNS to resolve names to IP addresses.

CAUTION On some machines, the RM/InfoExpress server program may terminate with a “Signal (11) caught” (segmentation fault) error message when accessed by a client if the `/etc/hosts` file on the server machine does not contain the entries required by RM/InfoExpress. The client would most likely receive a “COBOL I/O error 30, Runtime Library error 12006.” The solution to the problem is to add the entries to the `/etc/hosts` file.

- The **services** file lists the service name and port number/protocol of all available services. The **rmaddsvc** program will update the **services** file during setup in order to add the following line:

```
RMFileServer 21069/tcp
```

No other line may contain RMFileServer (in any mixture of uppercase or lowercase letters), and no other line may contain the port number 21069. If port number 21069 is

already in use, select another unused port number. We recommend that you choose a port number between 5000 and 32000.

Note The user must ensure that the RMCFileServer line in the **services** file is identical on every machine (clients and servers) on the network.

Installing RM/InfoExpress Server on Windows

You can install the RM/InfoExpress server program on Windows by using the following methods:

- [Electronic Software Delivery Installation for Windows](#) (as described below)
- [CD-ROM Installation](#) (on page 12)

To verify that the installation was successful, see [Verifying the RM/InfoExpress Server](#) (on page 21) and [Verifying RM/InfoExpress Windows Client and Server Communication](#) (on page 23).

Electronic Software Delivery Installation for Windows

Note You must have an Internet connection and an Internet browser installed to proceed with this latter method of installation.

The email containing notification of your Electronic Software Delivery contains an attachment, a file named **liant.lic**. This file is a license certificate authorizing you to install the purchased software. We recommend that you create a directory on your machine to store the license certificates for your Liant products and save the **liant.lic** attachment to this directory with a name that is meaningful to you.

The RM/InfoExpress server program is available as a download from the Liant Electronic Software Delivery web site in two formats: Windows Self-Extracting EXE and ISO CD Image. From the web site, simply follow the download and decompress instructions for the file format selected, and then perform the installation instructions for that format, as outlined below.

- **Windows Self-Extracting EXE.** After downloading and decompressing the deliverables, and creating the installation components directory from the Windows Self-Extracting EXE format, follow these steps to install the RM/InfoExpress server program on Windows:

Note When the Windows Self-Extracting EXE is decompressed and the installation components directory is created, the **LiantInstall** program should start automatically. If this is the case, proceed to step 6. Otherwise, begin with step 1. Be sure to login as Administrator and close any other applications that may be running before you begin.

1. Place a copy of your RM/InfoExpress license certificate, **liant.lic**, in the directory containing the installation components.
2. Click **Start**, and then click **Run**. In the Run dialog box, click the **Browse** button.
3. In the Browse dialog box, navigate to the directory containing the installation components.
4. Click on the file, **LiantInstall**, and then click **Open**.
5. In the Run dialog box, click **OK**.

6. The **LiantInstall** program begins executing. Follow the instructions presented on the screen and press the **Next** button to advance through the various pages.
7. On the Software License Agreement page, you must click “I accept the terms in the license agreement” in order to continue with the installation.
8. On the License Certificates page, the license certificate file for the product being installed is displayed. Do one of the following:
 - If the license certificate for RM/InfoExpress server software being installed is present in the list area, press the **Next** button.
 - If the license certificate for the RM/InfoExpress server software being installed is *not* present in the list area:
 - a. Press the **Add** button.
 - b. In the Select License Certificates dialog box, navigate to the directory containing the license certificate file for the RM/InfoExpress server software being installed and select the filename for the license certificate. (This license file, named **liant.lic**, is attached to the original electronic software delivery email for the product.)
 - c. Press the **Open** button and then press **Next**.
9. On the Installation Type page, do one of the following:
 - Select the “Standard Installation” option to install all the components of all the license certificates listed on the License Certificates page immediately, using their default settings. Press the **Install** button.
 - Select the “Custom Installation” option to select specific components (for those products with multiple components) of all license certificates listed on the License Certificates page, and install them, changing their default installation settings, as necessary.

Follow the custom installation instructions presented on the remaining pages. On the Ready to Begin Installations page, press the **Install** button.

When the installation for the RM/InfoExpress server components starts, follow the additional instructions presented by the installation program.
10. When either the standard or custom installation is complete, click the **Finished** button on the Installation Status page.

Note The RM/InfoExpress server is installed and run as a Windows service.

- **ISO CD Image.** The download format for ISO CD Image contains the full RM/InfoExpress product CD. Use CD-ROM Burning software, such as Nero (<http://www.nero.com>) or Roxio’s Easy CD Creator (<http://www.roxio.com>), to create the physical CD-ROM media. Follow the instructions described in [CD-ROM Installation](#) (on page 12) to install your product.

CD-ROM Installation

After downloading and decompressing the deliverables, and creating the installation components directory from the ISO CD Image format, follow these steps to install the RM/InfoExpress server program on Windows:

1. Log in as Administrator. Liant also recommends that you close any other applications that may be running.
2. Insert the RM/InfoExpress Server Program CD-ROM in the appropriate CD-ROM drive.
3. Do one of the following:
 - If the installation program starts automatically, proceed to Step 4.
 - If the installation program does *not* start automatically, click **Start**, and then click **Run**. In the Open text box of the Run dialog box, type the following:

```
d:LiantInstall
```

where, *d* is the drive letter of the CD-ROM drive. Click **OK**.

4. The **LiantInstall** program begins executing. Follow the instructions presented on the screen and press the **Next** button to advance through the various pages.
5. On the Software License Agreement page, you must click “I accept the terms in the license agreement” in order to continue with the installation.
6. On the License Certificates page, the license certificate for the product being installed is displayed. Do one of the following:
 - If the license certificate for the RM/InfoExpress server software being installed is present in the list area, press the **Next** button.
 - If license certificates for any products you do *not* wish to install are present in the list area, select them and press the **Remove** button. Then, press the **Next** button.
 - If the license certificate for the RM/InfoExpress server software being installed is *not* present in the list area:
 - a. Press the **Add** button.
 - b. In the Select License Certificates dialog box, navigate to the directory containing the license certificate file for the RM/InfoExpress server software being installed and select the filename for the license certificate.

This license file, usually named **liant.lic**, is included on the license diskette that came as part of the installation media.
 - c. Press the **Open** button and then press **Next**.

Note The **liant.lic** license certificate file can be copied from the diskette to a location on a hard drive and that location can be specified during installation. We recommend that you create a separate directory on your machine to store the license certificate files for all of your Liant products and save those files with a name that is meaningful to you.

7. On the Installation Type page, do one of the following:
 - Select the “Standard Installation” option to install all the components of all the license certificates listed on the License Certificates page immediately, using their default settings. Press the **Install** button.
 - Select the “Custom Installation” option to select specific components (for those products with multiple components) of all license certificates listed on the License Certificates page, and install them, changing their default installation settings, as necessary.

Follow the custom installation instructions presented on the remaining pages. On the Ready to Begin Installations page, press the **Install** button.

When the installation for the RM/InfoExpress components starts, follow the additional instructions presented by the installation program.
8. When either the standard or custom installation is complete, click the **Finished** button on the Installation Status page.

Note The RM/InfoExpress server is installed and run as a Windows service.

Installing RM/InfoExpress Server on UNIX

You can install the RM/InfoExpress server program on UNIX by using the following methods:

- [Electronic Software Delivery Installation for UNIX](#) (as described below)
- [CD-ROM Installation](#) (on page 14)

To verify that the installation was successful, see [Verifying the RM/InfoExpress Server](#) (on page 21) and [Verifying RM/InfoExpress UNIX Client and Server Communication](#) (on page 26).

Electronic Software Delivery Installation for UNIX

Note You must have an Internet connection and an Internet browser installed to proceed with this latter method of installation.

The email containing notification of your Electronic Software Delivery contains an attachment, a file named **liant.lic**. This file is a license certificate authorizing you to install the purchased software. We recommend that you create a directory on your machine to store the license certificates for your Liant products and save the **liant.lic** attachment to this directory with a name that is meaningful to you.

The RM/InfoExpress server program is available as a download from the Liant Electronic Software Delivery web site in two formats: UNIX GUNZIP TAR and ISO CD Image. From the web site, simply follow the download and decompress instructions for the file format selected, and then perform the installation instructions for that format, as outlined below.

- **UNIX GUNZIP TAR.** After downloading and decompressing the deliverables, and creating the installation components directory from the UNIX GUNZIP TAR format, follow these steps to install the RM/InfoExpress server program on UNIX:
 1. Place a copy of your RM/InfoExpress license certificate, **liant.lic**, in the directory containing the installation components.
 2. Change to the directory containing the installation components. For example, enter:

```
cd /RMStage
```

3. Execute the installation script using the following command:

```
sh ./install.sh
```

4. Follow the prompts and instructions on the screen to complete the installation.

Messages are displayed periodically indicating the status of the installation.

RM/InfoExpress is distributed with a default configuration that will satisfy your system requirements. Additional configuration options for your system are discussed in [Appendix D: Configuring RM/InfoExpress](#) (see page 91).

- **ISO CD Image.** The download format for ISO CD Image contains the full RM/InfoExpress product CD. Use CD-ROM Burning software, such as Nero (<http://www.nero.com>) or Roxio's Easy CD Creator (<http://www.roxio.com>), to create the physical CD-ROM media. Follow the instructions described in [CD-ROM Installation](#) (see the following section) to install your product.

CD-ROM Installation

There are four main steps to installing the RM/InfoExpress server program for UNIX from the downloaded format of the ISO CD image:

1. [Load the license file](#) (see the following topic).
2. [Load the distribution media](#) (see page 18).
3. [Perform the installation](#) (see page 19).
4. [Unload the distribution media](#) (see page 19).

Loading the License File

The Liant license file, **liant.lic**, is a normal text file distributed on an MS-DOS-formatted diskette. This file is a license certificate authorizing you to install the purchased software. Not all UNIX operating systems, however, can read an MS-DOS-formatted diskette, and not all UNIX server machines have diskette drives. To make the license file available to the RM/InfoExpress server for UNIX installation script, two techniques are provided:

1. [Mounting the diskette as an MS-DOS file system](#) (see the following topic).
2. [Transferring the Liant license file via FTP from a Windows client](#) (see page 17).

Mounting the Diskette as an MS-DOS File System

Use this option to load the license file if the UNIX operating system supports MS-DOS file systems and your hardware has a diskette drive installed. Instructions for specific platforms and versions of UNIX are provided. In the examples below, the license certificate file, **liant.lic**, is placed in the directory `/tmp`. We recommend, however, that you create a directory on your machine to store the license certificates for your Liant products and save the **liant.lic** file to this directory with a name that is meaningful to you.

- **HP-UX 11, IBM AIX 5.2, and Intel UNIX System V Release 4.** These platforms do not support mounting MS-DOS diskettes. To transfer the license file to the UNIX server, use the [FTP instructions](#) (see page 17).

- **Linux (kernel 2.6)**

- a. Insert the diskette into the diskette drive.
- b. Log in as root and enter:

```
mount -t msdos /dev/fd0H1440 /mnt/floppy
```

- c. Copy the license file to the `/tmp` directory:

```
cp /mnt/floppy/liant.lic /tmp/liant.lic
```

- d. Dismount the diskette with the following command and then remove the diskette from the diskette drive:

```
umount /mnt/floppy
```

- **SCO OpenServer 5**

- a. Insert the diskette into the diskette drive.
- b. Log in as root and enter:

```
mount -f DOS,lower /dev/fd0 /floppy
```

Note It may be necessary to create the mount directory, `/floppy`, before executing this command.

- c. Copy the license file to the `/tmp` directory:

```
cp /floppy/liant.lic /tmp/liant.lic
```

- d. Dismount the diskette with the following command and then remove the diskette from the diskette drive:

```
umount /floppy
```

- **SCO SVR5 (UnixWare 7.1.1 or later and SCO OpenServer 6)**

- a. Insert the diskette into the diskette drive.
- b. Log in as root and enter:

```
mount -F dosfs /dev/dsk/f0q18dt /Disk_A
```

- c. Copy the license file to the /tmp directory:

```
cp /Disk_A/liant.lic /tmp/liant.lic
```

- d. Dismount the diskette with the following command and then remove the diskette from the diskette drive:

```
umount /Disk_A
```

- **Sun Solaris SPARC (2.9) and Intel x86 (2.9)**

- a. Insert the diskette into the diskette drive.
- b. Log in as root and enter:

```
volcheck
```

- c. Copy the license file to the /tmp directory:

```
cp /floppy/liant/liant.lic /tmp/liant.lic
```

- d. Dismount the diskette with the following command and then remove the diskette from the diskette drive:

```
eject floppy
```

Transferring the Liant License File via FTP from a Windows Client

To transfer the Liant license file, **liant.lic**, from a Windows client to the UNIX server, use one of the many graphical FTP utilities available on Windows and transfer the **liant.lic** file as a text file. You can also follow the procedure described below. We recommend that you create a directory on your machine to store the license certificates for your Liant products and save the **liant.lic** file to this directory with a name that is meaningful to you

1. On the Windows client, insert the diskette into the diskette drive.

These instructions assume that this is drive A. If it is another drive, change the drive letter to the appropriate letter in the remaining instructions.

2. Open a Command Prompt window by clicking **Start** on the task bar, point to **Programs**, point to **Accessories**, and then click **Command Prompt**.
3. Connect to the UNIX server by entering:

```
ftp UnixServerName
```

where, *UnixServerName* is the network name of your UNIX server.

4. Change the directory to the /tmp directory:

```
cd /tmp
```

5. Specify a text file transfer:

```
ascii
```

6. Send the license file to the UNIX server:

```
send A:\LIANT.LIC liant.lic
```

7. Disconnect from the UNIX server:

```
bye
```

8. Close the Command Prompt window with the following command and then remove the diskette from the diskette drive:

```
Exit
```

Loading the Distribution Media

To load the distribution media on the UNIX machine:

1. Insert the RM/InfoExpress server for UNIX CD in the appropriate CD-ROM drive.
2. Log in as root.
3. Enter the appropriate mount command for your system. See the examples listed below.

Notes

- In the list that follows, */cdrom* is used as the mount directory name for all the UNIX operating systems. Some UNIX systems, however, already have an established mount directory for the CD-ROM. In this case, substitute the standard mount directory name for */cdrom* in the following list and in the subsequent instructions.
- The device names below are examples. The actual device name is dependent on the hardware configuration of your UNIX server. It may be necessary to substitute the proper value for your system. If needed, consult your UNIX System Administrator for more details.

System	Mount Command
HP-UX 11	<code>mount -F cdfs -o ro,cdcase /dev/dsk/c0t4d0 /cdrom</code>
IBM AIX 5.2	<code>mount -o ro -v cdrfs /dev/cd0 /cdrom</code>
Intel UNIX System V Release 4	<code>mount -o ro -F cdfs /dev/cdrom/c0t4l0 /cdrom</code>
Linux (2.6 kernel)	<code>mount -o ro -t iso9660 /dev/cdrom /mnt/cdrom</code>
SCO OpenServer 5	<code>mount -o ro -f ISO9660,lower /dev/cd0 /cdrom</code>
SCO SVR5 (UnixWare 7.1.1 or later and SCO OpenServer 6)	<code>mount -F cdfs -o ro /dev/cdrom/c1b0t0l0 /CD-ROM_1</code>
Sun Solaris SPARC (2.9) and Intel x86 (2.9)	If Solaris does not automatically load the CD-ROM, log in as root and enter: <code>volcheck</code>

Performing the Installation

After the CD-ROM has been successfully mounted, you will need to do the following:

1. Change the directory to the mount point for the CD-ROM. For example, enter:

```
cd /cdrom
```

2. From the mount point, execute the installation script using the following command:

```
sh ./install.sh
```

3. Follow the prompts and instructions on the screen to complete the installation.

Messages are displayed periodically indicating the status of the installation.

Unloading the Distribution Media

To unload (remove) the distribution media from the hardware:

1. Change your directory to a location other than the CD-ROM mount point directory, as described in [Loading the Distribution Media](#) (on page 18).
2. Enter the appropriate command for your system. See the examples listed below.
3. Remove the distribution media from the CD-ROM drive.

System	Umount Command
HP-UX 11 IBM AIX 5.2 Intel UNIX System V Release 4 SCO OpenServer 5	<code>umount /cdrom</code>
Linux (2.6 kernel or later)	<code>umount /mnt/cdrom</code>
SCO SVR5 (UnixWare 7.1.1 or later and SCO OpenServer 6)	<code>umount /CD-ROM_1</code>
Sun Solaris SPARC (2.9) and Intel x86 (2.9)	<code>eject cdrom</code>

RM/InfoExpress Clients

This section describes how to set up and install the RM/InfoExpress client software on Windows and UNIX workstations.

Setting Up the TCP/IP Package for RM/InfoExpress Clients on Windows and UNIX

In order for RM/InfoExpress clients to access the RM/InfoExpress server, you must make sure that you have installed and configured the TCP/IP communication protocol package correctly on 32-bit Windows and UNIX client workstations.

For both Windows and UNIX implementations, you may need to modify the **hosts** file and **services** file:

- The **hosts** file lists the IP (Internet Protocol) addresses and host name(s) of all machines (clients and servers) that are connected to your network. As an alternative to using a **hosts** file on every machine, you can use DNS (Domain Name Service). One machine or a few machines run DNS; all of the other machines on the network access DNS to resolve names to IP addresses.
- The **services** file lists the service name and port number/protocol of all available services.

On Windows, you must locate and edit the **services** file for your Windows Sockets implementation to add the following line, whereas on UNIX, the **rmaddsvc** program will automatically update the services file during setup:

```
RMCFfileServer 21069/tcp
```

Verify that no other line contains RMCFfileServer (in any mixture of uppercase or lowercase letters) and that no other line contains the port number 21069. If port number 21069 is already in use, select another unused port number. We recommend that you choose a port number between 5000 and 32000.

Note The user must ensure that the RMCFfileServer line in the **services** file is identical on every machine (clients and servers) on the network.

Installing RM/InfoExpress Clients on Windows and UNIX

The RM/InfoExpress Windows 32-bit client program (**rmtcp32.dll**) is installed by default when you select the “Standard Installation” option when installing RM/COBOL for Windows. However, if you did not install it, run the RM/COBOL installation procedure again, selecting the “Custom Installation” option to install only the RM/InfoExpress Client feature. If you wish to run the client verification program, choose the Verification Suite option also. To verify that the installation was successful, see [Verifying the RM/InfoExpress Windows Client](#) (on page 23).

The RM/InfoExpress UNIX client program (**librminfo.so**) is installed by default with RM/COBOL for UNIX. The RM/COBOL for UNIX runtime uses the **librminfo.so** support module (a shared object) to provide access to the RM/InfoExpress server. To verify that the installation was successful, see [Verifying RM/InfoExpress UNIX Client and Server Communication](#) (on page 26).

Verification

For both the RM/InfoExpress client and server software components, the first step in system verification is to confirm that the TCP/IP network software is running correctly on the client machine as well as the server machine.

For RM/InfoExpress client verification, follow all the vendor's recommendations making sure you have properly configured the TCP/IP network and that the software is running correctly. System utilities, such as **ping**, can help ensure proper configuration and/or communication between the client and server machines.

Verifying the RM/InfoExpress Server

The following procedures verify that the RM/InfoExpress server programs have been installed correctly for 32-bit Windows and UNIX operating systems, and that they can run properly.

Note Only one RM/InfoExpress server program may be active on any given server machine.

Windows Server

The RM/InfoExpress server for Windows is installed as, and is intended to be run as, a Windows service, under the direction of the Windows Service Control Manager (SCM). Initially, the server is configured to be started and stopped manually. However, it can easily be reconfigured to start automatically when Windows is initialized, as described in [Configuring the RM/InfoExpress Windows Server Program](#) (on page 33).

Note For information on specifying server configuration options on Windows, see the following topics:

- [Windows Server Command Line Options](#) (on page 34)
- [Windows Server Display Command Line Option](#) (on page 35)
- [Appendix D: Configuring RM/InfoExpress](#) (on page 91)

To start the RM/InfoExpress server for Windows:

1. Click **Start** on the task bar.
2. On Windows 2000 Server, Windows Server 2003, and Windows Server 2008, start the Windows Service Control Manager:
 - a. Click **Run**.
 - b. In the Open text box of the Run dialog box, type the following and then click **OK**:

```
services.msc
```

- c. Select **RM/InfoExpress Server** in the list of services.
- d. To start the service, press the **Start the service** link located to the left, or right-click over the service name and select **Start** from the pop-up menu.

These actions will launch the RM/InfoExpress server program for Windows, which initially runs under the System account and has access to any resources that this account is permitted to use. (Most systems log on to a System account, rather than a user

account.) To change the account under which the server program runs, see [Configuring the RM/InfoExpress Windows Server Program](#) (on page 33).

3. In the RM/InfoExpress folder, double-click the **rmdistcp** icon to start the RM/InfoExpress server display program.

The RM/InfoExpress server main screen is displayed, as illustrated in [Figure 3: Server Display Main Screen](#) (see page 47). The server is ready to process requests from client machines.

Note The RM/InfoExpress Windows server display program, **rmdistcp.exe**, monitors the server activity and does not affect the communication between the client and server.

If the server main screen does not appear, check that no other RM/InfoExpress server program is already running on the machine. If other messages are displayed, contact Liant technical support services.

Note The RM/InfoExpress Windows server program can also be launched in user mode using the icon created by default in the RM/InfoExpress program folder. To start the server, simply double-click on the RM/InfoExpress Windows server icon. The server will run using the current account and will be terminated when you log out. When launched in this mode, there is also a small, 10- to 20-second delay before the server becomes active.

UNIX Server

On the UNIX server machine, start the RM/InfoExpress UNIX server and server display programs, **rmservertcp** and **rmdisptcp**, by entering the following commands:

```
/usr/rminfo/rmservertcp
```

```
/usr/rminfo/rmdisptcp -t
```

The RM/InfoExpress server main screen is displayed, as illustrated in [Figure 3: Server Display Main Screen](#) (see page 47). The server is ready to process requests from client machines. If the server main screen does not appear, check that no other RM/InfoExpress server program is already running on the machine. If other messages are displayed, contact Liant technical support services.


Note For information on specifying server configuration options on UNIX, see the following topics:

- [UNIX Server Command Line Options](#) (on page 30)
- [UNIX Server Display Command Line Option](#) (on page 31)
- [Appendix D: Configuring RM/InfoExpress](#) (on page 91)

Verifying the RM/InfoExpress Windows Client

If you choose both the RM/InfoExpress Client and Verification Suite features when installing RM/COBOL for Windows, a program-item icon labeled **ixverify** is created in the RM/COBOL program folder. Choose this icon to invoke the RM/InfoExpress Windows client verification program. The RM/InfoExpress Client WinSock Info message box is displayed in the center of the screen, as illustrated in [Figure 1](#).

Figure 1: RM/InfoExpress Client WinSock Info Message Box



If no message box appears, the RM/InfoExpress Windows client software is not properly installed or started. Check that the RM/InfoExpress Windows client DLL file (**rmtcp32.dll**) exists in your application installation directory.

Note This client verification does not attempt to connect to any server. It simply verifies that the Windows Sockets implementation is sufficient to allow the RM/InfoExpress Windows client DLL to be loaded and run.

Verifying RM/InfoExpress Windows Client and Server Communication

The following procedures verify that the RM/InfoExpress Windows client program can correctly communicate with the RM/InfoExpress server program using the TCP/IP communication protocol. We recommend that you first read Chapter 3: *Installation and System Considerations for Microsoft Windows*, in the *RM/COBOL User's Guide*, for more information.

1. Start the RM/InfoExpress server program running on the server machine, as described in [Verifying the RM/InfoExpress Server](#) (on page 21).
2. Select the RM/COBOL folder from the Windows desktop.
3. Copy the RM/COBOL Runtime folder icon to a new icon:
 - a. Choose the RM/COBOL Runtime icon by clicking the mouse pointer on the icon.
 - b. Right-click the RM/COBOL Runtime icon and choose the Copy option from the menu.
 - c. Move the mouse pointer to a new location, right-click, and choose the Paste option from the menu.

Note An alternative procedure to Steps 3 (b) and (c) is to hold down the Ctrl key and the mouse button simultaneously while dragging the icon to a new location. Then select the copied icon by clicking on it.

4. Modify the properties of the copied icon:
 - a. Right-click on the copy of the RM/COBOL Runtime icon and choose the Rename option from the menu.
 - b. Type a new name for the icon (for example, IXDEMO) and press Enter.
 - c. Right-click on the renamed copy of the RM/COBOL Runtime icon and choose the Properties option from the menu. The Properties dialog box is displayed.
 - d. Select the Shortcut tab.
 - e. Press End to enter input at the end of the existing command and then press Backspace to erase the question mark.
 - f. Do one of the following:

- For a UNIX server, enter the following:

```
\\server\usr\rminfo\infoxdmo x=rmtcp32.cfg
```

- For a Windows server, enter the following:

```
\\server\infoxdmo x=rmtcp32.cfg
```

Note You may type either backslashes (\) or forward slashes (/) to separate the edgenames of the path, but do not mix them. Notice the double backslashes or double forward slashes at the beginning. Substitute the actual machine name of your server machine (where the RM/InfoExpress server program is running as described in Step 1) for *server*. This name is usually displayed as Machine ID at the bottom of the server main screen, but it is whatever name is specified in your **hosts** file or known to your DNS that maps to the IP address of the UNIX server machine.

- Under UNIX, the rest of the pathname assumes that RM/InfoExpress was installed into **/usr/rminfo** during the server installation procedure. If it was installed elsewhere, substitute the correct pathname.
- Under Windows, RM/InfoExpress is normally installed in the **\Program Files\Liant\RMInfoExpress** directory, which is the server's current directory.

Step 4 (f) also adds a configuration record file to the **runcobol** command. This configuration record file (**rmtcp32.cfg**) is used by **ixverify**. It must reside in the directory named in the Working Directory text box shown in the Program Item Properties dialog box. This file should contain the following information:

```
EXTERNAL-ACCESS-METHOD CREATE-FILES=YES NAME=RMTCP32 OPTIONS='I'
```

If you make an error, click Cancel and return to the beginning of Step 4.

- g. Click OK or press Enter to complete the modification. The dialog box closes and the new icon appears.
5. Run the new icon by double-clicking on it or pressing Enter with the icon selected.
6. The RM/InfoExpress Client WinSock Info message box is displayed on the screen, as described in [Verifying the RM/InfoExpress Windows Client](#) (on page 23).

Note This message box is displayed because the **OPTIONS='I'** keyword is specified on the EXTERNAL-ACCESS-METHOD configuration record in the **rmtcp32.cfg** file. In a production environment, omit **OPTIONS='I'** so that the message box will not be displayed.

7. Click OK or press Enter to acknowledge the message box.

The **infoxdmo** verification program window displays the following information:

```
RM/InfoExpress Verification Program
  1. RM/COBOL                      File Test
  2. RM/InfoExpress                 File Test
  3. Exit Program

Enter test number
```

- a. If a return code 252 error (STOP sign) box is displayed, the **infoxdmo** verification program could not be loaded from the server.
- b. If a “COBOL I/O error 30, Runtime Library error 11004” is displayed, the server name has probably been entered incorrectly. Click OK or press Enter. Return to Step 5 and then specify the correct server name in Step 6. If the server name was correct, check that the **hosts** file (or DNS) contains the server name and that the **services** file contains the proper [RMCFfileServer line](#) (see page 20).
- c. If “COBOL procedure error 204” is displayed, the server name is correct but the remaining path is incorrect. Click OK or press Enter. Return to Step 5 and then specify the correct pathname in Step 6.
- d. Other return code values and other error codes are described in the *RM/COBOL User’s Guide*, and in [Appendix A: Messages](#) (see page 71) of this manual. If an error message occurs, check the following:
 - The status of the RM/InfoExpress server. (Is it still running?)
 - The pathname on the server machine of the **infoxdmo** verification program.
 - The server name in your **hosts** file.
 - The RMCFfileServer entry in your **services** file.

If you cannot determine the cause of the problem and correct it, contact Liant technical support services.

8. At the “Enter test number” prompt, type 2 and press Enter. The following prompt is displayed:

```
Enter remote directory where files are to be created.
```

9. Enter the name of the directory on the RM/InfoExpress server where the files are to be created. For example:

```
\\server\usr\rminfox
```

The directory must already exist on the server machine, and the RM/InfoExpress server user must have read and write permissions to it.

The **infoxdmo** verification program creates one indexed file (**inxfl**) and performs five tests: write sequential, read sequential, read random, rewrite random, and delete random. Timing information for each test is shown.

10. When the five tests are complete, the “Type any key to continue . . .” prompt is displayed. At this point, RM/InfoExpress Windows client and server communication verification is successfully complete.

You may run other tests in the verification program, run test number 2 specifying a different server, or exit the program.

Verifying the RM/InfoExpress UNIX Client

To verify that the RM/InfoExpress UNIX client shared object program can be loaded, execute the RM/COBOL runtime with the `-v` option to display the banner with a list of support modules loaded by the RM/COBOL runtime system.

```
runcobol xxx -v
```

The shared object, **librminfo.so**, should be listed under the “Dynamic libraries loaded” section, as illustrated below.

```
RM/COBOL Runtime - Version nn.nn for IBM AIX.  
RM/COBOL Runtime System issued to any Company Name.  
Configured for one user.  
Copyright (c) 1985-2nnn by Liant Software Corp. All rights reserved.  
Registration Number: 8C-1000-15537-0001  
  
RM/COBOL: Dynamic libraries loaded:  
($XEDIR=.)  
$XEDIR/librmterm.so - Termino Terminal Interface - Version nn.nn.  
$XEDIR/librminfo.so - RM/InfoExpress Client - Version nn.nn.
```

If the **librminfo.so** shared object does not appear in the Dynamic libraries loaded list, then the RM/InfoExpress UNIX client is not properly installed. Check that the RM/InfoExpress UNIX client shared object (**librminfo.so**) exists in the same directory as the RM/COBOL runtime (**runcobol**).

Verifying RM/InfoExpress UNIX Client and Server Communication

The following procedures verify that the RM/InfoExpress UNIX client program can correctly communicate with the RM/InfoExpress server program using the TCP/IP communication protocol. We recommend that you first read Chapter 2: *Installation and System Considerations for UNIX*, in the *RM/COBOL User's Guide*, for more information.

1. Start the RM/InfoExpress server program running on the server machine, as described in [Verifying the RM/InfoExpress Server](#) (on page 21).
2. Run the verification program, **infoxdmo**, using the RM/InfoExpress UNIX client program, **librminfo.so**, by entering the following command:

```
runcobol infoxdmo
```

The shared object, **librminfo.so**, will be loaded automatically by the RM/COBOL runtime system (**runcobol**).

3. Check that your `PATH` environment variable is set to point to the directory where **librminfo.so** and **runcobol** are installed, and the `RUNPATH` environment variable is pointing to the directory where **infoxdmo.cob** is present.

Note The **infoxdmo.cob** utility program may reside on your UNIX or Windows server machine. You can load the program across the network by specifying the server path in the `RUNPATH` environment variable. For example: `RUNPATH=//server/path`. Remember, however, when setting environment variables on UNIX, you must use

forward slashes; for example, `RUNPATH=\\server\path`. Under UNIX, backslashes are treated as escape characters.

The **infoxdmo** verification program window displays the following information:

```
RM/InfoExpress Verification Program
  1. RM/COBOL                      File Test
  2. RM/InfoExpress                 File Test
  3. Exit Program

Enter test number
```

- a. If a “COBOL I/O error 30” is displayed, look at the explanation in [Appendix A: Messages](#) (on page 71) or in the *RM/COBOL User's Guide*, for the corresponding error.
- b. For any RM/InfoExpress error, check the following:
 - The status of the RM/InfoExpress server. (Is it still running?)
 - The server name in your **hosts** file.
 - The [RMCFileServer entry](#) (see page 20) in your **services** file.

If you cannot determine the cause of the problem and correct it, contact Liant technical support for assistance.

4. At the “Enter test number” prompt, type 2 and press Enter. The following prompt is displayed:

```
Enter remote directory where files are to be created.
```

5. Enter the name of the directory on the RM/InfoExpress server where the files are to be created. For example:

```
//server/usr/rminfox
```

Note You may type either backslashes (\) or forward slashes (/) to separate the edgenames of the path, but do not mix them. Notice the double backslashes or double forward slashes at the beginning. Substitute the actual machine name (in uppercase) of your server machine (where the RM/InfoExpress server program is running as described in Step 1) for *server*. This name is usually displayed as Machine ID at the bottom of the server main screen, but it is whatever name is specified in your **hosts** file or known to your DNS that maps to the Internet Protocol address of the server machine.

The directory must already exist on the server machine and the RM/InfoExpress server must have read and write permissions to it.

The **infoxdmo** verification program creates one indexed file (**inxfl**) and performs five tests: write sequential, read sequential, read random, rewrite random, and delete random. Timing information for each test is shown.

6. When the five tests are complete, the “Type any key to continue...” prompt is displayed. At this point, RM/InfoExpress client and server communication verification is complete.

You may run other tests in the verification program, run test number 2 specifying a different server, or exit the program.

Chapter 2: Configuring and Running the RM/InfoExpress Server

This chapter describes the procedures required to configure and run (start) the RM/InfoExpress servers for UNIX and Windows.

Server Configuration Options

RM/InfoExpress server configuration options can be set either in the server configuration file (**rmixsrvr.ini**) or on the command line. The command line specification overrides the configuration file setting. While Liant recommends that you specify the configuration options in the server configuration file, the ability to specify configuration options on the command line ensures backward compatibility with previous releases, and enables special, temporary invocations of the server without affecting the settings in the configuration file. For example, there may be times when it would be helpful to specify the **-d** option in order to create a debug file to send to Liant technical support services.

All command line options have a configuration file equivalent. However, starting with version 2.1, all new program options must be specified in the configuration file. There is no command line equivalent.

For more information, see [Appendix D: Configuring RM/InfoExpress](#) (on page 91).

Starting the RM/InfoExpress UNIX Server Program

On the UNIX server machine, start the RM/InfoExpress UNIX server and server display (screen handler) programs, **rmservertcp** and **rmdisptcp**, by entering:

```
/usr/rminfo/rmservertcp [-option]
```

```
/usr/rminfo/rmdisptcp [-option]
```

Notes

- The RM/InfoExpress UNIX server display program, **rmdisptcp**, monitors the server activity and does not affect the communication between the client and server. On some machines, the server daemon may take a few seconds to initialize the underlying network. If the server display (**rmdisptcp**) is invoked immediately after the server is started, the server display program will wait until the network initialization is complete.
- If you start **rmservertcp** in a UNIX window opened using a telnet session on your workstation, then you may not be able to close the telnet session until the server is terminated. Always start the server from a terminal connected to the UNIX machine.

The RM/InfoExpress server main screen is displayed, as illustrated in [Figure 3: Server Display Main Screen](#) (on page 47). The server is ready to process requests from client machines. If the server main screen does not display, follow the instructions in [Verifying the RM/InfoExpress Server](#) (on page 21).

The following sections describe the server program and server display program command line options.

UNIX Server Command Line Options

Command line options of the RM/InfoExpress UNIX server program (**rmservertcp**) can be any of the following:

- **-c n|u|l**. Indicates how the cases of pathnames from the clients are converted. The **-c** option has three values:
 - **-c n**. Indicates that no filename mapping is performed. This is the default value.
 - **-c u**. Indicates that the entire filename is mapped to uppercase before the Open request is attempted. The option may be specified as **-c upper**, if desired.
 - **-c l**. Indicates that the entire filename is mapped to lowercase before the Open request is attempted. The option may be specified as **-c lower**, if desired.

Note The **-c** command line option is equivalent to the `ConvertFileName` configuration option, which is discussed in [UNIX Server-Specific Configuration Options](#) (on page 101). The command line option overrides the configuration option.

- **-d pathname**. This option causes the file *pathname* to be created and trace information to be written into it. After the RM/InfoExpress server program is terminated, send this file to Liant technical support services for further investigation. Use this option only when you are investigating a problem with the help of Liant technical support services. Under normal conditions, using this option affects server operations negatively.

Note The `-d` command line option is equivalent to the `InfoxDebug` configuration option, as described in [Common Configuration Options](#) (on page 93). The command line option overrides the configuration option.

- **-k *dddd***. Indicates the maximum number of clients to be served. If more clients are to be served, the server should be brought down and started again. The default value is 50. This value cannot be greater than the number of clients for which the server is licensed.

Note The `-k` command line option is equivalent to the `UseCount` configuration option, which is described in [Common Server-Specific Configuration Options](#) (on page 99). The command line option overrides the configuration option.

- **-p *nnnnn***. Indicates the common buffer pool size. Do not change the default value for this parameter unless instructed by Liant technical support services.

Note The `-p` command line option is equivalent to the `FileBufferPool` configuration option, as explained in [Common Server-Specific Configuration Options](#) (on page 99). The command line option overrides the configuration option.

- **-z *nnnnn***. Indicates the maximum amount of data that can be handled by the TCP `send` function. The default value is system-dependent and has been set by Liant. Do not specify this parameter unless instructed to do so by Liant technical support services.

Note The `-z` command line option is equivalent to the `MaxSendSize` configuration option, which is discussed in [Common Configuration Options](#) (on page 93). The command line option overrides the configuration option.

UNIX Server Display Command Line Option

The following is an option for the RM/InfoExpress UNIX server display (screen handler) program, `rmdisptcp`:

- **-t**. Indicates that the user is requesting to terminate the server or communication to a particular client. If this option is not specified, the user can terminate only the server display program. Because the server display program does not support any configuration file, this option must be specified on the command line.

For example, the following command will allow the user to terminate the server program:

```
rmdisptcp -t
```

Starting and Stopping the RM/InfoExpress Windows Server Program

On the Windows server machine, it is necessary to start the Windows Service Control Manager (SCM) in the Windows Control Panel to run the RM/InfoExpress server software. Initially, the server is configured to be started and stopped manually. However, it can easily be reconfigured to start automatically when Windows is initialized, as described in [Configuring the RM/InfoExpress Windows Server Program](#) (on page 33).

Note See the description of the command line options for the [Windows server](#) and the [Windows server display](#) programs, beginning on page 35.

Starting the Server

To stop the RM/InfoExpress server for Windows:

1. Click **Start** on the task bar.
2. On Windows 2000 Server, Windows Server 2003, and Windows Server 2008, start the Windows Service Control Manager:
 - a. Click **Run**.
 - b. In the Run dialog box, in **Open**, type the following and then click **OK**:

```
services.msc
```
 - c. Select **RM/InfoExpress Server** in the list of services.
 - d. To start the service, press the **Start the service** link located to the left, or right-click over the service name and select **Start** from the pop-up menu.

These actions will launch the RM/InfoExpress server program for Windows, which initially runs under the System account and has access to any resources that this account is permitted to use. (Most systems log on to a System account, rather than a user account.) To change the account under which the server program runs, see [Configuring the RM/InfoExpress Windows Server Program](#) (on page 33).

3. In the RM/InfoExpress folder, double-click on the **rmdistcp** icon to start the RM/InfoExpress server display program.

The RM/InfoExpress server main screen is displayed, as illustrated in [Figure 3: Server Display Main Screen](#) (on page 47). The server is ready to process requests from client machines. (The RM/InfoExpress Windows server display program, **rmdistcp.exe**, monitors the server activity and does not affect the communication between the client and server.)

Note Beginning in version 8, the **-t** command line option is automatically added to the server display program icon. The **-t** option allows you to terminate a server or the communication to a particular client when the server display program is terminated.

If the server main screen does not appear, check that no other RM/InfoExpress server program is already running on the machine. If other messages are displayed, contact Liant technical support services.

Note The RM/InfoExpress Windows server program also can be launched in user mode using the icon created by default in the RM/InfoExpress program folder. To start the server, simply double-click on the RM/InfoExpress Windows server icon. (You may wish to add command line options to the Target command line in the Shortcut tab of the Properties dialog box for the icon, or you may use the command line options from a DOS command line. For more information about Windows shortcuts, see “Creating a Windows Shortcut” in Chapter 3: *Installation and System Considerations for Microsoft Windows*, in the *RM/COBOL User’s Guide*.) The server will run using the current account and will be terminated when you log out. When launched in this mode, there is also a small, 10- to 20-second delay before the server becomes active.

Stopping the Server

To stop the RM/InfoExpress server for Windows:

1. Start the Windows Service Control Manager (SCM) and find the server in the list of services, as described previously.
2. On Windows 2000 Server, Windows Server 2003, and Windows Server 2008, click the **Stop the service** link located to the left, or right-click over the service name and click **Stop** from the pop-up menu.

The RM/InfoExpress server will terminate.

Note The server can also be terminated from within the RM/InfoExpress server display program (**rmdistop.exe**) when that program is started with the -t option. When halted in this manner, it is possible that the Windows Service Control Manager (SCM) will not detect that the server has terminated. To restart the server, first stop the service and then start the service again, using the methods described in the previous topic.

Configuring the RM/InfoExpress Windows Server Program

It is possible to configure the RM/InfoExpress Windows server program to load automatically when Windows is started and to run under a specific log on account. Instructions follow for both configurations.

Starting the Server Automatically

To configure the RM/InfoExpress server to load automatically when Windows is started:

1. Start the Windows Service Control Manager and find the server in the list of services, as described in [Starting and Stopping the RM/InfoExpress Windows Server Program](#) (on page 31).
2. On Windows 2000 Server, Windows Server 2003, and Windows Server 2008, right-click over the service name and select **Properties** from the pop-up menu.
3. Under Startup Type, select **Automatic**.

The server will now be loaded automatically the next time Windows is started.

Running Under a Specific Log On Account

To configure the server to run under a specific account, take the following steps:

1. Start the Windows Service Control Manager and find the server in the list of services, as described in [Starting and Stopping the RM/InfoExpress Windows Server Program](#) (on page 31).
2. On Windows 2000 Server, Windows Server 2003, and Windows Server 2008, right-click over the service name and select **Properties** from the pop-up menu.
3. In the Properties dialog box, select the **Log On** tab.
4. Under the **Log On As** option, select either the **Local System Account** option to run the server under the default account, or enter the name and password of a selected account to run under another account.

Note Most services log on to a System account, rather than a user account.

Windows Server Command Line Options

Command line options for the RM/InfoExpress Windows server program (**rmsrvtcp.exe**), when launched from the icon or from a DOS command line, can be any of the following:

- **-d *pathname***. This option causes the file *pathname* to be created and trace information to be written into it. After the RM/InfoExpress server program is terminated, send this file to Liant technical support services for further investigation. Use this option only when you are investigating a problem with the help of Liant technical support services. Under normal conditions, using this option affects server operations negatively.

Note The **-d** command line option is equivalent to the InfoxDebug configuration option, as described in [Common Configuration Options](#) (on page 93). The command line option overrides the configuration option.

- **-k *dddd***. Indicates the maximum number of clients to be served. If more clients are to be served, the server should be brought down and started again. The default value is 50. This value cannot be greater than the number of clients for which the server is licensed.

Note The **-k** command line option is equivalent to the UseCount configuration option, which is described in [Common Server-Specific Configuration Options](#) (on page 99). The command line option overrides the configuration option.

- **-p *nnnnn***. Indicates the common buffer pool size. Do not change the default value for this parameter unless instructed by Liant technical support services.

Note The **-p** command line option is equivalent to the FileBufferPool configuration option, as explained in [Common Server-Specific Configuration Options](#) (on page 99). The command line option overrides the configuration option.

- **-z *nnnnn***. Indicates the maximum amount of data that can be handled by the TCP **send** function. The default value is system-dependent and has been set by Liant. Do not specify this parameter unless instructed to do so by Liant technical support services.

Note The **-z** command line option is equivalent to the MaxSendSize configuration option, which is discussed in [Common Configuration Options](#) (on page 93). The command line option overrides the configuration option.

Windows Server Display Command Line Option

The following is an option for the RM/InfoExpress Windows server display (screen handler) program, **rmdistcp.exe**:

- **-t**. Indicates that the user is requesting to terminate the server or communication to a particular client. If this option is not specified, the user can terminate only the screen display program. Because the server display program does not support any configuration file, this option must be specified on the command line.

For example, the following command will allow the user to terminate the server program:

```
rmdistcp.exe -t
```


Chapter 3: Using RM/InfoExpress with RM/COBOL for Windows Programs

This chapter describes the procedures required to use RM/InfoExpress with RM/COBOL for Windows programs, including how to access the RM/InfoExpress Windows client program, how RM/COBOL for Windows programs point to network data files, and how to execute RM/COBOL for Windows programs for use with RM/InfoExpress.

Note For information on how to start the RM/InfoExpress server programs on either Windows or UNIX, refer to the appropriate sections in [Chapter 2: Configuring and Running the RM/InfoExpress Server](#) (on page 29).

Accessing the RM/InfoExpress Windows Client Program

The RM/InfoExpress Windows client program is **rmtcp32.dll**. The RM/COBOL runtime system for Windows (**runcobol**) invokes the client program automatically when an EXTERNAL-ACCESS-METHOD record, specifying NAME=RMTCP32, is included in the RM/COBOL configuration file. See the EXTERNAL-ACCESS-METHOD configuration record section in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*, for more information.

Note The OPTIONS='I' keyword, which causes an informative message box to be displayed, normally should not be specified on the EXTERNAL-ACCESS-METHOD configuration record. Other client-specific configuration options are described in [Appendix D: Configuring RM/InfoExpress](#) (on page 91).

Pointing to Network Data Files

This section describes several different methods that can be used in an RM/COBOL for Windows program to specify the pathnames of remote network data files, which are to be accessed by RM/InfoExpress.

Specifying Synonyms

Generally, RM/COBOL programs contain synonyms in the *file-access-name* field of the SELECT clause. For example:

```
SELECT INX-FILE ASSIGN TO RANDOM, "inxfl"
```

The synonyms are mapped to the actual pathname before executing the RM/COBOL program.

Synonym specification depends on the operating system on which the runtime system application and the RM/InfoExpress client software are running. If you are using RM/COBOL for Windows, synonyms are specified by setting properties.

For example, to access a file on a UNIX server from a Windows client, set the following synonym:

```
inxfl=\\Unix_server\usr\infox\inxfl
```

In this example, the synonym **inxfl** points to a file **inxfl** in directory **infox** of directory **usr** on a UNIX server, **Unix_server**. It is also possible to use DOS environment variables (created with the DOS SET command) as synonyms if the Windows runtime system is started with a command line from a DOS box running under Windows. For more information, refer to the "Directory Search Sequences" section in Chapter 3: *Installation and System Considerations for Microsoft Windows*, of the *RM/COBOL User's Guide*.

Here are three examples using synonyms:

Example 1

```
inxfl=\\Unix_server\usr\infox\inxfl
```

Example 2

```
relfl=Q:\usr\infox\relfl
```

Example 3

```
inxfl=\\Win_server\SharedFiles\inxfl
```

where,

inxfl and **relfl** (specified on the left side of the SET expression) are both synonyms.

Unix_server is the name of the UNIX server accessed by RM/InfoExpress, as shown in the **hosts** file or as known by DNS.

Q is a drive letter mapped to a UNIX server.

\usr\infox\inxfl and **\usr\infox\relfl** are the pathnames on the server.

Win_server is the name of the Windows server, as shown in the **hosts** file or as known by DNS.

SharedFiles is the share name known to the Windows server running on *Win_server*.

In Examples 1 and 3, RM/InfoExpress is able to process the **inxfl** file because the pathname begins with double backslashes (\\). It could also begin with double forward slashes (/).

In Example 2, RM/InfoExpress is unable to process the **relfl** file because it is not using the appropriate naming convention. Processing, however, is handled through conventional network access.

Thus, for RM/COBOL files specified by filename only, you may access server files by using a synonym that points to a server directory.

Specifying RUNPATH Environment Variables

Specifying an RM/InfoExpress server in one of the RUNPATH components causes RM/COBOL to access the file using RM/InfoExpress. For example:

```
RUNPATH=C:\prog;N:\data;\\Unix_server\usr\data;  
          \\Win_server\Shares\data
```

causes RM/COBOL to search for a file first in the directory **prog** on the local disk C; then in the directory **data** on the network drive **N:** (assuming that drive N is mapped to a network volume) using conventional network access; next in the subdirectory **data** of directory **usr** on the server **Unix_server** using RM/InfoExpress; and lastly, in the directory **data** in whatever directory is associated with the **Shares** share name on **Win_server** using RM/InfoExpress.

For more information on the RUNPATH environment variable specification, refer to the "Locating RM/COBOL Files" section in Chapter 3 of the *RM/COBOL User's Guide*.

Specifying Explicit Pathnames in the RM/COBOL Program

You must change the pathname in the SELECT clause of the RM/COBOL program for filenames that include drive specifiers, computer names, or directory paths, and that do not already point to a server directory. For example:

```
SELECT DATA-FILE ASSIGN TO RANDOM,  
       "\\Unix_server\usr\infox\data.fil"
```

This type of pathname specification makes the program less portable, however, because whenever the location of the file **data.fil** changes (from one server to another), you must recompile the source program.

Specifying Complete Pathnames Using RM/COBOL Data-Names

Some RM/COBOL programs use data-names to change pathnames dynamically. For example, the SELECT statement:

```
SELECT INX-FILE ASSIGN TO RANDOM, DATA-FIL
```

In this example, DATA-FIL is the data-name defined in the DATA DIVISION, and it contains the complete pathname of the file at the time the file was opened. These data-names must include the name of a UNIX machine or the Windows server on which an RM/InfoExpress server is running. For example, DATA-FIL could contain the following:

```
\\Unix_server\usr\infox\data.fil
```

Executing RM/COBOL Programs

Execute your RM/COBOL program by entering the following command line, as described in the “System Configuration” section of Chapter 3: *Installation and System Considerations for Microsoft Windows*, of the *RM/COBOL User’s Guide*.

```
runcobol name [option]
```

where,

name points to RM/COBOL object files.

option is any valid RM/COBOL Runtime Command option.

Before executing the **runcobol** command, set up the environment to create and access files on the server machine, and create a configuration file to define the external access method.

Execute the RM/COBOL verification suite for Windows, as described in Chapter 5: *System Verification*, of the *RM/COBOL User’s Guide*.

Chapter 4: Using RM/InfoExpress with RM/COBOL for UNIX Programs

This chapter describes the procedures required to use RM/InfoExpress with RM/COBOL for UNIX programs, including:

- How to access the RM/InfoExpress UNIX client program.
- How RM/COBOL for UNIX programs point to network data files.
- How to execute RM/COBOL for UNIX programs for use with RM/InfoExpress.

Note For information on how to start the RM/InfoExpress server programs on either UNIX or Windows, refer to the appropriate sections in [Chapter 2: Configuring and Running the RM/InfoExpress Server](#) (on page 29).

Accessing the RM/InfoExpress UNIX Client Program

The RM/InfoExpress client shared object for UNIX is named **librminfo.so**.

By specifying the keyword NAME=NONE on the EXTERNAL-ACCESS-METHOD record in the configuration file, you can bypass the RM/InfoExpress UNIX client code in **librminfo.so**. See the EXTERNAL-ACCESS-METHOD configuration record section in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*, for more information.

Pointing to Network Data Files

This section describes several different methods that can be used in an RM/COBOL for UNIX program to specify the pathnames of remote network data files, which are to be accessed by RM/InfoExpress.

Specifying Synonyms

Generally, RM/COBOL programs contain synonyms in the *file-access-name* field of the SELECT clause. For example:

```
SELECT INX-FILE ASSIGN TO RANDOM, "inxfl"
```

The synonyms are mapped to the actual pathname before executing the RM/COBOL program.

Synonym specification depends on the operating system on which the runtime system application and the RM/InfoExpress client software are running. For example, to access a file on a UNIX server from a UNIX client, execute the following command (assuming Bourne shell) prior to invoking the client:

```
inxfl=//UNIX_SERVER/usr/infox/inxfl; export inxfl
```

In this example, the synonym **inxfl** points to a file **inxfl** in directory **infox** of directory **usr** on a UNIX server, **UNIX_SERVER**. See also the description of synonyms in the “Directory Search Sequences” section in Chapter 2: *Installation and System Considerations for UNIX*, of the *RM/COBOL User’s Guide*.

Specifying RUNPATH Environment Variables

Specifying an RM/InfoExpress server in one of the RUNPATH components causes RM/COBOL to access the file using RM/InfoExpress. For example:

```
RUNPATH=/usr/local/infox://UNIX_SERVER/usr/data://  
Win_server/Shares/data
```

causes RM/COBOL to search for a file first in the directory **/usr/local/infox** on the local disk using conventional network access; then in the directory **data** in directory **usr** on **UNIX_SERVER** using RM/InfoExpress; and lastly, in the directory **data** in whatever directory is associated with the **Shares** share name on **Win_server** using RM/InfoExpress.

For more information on the RUNPATH environmental variable specification, refer to the “Locating RM/COBOL Files” section in Chapter 2 of the *RM/COBOL User’s Guide*.

Specifying Explicit Pathnames in the RM/COBOL Program

For filenames that include directory paths and that do not already point to a server directory, you must change the pathname in the SELECT clause of the RM/COBOL program. For example:

```
SELECT DATA-FILE ASSIGN TO RANDOM,  
      "//UNIX_SERVER/usr/infox/data.fil"
```

This type of pathname specification makes the program less portable, however, because whenever the location of the file **data.fil** changes (from one server to another), you must recompile the source program.

Specifying Complete Pathnames Using RM/COBOL Data-Names

Some RM/COBOL programs use data-names to change pathnames dynamically. For example, the SELECT statement:

```
SELECT INX-FILE ASSIGN TO <RANDOM> DATA-FIL
```

In this example, DATA-FIL is the data-name defined in the DATA DIVISION, and it contains the complete pathname of the file at the time the file was opened. These data-names must include the name of a UNIX machine or the Windows server on which an RM/InfoExpress server is running. For example, DATA-FIL could contain the following:

```
//UNIX_SERVER/usr/infox/data.fil
```

Executing RM/COBOL Programs

Execute your RM/COBOL program by entering the following command line on the terminal of your UNIX client machine:

```
librminfox name [option]
```

where:

name points to RM/COBOL object files.

option is any valid RM/COBOL Runtime Command option.

Before executing the **librminfox** command, set up the environment to create and access files on the server machine.

Execute the RM/COBOL verification suite for UNIX, as described in Chapter 5: *System Verification*, of the *RM/COBOL User's Guide*.

Chapter 5: RM/InfoExpress Server Operations

The RM/InfoExpress user interface is implemented for UNIX character-based terminals and the Windows console interface. The RM/InfoExpress server display (screen handler) program examines information and data from the server and client, and updates the screen once every second.

CAUTION Multiple RM/InfoExpress server display programs, with screens other than the main screen displayed, may affect server performance. As long as a server display program is running with its main menu selected, it does not noticeably affect server performance.

Keyboard Functions

The following list describes the keys used in the RM/InfoExpress server display program.

Key	Action
<i>n N</i>	Any command or response may be selected by pressing the first character of the command. Case is not important. For example: S for Select file, t for Terminate, or a number, if appropriate.
Escape (Esc)	Selects No in response to a query from the command line. Also backtracks through a menu path.
Home	Returns to the RM/InfoExpress server display main screen.
Up Arrow	Moves the cursor up during client or file selection.
Down Arrow	Moves the cursor down during client or file selection.
Left Arrow	Moves the cursor left during the selection of menu commands and responses.
Right Arrow	Moves the cursor right during the selection of menu commands and responses.
Page Up (PgUp) or Ctrl+B	Scrolls the screen up to examine and review client and file information.
Page Down (PgDn) or Ctrl+F	Scrolls the screen down to examine and review client and file information.
Enter	Chooses the currently highlighted item for command and response selection, and for individual client or file selection.

Server Display Screen Format

Except for the main screen (illustrated on the following page), each RM/InfoExpress server display program screen has the same basic format, as illustrated in [Figure 2](#).

Figure 2: Server Display Screen Format

Files	Client name	User name	Messages	System type
1	scoaware	porting	729	UNIX
1	vogon	qa	3	UNIX
0	rs6000	support	309	UNIX
0	WCUBED	Michael	208	MS_WINDOWS

The elements of the RM/InfoExpress server display screen are described as follows:

- **Activity area.** The activity area contains information related to the current activity or server display screen.
- **Command line.** The command line, located at the bottom of the screen, shows command names, user prompts, or user queries.
- **Date.** The date area displays the current system date.
- **Product name.** The product name displays the product name and version information.
- **Time.** The time area displays the current system time.
- **Title line.** The title line displays the name of the server display screen.

Server Display Commands

The first screen you see when you start the RM/InfoExpress server display program is the RM/InfoExpress main screen, as illustrated in [Figure 3](#).

Figure 3: Server Display Main Screen

```

                                LIANT SOFTWARE CORPORATION
                                RM/InfoExpress Version nn.nn
                                Copyright 1986-2nnn All Rights Reserved
                                Liant Software Corporation
                                Registration Number: 9D-0090-10016-0016
                                2:53 pm Sunday, July 31, 2nnnn Up 10 days
                                Active clients 4
                                Open files (unique, all, max) 4 6 100
                                Dynamic load 0.0 %
                                Messages processed 1,296
                                Machine ID: MyCOMPUTER
                                Command: Clients Files Log Terminate
  
```

The RM/InfoExpress server display main screen lists the current time, date, the uptime (in days), and identifies the RM/InfoExpress server machine (in the Machine ID field). It also provides an overview of current network activity, including the following:

- The Active clients field indicates the total number of clients currently connected to this RM/InfoExpress server. Other programs using RM/COBOL are not shown.
 Note that the active client count on the main screen of the server display program sometimes shows a value that is more than the number of clients actually connected. This behavior is most noticeable when sessions are established and released rapidly.
- The Open files field records a count of the number of files currently open. The first number indicates the number of unique files that are currently opened. The second number indicates the total number of all files currently opened by all clients. The third number is the maximum number of open files allowed (you may increase this number by using the [FileCount option](#), described on page 99, in the server configuration file, **rmixsrvr.ini**).
- The Dynamic load field shows the percentage of CPU utilization by the server.
- The Messages processed field indicates the number of client requests honored by the server.

The command line at the bottom of the server display main screen contains the following command options:

- **Clients.** This command lists all clients and reports on specific clients. Clients may be selected any time the Clients field appears in the command line. For more information, see [Client Information](#) (on page 48).
- **Files.** This command lists all currently open files and reports on specific files. Files may be selected any time the Files field appears in the command line. For more information, see [File Information](#) (on page 50).

- **Log.** This command provides access to two sub-screens: Open Log and Error Log. Select log information from a command line or by pressing the letter **L** at any time. For more information, see [Open Log Information](#) (on page 51) and [Error Log Information](#) (on page 52).
- **Terminate.** This command provides a number of termination modes. Terminate may be selected any time the Terminate field appears in the command line. For more information, see also [Termination of Communication Activity](#) (on page 53).

Each command and its associated screens, prompts, and queries are described in the following sections. To return to the server display main screen from any of the following screens, press the letter **M** or choose **Main** from the command line.

Client Information

The Client Information screen, illustrated in [Figure 4](#), is displayed when you choose the **Clients** command from the RM/InfoExpress server display main screen.

Figure 4: Client Information Screen

RM/InfoExpress Version nn.nn 3:21 pm Tuesday, September 25, 2nnn				
Client Information				
Files	Client name	User name	Messages	System type
1	scoware	porting	729	UNIX
1	vogon	qa	3	UNIX
0	rs6000	support	309	UNIX
0	WCUBED	Michael	208	MS_WINDOWS

Command: **Select Client** Files Main Terminate

The Client Information screen lists all active clients by name, the number of files each client has open, the total number of messages processed for each client, and the type of operating system on which the client is running. Whenever there are more clients or files than can be displayed on a single screen, a message is displayed on the screen advising that Page Up or Page Down may be used to request the previous or next screen.

Use the command **Select Client** to select a particular client in order to see information that is more detailed. Press Enter or the letter **S** to choose the **Select Client** command. The following prompt is displayed on the command line:

```
Select Client to display (using PgUp, PgDn, or Arrow keys)
```

Use Page Up, Page Down, or the arrow keys to select a client and press Enter. The Client Files screen is displayed, as illustrated in [Figure 5](#).

Figure 5: Client Files Screen

```
RM/InfoExpress Version nn.nn          3:22 pm          Tuesday, September 25, 2nnn
-----
Client Files
-----
ga@vogon has      1 files open:          3 messages
-----
ORG  OPEN  ACCESS  FILENAME
-----
INX  I-O   Dynamic  c:\rminfox\rmqa\INXFA
-----
Command:  Clients      Files      Main      Terminate
```

The Client Files screen shows the total number of files currently opened by the client, and the total number of messages passed between the client and the server. For each open file, the Client Files screen also shows the following information.

- The ORG column indicates the file organization:
 - INX (Indexed)
 - SEQ (Sequential)
 - REL (Relative)
- The OPEN column indicates the type of open mode:
 - I-O (Input/Output)
 - Input
 - Output
 - Extend
- The ACCESS column indicates the type of access:
 - Dynamic
 - Sequent(ial)
 - Random
- The FILENAME column indicates the absolute pathname.

File Information

The File Information screen, illustrated in [Figure 6](#), is displayed when you choose the **Files** command from the RM/InfoExpress server display main screen.

Figure 6: File Information Screen

```
RM/InfoExpress Version nn.nn          3:23 pm          Tuesday, September 25, 2nnn
-----
File Information
-----
Open count      File name
-----
1               c:\rminfox\rmqa\INXFA
1               d:\rminfox\PINXFL
-----
Command:  Clients      Select File      Main      Terminate
```

The File Information screen lists the absolute pathname for each file and the number of times each file has been opened. Whenever there are more clients or files than can be displayed on a single screen, a message is displayed on the screen advising that Page Up or Page Down may be used to request the previous or next screen.

Use the command **Select File** to select a particular file in order to see information that is more detailed. Press Enter or type the letter **S** to choose the **Select File** command. The following prompt is displayed on the command line:

```
Select file to display (using PgUp, PgDn or Arrow keys)
```

Use Page Up, Page Down, or the arrow keys to select a file and press Enter. The File Clients screen is displayed, as illustrated in [Figure 7](#).

Figure 7: File Clients Screen

```
RM/InfoExpress Version nn.nn          3:24 pm          Tuesday, September 25, 2nnn
-----
File Clients
-----
c:\rminfox\rmqa\INXFA open          1 times
-----
ORG  OPEN  ACCESS  USERNAME
-----
INX  Input  Sequent qa@vogon
-----
Command:  Clients      Files      Main      Terminate
```

The File Clients screen shows the number of clients that have opened this file since the server was initiated and lists the clients that currently have the file open. In addition to the user name of the client (USERNAME), this screen indicates the file organization (ORG), the type of open mode (OPEN), and the type of access (ACCESS) of the client. (For more explanation of [these columns](#), see page 49.)

Open Log Information

The Open Log screen, illustrated in [Figure 8](#), is displayed when you choose the **Log** command from the RM/InfoExpress server display main screen, and then choose the **Open Log** command or press the letter **O**. The Open Log screen displays information about a maximum of 24 previous opens by the server, beginning with the latest open.

Figure 8: Open Log Screen

RM/InfoExpress Version nn.nn		3:25 pm	Tuesday, September 25, 2nnn	
Open Log				
Client/User	File name	Error	Exist?	Org Time
scoware	d:\rminfox\PINXFL		Yes	INX 15:15:51
porting				
WCUBED	c:\rminfox\seqfl		Yes	SEQ 15:15:15
michael				
WCUBED	c:\rminfox\seqfl		Yes	SEQ 15:15:15
michael				
WCUBED	c:\rminfox\seqfl		Yes/No	SEQ 15:15:15
michael				
WCUBED	c:\rminfox\seqfl	35,01	Yes	SEQ 15:15:15
Michael				
HEADY	d:\rminfox\inxfl	35,01	Yes	INX 15:12:33
Rs6000				
support	c:\rminfox\relfl		Yes	REL 15:10:19
Rs6000				
support	c:\rminfox\relfl		Yes	REL 15:10:16
PgDn (Ctrl-F) for more				
Command:	Main	Freeze	Unfreeze	Toggle

Note On the Open Log screen and the [Error Log screen](#) (on page 52), filenames up to 32 characters long and client names up to 12 characters long can be displayed without loss of information. If necessary, use the DotsBias option, described in [Common Server-Specific Configuration Options](#) (on page 99), to control which part of longer filenames is lost. To navigate to the Error Log screen from this location, press the Esc key (to go back to the previous screen), followed by the letter **E**.

The command line provides three commands: **Freeze**, **Unfreeze**, and **Toggle**. To choose a command, use the arrow keys or press the first letter of the desired command.

- The **Freeze** command temporarily suspends the updating of the Open Log screen for that particular server display application. However, it does not affect the logging of the new opens into the data structures by the server.
- The **Unfreeze** command causes the server display program to update the Open Log screen with the information from the server data structures.
- The **Toggle** command causes the information on the Open Log screen to be displayed in a different form, illustrated in [Figure 9](#), which is useful for Liant technical support.

Figure 9: Open Log Screen (Toggled)

RM/InfoExpress Version nn.nn		3:25 pm		Tuesday, September 25, 2nnn	
Open Log					
Client/User	File name	Error	Flags	Org	Time
scoware	d:\rminfox\PINXFL		00,C9,28	INX	15:15:51
porting					
WCUBED	c:\rminfox\seqfl		80,89,0C	SEQ	15:15:15
michael					
WCUBED	c:\rminfox\seqfl		80,49,08	SEQ	15:15:15
michael					
WCUBED	c:\rminfox\seqfl		80,60,09	SEQ	15:15:15
michael					
WCUBED	c:\rminfox\seqfl	35,01	80,61,09	SEQ	15:15:15
michael					
HEADY	d:\rminfox\inxfl	35,01	80,E1,09	INX	15:12:33
rs6000					
support	c:\rminfox\relfl		80,FD,0C	REL	15:10:19
rs6000					
support	c:\rminfox\relfl		80,C9,08	REL	15:10:16
PgDn (Ctrl-F) for more					
Command:	Main	Freeze	Unfreeze	Toggle	

Error Log Information

The Error Log screen, illustrated in [Figure 10](#), is displayed when you choose the **Log** command from the RM/InfoExpress server display main screen, and then choose the **Error Log** command or press the letter **E**. The Error Log screen displays a maximum of 24 errors, beginning with the most recent error. It also lists the name of the client for which the error was issued, the error code detected by the server, the time the error occurred, the location within the RM/InfoExpress server code at which the error occurred, and an explanation (or status) of the error.

Figure 10: Error Log Screen

RM/InfoExpress Version nn.nn		3:28 pm		Tuesday, September 25, 2nnn	
Error Log					
Client/User	Error	Time	Loc	Command/Filename	
scoware	10	15:26:34	17	Read Next Record	
porting				d:\rminfox\PINXFL	
vogon	10	15:26:13	17	Read Next Record	
qa				c:\rminfox\rmqa\INXFA	
WCUBED	35,01	15:15:15	17	Open Output, File must exist	
michael				c:\rminfox\seqfl	
HEADY	35,01	15:12:33	17	Open Output, File must exist	
				d:\rminfox\inxfl	
rs6000	35,01	15:10:16	17	Open Output, File must exist	
support				c:\rminfox\relfl	
rs6000	30,12,3	15:09:45	17	Open Output, File may/may not exist	
support				C:\Program Fil...s\cdrvie\relfl	
rs6000	35,01	15:09:45	17	Open Output, File must exist	
support				C:\Program Fil...s\cdrvie\relfl	
PgDn (Ctrl-F) for more					
Command:	Main	Freeze	Unfreeze	Toggle	

Note On the Error Log screen and the [Open Log screen](#) (on page 51), filenames up to 32 characters long and client names up to 12 characters long can be displayed without loss of information. If necessary, use the DotsBias option, described in [Common Server-Specific Configuration Options](#) (on page 99), to control which part of longer filenames is lost. To navigate to the Open Log screen from this location, press the Esc key (to go back to the previous screen), followed by the letter **O**.

The command line provides three commands: **Freeze**, **Unfreeze**, and **Toggle**. To choose a command, use the arrow keys or press the first letter of the desired command.

- The **Freeze** command temporarily suspends the updating of the Error Log screen for that particular server display application. However, it does not affect the logging of the new errors into the data structures by the server.
- The **Unfreeze** command causes the server display program to update the Error Log screen with the information from the server data structures.
- The **Toggle** command causes the information on the Error Log screen to be displayed in a different form, illustrated in [Figure 11](#), which is useful for Liant technical support.

Figure 11: Error Log Screen (Toggled)

RM/InfoExpress Version nn.nn		3:28 pm		Tuesday, September 25, 2nnn	
Error Log					
Client/User	Error	Time	Loc	FAP	Message
scoware	10	15:26:34	17	01 FF 12 00 00 01 0A 03 01 06 19 01 82 1E	01 19 05 04 BC 0F 6B 00 07 10 53 69 61 72
porting					
vogon	10	15:26:13	17	01 FF 12 00 00 01 0A 03 01 06 19 01 82 1E	01 28 05 04 CC 0F 6B 00 0F 6B 00 24 06 00
qa					
WCUBED	35,01	15:15:15	17	01 FF 24 00 00 01 01 03 01 02 0A 01 1E 0D	01 08 0E 01 08 16 04 80 61 09 00 06 0D 5C
michael					
HEADY	35,01	15:12:33	17	01 FF 34 00 00 01 01 03 01 06 0A 01 1E 0D	01 08 0E 01 08 12 08 03 00 00 00 03 00 09
rs6000					
support	35,01	15:10:16	17	01 FF 24 00 00 01 01 03 01 04 0A 01 1E 0D	01 08 0E 01 08 16 04 80 E1 09 00 06 0D 2F
rs6000					
support	30,12,3	15:09:45	17	01 FF 24 00 00 01 01 03 01 04 16 04 80 E0	09 00 0A 01 1E 0D 01 08 0E 01 08 06 0D 2F
rs6000					
support	35,01	15:90:45	17	01 FF 24 00 00 01 01 03 01 04 0A 01 1E 0D	01 08 0E 01 08 16 04 80 E1 09 00 06 0D 2F

PgDn (Ctrl-F) for more

Command:	Main	Freeze	Unfreeze	Toggle
----------	------	--------	----------	--------

Termination of Communication Activity

The **Terminate** command provides access to a variety of termination nodes.

When you select the **Terminate** command from anywhere within the RM/InfoExpress server program, the Terminate command line is displayed, as illustrated in [Figure 12](#).

Figure 12: Terminate Command Line

Terminate:	Display	Client	Server
------------	---------	--------	--------

The **Terminate** commands are described in the next sections.

Note To avoid terminating the RM/InfoExpress server program accidentally, the default behavior of the RM/InfoExpress server display program has changed. When you start the screen display program, you can terminate only the screen display program itself, not the server program or communication to a particular client. The Terminate command line on the server display main screen will show only the Display command. However, if the **-t** option is specified on the command line for the server display program, then you may also terminate the server or communication to a particular client. The illustration in [Figure 12](#) and the following discussion assume that the **-t** option is specified for the screen display program. For more information, see [UNIX Server Display Command Line Option](#) (on page 31) and [Windows Server Display Command Line Option](#) (on page 35).

Termination of Server Display

It is possible to temporarily terminate the screen interface (server display program) in order to increase the processing power of the server. Press the letter **D** to choose the **Display** command from the Terminate command line. The server display program will be terminated without affecting the server or any clients.

Termination of Client Communications

Termination of communications between the client and server should be requested only if the particular client is interfering with other clients on the network (for instance, a runaway program has left a record locked). Keep in mind that any access to open files will result in I/O errors on shared files on the terminated client. This action does not remove the client program.

Press the letter **C** to choose the **Client** command from the Terminate command line. The Client Information screen (see [Figure 4](#) on page 48) is displayed with the following prompt at the command line:

```
Select Client to terminate (using PgUp, PgDn or Arrow Keys)
```

Use Page Up, Page Down, or the arrow keys to select a client and press Enter. The Client Files screen is displayed (see [Figure 5](#) on page 49) with the following prompt at the command line:

```
Terminate selected Client? No Yes
```

Press the letter **Y** to terminate communication. Press Enter or Escape or the letter **N** to cancel the command.

Note The use of the server display (screen handler) program is for administrative purposes only. When invoked multiple times, only one administrator should perform operations such as terminating clients.

Termination of the Server

To terminate the server, press the letter **S** from the Terminate command line. The following command line is displayed, as illustrated in [Figure 13](#).

Figure 13: Quit Command Line



```
Quit:      When Idle      In a while      Now
```

The **Quit** commands are described in the following sections.

Quit When Idle

Press the letter **W** to choose the **When Idle** command. The following prompt is displayed:

```
Quit when idle?
```

Press the letter **N** or press Escape to cancel the command. Otherwise, when all clients are idle, the following prompt is displayed:

```
Terminate Server Now? No Yes
```

Press the letter **Y** to terminate the server immediately. Press the letter **N**, Escape, or Home to cancel the command.

Quit in a While

Press the letter **I** to choose the **In A While** command. The following command line is displayed, as illustrated in [Figure 14](#).

Figure 14: Quit in a While Command Line

Quit in:	3 minutes	5 minutes	10 minutes	20 minutes
----------	-----------	-----------	------------	------------

When you choose one of the time options, the number of minutes will decrement as the specified time elapses. You can cancel the termination at any time by pressing the letter **N** or Escape. Otherwise, when all clients are idle, the following prompt is displayed:

```
Terminate Server Now? No Yes
```

Press the letter **Y** to terminate the server immediately. Press the letter **N**, Escape, or Home to cancel the command.

Quit Now

Press the letter **N** to choose the **Now** command. The following prompt is displayed:

```
Terminate Server Now? No Yes
```

Press the letter **Y** to terminate the server immediately. Press the letter **N**, Escape, or Home to cancel the command.

The recommended way to terminate the server is by using the command sequence (Terminate, Server, Now, Yes) of the screen display (screen handler) program when no active client is connected.

WARNING Never attempt to terminate one or more RM/InfoExpress UNIX server processes using the **kill** command. This may cause the server to terminate without cleaning up resources and closing open files. For example, using the **kill** command causes the server to exit without removing the IPC (Inter Process Communications) objects, such as shared memory segments and semaphores. As a result, when the server is started next time, it fails with server error code 1 (RMIX_API_ERR_SERVER_ALREADY_EXISTS). For more information, see [Removing IPC Objects After Server Failure](#) (on page 89) in Appendix C: *Troubleshooting*.

Chapter 6: File Security on the RM/InfoExpress UNIX Server

An important consideration in RM/InfoExpress is protecting the system and its data from unauthorized access. This chapter describes the implementation of file security on the RM/InfoExpress UNIX server and the authentication procedures performed by the server on various clients to grant access to the files on the server.

UNIX System Security

The basic security features of UNIX operating systems allow a user of a UNIX server to belong to one of three categories of file access: Owner, Group, and Others. Each category of users can have different access permissions to files. The possible file access permissions are read, write, and execute. For example, if only the Owner of the file has write permission, the UNIX operating system will prevent any other user from writing to the file.

On a standalone UNIX server, the operating system validates the authenticity of the user at login time using information stored in the system password file and other security files. In a networked, client/server environment, however, users may log in to the UNIX server from remote, non-UNIX clients. To validate users on these clients, UNIX uses other security database files such as `.rhosts` or `hosts.equiv`. For more information, see [rhosts File Entry](#) (on page 60).

Note The RM/InfoExpress UNIX server software does not look at `hosts.equiv`, nor does it use the `ruserok` function.

When a user on a remote client logs in to the UNIX server, the networking software on the client passes information to the server about that user, including the server user name, password, and client machine name. After the user has been authenticated, the user on the remote client is allowed to access the files on the server as one of the local users of that server. For more information on file security provided by the UNIX operating system, refer to your UNIX system documentation.

RM/InfoExpress File Security

The implementation of file security in RM/InfoExpress uses the UNIX system security philosophy to protect the files on the RM/InfoExpress UNIX server from unauthorized access by users on client machines. To be able to use the file security features of RM/InfoExpress, a security parameter file, **ixpwwfile**, must be created on each client machine and each UNIX server using the utility program, **ixsecure.cob**. For more information on this utility, see [Appendix E: RM/InfoExpress Security Parameter File Update Utility](#) (on page 105).

On a client machine, **ixpwwfile** contains information needed to connect the RM/InfoExpress client to different RM/InfoExpress UNIX servers. Similarly, on the server, **ixpwwfile** is created by the server administrator and contains information that permits different clients to be connected to this server. Only the server administrator should have read and write permissions to the server security parameter file.

The client passes information obtained from **ixpwwfile** to the server when a session is established. The server validates this information against the server's version of **ixpwwfile**.

RM/InfoExpress UNIX Server Security Levels

The RM/InfoExpress UNIX server can be invoked at one of six security levels using the configuration option, `ServerSecurityLevel=number`, where *number* has a value in the range of 0 through 5. These six security levels are described in [Table 1](#). Refer also to [Appendix D: Configuring RM/InfoExpress](#) (on page 91), for more information about server configuration.

If the `ServerSecurityLevel` option is absent in the configuration file, the server runs in “compatibility mode”; that is, the server behaves like a version 2.0 RM/InfoExpress UNIX server. See [Server Compatibility with Older and Newer Clients](#) (on page 61).

Note Older RM/InfoExpress clients can only connect to RM/InfoExpress servers running at security levels “compatible”, 0, or 1.

At other security levels, the server performs various tests on the client to validate its authenticity to access files on the server. These tests become more stringent as the security levels increase, which means that starting the server at level 5 provides the highest level of security to files on the server.

When the RM/InfoExpress UNIX server is run with security enabled, the server-user-name passed from the client is used, if possible, as the User ID while accessing files. If the server-user-name is not present (as is the case for older versions of the RM/InfoExpress client) or invalid, the server will either run the process with the default server user or disallow the client connection to the server. Only servers running at security level 0 or 1 will use the default server user. A server running at security level 0 or 1 will terminate with an error if the default server user is invalid. Servers running at security level 2 or higher will disallow the client connection unless the server-user-name is present and valid. See [Setting Up the Network to Run RM/InfoExpress with Security Enabled](#) (on page 62) for more information.

The RM/InfoExpress UNIX server security levels are summarized in [Table 1](#). Terminology used in the table is defined following the table.

Table 1: RM/InfoExpress UNIX Server Security Levels

Server Security Level	Requires	To
0	A valid server-user-name.	Verify that server-user-name is valid. If validation fails, server runs the process as the default server user.
1	A valid server-user-name. An appropriate entry in the .rhosts file	Verify that server-user-name and .rhosts entry are valid. If validation fails, server runs the process as the default server user.
2	A valid server-user-name. An appropriate entry in the .rhosts file.	Verify that server-user-name and .rhosts entry are valid. If validation fails, client connection is disallowed.
3	A valid server-user-name. An appropriate entry in the ixpwwfile file. The correct user password. The password is normally obtained from ixpwwfile on the client.	Verify that server-user-name and password are valid. If validation fails, client connection is disallowed.
4	A valid server-user-name. An appropriate entry in the .rhosts file. An appropriate entry in the ixpwwfile file. The correct user password. The password is normally obtained from ixpwwfile on the client.	Verify that server-user-name, .rhosts entry, ixpwwfile entry, and password are valid. If validation fails, client connection is disallowed.
5	A valid server-user-name. An appropriate entry in the .rhosts file. An appropriate entry in the ixpwwfile file. The correct user password. The user must enter the password on the client.	Verifies that server-user-name, .rhosts entry, ixpwwfile entry, and password entered by the user are valid. If validation fails, client connection is disallowed.

Server-User-Name

In [Table 1](#), a “valid server-user-name” means that the **ixpwwfile** file on the client contains an entry specifying the name of the server machine, the name of the client machine, and a valid user-name to be used on the server. For more information, see [ixpwwfile File Entry](#) (on page 60).

Default Server User

At security level 0 or 1, the server allows the client to run as a default user on the server when the client fails to meet the security requirements of the server. Normally, the default server user will be allowed to access files that do not require high levels of security. The default server user, which must be a valid user on the server, is specified using the configuration parameter, `DefaultServerUser`. For more information about this parameter, refer to [UNIX Server-Specific Configuration Options](#) (on page 101). See also the discussion of compatibility of older clients with the new server in [Server Compatibility with Older and Newer Clients](#) (on page 61).

.rhosts File Entry

The **.rhosts** file, present in each user's home directory on the server, is used by the UNIX operating system to validate the permissions of clients who try to access the files on the server owned by the local user. This ASCII file contains information about the client machine and one of its users. The following is a template for an entry line in the **.rhosts** file:

```
machine-name      [ user-name ]
```

where *machine-name* is the node name of a client machine, and *user-name* is the name of the user on that machine who, when connected to the server, will obtain the owner's permissions on files owned by the local user. If *user-name* is not found on the entry, all the users on the client machine have permission to access files.

Note *user-name* refers to the name used on the client machine, not on the server machine. The *user-name* may match the name used on the server machine, or it may be different.

An "appropriate entry in the **.rhosts** file" in [Table 1](#) (on page 59) means that the **.rhosts** file exists in server-user-name's home directory, the **.rhosts** file owner is server-user-name, only the owner has write permissions (that is, the file permissions must be "rw-r--r--"), and a line exists in the **.rhosts** file specifying client machine-name and, optionally, the client user-name.

ixpwwfile File Entry

To successfully establish a session with the server running at one of the six security levels, clients must pass certain information to the server at the time the session is established. This information is created and stored in an **ixpwwfile** security parameter file for each client and each server system.

Each record in the **ixpwwfile** security parameter file consists of four fields:

```
{server-machine-name, client-machine-name, server-user-name, password}
```

where *server-machine-name* is the name of the machine running the RM/InfoExpress UNIX server with which the client (*client-machine-name*) will establish the session. *server-user-name* is the name of the user on the server by which the client is known. *password* is the password string of the user (*server-user-name*) on the server.

For information about how to run the utility program to create and update **ixpwwfile**, refer to [Appendix E: RM/InfoExpress Security Parameter File Update Utility](#) (on page 105).

An "appropriate entry in the **ixpwwfile** file" in [Table 1](#) (on page 59) means that the **ixpwwfile** file on the server (pointed to in the **rmixsrvr.ini** configuration file) contains an entry specifying the *server-machine-name*, *client-machine-name*, and *server-user-name*. Note

that the *password* should not be present in the entry on the RM/InfoExpress server. The *password* is ignored.

User Password

In [Table 1](#), “correct user password” means that the password sent by the client matches the UNIX system password for *server-user-name* on the server.

Additional Parameters Needed for Non-UNIX Clients

Every UNIX and 32-bit Windows machine on the network is recognized by its node name. There is, however, no concept of a node name on a machine running the Windows 3.1 operating system. For proper recognition, workstations running Windows 3.1 must define the *client-machine-name* using the ClientName configuration parameter.

Note This discussion of the ClientName configuration parameter is for backward-compatibility issues only as this option was provided for 16-bit Windows clients. RM/InfoExpress no longer supports this option.

Client Validation by the Server at Different Security Levels

At the time the connection between the client and the server is established, each client passes information obtained from the **ixpfile** security parameter file and the configuration file to the RM/InfoExpress UNIX server. The server then validates this information using the UNIX security database files such as **etc/passwd**, **\$HOME/.rhosts**, and so forth, and the **ixpfile** security parameter file on the server.

Server Compatibility with Older and Newer Clients

The following server and client compatibility issues are discussed below.

Older Clients with the New Server

Earlier versions of RM/InfoExpress clients can communicate with the new server running in “compatibility mode” (that is, no security level specified or at security levels 0 or 1). These clients run as the default server user. When the server security level is 2 or greater, however, the server rejects the client connections. One of the following error messages is displayed:

```
RMIX_ERR_SERVER_USERNAME_PARAM_NOT_FOUND
```

- OR -

```
RMIX_ERR_USER_PASSWORD_NOT_FOUND
```

New Clients with an Older Server

New versions of RM/InfoExpress clients can communicate with older (pre-2.1) versions of the RM/InfoExpress UNIX server without any problem. At the time the session is established, the information passed by the new client will be ignored by the older server.

Setting Up the Network to Run RM/InfoExpress with Security Enabled

The following sections provide instructions for setting up each of the six levels of file security on the RM/InfoExpress UNIX server. (The setup differences between server security levels are summarized in [Table 2](#) on page 70.) In these procedures, two UNIX machines are connected to a network and are known on that network as *serverU* and *clientU*. A third machine running Windows, known on the network as *clientW*, is also connected on the same network.

A UNIX user running RM/COBOL with the RM/InfoExpress client on machine *clientU* wants to access data files on the RM/InfoExpress server running on machine *serverU*. On the client machine, the user logs in as *clientUser1*, but on the server machine, the user logs in as *serverUser1* with password *pass1*. (Note that *serverUser1* may be the same as or different from *clientUser1*.)

Similarly, a Windows user running RM/COBOL with the RM/InfoExpress client on machine *clientW* wants to access data files on the RM/InfoExpress server running on machine *serverU*. On the client machine, the user is known as *clientUser2*, but on the server machine the user is known as *serverUser2* with password *pass2*. (Note that *serverUser2* may be the same as or different from *clientUser2*.)

It is assumed that the following software is installed and available:

- RM/COBOL with the RM/InfoExpress client on the UNIX client machine (in directory **/usr/rmcobol**) and on the Windows client machine (in directory **c:\rmcobol**)
- RM/COBOL on the UNIX server machine (in directory **/usr/rmcobol**)
- RM/InfoExpress server on the UNIX server machine (in directory **/usr/rminfo**)

The following notes apply to the procedures for setting up RM/InfoExpress to run at each of the six security levels:

Note 1 “create an **ixpfile**” means to run **runcobol ixsecure.cob** with your current directory set to where you want the **ixpfile** security parameter file to reside or with the IXPWFILE environment variable pointing to the path.

Normally, **ixpfile** on the UNIX server is maintained by the RM/InfoExpress server administrator, and only such file is present on the UNIX server machine, generally in the **/usr/rminfo** directory. The **ixpfile** file on a Windows client machine is normally maintained by the owner of the Windows machine and resides in the RM/COBOL install directory, **c:\rmcobol**. On a UNIX client machine, each RM/InfoExpress client has his own copy of **ixpfile**. The client or server configuration file (either **rmixclnt.ini** or **rmixsrvr.ini**) can be used to configure other locations for **ixpfile**. The environment variable IXCONFIG may be used to specify the location and pathname of the configuration file on UNIX.

RM/COBOL with the RM/InfoExpress client will look for **ixpfile** in the location specified by the IxPwFile option in the Security section of the client configuration file. If the IxPwFile option is not present in the configuration file, then RM/COBOL with the RM/InfoExpress client will attempt to open file **ixpfile** in the current working directory.

If the server security level is 3 or 4, passwords may be stored in the client **ixpwwfile**; therefore, it should reside in a secure place (with appropriate owner and restrictive permissions on UNIX).

Note 2 “create a *filename.ini* file” means to use a text editor of your choice to create the appropriate configuration file:

- **/usr/rminfo/rmixsrvr.ini** for a UNIX server.
- **c:\windows\rmixclnt.ini** for a Windows client.
- **/usr/rmcobol/rmixclnt.ini** for a UNIX client, if only a single client configuration file is to be used when no user passwords are required in the security parameter file. If multiple configuration files are required so that each UNIX user can be responsible for the UNIX system password stored in a tradition **ixpwwfile** file, then the configuration file should be placed in the current working directory or located using the IXCONFIG environment variable.

Note 3 “create a **.rhosts** file” means to use a text editor of your choice to create a file named **.rhosts** in the home directory of *serverUser*. The owner of the file must be *serverUser* and only the owner can have write permission. The **.rhosts** file entry is the following:

```
clientU clientUser
```

clientUser is optional; if not present, any client user-name on machine *clientU* is allowed. *clientUser* is a client user-name, not a server-user-name such as *serverUser*. Although *clientUser* and *serverUser* are often the same user-name, this is not required.

Note 4 Notation of the form:

```
serverU/clientU/serverUser1/pass1
```

will be used to indicate an **ixpwwfile** entry with *serverU* as the server-machine-name, *clientU* as the client-machine-name, *serverUser1* as the server-user-name, and *pass1* as the UNIX system password for the UNIX user ID *serverUser1*. The password will only be present for security levels 3 and 4.

Setup for Running RM/InfoExpress at Server Security Level 0

1. Create an **ixpwwfile** file (see [Appendix E](#) on page 105) on each of the two client machines, *clientU* and *clientW*.

- a. On machine *clientU*, create an **ixpwwfile** file and enter:

```
serverU / clientU / serverUser1
```

- b. On machine *clientW*, create an **ixpwwfile** file and enter:

```
serverU / clientW / serverUser2
```

2. Create a configuration (.INI) file (see [Appendix D](#) on page 91) on each of the three machines, *clientU*, *clientW*, and *serverU*.

- a. On machine *clientU*, create **rmixclnt.ini** and enter:

```
[Security]  
ixpwwfile=<path>
```

- b. On machine *clientW*, create **rmixclnt.ini** and enter:

```
[Security]  
ixpwwfile=<path>
```

- c. On machine *serverU*, create **rmixsrvr.ini** and enter:

```
[Security]  
ServerSecurityLevel=0  
DefaultServerUser=<server-user-name>
```

3. Start the RM/InfoExpress server on machine *serverU*, as described in [Starting the RM/InfoExpress UNIX Server Program](#) (on page 30).
4. Run the application on machines *clientU* and *clientW*.

Setup for Running RM/InfoExpress at Server Security Level 1

1. Create an **ixpwwfile** file (see [Appendix E](#) on page 105) on each of the two client machines, *clientU* and *clientW*.

- a. On machine *clientU*, create an **ixpwwfile** file and enter:

```
serverU / clientU / serverUser1
```

- b. On machine *clientW*, create an **ixpwwfile** file and enter:

```
serverU / clientW / serverUser2
```

2. Create a configuration (.INI) file (see [Appendix D](#) on page 91) on each of the three machines, *clientU*, *clientW*, and *serverU*.

- a. On machine *clientU*, create **rmixclnt.ini** and enter:

```
[Security]  
ixpwwfile=<path>
```

- b. On machine *clientW*, create **rmixclnt.ini** and enter:

```
[Security]  
ixpwwfile=<path>
```

- c. On machine *serverU*, create **rmixsrvr.ini** and enter:

```
[Security]  
ServerSecurityLevel=1  
DefaultServerUser=<server-user-name>
```

3. Create two [.rhosts files](#) (see page 60) on machine *serverU*.

- a. Log in as *serverUser1*, create **\$HOME/.rhosts** and enter:

```
clientU clientUser1
```

- b. Log in as *serverUser2*, create **\$HOME/.rhosts** and enter:

```
clientW clientUser2
```

4. Start the RM/InfoExpress server on machine *serverU*, as described in [Starting the RM/InfoExpress UNIX Server Program](#) (on page 30).

5. Run the application on machines *clientU* and *clientW*.

Setup for Running RM/InfoExpress at Server Security Level 2

1. Create an **ixpwwfile** file (see [Appendix E](#) on page 105) on each of the two client machines, *clientU* and *clientW*.

- a. On machine *clientU*, create an **ixpwwfile** file and enter:

```
serverU / clientU / serverUser1
```

- b. On machine *clientW*, create an **ixpwwfile** file and enter:

```
serverU / clientW / serverUser2
```

2. Create a configuration (.INI) file (see [Appendix D](#) on page 91) on each of the three machines, *clientU*, *clientW*, and *serverU*.

- a. On machine *clientU*, create **rmixclnt.ini** and enter:

```
[Security]  
ixpwwfile=<path>
```

- b. On machine *clientW*, create **rmixclnt.ini** and enter:

```
[Security]  
ixpwwfile=<path>
```

- c. On machine *serverU*, create **rmixsrvr.ini** and enter:

```
[Security]  
ServerSecurityLevel=2
```

3. Create two [.rhosts files](#) (see page 60) on machine *serverU*.

- a. Log in as *serverUser1*, create **\$HOME/.rhosts** and enter:

```
clientU clientUser1
```

- b. Log in as *serverUser2*, create **\$HOME/.rhosts** and enter:

```
clientW clientUser2
```

4. Start the RM/InfoExpress server on machine *serverU*, as described in [Starting the RM/InfoExpress UNIX Server Program](#) (on page 30).
5. Run the application on machines *clientU* and *clientW*.

Setup for Running RM/InfoExpress at Server Security Level 3

1. Create an **ixpwwfile** file (see [Appendix E](#) on page 105) on each of three machines, *clientU*, *clientW*, and *serverU*.

- a. On machine *clientU*, create an **ixpwwfile** file and enter:

```
serverU / clientU / serverUser1 / pass1
```

- b. On machine *clientW*, create an **ixpwwfile** file and enter:

```
serverU / clientW / serverUser2 / pass2
```

- c. On machine *serverU*, create an **ixpwwfile** and enter:

```
serverU / clientU / serverUser1  
serverU / clientW / serverUser2
```

2. Create a configuration (.INI) file (see [Appendix D](#) on page 91) on each of the three machines, *clientU*, *clientW* and *serverU*.

- a. On machine *clientU*, create **rmixclnt.ini** and enter:

```
[Security]  
ixpwwfile=<path>
```

- b. On machine *clientW*, create **rmixclnt.ini** and enter:

```
[Security]  
ixpwwfile=<path>
```

- c. On machine *serverU*, create **rmixsrvr.ini** and enter:

```
[Security]  
ixpwwfile=<path>  
ServerSecurityLevel=3
```

3. Start the RM/InfoExpress server on machine *serverU*, as described in [Starting the RM/InfoExpress UNIX Server Program](#) (on page 30).

4. Run the application on machines *clientU* and *clientW*.

Setup for Running RM/InfoExpress at Server Security Level 4

1. Create an **ixpwwfile** file (see [Appendix E](#) on page 105) on each of three machines, *clientU*, *clientW*, and *serverU*.

- a. On machine *clientU*, create an **ixpwwfile** file and enter:

```
serverU / clientU / serverUser1 / pass1
```

- b. On machine *clientW*, create an **ixpwwfile** file and enter:

```
serverU / clientW / serverUser2 / pass2
```

- c. On machine *clientW*, create an **ixpwwfile** file and enter:

```
serverU / clientU / serverUser1  
serverU / clientW / serverUser2
```

2. Create a configuration (.INI) file (see [Appendix D](#) on page 91) on each of the three machines, *clientU*, *clientW*, and *serverU*.

- a. On machine *clientU*, create **rmixclnt.ini** and enter:

```
[Security]  
ixpwwfile=<path>
```

- b. On machine *clientW*, create **rmixclnt.ini** and enter:

```
[Security]  
ixpwwfile=<path>
```

- c. On machine *serverU*, create **rmixsrvr.ini** and enter:

```
[Security]  
ixpwwfile=<path>  
ServerSecurityLevel=4
```

3. Create two [.rhosts files](#) (see page 60) on machine *serverU*.

- a. Log in as *serverUser1*, create **\$HOME/.rhosts** and enter:

```
clientU clientUser1
```

- b. Log in as *serverUser2*, create **\$HOME/.rhosts** and enter:

```
clientW clientUser2
```

4. Start the RM/InfoExpress server on machine *serverU*, as described in [Starting the RM/InfoExpress UNIX Server Program](#) (on page 30).

5. Run the application on machines *clientU* and *clientW*.

Setup for Running RM/InfoExpress at Server Security Level 5

1. Create an **ixpwwfile** file (see [Appendix E](#) on page 105) on each of three machines, *clientU*, *clientW*, and *serverU*.

- a. On machine *clientU*, create an **ixpwwfile** file and enter:

```
serverU / clientU / serverUser1
```

- b. On machine *clientW*, create an **ixpwwfile** file and enter:

```
serverU / clientW / serverUser2
```

- c. On machine *clientW*, create an **ixpwwfile** file and enter:

```
serverU / clientU / serverUser1  
serverU / clientW / serverUser2
```

2. Create a configuration (.INI) file (see [Appendix D](#) on page 91) on each of the three machines, *clientU*, *clientW*, and *serverU*.

- a. On machine *clientU*, create **rmixclnt.ini** and enter:

```
[Security]  
ixpwwfile=<path>
```

- b. On machine *clientW*, create **rmixclnt.ini** and enter:

```
[Security]  
ixpwwfile=<path>
```

- c. On machine *serverU*, create **rmixsrvr.ini** and enter:

```
[Security]  
ixpwwfile=<path>  
ServerSecurityLevel=5
```

3. Create two [.rhosts files](#) (see page 60) on machine *serverU*.

- a. Log in as *serverUser1*, create **\$HOME/.rhosts** and enter:

```
clientU clientUser1
```

- b. Log in as *serverUser2*, create **\$HOME/.rhosts** and enter:

```
clientW clientUser2
```

4. Start the RM/InfoExpress server on machine *serverU*, as described in [Starting the RM/InfoExpress UNIX Server Program](#) (on page 30).

5. Run the application on machines *clientU* and *clientW*. The appropriate password entry dialog box is displayed.

Setup Differences Between Server Security Levels

[Table 2](#) summarizes the differences between the setup procedures for each server security level and the setup for the next higher level.

Note The entry in `ServerSecurityLevel=number` in step 2c of each setup procedure is incremented by one, beginning with level 1.

Table 2: Summary of Setup Differences Between Server Security Levels

Server Security Levels	Setup Differences
0 and 1	Setup for level 1 adds step 3, which is the requirement for .rhosts files on the server machine.
1 and 2	Setup for level 2 does not support older clients (such as 16-bit Windows clients). The <code>DefaultServerUser=<server-user-name></code> entry in level 1 step 2c is not needed because the server at level 2 refuses the connection rather than running as <code><server-user-name></code> .
2 and 3	Setup for level 3 uses passwords rather than .rhosts files. Steps 1a and 1b requires the entry of passwords in the client <code>ixpwwfile</code> entries, and level 3 step 1c is added because the server requires <code>ixpwwfile</code> entries (passwords are not needed here) for the clients that will connect to it. Level 3 step 2c adds the <code>ixpwwfile=<path></code> entry so that the server can access the ixpwwfile file created by level 3 step 1c. Level 2 step 3, which is the .rhosts file requirement, is not needed at level 3.
3 and 4	Setup for level 4 adds step 3, which is the requirement for .rhosts files on the server machine.
4 and 5	Setup for level 5 does not require passwords in steps 1a and 1b for the client <code>ixpwwfile</code> entries because the server forces clients to make the user enter the password via a dialog box on the client machine.

Appendix A: Messages

This appendix lists the error messages that can occur while RM/InfoExpress is being used.

Error Message Types

Errors that can occur when using RM/InfoExpress fall into two categories:

- **COBOL errors**, which do not start with the value 30. These errors are described in the appropriate RM/COBOL user's guide.
- **Non-COBOL permanent errors**, which have the following format:

30, error type, error code

where,

error type is used to identify the software that generates the error.

error code is the number returned by that software.

[Table 3](#) lists each error type, the error codes that can occur with each type, and the possible source of the error code for errors generated by RM/InfoExpress. Other error codes associated with error types such as UNIX and Windows can be found in the appropriate vendor documentation.

A complete description of each error type can be found in [Permanent Error Types](#) (on page 72). A complete [description of possible error codes](#) begins on page 73.

Notes

- For more information on error messages, refer to “Error Message Types” and “Error Message Formats” in Appendix A: *Runtime Messages*, in the *RM/COBOL User's Guide*.
- Earlier versions of RM/InfoExpress usually returned two errors: 255 for network-specific errors and 254 for errors detected by RM/InfoExpress. In this version of RM/InfoExpress, errors are returned as they occur, along with the appropriate error code.

Table 3: Error Types and Associated Error Codes

Permanent Error Type (Number and Description)	Possible Error Code (Number/Description)	Possible Error Code (Source)
15 - RM/InfoExpress Server Error	1 - 13	RM/InfoExpress API
	21 - 59	RM/InfoExpress
	12xxx	RM/InfoExpress Windows Sockets Interface
	4xx - 5xx	RM/InfoExpress BSD Sockets Interface
16 - RM/InfoExpress Client Error	21 - 59	RM/InfoExpress
	12xxx	RM/InfoExpress Windows Sockets Interface
	4xx - 5xx	RM/InfoExpress BSD Sockets Interface
21 - RM/InfoExpress WinSock Error	10xxx - 11xxx	Windows Sockets

Permanent Error Types

Error type 15: RM/InfoExpress Server Error

The RM/InfoExpress server generates this type of error when it encounters an error within its code. Errors such as incorrect File Access Protocol (FAP) message received from the client, out-of-memory, and so forth, fall into this category.

Possible error codes for error type 15 are described in the following topics:

- [RM/InfoExpress API-Generated Error Codes](#) (on page 73)
- [RM/InfoExpress-Generated Error Codes](#) (on page 75)
- [RM/InfoExpress Windows Sockets Interface Error Codes](#) (on page 82)
- [RM/InfoExpress BSD Sockets Interface Error Codes](#) (on page 83)

Error type 16: RM/InfoExpress Client Error

The RM/InfoExpress client generates this type of error when it encounters an error within its code. Errors such as incorrect File Access Protocol (FAP) message received from the RM/COBOL program (**runcobol**), incorrect FAP response from the server, out-of-memory, and so forth, fall into this category.

Possible error codes for error type 16 are described in the following topics:

- [RM/InfoExpress-Generated Error Codes](#) (on page 75)
- [RM/InfoExpress Windows Sockets Interface Error Codes](#) (on page 82)
- [RM/InfoExpress BSD Sockets Interface Error Codes](#) (on page 83)

Error type 21: RM/InfoExpress WinSock Error

RM/InfoExpress generates this type of error when either the Windows client program or the Windows server program receives an error from the underlying Windows Sockets software. Possible error codes are described in [RM/InfoExpress WinSock Error Codes](#) (on page 80).

RM/InfoExpress API-Generated Error Codes

Error codes 1 through 13 are common to the server program, the server display (screen handler) program, and the API application.

Error code 1: RMIX_API_ERR_SERVER_ALREADY_EXISTS

Failure Definition: Indicates that the server being started encounters a server already running in the system, or at least one of its components is present in the system.

Action: For RM/InfoExpress running on UNIX, this error occurs if the server invoked previously is not terminated, or it is terminated improperly. If the server has been terminated improperly, remove the related IPC (Inter Process Communications) objects (shared memory, key starting with 0x49584D and semaphore, key starting with 0x495853, displayed using the `ipcs` command) using the UNIX command `ipcrm`.

Error code 2: RMIX_API_ERR_OUT_OF_MEMORY

Failure Definition: Indicates that there is not enough memory available in the system for RM/InfoExpress (server or server display programs) to continue.

Action: Bring down all the connected clients, bring down the server, and make more memory available before starting the server again.

Error code 3: RMIX_API_ERR_TOO_MANY_USERS

Failure Definition: Indicates that too many server display programs are being invoked. The limit is nine for UNIX and Windows.

Action: Close any unnecessary server display applications.

Error code 4: RMIX_API_ERR_NOT_AUTHORIZED

Failure Definition: Indicates that the application using the server API attempted either to open the server database with a mode other than `O_RDONLY`, or it used an unauthorized API. This message may also indicate that the server display executable is corrupted.

Action: In case of a corrupted server display executable, install RM/InfoExpress again.

Error code 5: RMIX_API_ERR_SERVER_NOT_PRESENT

Failure Definition: Indicates that either the application using the server API or the server display application is being started without the server having been started.

Action: Start the server and then start the application.

Error code 6: RMX_API_ERR_CLIENT_ID_NOT_FOUND

Failure Definition: Indicates a malfunction of either the server or the server display program.

Action: Bring down all the connected clients, terminate the server, and restart.

Error code 7: RMX_API_ERR_TOO_MANY_CLIENTS

Failure Definition: Indicates that the server has run out of free slots for remote clients.

Action: Bring down unused client connections to release some slots on the server. Alternatively, you can also perform one of the following:

- Edit the server configuration file, **rmixsrvr.ini**, to include the UseCount option. For more information, see [Common Server-Specific Configuration Options](#) (on page 99).
- Bring down all the connected clients, terminate the server, and restart with the -k command line option. For more information, see [Chapter 2: Configuring and Running the RM/InfoExpress Server](#) (on page 29).

Error code 8: RMX_API_ERR_TOO_MANY_FILES

Failure Definition: Indicates that the server has run out of the free slots for open files.

Action: Close inactive open files from the client applications. Alternatively, edit the server configuration file, **rmixsrvr.ini**, to include the FileCount option. For more information, see [Common Server-Specific Configuration Options](#) (on page 99).

Error code 9: RMX_API_ERR_CLIENT_NOT_FOUND

Failure Definition: Indicates a server malfunction.

Action: Bring down all the connected clients, terminate the server, and restart.

Error code 11: RMX_API_ERR_FILE_NOT_FOUND

Failure Definition: Indicates a malfunction of either the server or the server display program.

Action: Bring down all the connected clients, terminate the server, and restart.

Error code 12: RMX_API_ERR_SERVER_APPLICATION_MISMATCH

Failure Definition: Indicates that either the server display or the server API application that is being started does not match the server running in the system.

Action: Use a matching server display. Also, make sure that the server display and the server belong to same release, even though they support the same protocol.

Error code 13: RMX_API_ERR_SERVER_DATABASE_NOT_OPEN

Failure Definition: Indicates a malfunction of either the server or the server display program.

Action: Bring down all the connected clients, terminate the server, and restart.

RM/InfoExpress-Generated Error Codes

Error codes 21 through 59 are common to the client, the server, and the server display.

Error code 21: RMIX_ERR_INVALID_FAP_MESSAGE

Failure Definition: Indicates an RM/InfoExpress system error.

Action: Contact Liant technical support for assistance.

Error code 22: RMIX_ERR_FILE_HANDLE_NOT_FOUND

Failure Definition: Indicates an RM/InfoExpress system error.

Action: Contact Liant technical support for assistance.

Error code 23: RMIX_ERR_OUT_OF_MEMORY

Failure Definition: Indicates that there is not enough memory available in the system for RM/InfoExpress (client or server) to continue.

Action: If the associated error type is 15 (RM/InfoExpress Server Error), bring down all the connected clients, bring the server down, and make more memory available before starting the server again. If the associated error type is 16 (RM/InfoExpress Client Error), terminate the client application and restart it after making more memory available on the client system.

Error code 24 RMIX_ERR_SESSION_REJECTED

Failure Definition: This error is reported by either the Windows client or the server. When returned by the server, it indicates a problem with the network interface. When returned by the Windows client, it indicates that the RM/COBOL runtime does not match the client.

Action: If returned by the server, contact Liant technical support for assistance. If returned by the client, use the version of the runtime that matches the Windows client.

Error code 26 RMIX_ERR_SIGNAL_CAUGHT

Failure Definition: Indicates an RM/InfoExpress system error.

Action: Contact Liant technical support for assistance.

Error code 27 RMIX_ERR_FAP_MANIPULATION

Failure Definition: Indicates an RM/InfoExpress system error.

Action: Contact Liant technical support for assistance.

Error code 28 RMX_ERR_IPC_OBJECTS_REMOVED

Failure Definition: Indicates that the server or the server display discovered Inter Process Communications (IPC) objects missing in the system. This error is specific to the server and the server display for UNIX.

Action: It may be that the IPC objects have been removed accidentally. Remove the other IPC objects and start the server and/or the server display again.

Error code 30 RMX_ERR_INVALID_COMMAND

Failure Definition: Indicates an RM/InfoExpress system error.

Action: Contact Liant technical support for assistance.

Error code 32 RMX_ERR_TOO_MANY_CLIENTS

Failure Definition: The server reports this error when the number of clients exceeds the value specified on the -k option (or the UseCount configuration file option) or the number of licensed use counts, whichever is less.

Action: Restart the server with a larger value on the UseCount configuration file option, as described in [Common Server-Specific Configuration Options](#) (on page 99), or use a server licensed for more users.

Error code 33 RMX_ERR_DEF_USER_NAME_NOT_FOUND

Failure Definition: The server, running at a security level of 0 to 2, reports this error when it detects that the name specified on the DefaultServerUser configuration file option or the user name **rmserver** is not a valid user on the server machine. This error may also occur if root is specified as the default user name.

Action: Using system administration tools, add a new user with the name specified. If that user already exists, check the **etc/passwd** file.

Error code 34 RMX_ERR_SECURITY_INFO_NOT_FOUND

Failure Definition: The RM/InfoExpress server reports this error when it cannot find a match for the *server-user-name*, *client-machine-name*, and *server-machine-name* triple passed by the client in the server's security parameter file, **ixpwwfile**.

Action: Update **ixpwwfile** by using the utility program **ixsecure.cob** on both the client and the server machines to add an entry for the *client-machine-name* and the *server-user-name* pair. For more information, see [Chapter 6: File Security on the RM/InfoExpress UNIX Server](#) (on page 57) and [Appendix E: RM/InfoExpress Security Parameter File Update Utility](#) (on page 105). For a Windows client, the client name is the Windows computer name. For a UNIX client, this is the node name and is given by the **uname** command.

Error code 35 RMX_ERR_USER_PASSWORD_PARAM_NOT_FOUND

Failure Definition: This error is normally reported by the RM/InfoExpress server running at a security level of 3 or higher.

Action: Contact Liant technical support for assistance.

Error code 36 RMX_ERR_SYSTEM_PASSWORD_MISMATCH

Failure Definition: The server, running at a security level of 3 or higher, reports this error when it detects that the *password* string stored in the **ixpwwfile** security parameter file on the client machine and on the server machine, and the password stored in the UNIX system, do not match.

Action: See that the *password* string entered interactively at the client terminal or stored in **ixpwwfile** on the client machine matches the *password* string stored in **ixpwwfile** on the server machine and the one stored in the UNIX system. To update the password entry in **ixpwwfile**, use the utility program **ixsecure.cob**. See [Appendix E: RM/InfoExpress Security Parameter File Update Utility](#) (on page 105).

Error code 37 RMX_ERR_SYSTEM_PASSWORD_NOT_FOUND

Failure Definition: The server, running at a security level of 3 or higher, reports this error when it cannot locate the user password in the UNIX system security database.

Action: This error normally occurs on UNIX systems that maintain the security database in a file different from the **/etc/passwd** file. This indicates that one or both of these files have been corrupted. Contact your system administrator.

Error code 38 RMX_ERR_RHOSTS_FILE_OPEN_ERROR

Failure Definition: The server reports this error when it cannot open the **.rhosts** file in the user's home directory.

Action: Seek your server administrator's help in creating the **.rhosts** file with appropriate entries in the user's home directory on the server machine.

Error code 39 RMX_ERR_RHOSTS_FILE_PERMISSIONS_INVALID

Failure Definition: The server reports this error when it finds the permissions of the **.rhosts** file in the user's home directory to be invalid.

Action: Set the permissions of the **.rhosts** file in the user's home directory on the server machine to be **"-rw-r--r--"** and make certain that the user is the owner of this file.

Error code 40 RMX_ERR_ENTRY_NOT_FOUND_IN_RHOSTS_FILE

Failure Definition: The server reports this error when it fails to find a matching client name entry (with the *client-machine-name* parameter passed by the client machine) in the **.rhosts** file on the server machine.

Action: With the help of your server administrator, edit the **.rhosts** file in the user's home directory on the server machine and add a new entry containing the *client-machine-name* and an optional *server-user-name*.

Error code 41 RMX_ERR_NO_SESSION

Failure Definition: Both the server and the client may report this error. Although not fatal, this error is still considered an RM/InfoExpress system error.

Action: Contact Liant technical support for assistance.

Error code 42 RMIX_ERR_SERVER_USER_NAME_PARAM_NOT_FOUND

Failure Definition: The server, running at a security level of 0 to 5, reports this error when it detects that the *server-user-name* parameter is absent in the information passed by the client when connections are established.

Action: This error may occur when an old client tries to establish a connection with the new server running at security level 2 or higher. This error may also occur when the new client cannot provide the required information to the server due to some problem in processing the security parameter file, **ixpwfile** (for example, the file is not present on the client machine). Upgrade to a new version of the RM/InfoExpress client in order to use security features on the server.

Error code 43 RMIX_ERR_CLIENT_MACH_NAME_PARAM_NOT_FOUND

Failure Definition: The server, running at a security level of 0 to 5, reports this error when it detects that the *client-machine-name* parameter is absent in the information passed by the client when connections are established.

Action: This error may occur when an old client tries to establish a connection with the new server running at security level 2 or higher. This error may also occur when the new client cannot provide the required information to the server due to some problem in processing the security parameter file, **ixpwfile** (for example, the file is not present on the client machine). Upgrade to a new version of the RM/InfoExpress client in order to use security features on the server.

Error code 44 RMIX_ERR_SERVER_SECURITY_INFO_FILE_ERROR

Failure Definition: This error occurs when the server fails to open the security parameter file, **ixpwfile**, on the server machine.

Action: Make sure that a valid security parameter file, **ixpwfile**, is present on the server machine. If this file does not exist, create it using the **ixsecure.cob** utility program (see Appendix E).

Error code 45 RMIX_ERR_MALFORMED_MESSAGE

Failure Definition: Indicates an RM/InfoExpress system error. This error occurs when either the client or the server fails to decompress the message received from the session partner.

Action: Contact Liant technical support for assistance.

Error code 46 RMIX_ERR_NO_MEMORY_FOR_COMPRESSION

Failure Definition: There was insufficient memory to compress or decompress the data.

Action: Set the IxCompress configuration file option to No to disable message compression, as described in [Common Configuration Options](#) (on page 93). Message compression should not be used for records of more than 64000 bytes.

Error code 47 RMIX_ERR_TOO_MANY_FILES

Failure Definition: The client(s) have exceeded the total number of open files supported by the server.

Action: Increase the value of the FileCount configuration file option and restart the server, as discussed in [Common Server-Specific Configuration Options](#) (on page 99).

Error code 48 RMIX_ERR_SYSTEM_PASSWORD_FILE_OPEN_ERROR

Failure Definition: This error occurs when an invalid `/etc/passwd` file (which may be missing) or the `server-user-name` with which the client is trying to run is not present on the server machine.

Action: Contact your system administrator.

Error code 49 RMIX_ERR_CLIENT_SECURITY_INFO_FILE_ERROR

Failure Definition: This error occurs when the client fails to open the security parameter file, `ixpwfile`, on the client machine.

Action: Make sure that a valid security parameter file, `ixpwfile`, is present on the client machine. If this file does not exist, create it using the `ixsecure.cob` utility program. See [Appendix E: RM/InfoExpress Security Parameter File Update Utility](#) (on page 105).

Error codes 50 — 59

Failure Definition: Error codes 50 through 59 represent internal errors in the RM/InfoExpress server program. Error code 54 may indicate an attempt to use an old client with a new server in a mode other than compatibility mode.

Action: Contact Liant technical support for assistance.

RM/InfoExpress WinSock Error Codes

[Table 4](#) lists the possible error codes for permanent error type 21, which is described on page 73. Codes in the 10000 range represent network or system errors. Codes in the 11000 range represent database errors.

Table 4: Error Codes Generated by Windows Sockets

Error Code	Description	Windows Sockets Error Equivalent	UNIX Error Equivalent
10004	Interrupted system call	WSAEINTR	EINTR
10009	Bad file number	WSAEBADF	EBADF
10013	Permission denied	WSAEACCES	EACCES
10014	Bad address	WSAEFAULT	EFAULT
10022	Invalid argument	WSAEINVAL	ENOTSOCK
10024	Too many open files	WSAEMFILE	EMFILE
10035	Operation would block	WSAEWOULDBLOCK	EWOLDBLOCK
10036	Blocking operation in progress	WSAEINPROGRESS	EINPROGRESS
10037	Operation already in progress	WSAEALREADY	EALREADY
10038	Operation on non-socket	WSAENOTSOCK	ENOTSOCK
10039	Destination address required	WSAEDESTADDRREQ	EDESTADDRREQ
10040	Message too long	WSAEMSGSIZE	EMSGSIZE
10041	Wrong protocol type	WSAEPROTOTYPE	EPROTOTYPE
10044	Socket type not supported	WSAESOCKTNOSUPPORT	ESOCKTNOSUPPORT
10045	Operation not supported	WSAEOPNOTSUPP	EOPNOTSUPP
10046	Protocol family not supported	WSAEPFNOSUPPORT	EPFNOSUPPORT
10047	Address family not supported	WSAEAFNOSUPPORT	EAFNOSUPPORT
10048	Address already in use	WSAEADDRINUSE	EADDRINUSE
10049	Cannot assign address	WSAEADDRNOTAVAIL	EADDRNOTAVAIL
10050	Network is down	WSAENETDOWN	ENETDOWN
10051	Network is unreachable	WSAENETUNREACH	ENETUNREACH
10052	Network reset connection	WSAENETRESET	ENETRESET
10053	Connection was aborted	WSAECONNABORTED	ECONNABORTED
10054	Peer reset connection	WSAECONNRESET	ECONNRESET
10055	No available buffer space	WSAENOBUFS	ENOBUFS
10056	Socket already connected	WSAEISCONN	EISCONN
10057	Socket not connected	WSAENOTCONN	ENOTCONN

Table 4: Error Codes Generated by Windows Sockets (Cont.)

Error Code	Description	Windows Sockets Error Equivalent	UNIX Error Equivalent
10058	Socket was shut down	WSAESHUTDOWN	ESHUTDOWN
10059	Too many references	WSAETOOMANYREFS	ETOOMANYREFS
10060	Connection timed out	WSAETIMEDOUT	ETIMEDOUT
10061	Connection refused	WSAECONNREFUSED	ECONNREFUSED
10062	Symbolic link loop	WSAELOOP	ELOOP
10063	Pathname too long	WSAENAMETOOLONG	ENAMETOOLONG
10064	Host is down	WSAEHOSTDOWN	EHOSTDOWN
10065	Host is unreachable	WSAEHOSTUNREACH	EHOSTUNREACH
10066	Directory not empty	WSAENOTEMPTY	
10067	Process limit	WSAEPROCLIM	
10091	Network is unusable	WSASYSNOTREADY	
10092	Version not supported	WSAVERNOTSUPPORTED	
10093	Startup not done	WSANOTINITIALISED	
11001	Host not found	WSAHOST_NOT_FOUND	HOST_NOT_FOUND
11002	Try again	WSATRY_AGAIN	TRY_AGAIN
11003	No recovery	WSANO_RECOVERY	NO_RECOVERY
11004	No data	WSANO_DATA	NO_DATA

RM/InfoExpress Windows Sockets Interface Error Codes

Codes in the 12000 range, shown in [Table 5](#), are generated by the Windows Sockets interface portion of the RM/InfoExpress Windows client program or the Windows server program and represent memory allocation failures or unexpected conditions.

These errors are considered RM/InfoExpress system errors. When these errors are detected, contact Liant technical support for assistance.

Table 5: Error Codes Generated by the RM/InfoExpress Windows Sockets Interface

Error Code	Description
12001	Insufficient memory for connect.
12002	Internal socket number already in use.
12003	Unexpected event occurred during connect.
12004	Unexpected error condition from connect.
12005	Unexpected event occurred during initial receive.
12006	Received data length error (client/server not synchronized).
12007	Received data length error (client/server not synchronized).
12008	Received data length error (client/server not synchronized).
12009	Received data length inconsistent with FAP message length.
12010	Unexpected event occurred during secondary receive.
12011	Unexpected event occurred during send.
12012	Internal buffer length too small for status.
12013	Insufficient memory for status.
12014	Unknown error during asynchronous wait.
12015	Unknown error during event wait.
12016	Received data length error.
12017	Unknown error during asynchronous-wait.
12018	Unknown error during event wait.
12019	Unknown error during event wait.

RM/InfoExpress BSD Sockets Interface Error Codes

Error codes 401 through 413 are generated by the BSD Sockets interface portion of the RM/InfoExpress client and the server. These error codes are defined in [Table 6](#).

These errors are considered RM/InfoExpress system errors. When these errors are detected, contact Liant technical support for assistance.

Table 6: Error Codes Generated by the RM/InfoExpress BSD Windows Sockets Interface

Error Code	Description
401	Insufficient for connect.
402	Socket already in use.
403	Out of memory.
406	Received data length error (client/server not synchronized).
407	Received data length error (client/server not synchronized).
408	Received data length error (client/server not synchronized).
409	Received data length inconsistent with FAP message length.
412	Internal buffer length too small for status.
501	BSD Sockets error HOST_NOT_FOUND.
502	BSD Sockets error TRY_AGAIN.
503	BSD Sockets error NO_RECOVERY.
504	BSD Sockets error NO_DATA.

Appendix B: Limits and Ranges

This appendix describes RM/InfoExpress limits and ranges.

Limits and Ranges

The following limitations apply to RM/InfoExpress:

1. It is not possible to run more than one RM/InfoExpress server program at a time on a given machine.
2. No more than nine RM/InfoExpress UNIX and Windows server display (screen handler) programs may be run at one time on a given machine.

Appendix C: Troubleshooting RM/InfoExpress

This appendix is designed to help if you run into any problems when using RM/InfoExpress. Each section offers steps you can take to solve the problem.

Failure to Locate File or Path

Error messages that occur while accessing the file on the server machine, for example, “File not found” or “Path not found”, generally indicate one of the following conditions:

1. The RM/InfoExpress UNIX server program is not running on a UNIX server machine. In this case, load **rmservtcp**.
2. The complete filename (defined using the synonym or other means) does not correctly point to the location on the server. Check your environment variables and synonyms.
3. In the case of a Windows client, the **rmtcp32** and **winsock** DLLs are not in the execution path.
4. For a Windows client, the **runcobol** configuration file contains an incorrect DLL name or the DLL specified on the NAME option of the EXTERNAL-ACCESS-METHOD record cannot be located.
5. Invoke the RM/InfoExpress server with the **-c l** option so that pathnames from Windows clients will be converted to lowercase by the server.
6. While accessing files from a UNIX client, make certain that the machine name specified in the pathname is the same as the one in the **/etc/hosts** file on the client machine. For example, the machine name “HAL9000” in the pathname defined by **INXFL=//RS6000/rminfo/inxfl** matches the name “HAL9000” in the **/etc/hosts** file entry 111.22.333.44 hal9000 HAL9000.

RM/InfoExpress Client Entries Not Terminating

Certain situations on some versions of UNIX, when running RM/InfoExpress using the TCP/IP protocol, can cause the server not to notice that a client has been terminated. This occurs only if the client is terminated in a non-standard method, such as turning off the client workstation or experiencing a system failure on the client workstation. In such instances, the RM/InfoExpress client is unable to inform the server that the client is terminating. Although the operating system eventually notifies the RM/InfoExpress server that the connection has been broken, it could take several hours on some implementations of UNIX before the notification occurs.

One version of UNIX that exhibits this behavior is AIX running on the RS/6000. To reduce the amount of time before the inactivity on a TCP/IP connection is interpreted as a lost connection under AIX, use the following **no** command:

```
no -o tcp_keepidle=200 -o tcp_keepintvl=60
```

where,

-o is a network option.

Note On AIX 5.2, there is a defect that prevents a single **no** command from having two **-o** options. In this case, you must use two **no** commands.

tcp_keepidle determines the number of half-seconds to wait after the last successful I/O operation before attempting to determine whether a connection has been lost.

tcp_keepintvl determines the number of half-seconds to wait between requests for a response from the possibly lost connection.

After ten requests with no response, the operating system reports a lost connection to the server. The settings shown in this example will report a broken connection after 400 seconds ($100+30*10$).

Note You must run the **no** commands each time the network is started since it does not permanently change the default configuration values.

Removing IPC Objects After Server Failure

The recommended way to terminate the server is by using the command sequence (Terminate, Server, Now, Yes) of the screen display (screen handler) program when no active client is connected.

Using the **kill** command causes the RM/InfoExpress UNIX server to exit without removing the IPC (Inter Process Communications) objects, such as shared memory segments and semaphores. Consequently, when the server is started next time, it fails with server error code 1 (RMIX_API_ERR_SERVER_ALREADY_EXISTS).

In this situation, remove the IPC objects using the following UNIX commands:

```
ipcrm -m <shm_id> -s <sem_id>
```

where the `<shm_id>` and `<sem_id>` objects are obtained by using the UNIX command:

```
ipcs
```

Note that the key values for RM/InfoExpress IPC objects start with the value 0x49584D for shared memory and 0x495853 for semaphores.

Appendix D: Configuring RM/InfoExpress

RM/InfoExpress can be uniformly configured across all implementations of clients and servers. To maintain compatibility with previous versions of RM/InfoExpress, environment variables supported by previous versions can be used to override the settings of the configuration file. On the server, all the command line options can be specified in the configuration file.

This appendix describes the configuration files and their options.

Configuration Files and Options

Even though the names of the configuration files used by different implementations of RM/InfoExpress are different, the format of all these files is identical. The configuration files are as follows:

<u>Use</u>	<u>To set configuration parameters for</u>
rmixclnt.ini	RM/InfoExpress Windows and UNIX client programs.
rmixsrvr.ini	Either the RM/InfoExpress UNIX or the Windows server program.

For Windows clients and Windows servers, the configuration file must be present in the Windows directory (usually C:\WINDOWS). For UNIX clients and UNIX servers, the configuration file must be present in the current directory or the directory pointed to by the environment variable, IXCONFIG.

In a configuration file, any line beginning with a semi-colon (;) is treated as a comment and is not processed.

The client and server configuration files are divided into sections, each of which consists of a group of related options that you can use to customize your implementation of RM/InfoExpress. Some configuration options are used only by the client, while others are used only by the server. Some options are specific to the type of server. Still others are common to both client and server. All configuration options are shown in the sample configuration file that follows. See the more [detailed descriptions of the configuration options](#) on page 93.

Note Option names are not case-sensitive.

Sample Configuration File

```
[Debug]
;###Common###
InfoxDebug=debug filename

[Options]
;###Common###
IxCompress=Yes|No
ReconnectEnable=Yes|No

;###Client-Specific###
KeepSession=Yes|No
PathPrefixExcluded=list
PathPrefixIncluded=list
ReconnectDelay=number
StartupLogPath=directory-path

;###Server-Specific, All Servers###
DotsBias=number
FileBufferPool=number
FileCount=number
FileProcessCount=number
MinimumBlockSize=number
RoundToNiceBlockSize=Yes|No
UseCount=number
ReconnectTimeout=number
LargeFileLockLimit=number
InxUseLargeLimit=Yes|No
RelUseLargeLimit=Yes|No
SeqUseLargeLimit=Yes|No

;###Server-Specific, UNIX Server Only###
ConvertFileName=NoConvert|UpperCase|LowerCase

;###Server-Specific, Window Server Only###
UseCurrentDirectory=Yes|No
UseSystemShares=Yes|No

[Security]
;###Common###
EncodeData=Yes|No
IxPwFile=pathname

;###Client-Specific###
AcceptPassword=Yes|No

;###Server-Specific, UNIX Server Only###
DefaultServerUser=server-user-name
ServerSecurityLevel=number
```

```
[Sharing]
;###Server-Specific, Windows Server Only###
share-name=share-path

[Tcp]
;###Common###
MaxSendSize=number

[Winsock]
;###Common###
IgnoreHangupError=Yes|No           (Windows only)

;###Client-Specific###
UseBlockingIO=Yes|No
```

Common Configuration Options

The following configuration options, listed alphabetically, are *common* to both the client and server components of RM/InfoExpress:

- **EncodeData.** The EncodeData option in the [Security] section is used to encode messages to provide more security to the data transmitted on the network. EncodeData=No is the default. When the value is set to Yes, the RM/InfoExpress component (either the client or the server) negotiates the encoding algorithm of the messages exchanged with its session counterpart. If both the session partners have the value set to Yes, the messages are encoded before they are sent and unencoded immediately after they are received. However, if any of the session partners have the value set to No, the message encoding does not take place. Message encoding will not take place if either of the session partners is using a release of RM/InfoExpress earlier than version 2.1.
- **IgnoreHangupError.** The IgnoreHangupError option in the [Winsock] section is used only by RM/InfoExpress on Windows. If the value is IgnoreHangupError=Yes, any error returned by Windows Sockets functions, called while the Windows client is trying to disconnect the session with the server, are ignored. Do not specify this option unless instructed to do so by Liant technical support services.

IgnoreHangupError=No is the default value. If the value is set to No, a possibly serious error, should one occur while disconnecting the session with the server, is returned to the Close operation. This is normal behavior for any I/O operation.

- **InfoxDebug.** The InfoxDebug option in the [Debug] section causes the file whose pathname is given by *debug filename* to be created and trace information written into it. After the client RM/COBOL application is terminated, send this file to Liant technical support services for further investigation. Use this option only when you are investigating a problem with the assistance of Liant technical support services. Using this option under normal conditions affects client operations negatively.

On the server, the InfoxDebug configuration option is equivalent to the -d command line option, as described in the appropriate sections of [Starting the RM/InfoExpress UNIX Server Program](#) (on page 30) and [Starting and Stopping the RM/InfoExpress Windows Server Program](#) (on page 31). Note that the command line option overrides the configuration option.

- **IxCompress.** The IxCompress option in the [Options] section is used to compress messages transmitted on the network. Depending on the compressibility of the messages, which may contain COBOL data records, this option may improve the performance on the network. IxCompress=Yes is the default. When the value is set to Yes, the RM/InfoExpress component (either the client or the server) negotiates the compressibility of the messages exchanged with its session counterpart. If both the session partners have the value set to Yes, the messages are compressed before they are sent and decompressed immediately after they are received. However, if any of the session partners have the value set to No, the message compression does not take place. Message compression will not take place if either of the session partners is using a release of RM/InfoExpress earlier than version 2.1.
- **IxPwFile.** The value of *pathname* specified on the IxPwFile option in the [Security] section is used to locate the file containing the security parameters. If this option is absent, RM/InfoExpress looks for the security parameter file, **ixpwfile**, in the current directory. See [Chapter 6: File Security on the RM/InfoExpress UNIX Server](#) (on page 57).
- **MaxSendSize.** The MaxSendSize option in the [Tcp] section may be specified for those TCP/IP implementations that have a limitation. We recommend that you leave this value unspecified unless you know that the TCP/IP in use has a limitation. Some UNIX systems have a limit of 4096 bytes. Note that this value is *not* the same value as the size of the maximum packet allowed on the network

The value specified by the MaxSendSize option is used to determine whether the RM/InfoExpress client or server code must perform multiple send operations on a given message. The underlying TCP stack implementation determines the maximum allowable value for a single send operation. Multiple send operations may be required for some large messages. The TCP stack will transmit the data in as many network packets as required by the underlying network. Again, for large messages, multiple network packets may be required.

If I/O errors occur on a file with a record size larger than about 4000 bytes while files with smaller record sizes perform normally, try specifying MaxSendSize=4096. The default value is system-dependent, but is currently 4096 or larger. The value cannot be less than 512.

On the server, the MaxSendSize configuration option is equivalent to the `-z` command line option, as described in the appropriate sections of [Starting the RM/InfoExpress UNIX Server Program](#) (on page 30) and [Starting and Stopping the RM/InfoExpress Windows Server Program](#) (on page 31). Note that the command line option overrides the configuration option.

- **ReconnectEnable.** The ReconnectEnable option in the [Options] section determines whether reconnection logic in the client or server is enabled or disabled. For the client, the option determines whether the client will attempt to reconnect the session with the server if the connection is broken. For the server, this option determines whether the server will keep the file manager process and the current state of its open files intact waiting for the client to reconnect and continue from where it left off when the connection was broken.

Both the client and server sides of a connection must have reconnection enabled for the attempt to succeed. If the value is set to No for the client and the server, then they both behave identically to previous RM/InfoExpress releases; that is, the client reports an error to the COBOL program and the server closes files and terminates the file manager process running on behalf of the client. The default value is Yes for the client and No for the server. These defaults allow reconnection to any given server to be enabled simply by changing the **rmixsrvr.ini** file for that server and starting the server again.

Beginning with version 8, a limited reconnection capability, which allows a connection that becomes broken to be reconnected automatically, has been added to the RM/InfoExpress client and server logic. The client and server continue normal operation without the client run unit (COBOL program) ever being aware of the disconnection. The server writes a log file, named RMRECONN.LOG, which is created in the directory specified in the environment variable RM_RECONN_LOG_PATH, if defined. If this environment variable is not defined, the log file is created in the TEMP directory on Windows or in the current directory on UNIX. Although it is not recommended, you can disable the log file by setting the RM_RECONN_LOG_PATH environment variable to a non-existent directory name.

TCP/IP provides a capability, known as “keepalive” support, to determine automatically whether an idle connection is still intact. When a connection has been idle for a certain period of time, TCP/IP transmits keepalive packets to see whether they are acknowledged, thus indicating an intact connection. After several retries—with each attempt receiving no acknowledgement—TCP/IP informs RM/InfoExpress that the connection is broken.

Having keepalive support enabled and keepalive packets being sent every short interval helps the reconnection logic work in a reasonable manner. Unfortunately, systems typically have keepalive support disabled or set to occur only after two hours of inactivity. Liant recommends enabling keepalive support, if necessary, and setting the keepalive delay time to a cycle of two minutes or less. Since the method of setting these system TCP/IP variables varies from system to system, consult your system administration documentation. On UNIX, these TCP/IP parameters are normally part of the kernel parameters that UNIX system administrators can set. On all versions of Windows, these TCP/IP parameters are set in the Windows registry under the following key:

```
HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\Tcpip\Parameter
```

In particular, it is the value name `KeepAliveTime`, the `REG_DWORD` value that defaults to 7,200,000 milliseconds (two hours), which is the value that Liant recommends changing to 120,000 milliseconds (two minutes) or less. More information is available by searching the Microsoft Support Knowledge Base for “keepalive configuration.” RM/InfoExpress calls the `setsockopt` function to enable the `SO_KEEPALIVE` socket option.

Client-Specific Configuration Options

The following configuration options, listed alphabetically, are *specific* to RM/InfoExpress clients:

- **AcceptPassword.** The AcceptPassword option in the [Security] section specifies whether the client should always accept passwords interactively. The default value is No. The server requires a password from the client when the server is running at security level 3, 4, or 5. At level 5, the server forces the client to always accept the password interactively, ignoring any password stored in the **ixpwfile** file on the client machine.

When AcceptPassword=No is set and the server is running at level 3 or 4, the client obtains the password from the **ixpwfile** on the client machine and sends it to the server.

When AcceptPassword=Yes is set and the server is running at level 3 or 4, the client accepts the password interactively (as it does for level 5).

The server administrator may wish to set AcceptPassword=Yes on unsecured client machines where it is undesirable to store any passwords (even though they are encoded) in the **ixpwfile** on that client machine.

- **KeepSession.** Located in the [Options] section. KeepSession=Yes is the default. If the value is set to Yes, the client keeps the session with the server until the run unit terminates, even if all files on that server are closed before that time. This option is sometimes necessary when the client application opens and closes files rapidly, causing sessions to be established and released in rapid succession. Some network implementations cannot handle such frequent session creation, which can lead to errors and program hangs. This option may also improve performance slightly by eliminating the overhead of releasing and re-establishing a session between the Close of one remote file and the Open of another remote file on the same server. The drawback of specifying this option is that sessions may be kept with several servers for long periods of time when they will never be used again, thereby consuming network resources. Errors may occur if some network resources are exhausted.

If the value is KeepSession=No, the client releases the session with the server when the last open file is closed. In addition, the UNIX client supports this option as an environment variable (also called KEEPSSESSION), which when set, overrides the current setting.

- **PathPrefixExcluded** and **PathPrefixIncluded.** These two configuration options are both used to allow an RM/InfoExpress client to exclude selected UNC-style pathnames (beginning with \\ or //) from access via RM/InfoExpress. (Prior to version 8, RM/InfoExpress always attempted access to all UNC-style pathnames.) The PathPrefixExcluded option in the [Options] section determines which pathname prefixes are not to be accessed via RM/InfoExpress. The PathPrefixIncluded option in the [Options] section determines which pathname prefixes can be accessed via RM/InfoExpress.

In each option, the *list* is a comma-separated list of pathname prefix strings. Embedded spaces within each string are kept while leading and trailing spaces are ignored. Matching is case-insensitive and slash (/) matches backslash (\). Thus, \\SRV1\TMP is equivalent to //srv1/tmp. Only whole edgenames are matched, where edgename means the text between two slashes or backslashes or end of string. Consequently, //srv matches //srv/tmp/file.ext but does not match //srv1/tmp/file.ext. No wildcard characters are allowed.

Consider the following to determine when and how to use these closely related options:

- If only PathPrefixExcluded is specified, matching pathnames are excluded and all other pathnames are included.
- If only PathPrefixIncluded is specified, matching pathnames are included and all other pathnames are excluded.
- If both PathPrefixExcluded and PathPrefixIncluded are specified, the longest matching prefix string determines exclusion or inclusion, and pathnames matching none of the prefix strings are included by default.
- If neither PathPrefixExcluded nor PathPrefixIncluded is specified, all pathnames are included (which is the same behavior as prior versions of RM/InfoExpress).

Typically, you would specify either PathPrefixExcluded or PathPrefixIncluded based upon which pathname prefix list is the shortest or most well defined to enumerate. However, both options can be specified for more complicated exclusion and inclusion schemes.

For example, specifying:

```
PathPrefixExcluded=//srv1, //srv2  
PathPrefixIncluded=//srv2/data, //srv2/tmp
```

means that an RM/InfoExpress client will not attempt to access any files on server **srv1** and will attempt to access only files whose pathnames begin with //srv2/data or //srv2/tmp on server **srv2**. You might want this in a situation in which **srv2** is a Windows server where all RM/InfoExpress data files reside in directories **data** and **tmp**, but there are also Windows printers that you want to access via pathnames //srv2/printer1, //srv2/printer2, and so forth. Note, however, that if printer1 and printer2 are the only two pathnames that you do not want to access via RM/InfoExpress on **srv2**, then specifying only the following would achieve the same result:

```
PathPrefixExcluded=//srv1, //srv2/printer1, //srv2/printer2
```

Any other pathname on **srv2**, such as //srv2/data/file, would be included by default since that pathname does not match any excluded path prefix.

- **ReconnectDelay.** The ReconnectDelay option in the [Options] section determines the number of milliseconds the client will delay before attempting to reconnect to the server after the client becomes aware that the connection has been broken. The default value is 100 (one tenth of a second).
- **StartupLogPath.** The StartupLogPath option in the [Options] section creates a file whose directory and pathname are given by *directory-path*, and writes logging information into the file. This client-side log file can be used to diagnose and troubleshoot problems when initially starting up the connection of the RM/InfoExpress client to the RM/InfoExpress server. This log file indicates errors that are encountered in the pre-connection, connect, and first message sent and received operations during the initial connection to the server. The log file also contains the client-side host name, the client-side IP address (from gethostbyname), the server-side host name, the server side IP address, and the result of the connect request.

To configure the location of this log file, RMCLIENT.LOG, specify the following configuration parameter in the [Options] section of the **rmixclnt.ini** file:

```
StartupLogPath=c:\Liant\Logs
```

Note The environment variable, RM_CLIENT_LOG_PATH, may also be used to configure and specify the location of the RMCLIENT.LOG file. Setting the environment variable takes precedence over setting the configuration parameter in the **rmixclnt.ini** file (as described above).

- **UseBlockingIO.** The UseBlockingIO option in the [Winsock] section is provided to improve the performance of the RM/InfoExpress Windows client. If the value is UseBlockingIO=Yes, Windows Sockets functions are called in blocking mode; that is, every function call will block until the request is complete. Using this value also ensures that Windows Sockets Asynchronous functions and the **PeekMessage** function are never called. Substantial performance improvements may occur, depending upon the type of Windows Sockets implementation used. However, the operator will not be able to cancel a Read operation waiting on a locked record. We suggest users experiment using their own benchmark programs to determine whether specifying the value Yes results in better performance for the specific TCP/IP implementation in use.

If the value is UseBlockingIO=No (the default value), Windows Sockets Asynchronous functions and the **PeekMessage** function are used; that is, functions are called in non-blocking mode. If any COBOL program using the Windows client executes a Read operation that waits on a locked record and the operator requires the ability to cancel that operation, the UseBlockingIO option must be set to No.

Sample RM/InfoExpress Windows Client Configuration File

The following is a sample Windows client configuration file (**rmixclnt.ini**).

```
[Debug]
;;; InFoxDebug=DBGFILE

[Security]
IxpWFile=d:\tmp\IXPWFIL

[Winsock]
UseBlockingIO=Yes
```

Common Server-Specific Configuration Options

CAUTION It is imperative that on every RM/InfoExpress server and RM/COBOL runtime system accessing any particular file from any machine, the values specified for the FileProcessCount, LargeFileLockLimit, RelUseLargeLimit, and SeqUseLargeLimit keywords in the RM/InfoExpress server configuration file must match the values specified in the corresponding configuration option in the RM/COBOL runtime system.

The following configuration options, listed alphabetically, are *common* to both the RM/InfoExpress UNIX server and the Windows server programs:

- **DotsBias.** The DotsBias option in the [Options] section is used to specify where an ellipsis (...) appears in filenames that are too long to fit in the display field of the server display program. The leftmost part of the filename appears to the left of the dots and the rightmost part of the filename appears to the right of the dots (the middle of the filename is replaced by the ellipsis.) The default value is zero, which causes the ellipsis to appear in the middle of the field. Negative values move the ellipsis to the left and positive values move the ellipsis to the right. Special value +9999 moves the ellipsis completely out of the right side of the field, thus displaying the leftmost part of the filename (truncated). This is equivalent to RM/InfoExpress version 2.0 behavior. Special value -9999 moves the ellipsis completely out of the left side so that the rightmost part of the filename is displayed (with no ellipsis). This option is cosmetic and has no effect on server operation other than the display.
- **FileBufferPool.** The FileBufferPool option in the [Options] section is used to specify the common buffer pool size on the server machine. The default value is zero, which causes the default size for the common buffer pool. Normally, you should not need to specify a value. This option corresponds to the BUFFER-POOL-SIZE keyword in the RUN-FILES-ATTR configuration record specified for **runcobol**, as described in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*.

The FileBufferPool configuration option is equivalent to the -p command line option, as described in the appropriate sections of [Starting the RM/InfoExpress UNIX Server Program](#) (on page 30) and [Starting and Stopping the RM/InfoExpress Windows Server Program](#) (on page 31). Note that the command line option overrides the configuration option.

- **FileCount.** The FileCount option in the [Options] section may be used to specify the number of files the server can have open simultaneously. The default value is ten times the UseCount. FileCount may need to be increased when every client application has more than ten files on the server open simultaneously. Reducing FileCount will reduce the server's shared and local memory requirements.
- **FileProcessCount.** The FileProcessCount option in the [Options] section determines the maximum number of run units that can have a file open at the same time. It applies to all file organizations. For record and file locks to perform correctly, all RM/InfoExpress servers and RM/COBOL runtime systems opening a file must use the same file process count. The maximum value for this keyword is 16384; the minimum value is 8. The default value is 1024. This option corresponds to the FILE-PROCESS-COUNT keyword in the RUN-FILES-ATTR configuration record specified for **runcobol**, as described in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*.
- **InxUseLargeLimit.** The InxUseLargeLimit option in the [Options] section determines which value to use for the lock limit when creating a version 4 indexed file. If the value is set to No (the default), the lock limit placed into the KIB is 2 GB for indexed files created by the RM/InfoExpress server. If the value is set to Yes, the lock limit placed into the KIB is the value of the LargeFileLockLimit option for indexed files created by

the RM/InfoExpress server. Note that existing version 4 indexed files always use the lock limit stored in their KIB. This option corresponds to the USE-LARGE-FILE-LOCK-LIMIT keyword in the RUN-INDEX-FILES configuration record specified for **runcobol**, as described in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*.

- **LargeFileLockLimit.** The LargeFileLockLimit option in the [Options] section determines the limit for the location to apply locks to a file that will be accessed as a large file. For record and file locks to perform correctly, all RM/InfoExpress servers and RM/COBOL runtime systems opening a particular file must use the same lock limit for that file. The lock limit also limits the actual amount of data that can be stored in a file. This limit will be used when a new indexed file is created provided the file version of the file is 3 or greater. Otherwise, this limit has no effect on indexed files. The value assigned to this keyword is specified in gigabytes (GB). The maximum value is 1048576, which equates to 1 petabyte (2^{50}). The minimum value is 1. The default value is 64. The lock limit for a normal file is 2 GB. This option corresponds to the LARGE-FILE-LOCK-LIMIT keyword in the RUN-FILES-ATTR configuration record specified for **runcobol**, as described in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*.
- **MinimumBlockSize.** The MinimumBlockSize option in the [Options] section determines the minimum disk block size for the indexed files created by the RM/InfoExpress server, represented as a decimal number. The maximum value for this keyword is 4096; the minimum value is 256. The default value is 1024. This option corresponds to the MINIMUM-BLOCK-SIZE keyword in the RUN-INDEX-FILES configuration record specified for **runcobol**, as described in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*.
- **ReconnectTimeout.** The ReconnectTimeout option in the [Options] section determines the number of minutes the server will keep the file manager process serving the client intact waiting for the client to reconnect to it. In particular, all file and record locks remain in place while the client is disconnected and will prevent access by other run units. The default value is 180 (three hours).
- **RelUseLargeLimit.** The RelUseLargeLimit option in the [Options] section determines which value to use for the limit when applying locks to a relative file. If the value is set to No (the default), the lock limit for relative files is 2 GB. If the value is set to Yes, the value of the LargeFileLockLimit option is used. For record and file locks to perform correctly, all run units RM/InfoExpress servers and RM/COBOL runtime systems opening a file must use the same lock limit for that file. This option corresponds to the USE-LARGE-FILE-LOCK-LIMIT keyword in the RUN-REL-FILES configuration record specified for **runcobol**, as described in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*.
- **RoundToNiceBlockSize.** The RoundToNiceBlockSize option in the [Options] section determines whether the block size computed for the indexed files created by the RM/InfoExpress server is forced to be a multiple of 512 (under Windows) or the value of BUFSIZ, taken from the C include file `<stdio.h>` (under UNIX). The default value for this keyword is Yes. This option corresponds to the ROUND-TO-NICE-BLOCK-SIZE keyword in the RUN-INDEX-FILES configuration record specified for **runcobol**, as described in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*.
- **SeqUseLargeLimit.** The SeqUseLargeLimit option in the [Options] section determines which value to use for the limit when applying locks to a sequential file. If the value is set to No (the default), the lock limit for sequential files is 2 GB. If the value is set to Yes, the value of the LargeFileLockLimit option is used. For record and file locks to perform correctly, all RM/InfoExpress servers and RM/COBOL runtime systems opening a file must use the same lock limit for that file. This option corresponds to the USE-LARGE-FILE-LOCK-LIMIT keyword in the RUN-SEQ-FILES configuration record

specified for **runcobol**, as described in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*.

- **UseCount.** The UseCount option in the [Options] section may be used to specify the number of clients that the server can serve simultaneously. This number must not be greater than the server's licensed client count. A reduced value on the UseCount option will reduce the server's shared and local memory requirements. The number of clients will default to the server's licensed client count unless the client count is "unlimited." In that case, it will default to 50.

The UseCount configuration option is equivalent to the -k command line option, as described in the appropriate sections of [Starting the RM/InfoExpress UNIX Server Program](#) (on page 30) and [Starting and Stopping the RM/InfoExpress Windows Server Program](#) (on page 31). Note that the command line option overrides the configuration option.

UNIX Server-Specific Configuration Options

The following configuration options, listed alphabetically, are *specific* to the RM/InfoExpress UNIX server:

- **ConvertFileName.** The ConvertFileName option, which is located in the [Options] section and can have three values, is used to process the filename before the file is opened on the server's native operating system. When ConvertFileName=NoConvert (the default value), no filename mapping is performed. ConvertFileName=UpperCase indicates that the entire filename is mapped to uppercase before the Open request is attempted. ConvertFileName=LowerCase indicates that the entire filename is mapped to lowercase before the Open request is attempted.

The ConvertFileName configuration option is equivalent to the -c command line option, as described in the appropriate sections of [Starting the RM/InfoExpress UNIX Server Program](#) (on page 30) and [Starting and Stopping the RM/InfoExpress Windows Server Program](#) (on page 31). Note that the command line option overrides the configuration option.

- **DefaultServerUser.** The DefaultServerUser option in the [Security] section specifies the user name (at security levels 0 or 1) to run on the server when the security validation fails. Normally, the default server user will be allowed to access files that do not require high levels of security. The default server user must be a valid user on the server. The default is DefaultServerUser=rmsserver.
- **ServerSecurityLevel.** The ServerSecurityLevel option in the [Security] section specifies the security level number at which the UNIX server is to run (for more information, see [Chapter 6: File Security on the RM/InfoExpress UNIX Server](#) on page 57). Valid values range from 0 through 5. If this option is not specified, the server runs in compatibility mode, that is, the behavior is equivalent to an RM/InfoExpress version 2.0 server.

Sample RM/InfoExpress UNIX Server Configuration File

The following is a sample UNIX server configuration file (**rmixsrvr.ini**).

```
[Debug]
;;; InfoxDebug=DBGFILE

[Security]
IxPwFile=/usr/foo/ixpfile
ServerSecurityLevel=5
DefaultServerUser=foo
```

Windows Server-Specific Configuration Options

The following configuration options are specific to the RM/InfoExpress Windows server:

- **share-name.** The *share-name* option in the [Sharing] section defines a share name and equates it with a pathname (*share-path*). On Windows, the edgename following the server machine name is a share name; for example, `\\server-name\share-name\rest-of-path-to-file`. All share names and paths are case-insensitive.

The server generates pathnames as follows:

1. Searches for the specified share name.
2. If found, substitutes the *share-path* for the name; if not found, searches for a null share name.
3. If found, prepends the *share-path* to the filename; if not found, checks the UseCurrentDirectory configuration flag.
4. If “Yes”, prepends the current working directory path to the filename; if “No”, returns a “35” error.

The generated pathname is then given to the RM/COBOL File Manager.

For example, if the [Sharing] section on host *serverW* contains

```
[Sharing]
cdrive=c:\tmp
AcctPayable=d:\acctpayable\data
=e:\guest\data
```

then the client path `\\serverW\cdrive\file.dat` causes the server to access

```
c:\tmp\file.dat
```

Similarly,

\\serverW\cdrive\red\white\blue	c:\tmp\red\white\blue
\\serverW\acctpayable\master.inx	d:\acctpayable\data\master.inx
\\serverW\file1	e:\guest\data\file1
\\serverW\xyzy\tmp\junk.x	e:\guest\data\xyzy\tmp\junk.x
\\serverW\cdrive	e:\guest\data\cdrive

If the null share name line (=e:\guest\data) did not exist and the server was started in c:\bin, then:

\\serverW\file1	c:\bin\file1
\\serverW\xyzy\tmp\junk.x	c:\bin\xyzy\tmp\junk.x
\\serverW\cdrive	c:\bin\cdrive

The server's current working directory is the default path for the null share name provided the UseCurrentDirectory option is set to Yes.

If there is no [Sharing] section and if UseCurrentDirectory=No and UseSystemShares=No are both set, then every open returns a 35 error.

The path associated with a share name is intended to start with a drive letter and to specify a valid directory so that the resulting final pathname is an absolute pathname on the server machine.

- **UseCurrentDirectory.** The UseCurrentDirectory option in the [Options] section determines whether or not the server's current directory pathname is prepended to the filename when the edgename following the server name does not match any valid share name. UseCurrentDirectory=Yes is the default.
- **UseSystemShares.** The UseSystemShares option in the [Options] section determines whether or not the Windows server system share names are used. UseSystemShares=Yes is the default. A Windows server system share name is defined in the Shared As portion of the Sharing tab of the disk or directory folder Properties. Note that RM/InfoExpress server ignores the Access Type and Passwords portions of the Sharing tab. If UseSystemShares=No is specified, only the share names defined in the **rmixsrvr.ini** file [Sharing] section are used.

Sample RM/InfoExpress Windows Server Configuration File

The following is a sample Windows server configuration file (**rmixsrvr.ini**).

```
[Debug]
;;;InfoxDebug=DBGFILE

[Sharing]
cdrive=c:\
ShareTemp=d:\tmp\shared\files

[Options]
UseCurrentDirectory=Yes
UseSystemShares=Yes
```

Appendix E: RM/InfoExpress Security Parameter File Update Utility

This appendix describes how to use the **ixsecure.cob** program to update the **ixpwwfile** parameter file with security-related information that is used by the server to authenticate the clients. Note that **ixpwwfile** must exist when the RM/InfoExpress server is run at security levels greater than level 2. The implementation of file security in RM/InfoExpress is detailed in [Chapter 6: File Security on the RM/InfoExpress UNIX Server](#) (on page 57).

The RM/COBOL object program, **ixsecure.cob**, is included with the RM/InfoExpress media to enable users to build the security parameter file, **ixpwwfile**. The RM/COBOL runtime system (**runcobol**) is needed to run this object program.

A separate parameter file (**ixpwwfile**) is required for each of the client machines and one for the server machine. The parameter file for the client machine may have several entries, each giving information about this client and one of the servers with which this client communicates. Similarly, the parameter file for the server machine may have several entries, each giving information about this server and one of the clients that may connect to the server.

Using the Utility

To run the security parameter file update utility, use the following command:

```
runcobol ixsecure
```

If the security parameter file, **ixpwfile**, is not in the current directory or has a different name, set the IXPWFILE environment variable to the current pathname of the file.

The RM/InfoExpress Security Parameter File Update utility Main screen, illustrated in [Figure 15](#), is displayed.

Figure 15: Security Parameter File Update Utility Main Screen

```
RM/InfoExpress Security Parameter File Update Utility

      1. Add an entry
      2. Modify an entry
      3. Delete an entry
      4. List all entries
      5. Exit/Quit to system

Select option using arrow keys, number, or letter:
```

To choose an option on this screen, move the cursor with the arrow keys to a particular option and press Enter. Alternatively, you can type the option number or the first letter of the option description (it is not necessary to press Enter afterwards). To exit the utility program, choose option 5.

Note If RM/COBOL finds an error while performing the requested operation, a message with the appropriate RM/COBOL runtime error is displayed on the last line of the screen, and the utility waits for acknowledgment.

When the **ixpwfile** is empty (such as the first time this utility is run on a machine), a warning message is displayed and the file is created.

Adding a New Entry

To add a new entry, choose option 1 on the Main screen. The RM/InfoExpress Security Parameter File Update utility Add Entry screen, illustrated in [Figure 16](#), is displayed.

Figure 16: Add Entry Screen

```
RM/InfoExpress Security Parameter File Update Utility
      ADD ENTRY

SERVER MACHINE NAME:.....
CLIENT MACHINE NAME:
SERVER USER NAME:
PASSWORD:
```

Type the requested information and press Enter on the last line to complete the entry. If you want to cancel the input at any time, press Esc. The utility displays the RM/InfoExpress Security Parameter File Update utility Main screen, illustrated in [Figure 15](#) on page 106. Otherwise, the entry will be added to the file.

The SERVER USER NAME is case-sensitive.

The SERVER USER NAME and CLIENT MACHINE NAME are not case-sensitive; that is, they will be displayed as entered but will be mapped to uppercase for use by RM/InfoExpress.

Note If you are creating a security parameter file for an RM/InfoExpress server, the password field on the Add Entry screen should be left blank (simply press Enter in this field). The password in an entry for the server security parameter file is always ignored.

Modifying an Existing Entry

To modify an existing entry, choose option 2 on the Main screen. The RM/InfoExpress Security Parameter File Update utility Modify Entry screen, illustrated in [Figure 17](#), is displayed.

Figure 17: Modify Entry Screen

```
RM/InfoExpress Security Parameter File Update Utility
                          MODIFY ENTRY

SERVER MACHINE NAME:  unixserver.....
CLIENT MACHINE NAME:  mypc
SERVER USER NAME:    user1
PASSWORD:

Select using DOWN-ARROW/UP-ARROW/ENTER/ESC:
```

Using the arrow keys, choose the entry you wish to modify. Update the information on the screen and press Enter on the last line to complete the entry. If you want to cancel the input at any time, press Esc. The utility displays the RM/InfoExpress Security Parameter File Update utility Main screen, illustrated in [Figure 15](#) on page 106. Otherwise, the current entry in the file will be replaced by this information.

Deleting an Existing Entry

To delete an existing entry, choose option 3 on the Main screen. The RM/InfoExpress Security Parameter File Update utility Delete Entry screen, illustrated in [Figure 18](#), is displayed.

Figure 18: Delete Entry Screen

```
RM/InfoExpress Security Parameter File Update Utility
      DELETE ENTRY

SERVER MACHINE NAME:  unixserver.....
CLIENT MACHINE NAME:  mypc
SERVER USER NAME:    user1
PASSWORD:

Select using DOWN-ARROW/UP-ARROW/ENTER/ESC:
```

Using the arrow keys, choose the entry you wish to delete and press Enter. If you want to cancel the input at any time, press Esc. The utility displays the RM/InfoExpress Security Parameter File Update utility Main screen, illustrated in [Figure 15](#) on page 106. Otherwise, the current entry in the file will be deleted.

After successful deletion, the following message is displayed for confirmation:

```
Confirm deletion (Y/N)
```

Type Y to confirm deletion. (To abandon the deletion, type N.) The following message is displayed to confirm the successful deletion of the entry from the file:

```
Record deleted successfully. Press any key...
```

Listing All Entries

To list all entries in the file, choose option 4 on the Main screen. The RM/InfoExpress Security Parameter File Update utility List Entries screen, illustrated in [Figure 19](#), is displayed showing the following information.

Figure 19: List Entries Screen

```
RM/InfoExpress Security Parameter File Update Utility
LIST ENTRIES

Server Machine Name  Client Machine Name  Server User Name
unixserver1          mypc                  user1
unixserver2          mypc                  user2

Press any key. . .
```

Press any key to return to the RM/InfoExpress Security Parameter File Update utility Main screen, illustrated in [Figure 15](#) on page 106. If the file contains more entries than can be displayed on one screen, additional screens will be displayed when a key is pressed. When all entries have been displayed, pressing a key will return to the Main screen.

Note The password information is not displayed.

Appendix F: Using RM/InfoExpress with Relativity

RM/InfoExpress can be used with Relativity for RM/COBOL to access the catalog and/or files stored on a server running the RM/InfoExpress server program. This appendix provides instructions for 32-bit RM/InfoExpress Windows clients.

Note Some earlier versions of Relativity are called Relational DataBridge.

Changes to Relativity Configuration for 32-Bit Windows Clients

The 32-bit RM/InfoExpress Windows client software (**rmtcp32.dll**) is installed with Relativity. Note that the RM/InfoExpress Windows client software is not supplied with the RM/InfoExpress server software or versions of Relativity prior to 2.5. It is distributed with the RM/COBOL for Windows runtime or development system or, alternatively, it can be downloaded from the Liant web site (www.liant.com). Contact Liant technical support services for more information.

The configuration procedures begin in the section [Configure Relativity to Use RM/InfoExpress](#) (on page 112). These instructions assume the following:

- You have the RM/InfoExpress server main program and server display program installed and running on your server machine. For more information, see the installation instructions in [Chapter 1: Installation and Verification](#) (on page 7).
- You have the complete Microsoft TCP/IP software package installed and configured in the Networking option on the Control Panel. (See also Chapter 1 of this manual.)
- You are running Windows clients.

Create a Configuration File

Create a file, called **rmixclnt.ini**, in the main Windows directory to set configuration parameters for RM/InfoExpress client programs. Include the following entry:

```
[Winsock]  
UseBlockingIO=Yes
```

This entry prevents a 10055 system error: “No available buffer space”. This configuration parameter is discussed in [Client-Specific Configuration Options](#) (on page 96).

Configure Relativity to Use RM/InfoExpress

There are two aspects to configuring the Relativity ODBC data source setup: configuring Relativity to use RM/InfoExpress and specifying the location of the Relativity catalog on the server.

Note All setup options can be configured from the Windows client workstation using the ODBC Data Source Administrator that is distributed with Relativity.

To configure Relativity to use RM/InfoExpress:

1. On the Windows client workstation, open the **Control Panel**.
2. To access the ODBC Data Source Administrator from the Control Panel, double-click **Administrative Tools**.
3. On the Administrative Tools page, double-click **Data Sources (ODBC)**.
4. In the ODBC Data Source Administrator dialog box, select the **User DSN** tab and then click **Add**.
5. In the Create Data Source dialog box, double-click **Relativity (*.rcg)** as the driver type.
6. In the Relativity dialog box, select the **RM/COBOL** option in the File Manager tab and then select the **RM/InfoExpress** tab to display the RM/InfoExpress page.
7. In the RM File Manager options area, select the **Enable RM/InfoExpress** check box, which enables access to RM/InfoExpress.

The option for “Allow File Creation” is selected by default.

8. Next, click the **Display Initial Message Box** option to verify correct operation.

This action is useful when first configuring Relativity to use RM/InfoExpress. A message box will be displayed when RM/InfoExpress is first called. If the message box is not displayed, it indicates that any problems are not network related, but are caused by the software installation. Similarly, if there is a problem but the message box is displayed, the problem is related to the network.

Note After installation is verified, you may return to the RM/InfoExpress tab using the 32-bit ODBC Administrator, as described in Step 3, and clear the Display Initial Message Box option.

9. In the Relativity dialog box, select the **DSN** tab.

This tab has entries for the data source name and description, as well as buttons to select or create a Relativity catalog.

Continue by specifying the location of the Relativity catalog on the server:

1. In the **Data Source Name** box on the DSN tab, enter the name needed for the data source (what users will see from their ODBC-enabled application, such as Microsoft Access or Excel).
2. Click the **Select Catalog** button. The Select Catalog for Data Source dialog box is displayed.
3. In the Select Catalog for Data Source dialog box, select the **Use RM/InfoExpress only** check box.
4. In the **File name** box, enter the complete pathname.

You must specify the name in the following format:

```
\\RMInfoExpressServer\PathToFile
```

where *RMInfoExpressServer* must match the TCP/IP host name for the server machine on this client (for example, \\HOSTNAME\test.rcg). The following example specifies a Relativity catalog called **shirt3.rcg** in the directory **/usr/relsamples** on the server **unixware21**:

```
\\unixware21\usr\relsamples\shirt3.rcg
```

5. After you enter a valid RM/InfoExpress server and filename, click **Open**. The Relativity catalog name will be validated and returned to the Relativity dialog box as the name of the Relativity catalog for the data source. This information is displayed in the Catalog Name area.
6. In the Relativity dialog box, click **OK** to complete creation of the Relativity data source.

Appendix G: Summary of Enhancements

This appendix provides a summary of the new features and changes in the various releases of RM/InfoExpress. It also tells you where to look for more information about them.

The enhancements and changes for the most recent release described by this document are listed first. The information in this appendix is historical and was accurate at the time written for the specific version being described. Various features may have changed in later releases, and, possibly, some features may have been removed.

Note The RM/InfoExpress version number refers to the RM/InfoExpress server; RM/InfoExpress client(s) do not have version numbers.

Version 12 Enhancements

The following summarizes the major new enhancements in RM/InfoExpress version 12:

- The RM/InfoExpress server File Manager has been updated to RM/COBOL version 12 compatibility.
- Client-side logging is a new capability to diagnose initial connection problems from the RM/InfoExpress client to the RM/InfoExpress server. The RMCLIENT.LOG file logs errors that are encountered in the pre-connection, connect, and the first message sent and received operations. In addition, this new log file contains the following information for each connection:
 - the client-side host name
 - the client-side IP address (from gethostbyname)
 - the server-side host name
 - the server-side IP address
 - the result of the connect request

For more information, see the StartupLogPath configuration parameter in [Client-Specific Configuration Options](#) (on page 96) of Appendix D: *Configuring RM/InfoExpress*.

Version 11 Enhancements

The following summarizes the major new enhancements in RM/InfoExpress version 11:

- The RM/InfoExpress server File Manager has been updated to RM/COBOL version 11 compatibility.
- Support for Microsoft Windows Vista was added.

Version 10 Enhancements

The following summarizes the major new enhancements in RM/InfoExpress version 10:

- The RM/InfoExpress server File Manager has been updated to RM/COBOL version 10 compatibility.

Version 9 Enhancements

The following summarizes the major new enhancements in RM/InfoExpress version 9:

- The RM/InfoExpress server File Manager has been updated to RM/COBOL version 9 compatibility. (For further information, see “Version 9 Enhancements” in Appendix L: *Summary of Enhancements*, of the *RM/COBOL User’s Guide*.)
- The RM/InfoExpress server display main screen now shows the server uptime (in days) at the end of the date and time line. It can also now display 999,999,999,999 (one trillion—U.S.—minus one) total messages after which the count wraps back to zero. See [Server Display Commands](#) (on page 47).
- The Windows server (**rmsrvtcp.exe**) now uses WinSock 2. In particular, this allows a much larger connection queue (WinSock 1 had a maximum backlog of 5), which should avoid error 10061.
- The Windows server installation creates a Windows Firewall Exception, if applicable, for the RM/InfoExpress TCP port number 21069. If you change the port number (which is *not* recommended), you must change both the **services** file and the Windows Firewall configuration.

Version 8 Enhancements

This section summarizes the major enhancements available in version 8 of RM/InfoExpress.

Support for Large Files

Because the RM/InfoExpress server contains the RM/COBOL file management system, the RM/InfoExpress server includes the same support for large files as that offered by the RM/COBOL runtime system (**runcobol**).

When running under operating systems that support files larger than 2 GB (gigabytes), the RM/COBOL runtime system allows RM/COBOL files to grow past limits imposed in previous versions. This support is provided by the **LARGE-FILE-LOCK-LIMIT** keyword of the **RUN-FILES-ATTR** configuration record. In order to use this new limit on relative or sequential files, you must use the **USE-LARGE-FILE-LOCK-LIMIT** keyword in a **RUN-REL-FILES** or **RUN-SEQ-FILES** configuration record. In RM/InfoExpress, the server configuration file (**rmixsrvr.ini**) contains keywords that correspond to those in the RM/COBOL runtime system and that provide the same support. For record and file locks to perform correctly, all RM/InfoExpress servers and RM/COBOL runtime systems opening a file must use the same lock limit for that file.

On the Windows 9x class of operating systems, files up to 4 gigabytes (GB) are supported. The Windows NT class of operating systems supports multiple terabyte files on the NT file system. Only files on FAT32 (file system format supported for Windows 9x-class operating systems) or NTFS (file system format supported on Windows NT-class operating systems) may be larger than 2 GB.

For more information, see [Appendix D: Configuring RM/InfoExpress](#) (on page 91) of this manual and Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*. In order to use this new limit on indexed files, you must use an indexed file version level of 3 (see the "Very Large File Support" topic in Chapter 8: *RM/COBOL Features*, of the *RM/COBOL User's Guide* for more information). Additional information about UNIX and Windows systems that support large files also can be found in the "Using Large Files" topic in Chapter 2: *Installation and System Considerations for UNIX* and in Chapter 3: *Installation and System Considerations for Microsoft Windows*, respectively, of the *RM/COBOL User's Guide*.

Atomic I/O Support for File Version Level 4

In RM/InfoExpress, as in RM/COBOL, file version level 4 indexed files optionally support the new "atomic I/O" capability, which provides a means for users to avoid almost all 98 errors caused by failures that occur while a file is open. Files created with atomic I/O will almost never need recovery. If a crash occurs during a COBOL I/O operation, the file will be automatically and quickly recovered the next time the file is opened or a write operation is performed. The **ENABLE-ATOMIC-IO** keyword has been added to the **RUN-INDEX-FILES** configuration record to determine whether indexed files created by the runtime system use atomic I/O.

The default indexed file version for new files has been changed from 2 to 4 to automatically provide the higher level of reliability to new files. The **DEFAULT-FILE-VERSION-NUMBER** keyword of the **RUN-INDEX-FILES** configuration record may be used to specify a different value.

Version 4 indexed files may, like version 3 files, grow to a larger size than version 0 or 2 files. However, unlike version 3 files, version 4 files may be either large or regular sized

files, depending on the new USE-LARGE-FILE-LOCK-LIMIT keyword of the RUN-INDEX-FILE configuration record. This new keyword determines whether the LARGE-FILE-LOCK-LIMIT or the FILE-LOCK-LIMIT keyword of the RUN-FILES-ATTR configuration record is used to determine the largest address that can be locked in the file. This, in turn, determines how large the file can be.

Limited Automatic Session Reconnection

Beginning with version 8, a limited reconnection capability, which allows a connection that becomes broken to be reconnected automatically, has been added to the RM/InfoExpress client and server logic. The client and server continue normal operation without the client run unit (COBOL program) ever being aware of the disconnection. To enable this capability, you must set ReconnectEnable=Yes in the [Options] section of the **rmixsrvr.ini** server configuration file, as explained in [Appendix D: Configuring RM/InfoExpress](#) (on page 91).

Client Path Prefix Inclusion and Exclusion

A new feature has been added in version 8 to allow the RM/InfoExpress client to exclude selected UNC-style pathnames (beginning with \\ or //) from access via RM/InfoExpress. Prior versions of RM/InfoExpress always attempted access to all UNC-style pathnames. In the **rmixclnt.ini** configuration file in the [Options] section, you can specify PathPrefixIncluded=*list* and PathPrefixExcluded=*list*. For more information, see [Appendix D](#) (on page 91).

Version 2.1 Enhancements

This section summarizes the major enhancements available in version 2.1 of RM/InfoExpress.

RM/InfoExpress Server Now Supported on Windows NT Version 4.0

A version of the RM/InfoExpress server software now runs on the Windows NT Server (version 4.0).

File Security on the RM/InfoExpress UNIX Server

The RM/InfoExpress UNIX server now provides enhanced file security. The level of security is specified at the time the server is invoked. The server performs various validations on the authenticity of the client(s) before granting access to a file. For more information, see [Chapter 6: File Security on the RM/InfoExpress UNIX Server](#) (on page 57).

New Utility to Update RM/InfoExpress Parameter File

To make the RM/InfoExpress server screens display similar information about all types of clients, all new clients now provide client-specific information (such as *client-machine-name* and *user-name* of the client on the server, as described in Chapter 6) to the server from a security parameter file. This parameter file, default name **ixpwfile**, is created using a utility program, **ixsecure.cob**. For more information about how to use this utility, refer to [Appendix E: *RM/InfoExpress Security Parameter File Update Utility*](#) (on page 105).

Improved Server Screens

Additional information has been added to the server screens to identify the clients. For example, the Error Log screen now displays the name of the file on which the error occurred.

Optional Message Compression

This version of RM/InfoExpress optionally compresses messages before transmitting them on the network. Depending on the compressibility of the messages, which include the records from RM/COBOL data files, compression may improve the performance of RM/InfoExpress over WANs and heavily loaded LANs.

Optional Message Encoding

This version of RM/InfoExpress optionally encodes messages before transmitting them on the network to provide more security for the COBOL data.

Initialization File Support

All implementations of RM/InfoExpress now allow configuration information to be stored in a file that is in an .INI format. For more information, see [Appendix D: *Configuring RM/InfoExpress*](#) (on page 91).

-m Server Option Obsolete

The RM/InfoExpress server now automatically expands the message buffer size (previously set using the -m option on the server command line) as required by each session. The user should no longer receive the error RMIX_ERR_OUT_OF_MEMORY when transmitting records larger than 5000 bytes.

Use Count Check by the Server

The RM/InfoExpress server now limits the number of client connections to the value specified by the UseCount configuration option or the licensed use count, whichever is less. For more information, see the [UseCount configuration option](#) (on page 101).

New File Count Option

The RM/InfoExpress server can now be configured for any number of simultaneously open files, independent of the licensed use count. For more information, see the [FileCount configuration option](#) (on page 99).

New Option to Handle the Display of Long Filenames

The RM/InfoExpress screen handler (server display) program can now be configured to display more reasonably a filename that is too long to fit in the display field of the screen handler. For more information, see the DotsBias configuration option as described in [Appendix D](#) (on page 91).

Version 2.0.2 Enhancements

This section summarizes the major enhancements available in version 2.0.2 of RM/InfoExpress.

New Server Option Enables the RM/plusDB Interface

The -b option has been added in order to enable RM/InfoExpress to communicate with RM/plusDB. Use the -b option when invoking the RM/InfoExpress server with the RM/plusDB product if every filename is to be checked for an RM/plusDB table name by the server before opening the RM/COBOL data file.

Note Beginning with version 8 of RM/InfoExpress, Liant Software no longer develops or supports RM/plusDB. This option is maintained for backward compatibility only and should be ignored. Do not specify this option unless you have used RM/plusDB in your application.

Version 2.0 Enhancements

This section summarizes the major enhancements available in version 2.0 of RM/InfoExpress.

RM/InfoExpress UNIX Server Filename Case-Sensitivity

For the RM/InfoExpress UNIX server, the `-c` option allows you to specify whether to map the filename on an Open request to uppercase, lowercase, or leave it unaltered (the default). For more information, see [Chapter 2: Configuring and Running the RM/InfoExpress Server](#) (on page 29).

RM/InfoExpress UNIX Server Configuration Option

For the RM/InfoExpress UNIX server, the `-c 1` configuration option must be specified if the pathnames are to be converted to lowercase (as in the previous version). The default is no conversion. For more information, see [Chapter 2](#) (on page 29).

RM/InfoExpress UNIX Server Runs as a Daemon

This version of the RM/InfoExpress UNIX server runs unattended in the background and no longer requires an additional terminal. The server uses data structures built-in shared memory. The server modifies the data structures using a well-defined administrative API (Application Programming Interface) to preserve the integrity of the server data structures.

RM/InfoExpress Screen Handler Program

The screen handler (server display) portion of RM/InfoExpress has been removed from the server program and is now a separate application. The screen handler application shares the data structures present in shared memory along with the server daemon. The screen handler accesses the data structures using a well-defined administrative API.

The screen handler program is improved to read an entire screen of information in a single operation, thus providing more consistency to the data it displays.

Under UNIX, the screen handler can be invoked more than once on the system, making it possible for multiple users to view the server statistics simultaneously. The screen handler application can be run from any terminal on the UNIX system.

The command sequence, Terminate Display, now terminates the screen handler program without affecting the server or any clients.

The following sections describe two additional modifications to the screen handler program.

Changes in the Default Behavior

The default behavior of the screen handler (server display) program allows only the termination of the screen handler program itself. This prevents you from accidentally stopping the server or a specific client. To terminate the server or a particular client, you must specify the `-t` option (as described in [Chapter 2: Configuring and Running the RM/InfoExpress Server](#) on page 29) when you start the screen handler program.

New Screens

The Error Information screen has been replaced by two new screens.

The Open Log screen displays information about the most recent 24 open operations performed by the server. The Error Log screen displays information about the most recent 24 errors, including the complete error code and location of the error. For more information, see [Chapter 5: RM/InfoExpress Server Operations](#) (on page 45).

More COBOL Information Added to Existing Screens

More COBOL-related information has been added to existing screens. The Client Files Information screen now displays the organization, open mode, and the access mode of each file currently opened by the client. A new field, System name, has been added to the Client Information screen. This field displays the type of operating system on which the client is running. See [Chapter 5](#) (on page 45) for further details.

Improved Error Handling

Error handling has been improved in this version of RM/InfoExpress. Additional information, such as the location of the occurrence, is also now maintained.

KEEPSESSION Configuration Option

The default value for the KEEPSESSION configuration option has changed from NO to YES. For more information, see [Appendix D: Configuring RM/InfoExpress](#) (on page 91).

Index

A

AcceptPassword configuration option 98
AIX operating system 17

B

Block size 102
Bold type, use of as a document convention 5
Browsers 12–16
BSD Sockets software, error messages 74, 85
Buffer pool size 33, 36, 101
BUFFER-POOL-SIZE keyword, RUN-FILES-ATTR
configuration record 101

C

-c command line option, server 32, 103
Case-sensitivity, configuration options 32, 93, 123
Character-based terminals 47
Client program 10
accessing 39, 43
configuration file options 93, 95, 98
executing RM/COBOL programs with 42, 45
installation 22
pointing to network data files 40–42, 44–45
setting up TCP/IP package 22
system requirements 9–10
terminating communication to 33, 37, 55, 90
verification, installation 23–29, 23–29
Clients, validating 59
Command line options, server 31, 32, 36
buffer pool size (-p) 33, 36, 101
debug (-d) 32, 36, 95
display program (-t) 33, 34, 35, 37, 55
mapping filenames (-c) 32, 103
maximum amount of data handled by TCP send
function (-z) 33, 36, 96
maximum number of clients open (-k) 33, 36, 103
Communication, client and server machines 25, 28
Compatibility mode 60, 63, 103

Compiler options (RM/COBOL), hyphens,
used with 5
Configuration 93. *See also* Configuration file
options; Command line options, server.
client 93, 95, 98
files, samples of 94, 100, 104, 106
server 93, 95, 101, 103, 104
with RM/COBOL 93, 119
Configuration file options 93
client 98
AcceptPassword 98
KeepSession 98
PathPrefixExcluded 98
PathPrefixIncluded 98
ReconnectDelay 99
StartLogPath 99
UseBlockingIO 100
client and server 95
EncodeData 95
IgnoreHangupError 95
InfoxDebug 33, 36, 95
IxCompress 96
IxPwFile 64, 96
MaxSendSize 33, 36, 96
ReconnectEnable 96
server 31, 101, 103, 104
ConvertFileName 32, 103
DefaultServerUser 62, 63, 72, 103
DotsBias 53, 54, 101
FileBufferPool 33, 36, 101
FileCount 101
FileProcessCount 101
InxUseLargeLimit 101
LargeFileLockLimit 102
MinimumBlockSize 102
ReconnectTimeout 102
RelUseLargeLimit 102
RoundToNiceBlockSize 102
SeqUseLargeLimit 102
ServerSecurityLevel 60, 63, 72, 103
share-name 104
UseCount 33, 36, 103
UseCurrentDirectory 105
UseSystemShares 105
Configuration files
client (rmixclnt.ini) 64–71, 93
server (rmixsrvr.ini) 64–71, 93
Configuration records, RM/COBOL
EXTERNAL-ACCESS-METHOD 39, 43
RUN-FILES-ATTR 101, 102, 119
RUN-REL-FILES 119
RUN-SEQ-FILES 119
Console interface 47
Conventions and symbols used in this manual 5
ConvertFileName configuration option 32, 103

D

- d command line option, server 32, 36, 95
- Data-names, RM/COBOL programs 42, 45
- Debugging 32, 36, 95
- DefaultServerUser configuration option 62, 63, 72, 103
- Directory search sequence, synonyms 40, 44
- DNS. *See* Domain Name Service.
- Documentation overview 3
- Domain Name Service 11, 22
- DOS environment variables 40
- DotsBias configuration option 53, 54, 101
- Downloading, from Web 12–16

E

- Ellipsis in filenames 101
- EncodeData configuration option 95
- Encoding messages 95
- Enhancements to RM/InfoExpress
 - version 10 118
 - version 11 118
 - version 12 117
 - version 2.0 123
 - version 2.0.2 122
 - version 2.1 120
 - version 8 119
 - version 9 118
- Environment variables
 - DOS 40
 - IXCONFIG 64, 93
 - IXPWFIL 64
 - IXPWFIL 108
 - KEEPSESSION 98
 - PATH 28
 - RM_CLIENT_LOG_PATH 100
 - RM_RECONN_LOG_PATH 97
 - RUNPATH 28, 41, 44
 - troubleshooting 89
- Error messages 73–85
- Explicit pathnames 41, 45
- EXTERNAL-ACCESS-METHOD configuration record 39, 43

F

- Failure to locate file or path 89
- File access, network 40, 44
- File lock limit 101, 102, 119
- File security 10, 60, 107. *See also* Security, on UNIX server.
- File security parameter file update utility (ixsecure.cob) 10, 60, 107
- File version level, in indexed files 101, 119
- FileBufferPool configuration option 33, 36, 101

- FileCount configuration option 101
- FileProcessCount configuration option 101
- FILE-PROCESS-COUNT keyword, RUN-FILES-ATTR configuration record 101

Files

- client program
 - librminfo.so, UNIX 10, 22, 28, 43
 - rmtcp32.dll, Windows 10, 22, 39
- configuration
 - rmixclnt.ini 93, 100
 - rmixsrvr.ini 31, 93, 104, 106
 - sample of 94
- hosts 11, 22, 27
- rhosts 59, 62, 65
- server display program
 - rmdisptcp, UNIX 10, 32
 - rmdistcp.exe, Windows 10
- server program
 - rmservertcp, UNIX 10, 32
 - rmsrvtcp.exe, Windows 10
- services 11, 22, 27

H

- hosts file 11, 22, 27
- HP-UX operating system 17
- Hyphen (-), using with optional, RM/COBOL compilation and runtime options 5

I

- IBM AIX operating system 17
- IgnoreHangupError configuration option 95
- Indexed files 101, 119
- InfoDebug configuration option 33, 36, 95
- infxdmo, verification program 27, 28
- Installation
 - client program 10, 22
 - server display program 10, 12, 15
 - server program 10, 12, 15
 - setting up TCP/IP package for
 - RM/InfoExpress clients 22
 - RM/InfoExpress servers 11
 - system considerations 16. *See also* Configuration records
 - system requirements 9–10
 - verification 23–29
- Intel UNIX System V Release 4 operating system 17
- Intel x86 operating system 18
- InxUseLargeLimit configuration option 101
- IPC objects, removing after server failure 57, 91
- Italic type, use of as a document convention 5
- IxCompress configuration option 96
- IXCONFIG environment variable 64, 93
- ixpwfile (security parameter file) 60, 62, 64, 107
- IxPwFile configuration option 64, 96

IXPWFIL environment variable 64, 108
 ixsecure.cob, file security parameter file update
 utility 10, 60, 107
 ixverify, Windows client verification program 25

K

-k command line option, server 33, 36, 103
 Keepalive support, TCP 97
 KeepSession configuration option 98
 KEEPSESSION environment variable 98
 Key combinations, document convention for 5
 Keyboard interface, server display program 47
 kill command, UNIX 57, 91

L

Large file support 102, 119
 LargeFileLockLimit configuration option 102
 LARGE-FILE-LOCK-LIMIT keyword, RUN-
 FILES-ATTR configuration record 102, 119
 liant.lic (license certificate file). *See* License file.
 librminfox.so, client program, UNIX 10, 22, 28, 43
 License file 12, 14, 15, 16
 use count 103
 Limits and ranges 87
 Linux operating system 17
 Local area networks (LANs) 3
 Log file, initial client connection to server 99

M

MaxSendSize configuration option 33, 36, 96
 Messages
 compression 96
 encoding 95
 error 73–85
 large 96
 MinimumBlockSize configuration option 102

N

Network
 accessing clients 39, 43
 compressing messages 96
 data files, pointing to 40–42, 44–45
 security 64. *See also* Security, on UNIX server.

O

Online services 6
 Organization of this manual 3

P

-p command line option, server 33, 36, 101
 Passwords, client 98
 PATH environment variable 28
 Pathnames 26, 89
 case-sensitivity 32
 explicit 41, 45
 specifying 40–42, 44–45
 UNC-style 98, 120
 PathPrefixExcluded configuration option 98
 PathPrefixIncluded configuration option 98
 PDF format 3
 Performance, network 96
 Ports, user 11, 22

R

ReconnectDelay configuration option 99
 ReconnectEnable configuration option 96
 Reconnecting server and client 96, 99
 ReconnectTimeout configuration option 102
 Registration, product 6
 Related publications 4
 Relativity, using with 113
 RelUseLargeLimit configuration option 102
 rhosts file 59, 62, 65
 RM/COBOL
 compilation options, hyphens, used with 5
 configuration file options 93, 119
 list support modules loaded by the RM/COBOL
 runtime option (V) 28
 runtime options, hyphens, used with 5
 using with RM/InfoExpress 39, 43
 RM/InfoExpress
 client program 10
 accessing 39, 43
 configuration file options 93, 95, 98
 executing RM/COBOL programs with 42, 45
 installation 22
 pointing to network data files 40–42, 44–45
 setting up TCP/IP package 22
 system requirements 9–10
 terminating communication to 33, 37, 55, 90
 verification, installation 23–29
 configuring with RM/COBOL 93, 119
 enhancements, summary of 117
 error messages 73–85
 installation 12, 15, 22
 limits and ranges 87
 messages 73–85
 Relativity, using with 113
 RM/COBOL, using with 39, 43
 security, on UNIX server 59, 96, 103, 107. *See also* Security, on UNIX server.

- server display program 10, 12, 15
 - command line option 33, 34, 35, 37, 55
 - commands
 - Clients 50
 - Error Log 54
 - Files 52
 - Main 50
 - Open Log 53
 - Terminate 55
 - Client 56
 - Display 56
 - Server 56
 - keyboard functions 47
 - main screen 49
 - screen format, illustrated 48
 - starting 32, 33
 - terminating 33, 37, 55
 - server program 10
 - command line options 31, 32, 36
 - configuration 31
 - configuration file options 93, 95, 101, 103, 104
 - default server user 62, 63
 - installation 12
 - security, on UNIX 59, 96, 103, 107. *See also* Security, on UNIX server.
 - setting up TCP/IP package 11
 - starting 32, 33
 - automatically 35
 - system account 23, 34
 - system requirements 9–10
 - terminating 33, 35, 37, 55
 - verification, installation 23–29
 - version number, significance of 117
 - system requirements, installation 9–10
 - terminating 55
 - troubleshooting 89
 - verification, installation 23
 - RM_CLIENT_LOG_PATH environment variable 100
 - RM_RECONN_LOG_PATH environment variable 97
 - RMCLIENT.LOG 99
 - rmdisptcp, server display program, UNIX 10
 - rmdistcp.exe, server display program, Windows 10
 - rmixclnt.ini, client configuration file 64–71, 93, 100. *See also* Configuration file options.
 - rmixsrvr.ini, server configuration file 31, 64–71, 93, 104, 106. *See also* Configuration file options.
 - rmsvertcp, server program, UNIX 10
 - rmsrvtcp.exe, server program, Windows 10
 - rmtcp32.dll, client program, Windows 10, 22, 39
 - RoundToNiceBlockSize configuration option 102
 - RUN-FILES-ATTR configuration record 119
 - BUFFER-POOL-SIZE keyword 101
 - FILE-PROCESS-COUNT keyword 101
 - LARGE-FILE-LOCK-LIMIT keyword 102, 119
 - RUNPATH environment variable 28, 41, 44
 - RUN-REL-FILES configuration record, USE-LARGE-FILE-LOCK-LIMIT keyword 102, 119
 - RUN-SEQ-FILES configuration record, USE-LARGE-FILE-LOCK-LIMIT keyword 102, 119
 - Runtime options (RM/COBOL), hyphens, used with 5
- ## S
- SCO OpenServer 5 operating system 17
 - SCO OpenServer 6 operating system 18
 - Screen handler program. *See* Server display program.
 - Security, on UNIX server 59
 - .rhosts file 59, 62, 65
 - client validation 63
 - clients, non-UNIX 63
 - compatibility mode 60, 63, 103
 - configuration file options 60, 62, 63, 64, 72
 - default server user 62, 63, 72, 103
 - file security 60, 107
 - security levels 60, 63, 64, 72, 103
 - security parameter file (ixpwwfile) 60, 62, 64, 96, 107
 - setting up network 64
 - Send operations, maximum allowed 33, 36, 96
 - SeqUseLargeLimit configuration option 102
 - Server configuration file (rmixsrvr.ini) 31
 - Server display program 10, 12, 15
 - command line option 33, 34, 35, 37
 - commands
 - Clients 50
 - Error Log 54
 - Files 52
 - Main 50
 - Open Log 53
 - Terminate 55
 - Client 56
 - Display 56
 - Server 56
 - keyboard functions 47
 - main screen 49
 - screen format, illustrated 48
 - starting 32, 33
 - terminating 33, 37, 55, 56
 - Server program 10
 - command line options 31, 32, 36
 - configuration file options 93, 95, 101, 103, 104
 - installation 12, 15
 - security, on UNIX 59, 96, 103, 107
 - .rhosts file 59, 62, 65
 - client validation 63
 - clients, non-UNIX 63

- compatibility mode 60, 63
- configuration file options 60, 62, 63, 64, 72
- default server user 62, 63, 72
- file security 60
- security levels 60, 63, 64, 72
- security parameter file (ixpwwfile) 60, 62, 64
- server display program 12, 15
- setting up TCP/IP package 11
- starting 23, 24, 32, 33
 - automatically 35
 - System account 23, 34
 - system requirements 9–10
 - terminating 33, 37, 55
 - verification, installation 23–29
 - version number, significance of 117
- ServerSecurityLevel configuration option 60, 63, 72, 103
- services file 11, 22, 27
- share-name* configuration option 104
- Starting
 - server display program 32, 33
 - server program 32, 33
 - automatically 35
 - on a specific account 36
- StartupLogPath configuration option 99
- Sun Solaris SPARC operating system 18
- Support services, technical 6
- Symbols and conventions used in this manual 5
- Synonyms, directory search sequence 40, 44
- System account 23, 34, 36
- System requirements, installation 9–10

T

- t command line option, server display 33, 34, 35, 37, 55
- TCP/IP communication protocol 9, 11, 22, 23
 - keepalive support 97
 - send function 33, 36, 96
- TCP/IP package, setting up for
 - RM/InfoExpress clients 22
 - RM/InfoExpress servers 11
- Technical support services 6
- Terminating 33, 37
 - client communications 55, 56
 - client entries, troubleshooting 90
 - server 55, 56
 - server display 55, 56
- Transmission Control Protocol/Internet Protocol. *See* TCP/IP communication protocol
- Troubleshooting
 - client entries not terminating 90
 - failure to locate file or path 89
 - removing IPC objects after server failure 57, 91

U

- UNC-style pathnames 98, 120
- UNIX client 10. *See also* Client program; RM/InfoExpress.
 - accessing 43
 - configuration file options 93, 95, 98
 - installation 22
 - system requirements 9–10
 - verification, installation 23–29
- UNIX server 10,\. *See also* Server program; RM/InfoExpress.
 - command line options 32, 33
 - configuration file options 93, 95, 101, 103
 - file security parameter file update utility (ixsecure.cob) 10, 60, 107
 - installation 15
 - security 59
 - server display program 47
 - starting 32
 - verification, installation 23–29
- UnixWare operating system 18
- UseBlockingIO configuration option 100
- UseCount configuration option 33, 36, 103
- UseCurrentDirectory configuration option 105
- USE-LARGE-FILE-LOCK-LIMIT keyword
 - RUN-REL-FILES configuration record 102, 119
 - RUN-SEQ-FILES configuration record 102, 119
- UseSystemShares configuration option 105

V

- V Runtime Command option, RM/COBOL 28
- Validating clients 59
- Verification
 - UNIX client 28
 - UNIX client and server communication 28
 - UNIX server 24
 - Windows client 25
 - Windows client and server communication 25
 - Windows server 23
- Version number, RM/InfoExpress, client and server 117

W

- Web browser 12–16
- Web site services, Liant 6
- Wide area networks (WANs) 3
- Windows client 10. *See also* Client program;
RM/InfoExpress.
 - accessing 39
 - configuration file options 93, 95, 98
 - installation 22
 - system requirements 9–10
 - verification, installation 23–29
- Windows console 47
- Windows operating systems 10
- Windows server 10. *See also* Server program;
RM/InfoExpress.
 - command line options 36, 37
 - configuration file options 93, 95, 101, 104
 - installation 12
 - server display program 12, 47
 - starting 33
 - automatically 35
 - System account 23, 34
 - terminating 35
 - verification, installation 23–29
- Windows service *See* Windows Service
Control Manager (SCM)
- Windows Service Control Manager (SCM) 13, 15,
23, 33, 35
- Windows Sockets software 22, 25
 - blocking mode 100
 - error messages 74, 82, 84
 - IgnoreHangupError configuration option 95

Z

- z command line option, server 33, 36, 96