opentext™

ArcSight SOAR 3.9

Software Version: 3.9

Integration Guides

Document Release Date: October 2023 Software Release Date: October 2023

Legal Notices

Open Text Corporation

275 Frank Tompa Drive, Waterloo, Ontario, Canada, N2L 0A1

Copyright Notice

Copyright 2023 Open Text.

The only warranties for products and services of Open Text and its affiliates and licensors ("Open Text") are as may be set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Open Text shall not be liable for technical or editorial errors or omissions contained herein. The information contained herein is subject to change without notice.

Trademark Notices

"OpenText" and other Open Text trademarks and service marks are the property of Open Text or its affiliates. All other trademarks or service marks are the property of their respective owners.

Documentation Updates

The title page of this document contains the following identifying information:

- · Software Version number
- Document Release Date, which changes each time the document is updated
- · Software Release Date, which indicates the release date of this version of the software

To check for recent updates or to verify that you are using the most recent edition of a document, go to:

https://www.microfocus.com/support-and-services/documentation

Contents

Integration Guide for AbuseIPDB	23
Integration Overview	23
Integration Capabilities	23
Prerequisites	23
Configuration	23
Configuring AbuseIPDB	23
Configuring SOAR	23
Capabilities	24
Integration Guide for AlientVault OTX	26
Integration Overview	26
Integration Capabilities	26
Configuration	26
Integration Guide for Amazon EC2	30
Integration Overview	30
Integration Capabilities	30
Configuration	30
Integration Guide for Amazon GuardDuty	37
Integration Overview	
Integration Capabilities	37
Prerequisites	38
Configuration	38
Configuring Amazon GuardDuty	38
Configuring SOAR	39
Capabilities	39
Integration Guide for Amazon IAM	55
Integration Overview	55
Integration Capabilities	55
Configuration	56
Configuring SOAR	56
Capabilities	57
Integration Guide for Amazon S3	75
Integration Overview	75
Integration Capabilities	75

Prerequisites	75
Configuration	76
Configuring SOAR	76
Capabilities	77
Integration Guide for APIVoid	80
Integration Overview	80
Integration Capabilities	80
Prerequisites	80
Configuration	81
Configuring APIVoid	81
Configuring SOAR	81
Capabilities	81
Integration Guide for Anomali ThreatStream	93
Integration Overview	93
Integration Capabilities	93
Configuration	94
Additoinal Notes	96
Integration Guide for Arbor Networks APS	98
Integration Overview	
Integration Capabilities	98
Configuration	98
Prerequisites	98
Configuring Arbor Networks APS	98
Configuring SOAR	99
Integration Guide for AWS Network Firewall	100
Integration Overview	100
Integration Capabilities	100
Prerequisites	100
Configuration	101
Configuring AWS Network Firewall	101
Configuring SOAR	102
Capabilities	103
Integration Guide for Azure Network Security Groups	110
Integration Overview	110
Integration Capabilities	110
Prerequisites	110

Configuration	111
Configuring Microsoft Azure Network Security	111
Configuring SOAR	112
Capabilities	113
Integration Guide for Bind RPZ DNS	118
Integration Overview	118
Integration Capabilities	118
Configuration	118
Prerequisites	118
Configuring SOAR	118
Integration Guide for BMC Helix ITSM	120
Integration Overview	
Integration Capabilities	120
Prerequisites	121
Configuration	121
Configuring BMC Helix ITSM	121
Configuring SOAR	122
Integration Capabilities:	122
Integration Guide for BMC Helix Remedyforce	127
Configuring BMC Helix Remedyforce	128
Configuring SOAR	128
Capabilities	129
Integration Guide for Carbon Black Response (EDR)	142
Integration Overview	142
Integration Capabilities	142
Prerequisites	143
Configuring Carbon Black Response(EDR)	143
Configuring SOAR	143
Additional Notes	145
Integration Guide for Check Point R80	147
Integration Overview	147
Integration Capabilities	147
Prerequisites	147
Configuration	147
Configuring Check Point R80	147
Configuring SOAR	148

Capabilities	150
Integration Guide for Check Point SandBlast	153
Integration Overview	153
Integration Capabilities	153
Configuration	153
Prerequisites	153
Configuring Check Point SandBlast	153
Configuring SOAR	154
Integration Guide for CiscoASA Firewall	156
Integration Capabilities	156
Prerequisites	156
Configuration	156
Configuring Cisco ASA Firewall	156
Configuring SOAR	157
Capabilities	158
Integration Guide for Cisco Firepower Management Center	159
Integration Overview	
Integration Capabilities	
Prerequisites	159
Configuration	159
Configuring Cisco Firepower Management Center	159
Configuring SOAR	161
Capabilities	162
Integration Guide for Cisco Identity Service Engine	164
Integration Overview	
Integration Capabilities	164
Configuration	
Prerequisites	164
Configuring Cisco Identity Services Engine	164
Configuring SOAR	164
Integration Guide for Cisco Ironport Email Security	166
Integration Overview	
Integration Capabilities	
Configuration	
Prerequisites	
Configuring Cisco Ironport Email Security	

Configuring SOAR	167
Additional Notes	167
Integration Guide for Cisco Umbrella	168
Integration Overview	168
Integration Capabilities	168
Prerequisites	169
Configuration	169
Configuring Cisco Umbrella	
Configuring SOAR	169
Integration Capabilities	170
Integration Guide for CrowdStrike Falcon	178
Integration Overview	178
Integration Capabilities	178
Prerequisites	
Configuration	
Configuring CrowdStrike	
Configuring SOAR	
Capabilities	180
Integration Guide for Cyberark Central Credential Provider	
Integration Overview	
Configuration	
Prerequisites	
Configuring CyberArk Application Identity Manager	
Configuring SOAR	
Additional Notes	188
Integration Guide for CYMRU Malware Hash Registry Query	
Integration Overview	
Integration Capabilities	
Configuration	
Configuring CYMRU Malware Hash Registry Query	
Configuring SOAR	189
CyberRes Galaxy Threat Acclerator	
Integration Overview	
Integration Capabilities	
Prerequisites	
Configuring CyberRes Galaxy Threat Accelerator	191

Configuring SOAR	191
Capabilities	192
Integration Guide for CyThreat Threat Intelligence	194
Integration Overview	194
Integration Capabilities	194
Alert Source Capability	194
Prerequisites	194
Configuration	195
Configuring SOAR	195
Configuring CyThreat as an Alert Source	
Integration Capabilities	197
Integration Guide for DomainTools	198
Integration Overview	198
Integration Capabilities	198
Configuration	199
Configuring DomainTools	199
Configuring SOAR	199
Capabilities	200
Integration Guide for DNS Service	209
Integration Overview	209
Integration Capabilities	209
Configuration	209
Prerequisites	209
Configuring DNS Service	209
Configuring SOAR	209
Integration Guide for EmailRep	211
Integration Overview	211
Integration Capabilities	211
Prerequisite	211
Capabilities	212
Integration Guide for EnCase Endpoint Security	214
Integration Overview	
Integration Capabilities	
Prerequisites	215
Configuration	215
Configuring SOAR	216

Integration Capabilities:	216
Integration Guide for ESB Karar	227
Integration Guide for F5 Big-IP Advanced Firewall Manager	229
Integration Overview	
Integration Capabilities	229
Configuration	229
Configuring F5 Big-IP Advanced Firewall Manager	229
Integration Guide for FireEye HX	231
Integration Overview	231
Integration Capabilities	231
Configuring FireEye HX	231
Configuring SOAR	232
Integration Guide for Forcepoint Cloud Services	234
Integration Overview	234
Integration Capabilities	234
Configuration	234
Configuring Forcepoint Cloud Services	234
Configuring SOAR	234
Integration Guide for Forcepoint Content Gateway	236
Integration Overview	236
Integration Capabilities	236
Configuration	236
Prerequisites	
Configuring Facepoint Web Content Gateway	236
Configuring SOAR	237
Integration Guide for ForeScout CounterACT NAC	240
Integration Overview	240
Integration Capabilities	240
Configuration	240
Prerequisites	240
Configuring ForeScout CounterACT NAC	
Configuring SOAR	
Additional Notes	245
Integration Guide for Fortinet Forti Manager V2	246
Integration Overview	246
Integration Capabilities	246

Prerequisites	246
Configuration	247
Configuring Forti Manager	247
Configuring SOAR	247
Capabilities	247
Integration Guide for Fortinet FortiAnalyzer	250
Integration Overview	250
Integration Capabilities	250
Configuring Fortinet FortiAnalyzer	250
Configuring SOAR	250
Integration Guide for Fortinet FortiDDoS	253
Integration Overview	
Integration Capabilities	253
Configuration	253
Prerequisites	253
Configuring FortiDDoS	253
Configuring SOAR	254
Integration Guide for Fortinet FortiGate API	257
Integration Overview	257
Integration Capabilities	257
Configuration	257
Prerequisites	257
Configuring Fortinet FortiGate	257
Configuring SOAR	260
Additional Notes	261
Integration Guide for Fortinet FortiMail	262
Integration Overview	262
Integration Capabilities	262
Configuration	262
Prerequisites	262
Configuring FortiMail	262
Configuring SOAR	264
Additional Notes	266
Integration Guide for Fortinet FortiManager	267
Integration Overview	267
Integration Capabilities	267

Prerequisites	267
Configuring FortiManager	268
Configuring SOAR	269
Additional Notes	270
Integration Guide for Fortinet FortiSandbox	271
Integration Overview	271
Integration Capabilities	271
Configuration	271
Prerequisites	271
Configuring Fortinet Sandbox	271
Configuring SOAR	273
Integration Guide for FraudGuard	275
Integration Capabilities	275
Prerequisites	275
Configuring FraudGuard	275
Configuring SOAR	276
Capabilities	277
Integration Guide for FTP Server	281
Integration Overview	281
Integration Capabilities	281
Configuration	281
Prerequisites	281
Configuring SOAR	281
Integration Guide for Have I Been Pwned	284
Integration Overview	284
Integration Capabilities	284
Prerequisites	284
Configuration	284
Capabilities	285
Integration Guide for Generic HTTP SMS Gateway	288
Integration Overview	
Integration Capabilities	
Configuration	288
Configuring Generic HTTP SMS Gateway	288
Configuring SOAR	288
Integration Guide for HTTP Proxy	290

Integration Overview	290
Configuration	290
Prerequisites	290
Configuring HTTP Proxy	290
Configuring SOAR	290
Integration Guide for IBM Security X-Force	292
Integration Overview	292
Integration Capabilities	292
Configuration	292
Prerequisites	292
Configuring IBM X-Force Exchange	293
Configuring SOAR	293
Integration Guide for Infoblox DNS Firewall	296
Integration Overview	296
Integration Capabilities	296
Configuration	296
Prerequisites	296
Configuring Infoblox DNS Firewall	296
Configuring SOAR	297
Integration Guide for Intezer	299
Integration Overview	299
Integration Capabilities	300
Prerequisites	300
Configuration	300
Configuring Intezer	300
Configuring SOAR	300
Capabilities	301
Integration Guide for Invictus USTA ThreatIntelligence	305
Integration Overview	305
Integration Capabilities	305
Configuration	305
Prerequisites	305
Configuring Invictus USPA	306
Configuring SOAR	306
	306
Configuring Invictus USTA as Alert Source	306
Configuring Invictus USTA as Integration	307

Additional Notes	308
Integration Guide for IPInfo Integration Overview	
Integration Capabilities	
Configuration	
Capabilities	
Integration Guide for Jira	
Integration Overview	
Integration Capabilities	
Prerequisites	
Configuration	
Configuring SOAR	
Configuring Jira	
Capabilities	
Integration Guide for JDBC(Database) Server	
Integration Capabilities	
Configuration	
Prerequisites	
Configuring Database Server	
Configuring SOAR	
Integration Guides for Kannel SMS Gateway	
Integration Overview	
Integration Capabilities	
Supported Action Capabilities	
Configuring Kannel SMS Gateway	
Configuring SOAR	
Integration Guide for Kaspersky Security Center	
Configuration on Kaspersky Security Center	
Configuring SOAR	
Optional configuration	
Overriding built-in scripts	
Get Task Names	
Get Group Names	
Get Tag Names	
Host Information Enrichment	
Block Hash Action Capability	328

Rollback of block hash capability	329
Add tag to host capability	330
Rollback of Add Tag to Host Capability	331
Move system to group capability	333
Run task capability	334
Integration Guide for MAY Siber Scop NET	335
Prerequisites	335
Configuring MAY Siber Scop NET	335
Configuring SOAR	335
Integration Guide for McAfee ePolicy Orchestrator	337
Prerequisites	337
Configuration on McAfee ePolicy Orchestrator	338
Configuring SOAR	338
Integration Guide for McAfee Network Security Platform (IPS)	340
Configuration	340
Configuration on McAfee Network Security Platform (IPS)	340
Configuring SOAR	340
Integration Guide for McAfee Web Gateway	342
Prerequisites	342
Configuration on McAfee Web Gateway	342
Configuration on SOAR	343
Integration Guide for McAfee Web Gateway v2	344
Configuring McAfee Web Gateway v2	345
Configuring SOAR	345
Capabilities	347
Integration Guide for Micro Focus Arcsight ESM	351
Integration Guide for Micro Focus ArcSight Intelligence	351
Integration Guide for Micro Focus ArcSight Logger	352
Configuration	
Prereqisites	352
Configuration on Micro Focus ArcSight Logger	352
Configuring SOAR	352
Configuring SOAR	352
Integration Guide for Microsoft Active Directory	355
Configuration	355

Prerequisites	355
Configuration on Microsoft Active Directory	356
Configuring SOAR	356
Integration Guide for Microsoft Azure Active Directory	358
Integration Overview	358
Integration Capabilities	358
Prerequisites	358
Configuration	359
Configuring Microsoft Azure	359
Configuring SOAR	
Capabilities	360
Integration Guide for Microsoft Defender for CloudApps	368
Integration Overview	368
Integration Capabilities	368
Prerequisites	369
Configuration	
Configuring Microsoft Defender for CloudApps	
Configuring SOAR	
Capabilities	371
Integration Guide for Microsoft Defender Endpoint	384
Integration Overview	384
Integration Capabilities	384
Prerequisites	
Configuring Microsoft Defender	
Configuring SOAR	
Capabilities	387
Integration Guide for Micro Focus IT Service Manager	398
Integration Overview	398
Integration Capabilities	398
Prerequisites	398
Configuration	
Configuring Micro Focus IT Service Manager	
Configuring SOAR	
Capabilities	400
Integration Guide for Micro Focus UCMDB	402
Integration Overview	402

Integration Capabilities	402
Prerequisites	402
Configuration	402
Configuring Micro Focus UCMDB	402
Configuring SOAR	403
Capabilities	404
Integration Guide for Microsoft Exchange	
Prerequisites	
Configuration on Microsoft Exchange	
Configuration on SOAR	
Additional Notes	
Integration Guide for Microsoft Office365 Exchange EWS	
Configuration on Microsoft Exchange	
Using OAuth2 with Microsoft Exchange online Integrtations	
Configuring SOAR	
Additional Notes	413
Integration Guide for Microsoft Teams	414
Integration Overview	414
Integration Capabilities	414
Prerequisites	415
Configuration	415
Configuring Microsoft Teams	415
Authentication Parameters	
Configuring SOAR	
Integration Capabilities	416
Integration Guide for Microsoft Windows DNS Server	430
Configuration on Microsoft Windows DNS Server	430
Configuring ATAR	430
Integration Guide for Microsoft Windows Services (WinRM)	432
Configuring SOAR	432
Integration Guide for Microsoft Graph Security	434
Integration Overview	
Integration Capabilities	
Prerequisites	
Configuration	
Configuring Microsoft Azure	435

Configuring SOAR	435
Capabilities	436
Integration Guide for MISP	446
Integration Overview	446
Integration Capabilities	446
Prerequisites	446
Integration Guide for MxToolBox	449
Integration Overview	449
Integration Capabilities	449
Prerequisites	449
Configuration	449
Configuring MxToolBox	449
Configuring SOAR	450
Capabilities	451
Integration Guide for Netskope v1	452
Overview of the Plugin	452
Supported Integration Capabilities	452
Prerequisites	452
Configuration	453
Configuring Netskope	453
Configuring SOAR	453
Integration Capabilities:	454
Integration Guide for Netskope V2	456
Integration Overview	456
Integration Capabilities	456
Prerequisites	457
Configuration	457
Configuring Netskope	457
Configuring SOAR	458
Integration Capabilities:	458
Integration Guide for Ones BioAffix	464
Integration Capabilities	464
Prerequisites	464
Additional Notes	465
Integration Guide for Palo Alto Networks AutoFocus	466
Prerequisites	466

Configuration on Palo Alto Networks AutoFocus	467
Configuring SOAR	467
Integration Guide for Palo Alto Networks Firewall Prerequisites	
Configuration on Palo Alto Networks Firewall (API)	
Configuring SOAR	469
Additional Notes	470
Integration Guide for Palo Alto Networks Panorama	471
Prerequisites	471
Configuration on Palo Alto Networks Panorama	
Configuration on SOAR	472
Integration Guide for Recorded Future	474
Prerequisites	
Configuration on Recorded Future	
Configuring SOAR	475
Integration Guide for Robtex Lookup	
Configuration on Robtex Lookup	
Configuring SOAR	477
Integration Guide for Roksit DNS Firewall	479
Prerequisites	
Configuration on Roksit DNS Firewall	
Configuring SOAR	479
Integration Guide for RSA Security Analytics	481
Prerequisites	
Configuration on RSA Security Analytics Suite	
Configuring SOAR	482
Integration Guide for SailPoint	
Integration Overview	
Integration Capabilities	
Configuration	
Configuring SOAR	
Configuring SOAR	
Capabilities	
Integration Guide for SentinelOne	
Overview of the Plugin	489 490
Integration Capabilities	490

Prerequisites	490
Configuration	491
Configuring SentinelOne	491
Configuring SOAR	491
Integration Capabilities:	491
Integration Guide for ServiceNow	504
Integration Overview	504
Integration Capabilities	504
Prerequisites	504
Configuration	504
Configuring ServiceNow	504
Configuring SOAR	510
Capabilities	511
Integration Guide for Slack	512
Integration Overview	512
Integration Capabilities	513
Prerequisites	513
Configuring Slack	513
Configuring SOAR	514
Capabilities	514
Integration Guide for SMTP Mail Server	519
Prerequisites	519
Configuration	519
Configuring SOAR Email Notification	519
Configuring SOAR	520
Additional Notes	521
Integration Guide for Sophos XG Firewall	522
Prerequisites	522
Configuration on Sophos XG Firewall	522
Integration Guide for SORBS Query	525
Configuration on SORBS Query	
Configuring SOAR	
foIntegration Guide for Symantec Advanced Threat Protection	527
Configuring Symantec Advanced Threat Protection	
J J ,	527
Configuring SOAR	527

Integration Guide for Symantec Bluecoat Malware Analysis Appliance (MAA)	529
Prerequisites	529
Configuring SOAR	529
Integration Guide for Symantec Bluecoat Site Review	531
Configuration on Bluecoat Site Review	531
Configuring SOAR	531
Integration Guide for Symantec Data Loss Prevention (DLP)	532
Integration Capabilities	532
Prerequisites	532
Configuring Symantec DLP	532
Configuring SOAR	533
Integration Guide for Symantec DeepSight Intelligence	535
Prerequisites	535
Configuring Symantec DeepSight Intelligence	536
Configuring SOAR	536
Configuring Symantec DeepSight Intelligence as Alert Source	537
Configuring Symentec DeepSight Intelligence as Integration	537
Integration Guide for Symantec Endpoint Protection Manager	539
Prerequisites	539
Configuring Symantec Endpoint Protection Manager	540
Configuring SOAR	540
Integration Guide for Symantec Managed Security Services (MSS)	543
Configuring Symantec MSS	544
Configuring SOAR	544
Configuring Credentials	544
Configuring Symantec MSS as Alert Source	545
Configuring Symantec MSS as an Integration	547
Additional Notes	547
Integration Guide for Symantec Messaging Gateway	549
Prerequisites	549
Configuring Symantec Messaging Gateway	549
Configuring SOAR	550
Integration Guide for Tenable Nessus	552
ConfiguringTenable Nessus	552
Configuration on SOAR	552
Configuring SOAR	552

Integration Guide for Tenable Security Center	554
Prerequisites	554
Configuring Tenable Security Center	554
Configuring SOAR	555
Integration Guide for Trend Micro Apex Central	556
Integration Overview	556
Integration Capabilities	556
Prerequisites	556
Configuring Trend Micro Apex Central	556
Configuring SOAR	557
Capablities	558
Integration Guide for Trend Micro Vision One	559
Integration Overview	559
Integration Capabilities	559
Configuration	559
Configuring Trend Micro Vision One	559
Configuring SOAR	560
Capabilities	561
Integration Guide for Turkcell Threat Intelligence	567
Prerequisites	567
Configuration on Turkcell Threat Intelligence or Bozok	567
Configuring SOAR	568
Integration Guide for Udger	570
Integration Overview	570
Integration Capabilities	570
Prerequisites	570
Configuration	570
Configuring Udger	570
Configuring SOAR	571
Capabilities	571
Integration Guide for Urlscan	573
Integration Overview	573
Integration Capabilities	573
Configuration	573
Configuring SOAR	573
Capabilities	574

Integration Guide for VirusTotal	579
Prerequisites	579
Configuring VirusTotal	
Configuring SOAR	580
Additional Notes	582
Integration Guide for VMware ESXi	584
Configuring VMware ESXi	584
Configuring SOAR	584
Integration Guide for VxStream Sandbox	586
Configuration on VxStream Sandbox	586
Configuring SOAR	586
Integration Guide for WinRM	589
Configuring SOAR	
Configuring Domain-Controller for WinRM HTTPS Transport	
Force Group Policy Update	593
Additional Notes	593
and Documentation Feedback	50/

Integration Guide for AbuseIPDB

Integration Overview

Abuse Intelligence Production Data Base (Abuse IPDB) is a project dedicated to help combating the spread of hackers, spammers, and abusive activity on the internet.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with AbuseIPDB:

- Check IP
- Report IP

Prerequisites

You must have access to HTTPS as the ArcSight SOAR connects to AbuseIPDB API through this service.

Configuration

Configuring AbuseIPDB

- 1. Navigate to AbuseIPDB create an account.
- 2. Click API tab and create an API key.

Configuring SOAR

- Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor**:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, AbuseIPDB Credential).			Create API key

3. Click Configuration > Integrations > Create Integration.

4. Specify the following parameter values in the **Configuration Form**.

Parameter	Value		
Name	Display name of the integration.		
Туре	AbuseIPDB		
Address	https://api.abuseipdb.com	n	
Configuration	Specify the following conf	figuration parameters:	
	max.age.in.days	The max.age.in.days parameter determines how far back in time go to fetch reports [1, 365]. For example, max.age.in.days=30	
	cache.reusing.duration configure how far (in minutes) into the past this enrichment will look. For example, cache.reusing.duration=20		
	proxy.id ID of the Proxy integration if you access AbuseIPDB through a web proxy device. For example, proxy.id = 12345		
Credential	Credential that has been defined for this integration in the Credentials menu.		
Trust Invalid SSL Certificates	Select this option if web server's certificate is self-signed or is not recognized by browsers.		
Require Approval From	Select user(s) from list to ask the approval before executing actions on this integration.		
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.		

- 5. Click **Save** to save the integration definition.
- 6. Navigate to Configuration>Customization Library and edit AbuseIPDB Advanced Action Script Default Template.
- 7. Select the integration that you have added in Integrations menu.
- 8. Click **Save** to complete the integration.
- 9. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. Check IP

Enrichment capability for getting details about the IP.

The following table presents the **Check IP** capability details:

Capabilities Page 24 of 594

Input Parameter	Description	Туре	Scope Rescticted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration.	Integration	No	Yes
Max Age in Days	The max.age.in.days parameter determines how far back in time go to fetch reports.	Text	No	No
IP	IP to be checked.	Network Address	Yes	Yes

Output:

Case Scope:

Action	Туре	Category/ Value
Add	Scope Item	Keyword (Related)

Human Readable Output:



2. Report IP

Action capability for reporting an IP address:

Rollback: No

Duplicate Check: No

The following table provides the Report IP action capability details:

Input Parameter	Description	Туре	Scope Rescticted (Yes/No)	Required (Yes/No)
IP	IP to be reported.	Network Access	Yes	Yes
Category	Category of reported IP.	Enum	No	Yes
Comment	Comment for reported IP.	Text	No	No

Output:

Case Scope:

Action	Туре	Category/ Value
Add	Scope Item	Keyword (Related)

Human Readable Output: N/A

Capabilities Page 25 of 594

Integration Guide for AlientVault OTX

Integration Overview

AlienVault OTX is an open threat exchange platform supported by AlienVault and the community.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with AlienVault OTX:

- IP Indicator
- · Hash Indicator
- URL Indicator
- Domain Indicator
- Hostname Indicator

Use Case: Enrichment of artifacts detected in the organization

SOAR, when integrated with AlienValut OTX, can search for an artifact and gather information such as related threats and recent detections. This information may lead the investigation into a different path, and analysts can investigate and root out malicious activities in their networks.

This integration can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to AlienVault OTX API via HTTPS. Typically it runs on 443/tcp port. So access to this service is required.
- A user account is required for SOAR to connect to AlienVault OTX. It can be created from the following link:

https://otx.alienvault.com

Configuring AlienVault OTX

 AlienVault OTX requires an API key for access. Users can retrieve it from https://otx.alienvault.com/api after logging in with a valid credential.

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential
- 2. Fill in the Credential Editor form with the following information:

Туре	Name	Username	Password	Private Key
Internal Credential	Display name of credential set (i.e., AlienVault OTX Credentials)	Empty	Empty	API Key retrieved from the AlienVault OTX

- 3. Click Configuration > Integrations > Create Integration
- 4. Fill in the configuration form with the following information:

Parameter	Value
Name	Display name of AlienVault OTX integration on SOAR.
Туре	AlienVault OTX.
Address	Address of the cloud service is standard: https://otx.alienvault.com.

Configuration Page 27 of 594


Parameter	Value
Configuration	You need to specify the following configuration parameters:
	<pre># Integration ID of the proxy integration to use when co nnecting to current # integration. # If not provided, SOAR will try to use a direct connection. #proxy.id=123 #Max count of fetching NIDS list for IP Indicator enrichment #If not provided, SOAR will fetch last 10 NIDS(s) #ip.indicator.nids.list.entry.count=10 #Max count of fetching URL list for IP Indicator enrichment #If not provided, SOAR will fetch last 50 URL(s) #ip.indicator.url.list.entry.count=50 #Max count of fetching URL list for Domain Indicator enrichment #If not provided, SOAR will fetch last 50 URL(s) #domain.indicator.url.list.entry.count=50 #Max count of fetching Malware list for Hostname Indicator enrichment #If not provided, SOAR will fetch last 50 Malware(s) #hostname.indicator.malware.list.entry.count=50 #Max count of fetching URL list for Hostname Indicator enrichment #If not provided, SOAR will fetch last 50 URL(s) #hostname.indicator.url.list.entry.count=50 # configure how far (in minutes) into the past this enrichment will look. #cache.reusing.duration=20</pre>
Credential	Name of the credential set you've just created on step 2. (i.e., AlienVault OTX Credentials).
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or not recognized by browsers. Not selected.
Require	Select user(s) from list to ask her/his approval before
Approval From	executing enrichments on this integration.
Notify	Select user(s) from the list to notify when SOAR performs an enrichment on this integration.

- 5. Click Save to complete integration.
- 6. When you click the Test button the following pop up should be displayed if your credentials and address are valid.

Additional Notes

- AlienVault OTX integration on SOAR is an Advanced Action Script, and the content of the default script is accessible under Configuration > Customization Library.
- While defining the integration for the first time, you will encounter the following warning message, which is expected behavior for this type of integration.

Configuration Page 28 of 594



Configuration Page 29 of 594

Integration Guide for Amazon EC2

Integration Overview

Amazon EC2 (Elastic Compute Cloud) forms a central part of Amazon.com's cloud-computing platform, Amazon Web Services, by allowing users to establish virtual networks and rent virtual computers on which they can run their own applications. Amazon EC2 REST-API supports the following Amazon Web Services:

- Amazon EC2
- Amazon EBS
- Amazon VPC
- AWS VPN

Please note that this integration is in Beta.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Amazon EC2:

- Add Network ACL Entry (VPC)
- Delete Network ACL Entry (VPC)

Use Case: Blocking Attackers

SOAR when integrated with Amazon EC2, blocks the attacker's IP addresses while responding to a cyber-attack. The blocking can be performed automatically within a playbook or manually by an analyst.

Configuration


Prerequisites

- SOAR connects to Amazon EC2 API via HTTPS. Access to https://ec2.amazonaws.com (443/tcp port) is required.
- AWS Access Key and AWS Access Key Secret are required for SOAR to connect

Amazon Web Services.


Configuring on Amazon AWS

1. Log in to Amazon Console (https://aws.amazon.com). Navigate to My Security Credentials, and select Identity Access Management (IAM) service:




To add an IAM(identity and access management) user, click Access Management > Users >
Add User. While adding new user account, it is important to select Access Type as
Programmatic Access.

Configuration Page 31 of 594




3. You can skip the next steps in the Add User process until Access Key and Access Key Secret are displayed.



Configuration Page 32 of 594


4. To arrange access policy, click > Access Management > Policies, and search for the required policy in previously defined policies list.

For example, the following image shows the policy AmazonVPCFullAccess.




- 5. Select AmazonVPCFullAccess and open the Policy Summary.
 - a. Click Policy Usage > Attach.
 - b. In the Attach Policy menu, select the user that you have created in the previous steps, from the available users list in the system.

Configuration Page 33 of 594



6. You can verify if the permission is successful for the user account that you've created on the Policy Usage page.

Configuration Page 34 of 594



Configuring on SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Fill the Credential Editor form with the following information:
 - a. Internal Credential:

Туре	Name	Username:	Password	Private Key
Internal credential	Display name of credential set (i.e., Amazon AWS Credentials)	Access Key of IAM user you have created	Secret of Access Key of IAM user you have created	Empty

b. Credential Store:

Туре	Name
External credential	Name of the credential with full path of the safe on store

3. Click **Configuration > Integrations > Create Integration**. Fill the Configuration form with the following information:

Parameter	Value
Туре	Amazon EC2
Address	Address of the integration (https://ec2.amazonaws.com)


Configuration Page 35 of 594

Parameter	Value
Configuration	You need to specify the following configuration parameters
Credential	Name of the credential set you have just created on step 2. (i.e., Amazon AWS Credentials)
Trust Invalid SSL Certificates	No need to select
Require Approval From	Select user(s) from list to ask her/his approval before executing actions on this integration
Notify	Select user(s) from the list to notify when SOAR performs an action on integration

- 4. Click Save to complete integration.
- 5. Click the Test button. The following pop up will be displayed if your credential and address are valid.

Additional Notes

- Amazon EC2 integration on SOAR is an Advanced Script, and the content of the default script is accessible under Configuration > Customization Library.
- While defining the integration for the first time, you might encounter the following warning message, which is the expected behavior for this type of integration.



Configuration Page 36 of 594

Integration Guide for Amazon GuardDuty

Integration Overview

Amazon GuardDuty is a security monitoring service that analyses and processes data sources, such as AWS CloudTrail data events for Amazon S3 logs, CloudTrail management event logs, DNS logs, Amazon EBS volume data, Kubernetes audit logs, Amazon VPC flow logs, and RDS login activity. It uses threat intelligence feeds, such as lists of malicious IP addresses and domains, and machine learning to identify unexpected, potentially unauthorized, and malicious activity within your AWS environment. This can include issues such as escalation of privileges, use of exposed credentials, or communication with malicious IP addresses, domains, presence of malware on your Amazon EC2 instances and container workloads, or discovery of unusual patterns of login events on your database.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Amazon GuardDuty:

- List Detectors
- Get Detector Details
- Create Trusted IP List
- Delete Trusted IP List
- List Trusted IP List
- Get Trusted IP List Detail
- Add to trusted IP List
- Remove from trusted IP List
- Create Threat Intel List
- Delete Threat Intel List
- List Threat Intel List
- Get Threat Intel List Details
- Add to Threat Intel List
- Remove from Threat Intel List
- List Findings
- Get Finding Detail

- Archive Finding
- · Unarchive Finding
- Update Finding Feedback

Prerequisites

You must have access to HTTPS as the ArcSight SOAR connects to Amazon GuardDuty API through this service.

Configuration

Configuring Amazon GuardDuty

- Authentication: API requires Access Key and Secret Key to generate the AWS signature. Complete the following basic steps to generate the access Key and secret Key to access the Amazon GuardDuty Rest API:
 - a. Create your amazon account.
 - Navigate to the Identity and Access Management (IAM) section from your AWS Management Console to create a new user.
 - c. Click Add User to create a user.
 - d. Specifyyour preferred Username and make sure you select **Programmatic access**.
 - e. For permissions, you can add existing permission during this step. For most services, you can also add it from within the service configuration.
 Add the following scope to the user:

Scope	Required
AmazonGuardDutyFullAccess	Yes
IAMFullAccess	Yes
AmazonS3ReadOnlyAccess	Yes



On the last page, you will see the access key id and the secret code. You will need to save them somewhere securely.

Authentication parameters

Request Headers:

Prerequisites Page 38 of 594

Parameters	Data Type	Description	Required
Access Key	String	Access Key of the particular user.	Yes
Secret Key	String	Secret Key	Yes

2. Additional Configuration:

Configuration Parameter	Description
proxy.id	Proxy device to be used while communicating with remote system's API.
AWS Region	The region name to which the AWS server belongs too.
Service Name	Name of the AWS service.
Cache.reusing.duration	Default cache-reuse parameter.

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credentials.
- 2. Specify the following parameter values in the Credential Editor form:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, Amazon GuardDuty Credentials)	N/A	The Access Key to authenticate the Amazon GuardDuty APIs	Secret Key

- 3. Click Configuration > Integrations > Upload plugin.
- 4. Select your integration plugin zip file and click Save.
- 5. Select the integration that you have added to Integrations menu.
- 6. Click Save to complete the integration.
- 7. Click Test, If the credential and address are valid a success message is displayed.

Capabilities

1. List Detectors

Lists detector IDs of all the existing Amazon GuardDuty detector resources.

Request Headers:

Parameters	Datatype	Description	Required
Access Key	String	Access key of the particular user	Yes
Secret Key	String	Secret Key	Yes

Default Parameter:

Configuring SOAR Page 39 of 594

Query Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
MaxResults	You can use this parameter to indicate the maximum number of items that you want in the response. The default value is 50. The maximum value is 50.	Integer	No	No
NextToken	You can use this parameter when paginating results. Set the value of this parameter to null on your first call the list action. For subsequent calls to the action, fill nextToken in the request with the value of NextToken from the previous response to continue listing data.	String	No	No

Case Scope:

N/A

Human Readable Output:



2. Get Detector Detail

Retrieves an Amazon GuardDuty detector specified by the detectorId.

Request Headers:

Parameters	Datatype	Description	Required
Access Key	String	Access key of the particular user	Yes
Secret Key	String	Secret Key	Yes

Path Parameters:

Path parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
detectorId	The unique ID of the detector that you want to get.	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output

Capabilities Page 40 of 594

Кеу	Value
Status	ENABLED
Created At	2022-11-30T10:54:20.526Z
Update At	2022-11-30T10:54:20.526Z
Finding Publishing Frequency	SIX_HOURS
Data Sources	{"kubernetes": {"audif.logs": {"reason": null, "status": "ENABLED", "updatedAt": null }, "dnsLogs": {"reason": null, "status": "ENABLED", "updatedAt": null }, "cloudTrail": {"reason": null, "status": "ENABLED", "updatedAt": null }, "malwareProtection": {"serviceRole": "armaws:iam:100420467922:role/aws-service-role/malware- protection.guardduty.amazonaws.com/AWSServiceRoleForAmazonGuardDu tyMalwareProtection", "scanEc2InstanceWithFindings": {"rebsVolumes": { "reason": null, "status": "ENABLED", "updatedAt": null }}, "database": {"rds": { "databaseEvents": {"reason": null, "status": "ENABLED", "updatedAt": null }} }, "s3Logs": {"reason": null, "status": "ENABLED", "updatedAt": null }}
Tags	NA
Service Role	arn:aws:iam::100420467922:role/aws-service- role/guardduty.amazonaws.com/AWSServiceRoleForAmazonGuardDuty

3. Create Trusted IP List

Creates a new IPSet, which is called a trusted IP list in the console user interface. An IPSet is a list of IP addresses that are trusted for secure communication with AWS infrastructure and applications. GuardDuty does not generate findings for IP addresses that are included in IPSets. Only users from the administrator account can use this operation.

• Rollback: No

• Duplicate Control: No

Request Headers:

Parameters	Datatype	Description	Required
Access Key	String	Access key of the particular user	Yes
Secret Key	String	Secret Key	Yes

Path Parameters:

Path parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
detectorId	The unique ID of the detector that you want to get.	String	No	Yes

Request Body Parameters:

Capabilities Page 41 of 594

Request Body	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
activate	A Boolean value that indicates whether GuardDuty is to start using the uploaded IPSet. (Default is set to True always)	Bool	No	No
clientToken	The idempotency token for the create request.	String	No	No
format	The format of the file that contains the IPSet. Valid Values: TXT STIX OTX_CSV ALIEN_VAULT PROOF_POINT FIRE_EYE	String	No	Yes
location	The URI of the file that contains the IPSet.	String	No	Yes
name	The user-friendly name to identify the IPSet.	String	No	Yes

Case Scope: N/A

Human Readable Output: N/A

4. Delete Trusted IP List

Deletes the IPSet specified by the ipSetId. IPSets are called trusted IP lists in the console user interface.

• Rollback: No

• Duplicate Control: No

Request Headers:

Parameters	Datatype	Description	Required
Access Key	String	Access key of the particular user	Yes
Secret Key	String	Secret Key	Yes

Path Parameters:

Path Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
detectorId	The unique ID of the detector associated with the IPSet.	String	No	Yes
ipSetId	The unique ID of the IPSet to delete.	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

5. List Trusted IP List

Capabilities Page 42 of 594

Enrichment capability to search for domain names that match your specific search string. Unlike Domain suggestions, Domain Search finds currently registered or previously registered domain names that are either currently registered or have been registered in the past under one of the major gTLDs (.com, .net, .org, .info, .us, or .biz). Many countries code TLDs, or the new gTLDs.

Request Headers:

Parameters	Datatype	Description	Required
Access Key	String	Access key of the particular user	Yes
Secret Key	String	Secret Key	Yes

Path Parameters:

Path parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
detectorId	The unique ID of the detector that you want to get.	String	No	Yes

Default Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
MaxResults	You can use this parameter to indicate the maximum number of items you want in the response. The default value is 50. The maximum value is 50.	Integer	No	No
NextToken	You can use this parameter when paginating results. Set the value of this parameter to null on your first call to the list action. For subsequent calls to the action, fill nextToken in the request with the value of NextToken from the previous response to continue listing data.	String	No	No

Output:

Case Scope: N/A

Human Readable Output



6. Get Trusted IP List Details

Retrieves the IPSet specified by the ipSetId.

Request Headers:

Capabilities Page 43 of 594

Parameters	Datatype	Description	Required
Access Key	String	Access key of the particular user	Yes
Secret Key	String	Secret Key	Yes

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
detectorId	The unique ID of the detector that the IPSet is associated with.	String	No	Yes
IpSetId	The unique ID of the IPSet to retrieve.	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output

Key	Value
Name	testingFile7
Location	s3://newone12345678/sample.txt
Format	TXT
Status	INACTIVE
Tags	N/A

7. Add to Trusted IP List

Add IP to the Trusted IP list detail.

• Rollback: Yes

• Duplicate Control: Yes

Request Headers

Parameters	Datatype	Description	Required
Access Key	String	Access key of the particular user	Yes
Secret Key	String	Secret Key	Yes

Path Parameters:

Path Parameter	Description	Туре	Scope Restricted(Yes/No)	Required (Yes/No)
Bucket Name	The name of the S3 bucket	String	No	Yes
Key	The file path of S3 bucket file	String	No	Yes

Request Body Parameters:

Capabilities Page 44 of 594

Request Body	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
IPSET	The unique ID that specifies the IPSet that you want to update.	String	No	Yes

Case Scope: N/A

Human Readable Output: N/A

8. Remove from Trusted IP List

Remove the IP from Trusted IP list detail.

• Rollback: No

• Duplicate Control: No

Request Headers:

Parameters	Datatype	Description	Required	Parameters
Access Key	String	Access key of the particular user	Yes	Access Key
Secret Key	String	Secret Key	Yes	Secret Key

Path parameters:

Path Parameter	Description	Туре	Scope Restricted(Yes/No)	Required (Yes/No)
Bucket Name	The name of the S3 bucket	String	No	Yes
Кеу	The file path of S3 bucket file	String	No	Yes

Request Body Parameters:

Request Body	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
IPSET	The unique ID that specifies the IPSet that you want to update.	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

9. Create Threat Intel List

Creates a new ThreatIntelSet. ThreatIntelSets consist of known malicious IP addresses. GuardDuty generates findings based on ThreatIntelSets. Only users of the administrator account can use this operation.

• Rollback: No

• Duplicate Control: No

Capabilities Page 45 of 594

Request Headers

Parameters	Datatype	Description	Required
Access Key	string	Access key of the particular user	Yes
Secret Key	string	Secret Key	Yes

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
detectorId	The unique ID of the detector of the GuardDuty account that you want to create a threatIntelSet for.	String	No	Yes

Request Body Parameters

Request Body	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
clinetToken	The idempotency token for the create request.	String	No	No
format	The format of the file that contains the ThreatIntelSet. Valid Values: TXT STIX OTX_CSV ALIEN_VAULT PROOF_POINT FIRE_EYE	String	No	Yes
location	The URI of the file that contains the ThreatIntelSet.	String	No	Yes
name	A user-friendly ThreatIntelSet name displayed in all findings that are generated by activity that involves IP addresses included in this ThreatIntelSet.	String	No	Yes

Default Request Body Parameters:

Request Body	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
activate	A Boolean value that indicates whether GuardDuty is to start using the uploaded ThreatIntelSet.{Default Keep it as True}	Bool	No	No

Output:

Case Scope: N/A

Humnan Readable Output: N/A

10. Delete Threat Intel List

Capabilities Page 46 of 594

Deletes the ThreatIntelSet specified by the ThreatIntelSet ID.

Rollback: No

• Duplicate Control: No

Request Headers:

Parameters	Datatype	Description	Required
Access Key	string	Access key of the particular user	Yes
Secret Key	string	Secret Key	Yes

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
detectorId	The unique ID of the detector that the threatIntelSet is associated with.	String	No	Yes
threatIntelSetId	The unique ID of the threatIntelSet that you want to delete.	HOST, UNKNOWN, KEYWORD	No	Yes

Output:

Case Scope: N/A

Human Readable Output

11. List Threat Intel List

Lists the ThreatIntelSets of the GuardDuty service specified by the detector ID. If you use this operation from a member account, the ThreatIntelSets associated with the administrator account are returned.

Request Headers:

Parameters	Datatype	Description	Required
Access Key	string	Access key of the particular user	Yes
Secret Key	string	Secret Key	Yes

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
detectorId	The unique ID of the detector that the IPSet is associated with.	String	No	Yes

Default Parameters:

Capabilities Page 47 of 594

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
MaxResults	You can use this parameter to indicate the maximum number of items you want in the response. The default value is 50. The maximum value is 50.	integer	No	No
NextToken	You can use this parameter when paginating results. Set the value of this parameter to null on your first call to the list action. For subsequent calls to the action, fill nextToken in the request with the value of NextToken from the previous response to continue listing data.	String	No	No

Case Scope: N/A

Human Readable Output

ld	Name	Location	Format	Status	Tags
80c3132469ac6b11781 c78464a24be7a	testingFile	s3://newone12345678/ sample.txt	TXT	ERROR	N/A
b4c3138a4a6879ca994 cc9a8b2ta6bf2	test8	s3://newone12345678/ sample.txt	TXT	ERROR	N/A
e8c30bcbd345cd75b60 9ba9dae9ceb92	test01	s3://newone12345678/ sample.txt	TXT	ERROR	N/A

12. Get Threat Intel Details

Retrieves the ThreatIntelSet that is specified by the ThreatIntelSet ID.

Request Headers

Parameters	Datatype	Description	Required
Access Key	string	Access key of the particular user	Yes
Secret Key	string	Secret Key	Yes

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
detectorId	The unique ID of the detector that the IPSet is associated with.	String	No	Yes
Threat Intel	The unique ID of the threatIntelSet that you want to get.	HOST, UNKNON, KEYWORD	No	Yes

Output:

Case Scope: N/A

Human Readable Output

Capabilities Page 48 of 594

Key	Value
Name	testingFile
Location	s3://newone12345678/sample.txt
Format	TXT
Status	ERROR
Tags	N/A

13. Add To Threat Intel List

Add IP to the Threat intel List.

• Rollback: Yes

• Duplicate Control: Yes

Request Headers:

Parameters	Datatype	Description	Required
Access Key	string	Access key of the particular user	Yes
Secret Key	string	Secret Key	Yes

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
Bucket Name	The name of the S3 bucket	String	No	Yes
Key	The file path of S3 bucket file	String	No	Yes

Request Body Parameters:

Request Body	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
IPSET	The unique ID that specifies the IPSet that you want to update.	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

14. Remove from Threat Intel List

Remove IP from the Threat Intel List.

Rollback: No

Duplicate Control: No

Request Headers:

Capabilities Page 49 of 594

Parameters	Datatype	Description	Required
Access Key	string	Access key of the particular user	Yes
Secret Key	string	Secret Key	Yes

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
Bucket Name	The name of the S3 bucket	String	No	Yes
Key	The file path of S3 bucket file	String	No	Yes

Request Body Parameters:

Request Body	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
IPSET	The unique ID that specifies the IPSet that you want to update.	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

15. List Findings

Lists Amazon GuardDuty findings for the specified detector ID

Request Headers:

Parameters	Datatype	Description	Required
Access Key	string	Access key of the particular user	Yes
Secret Key	string	Secret Key	Yes

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
detectorId	The unique ID of the detector that the threatIntelSet is associated with.	String	No	Yes

Case Scope: N/A

Human Readable Output:

Capabilities Page 50 of 594

ld	Title	Description	Createdat	Updatedat	Severity
32c30b84f405c03e810 864077adbf8d7	API DescribeEventAggregat es was invoked using root credentials.	API DescribeEventAggregat es was invoked using root credentials from IP address 116.73.106.231.	2023-02- 03T11:29:30.635Z	2023-02- 06T08:53:42.528Z	2
bcc3083cf61c295f31a0 7534e046a113	API GetObject was invoked using root credentials.	API GetObject was invoked using root credentials from IP address 157.33.202.140.	2023-02- 02T04:54:31.224Z	2023-02- 03T10:01:06.783Z	2
1ac305e788705883a93 ccb033f0133ee	API DescribeEventAggregat es was invoked using root credentials.	API DescribeEventAggregat es was invoked using root credentials from IP address 103.5.134.251.	2023-02- 01T07:09:25.088Z	2023-02- 01T14:50:24.239Z	
cac300s05ef689fee5e8 bd178baa97a4	API DescribeEventAggregat es was invoked using root credentials.	API DescribeEventAggregat es was invoked using root credentials from IP address	2023-01- 30T05:57:45.581Z	2023-01- 31714:33:12.708Z	2

16. **Get Finding Detail**

Describes Amazon GuardDuty findings specified by finding IDs.

Request Headers

Parameters	Datatype	Description	Required
Access Key	string	Access key of the particular user	Yes
Secret Key	string	Secret Key	Yes

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
detectorId	The unique ID of the detector that the threatIntelSet is associated with.	String	No	Yes

Request Body Parameters:

Request Body	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
findingids	The IDs of the findings that you want to retrieve.	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output:

Capabilities Page 51 of 594

Кеу	Value
Schema Version	
Account kf	100426467922
Region	us-east-1
Partition	***
м	bcc3083c61c29593a07534e046a113
An .	am aws guardduly us east- 1 200420467922 detector/40c264162c63t/sig34sib696cs/61a341o/Inding/boc3003cf61c295/01s07534e046s113
type	Policy:IAMUserRootCredomialUsage
Resource	{"bccessKeyDetain"; ("accessKeyM"; "ASSAROYMGXTJMXFDQATX"; "principalid"; "100429467922", "userKaime"; "Boot", "userType"; "Boot", "sidexReDetails"; [("owner", ("id"); "desiration"), "publicAccess"; ("effective Permission"; "NOT, "publicAccess"; ("effective Permission"; "NOT, "publicAccess"; ("effective Permission"; "NOT, "publicAccess"; ("isosepublicAccess"; ("isosepublicAccess"); ("isosepublicAccess"; ("isosepublicAccess"); ("isosepublicAccess")
Service	["count: 456, "serviceName" "guarddury", "archived", false, "resourceRole", "TARGET", "detectand"; "48c/G4162/G518t0/3446/66c81a3414", "tevriffresSeen" "2023-02-02704-47-13-0002", "veenfl. ausSeen"; "2023-02-03170-56-03-0002", "addisonalinto", ("spe", "default", "value", "[0"], "accion", ("accion"), "archivel"; "AWS_API_CALL", "assApiCa5Accion", ("emricode", "NaSucNivibatioConfiguation", "serviceName"; "S3-amazonaes.com", "remotelpOstatio", ("country/", ("outry/Name", "india"), "opy", "Cop/fame", "Mumbail"), "gAddisoss/to "157-33-202-140", "geoLocation", ("orit "72-8656, "lat", 19-0748), "organization", ("assOrg"; "Relatace 340 Infocome Limited", "org", "367, "spe', "367, "ass", "55836")), "affoctedResources", (), "calletType"; "Remote 87", "apr': "GetObject"))]
Severity	
Created At	2023-02-02T04:54:31:224Z
Updated At	2023-02-00T10-01-06-783Z
Title	API GetObject was invoked using root credentials.
Description	API GetObject was invoked using root credentials from IP address 157.33.292.140.

17. Archive Findings

Archives GuardDuty findings that are specified by the list of finding IDs.

Rollback: Yes

Duplicate Control: No

Request Headers:

Parameters	Datatype	Description	Required
Access Key	string	Access key of the particular user	Yes
Secret Key	string	Secret Key	Yes

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
detectorId	The unique ID of the detector that the IPSet is associated with.	String	No	Yes

Request Body Parameters:

Capabilities Page 52 of 594

Request Body	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
findinglds	The IDs of the findings that you want to archive.	String	No	Yes

Case Scope: N/A

Human Readable Output: N/A

18. Unarchive Findings

Unarchives GuardDuty findings specified by the findingIds.

• Rollback: Yes

• Duplicate Control: No

Request Headers:

Parameters	Datatype	Description	Required
Access Key	string	Access key of the particular user	Yes
Secret Key	string	Secret Key	Yes

Path Parameters:

Path Parameter	Description		Тур	е	Scope restricted (Yes/No)	Required (Yes/No)		
detectorId	The unique ID of the detector that the IPSet associated with.	e detector that the IPSet is		t is String		ng	No	Yes
Request Body	Description				oe restricted /No)	Required (Yes/No)		
findingIds	The IDs of the findings that you want to archive.	Strir	ng	No		Yes		

Output:

Case Scope: N/A

Human Readable Output: N/A

19. Update Finding Feedback

Marks the specified GuardDuty findings as useful or not useful.

• Rollback: No

• Duplicate Control: No

Request Headers:

Capabilities Page 53 of 594

Parameters	Datatype	Description	Required
Access Key	string	Access key of the particular user	Yes
Secret Key	string	Secret Key	Yes

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
detectorId	The unique ID of the detector that the threatIntelSet is associated with.	String	No	Yes

Request Body Parameters:

Request Body	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
comments	Additional feedback about the GuardDuty findings.	String	No	Yes
Feedback	The feedback for the finding. Valid Values: USEFUL NOT_USEFUL	String	No	Yes
findinglds	The IDs of the findings that you want to mark as useful or not useful.	String	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

Capabilities Page 54 of 594

Integration Guide for Amazon IAM

Integration Overview

Amazon AWS Identity and Access Management (IAM) enables you to manage access to AWS services and resources securely. Using IAM, you can create and manage AWS users and groups, and use permissions to allow and deny their access to AWS resources.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with amazon IAM:

- Add User to Group
- Create Group
- Deactivate MFA Device
- Delete Access Key
- Delete All Access Keys
- Delete All SSH Public Keys
- Delete All Service Specific Credentials
- Delete Group
- Delete Login Profile
- Delete SSH Public Key
- Delete Service Specific Credential
- Delete User Policy
- Delete Virtual MFA Device
- Detach User Policy
- Get Access Key Last Used
- Get Group (List Group Members)
- Get Policy
- Get User Policy
- Get User
- List Access Keys
- List Attached User Policies

- List Entities for Policy
- List Groups
- List Groups for User
- List MFA Devices
- List SSH Public Keys
- List Service Specific Credentials
- List User Policies
- List User Tags
- List Users
- Remove User from Group

Configuration

Prerequisites

- You must have access to HTTPS as the ArcSight SOAR connects to amazon iam API through this service.
- Access key is required to access this service.

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor** form:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, Amazon IAM Credential).	Empty	Access Key	Secret Key

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form.

Parameter	Value
Name	Display name of the integration.
Туре	Amazon IAM
Address	Address of the integration (the format must be https://iam.amazonaws.com).

Configuration Page 56 of 594

Parameter	Value			
Configuration	Specify the following configuration parameters:			
	proxy.id	ID of the proxy integration if you access amazon web services through a web proxy device. For example: proxy.id = 12345.		
Credential	Credential	that has been defined for this integration in the Credentials menu.		
Trust Invalid SSL Certificates	Select this if web server's certificate is self-signed or is not recognized by browsers.			
Require Approval From	Select user(s) from list to ask the approval before executing actions on this integration.			
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.			

- 5. Click **Save** to save the integration definition.
- 6. Navigate to Configuration>Customization Library and edit Amazon IAM Advanced Action Script Default Template.
- 7. Select the integration that you have added in the Integrations menu.
- 8. Click **Save** to complete the integration.
- 9. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. Add User to Group

Action capability for adding a user to given group.

Rollback: Yes

• Duplicate Control: No

The following table presents the **Add User to Group** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is no-rollback.	N/A	N/A	No

Capabilities Page 57 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
User	Username to be added to group	Username Keyword Unknown	Yes	Yes
Group Name	Target group Name	String	No	Yes

Case Scope: N/A

Human Readable Output: N/A

2. Create Group

Action capability for creating a user group.

Rollback: No

• Duplicate Control: False

The following table presents the Create Group action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Path Prefix	Path where the group is created.	String	No	Yes
Group Name	Target group Name	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

3. Deactivate MFA

Action capability for deactivating user's multi factor authentication device.

• Rollback: No

• Duplicate Control: Yes

The following table presents the **Deactivate MFA** action capability details:

Capabilities Page 58 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username	Username Keyword Unknown	Yes	Yes
Serial Number	MFA Device's serial number	String	No	Yes

Case Scope: N/A

Human Readable Output: N/A

4. Delete Access Key

Action capability for deleting user's access key.

Rollback: No

• Duplicate Control: Yes

The following table presents the **Delete Access Key** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username	Username Keyword Unknown	Yes	Yes
Access Key ID	Access Key ID	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

5. Delete All Access Keys

Action capability for deleting user's all access keys.

• Rollback: No

• Duplicate Control: No

The following table presents the **Delete All Access Keys** action capability details:

Capabilities Page 59 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username	Username Keyword Unknown	Yes	Yes

Case Scope: No

Human Readable Output: No

6. Delete All Service Specific Credentials

Action capability for deleting user's all service specific credentials.

• Rollback: No

• Duplicate Control: No

The following table presents the **Delete All Service Specific Credentials** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username	Username Keyword Unknown	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

7. Delete All SSH Public Keys

Action capability for deleting user's all SSH public keys.

Rollback: No

• Duplicate Control: No

The following table presents the **Delete All SSH Public Keys** action capability details:

Capabilities Page 60 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User		Username Keyword Unknown	Yes	Yes

Case Scope: N/A

Human Readable Output: N/A

8. Delete Group

Action capability for deleting group.

• Rollback: No

• Duplicate Control: No

The following table presents the **Delete Group** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Group Name	Group name to be deleted	String	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

9. Delete Login Profile

Action capability for deleting user's login profile.

• Rollback: No

• Duplicate Control: No

The following table presents the **Delete Login Profile** action capability details:

Capabilities Page 61 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username	Username Keyword Unknown	Yes	Yes

Case Scope: N/A

Human Readable Output: N/A

10. Delete Service Specific Credential

Action capability for deleting user's service specific credential.

• Rollback: No

• Duplicate Control: Yes

The following table presents the **Delete Service Specific Credential** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username	Username Keyword Unknown	Yes	Yes
Credential ID	Service specific credential Id to be deleted	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

11. Delete SSH Public Key

Action capability for deleting user's SSH public key.

The following table presents the **Delete SSH Public Key** action capability details:

Capabilities Page 62 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username	Username Keyword Unknown	Yes	Yes
SSH Public Key Id	SSH Public Key Id to be deleted.	String	No	Yes

Case Scope: N/A

Human Readable Output: N/A

12. Delete User Policy

Action capability for deleting user policy.

Rollback: No

• Duplicate Control: No

The following table presents the **Delete User Policy** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username	Username Keyword Unknown	Yes	Yes
Policy Name	Policy to be deleted.	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: No/A

13. Delete Virtual MFA Device

Action capability for deleting virtual multi factor authentication device.

Rollback: No

• Duplicate Control: Yes

The following table presents the **Delete Virtual MFA Device** action capability details:

Capabilities Page 63 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Serial Number	Serial number of MFA device to be deleted.	String	No	Yes

Case Scope: N/A

Human Readable Output: N/A

14. Detach User Policy

Action capability for detaching policy from user.

• Rollback: No

• Duplicate Control: No

The following table presents the **Detach User Policy** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username	Username Keyword Unknown	Yes	Yes
Policy arn	Policy to be detached.	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

15. Get Access Key Last Used

Enrichment capability for retrieving last used information for access key.

The following table presents **Get Access Key Last Used** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Access Key ID	Key ID to be queried .	String	No	Yes

Capabilities Page 64 of 594

Case Scope:

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output:

User Name	Service	Region	Last Used Date
matt-acg	iam	us-east-1	1634811000

16. Get Group

Enrichment capability for retrieving list of group members.

The following table presents the **Get Group** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Group Name	Group Name	String	No	Yes

Output:

Case Scope:

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output:



17. Get Policy

Enrichment capability for retrieving policy information.

The following table presents the **Get Policy** action capability details:

Capabilities Page 65 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Policy arn	Policy arn.	String	No	Yes

Case Scope:

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output:



18. Get User

Enrichment capability for retrieving user details.

The following table presents the **Get User** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username	Username Keyword Unknown	Yes	Yes

Output:

Case Scope:

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output:

Capabilities Page 66 of 594



19. Get User Policy

Enrichment capability for adding a user to given group.

The following table presents the **Get User Policy** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username to be added to group	Username Keyword Unknown	Yes	Yes
Policy Name	Policy name	String	No	Yes

Output:

Case Scope:

Enrichment	Туре	Category Value
None	N/A	N/A

20. List Access Keys

Enrichment capability for listing user's access keys.

The following table presents the **List Access Keys** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username	Username Keyword Unknown	Yes	Yes

Output:

Case Scope:

Capabilities Page 67 of 594

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output:

User Name	Key Id	Status	Create Date
lamdev	AKIAWXMDQFJ736000000	Active	1634811053

21. List Attached User Policies

Enrichment capability for listing attached user policies.

The following table presents the List Attached User Policies action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username	Username Keyword Unknown	Yes	Yes

Output:

Case Scope:

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output: No



22. List Entities for User Policy

Enrichment capability for listing entities for given user policy.

The following table presents the List Entities for User Policy action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Policy Arn	Policy arn	String	No	Yes

Output:

Case Scope:

Capabilities Page 68 of 594

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output:



23. List Groups

Enrichment capability for listing groups under given path prefix.

The following table presents the **List Groups** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Path Prefix	Path Prefix under groups to be listed.	String	No	Yes

Output:

Case Scope:

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output:



24. List Groups for User

Enrichment capability for listing user's groups.

The following table presents the List Groups for User action capability details:

Capabilities Page 69 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username	Username Keyword Unknown	Yes	Yes

Case Scope:

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output:



25. List MFA Devices

Enrichment capability for listing user's MFA devices.

The following table presents the List MFA Devices action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username	Username Keyword Unknown	Yes	Yes

Output:

Case Scope:

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output: No

26. List Service Specific Credentials

Enrichment capability for listing user's service specific credentials.

Capabilities Page 70 of 594

The following table presents the List Service Specific Credentials action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username	Username Keyword Unknown	Yes	Yes

Output:

Case Scope:

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output:

Service Name	User Name	Service User Name	Credential Id	Status	Create Date
codecommitamazonaws.com	iamdev	iamdev-at-462521640000	ACCAWXMDQFJ7YE2V0000 0	Active	1633008565
cassandra.amazonaws.com	iamdev	iamdev-at-462521640000	ACCAWXMDQFJ743IJ00000	Active	1633008570

27. List SSH Public Keys

Enrichment capability for listing user's SSH Public Keys..

The following table presents the List SSH Public Keys action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username to be added to group	Username Keyword Unknown	Yes	Yes

Output:

Case Scope:

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output:

Capabilities Page 71 of 594

User Name	Key Id	Status	Upload Date
iamdev	APKAWXMDQFJ7Z2000000	Active	1633008559

28. List Users

Enrichment capability for listing users under the given path.

The following table presents the **List Uesrs** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Path Prefix	Path Prefix under users to be listed.	String	No	Yes

Output:

Case Scope:

Enrichment	Туре	Category Value	
None	N/A	N/A	

Human Readable Output:



29. List User Policies

Enrichment capability for listing user's policies.

The following table presents the List User Policies action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User		Username Keyword Unknown	Yes	Yes

Output:

Case Scope:

Capabilities Page 72 of 594

Enrichment	Туре	Category Value
None	N/A	N/A

30. List User Tags

Enrichment capability for listing user's tags.

The following table presents the List User Tags action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
User	Username	Username Keyword Unknown	Yes	Yes

Output:

Case Scope:

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output: No



31. Remove User from Group

Action capability for adding a user to given group.

• Rollback: Yes

• Duplicate Control: No

The following table presents the Add User to Group action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is no-rollback.	N/A	N/A	No

Capabilities Page 73 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
User	Username to be added to group	Username Keyword Unknown	Yes	Yes
Group Name	Target group Name	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

Capabilities Page 74 of 594

Integration Guide for Amazon S3

Integration Overview

Amazon S3 service is offered by Amazon Web Services which provides object storage through a web service framework.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Amazon S3:

- Create Bucket
- Delete Bucket
- Download File From Bucket
- List Bucket Objects
- List Buckets
- Get Bucket Location

These capabilities can be performed automatically within a playbook or manually by an analyst.

Prerequisites

- You must have access to HTTPS as the ArcSight SOAR connects to Amazon S3 API through this service.
- Access Key ID and Secret Access Key is also required for integration.

Configuration

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the Credential Editor form.

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, Amazon S3 Credential).		Access Key ID should be filled in this field.	Secret key should be filled in this field.

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form.

Parameter	Value			
Name	Display nan	ne of the integration.		
Туре	Amazon S3			
Address	Address of	the integration (the format must be https://s3.amazonaws.com).		
Configuration	Specify the	following configuration parameters:		
	proxy.id ID of the Proxy integration if you access Amazon S3 through a web proxy device. For example: proxy.id = 12345.			
	region Default region name that has to be used while working on be example, proxy.id = 12345.			
Credential	Credential that has been defined for this integration in the Credentials menu.			
Trust Invalid SSL Certificates	Select this if web server's certificate is self-signed or is not recognized by browsers.			
Require Approval From	Select user(s) from list to ask the approval before executing actions on this integration.			
Notify	Select user((s) from the list to notify when SOAR performs an action on this		

- 5. Click **Save** to save the integration definition.
- 6. Navigate to Configuration>Customization Library and edit Amazon S3 Advanced Action Script Default Template.
- 7. Select the integration that you have added in the Integrations menu.
- 8. Click **Save** to complete the integration.
- 9. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Configuration Page 76 of 594

Capabilities

1. Create Bucket

Action capability for creating a bucket in Amazon S3.

The following table presents the **Create Bucket** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Bucket Name	Name of the Amazon S3 Bucket that would be created.	String	N/A	Yes
Region	Region name of the bucket that would be created	List	N/A	No

Output:

Case Scope: N/A

Human Readable Output: N/A

2. Delete Bucket

Action capability for deleting a bucket in Amazon S3.

The following table presents the **Delete Bucket** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Bucket Name	Name of the Amazon S3 Bucket that would be deleted.	String	N/A	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

3. Download File From Bucket

Enrichment capability for downloading a file from bucket.

The following table presents the **Download File From Bucket** enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Bucket Name	Name of the bucket that contains the file.	String	N/A	Yes

Capabilities Page 77 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Кеу	Name of the file to be downloaded.	String	No	Yes
Do not Use Cache	SOAR does not use cached results if this box is checked.	Boolean	N/A	No
Region	Region name of the bucket that would be created	List	N/A	No

Output:

Case Scope:

Enrichment	Туре	Category/ Value
Download File From Bucket	Any	File
Download File From Bucket	String	File Name
Download File From Bucket	MD5	#
Download File From Bucket	SHA1	#

Human Readable Output:



4. List Bucket Objects

Enrichment capability for listing bucket objects in Amazon S3.

The following table presents the **List Bucket Objects** enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Bucket Name	Name of the bucket that contains the file.	String	N/A	Yes
Do not Use Cache	SOAR does not use cached results if this box is checked.	Boolean	N/A	No
Region	Region name of the bucket that would be created	List	N/A	No

Output:

Case Scope: N/A

Human Readable Output:



Capabilities Page 78 of 594

5. List Buckets

Enrichment capability for listing a buckets in Amazon S3.


The following table presents the **List Buckets**enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes

Output:

Case Scope: N/A

Human Readable Output:



6. Get Bucket Location

Enrichment capability of getting region of the bucket.

The following table presents the List Bucketsenrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Bucket Name	Name of the Bucket	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output:



Capabilities Page 79 of 594

Integration Guide for APIVoid

Integration Overview

APIVoid is an API service for threat analysis and threat detection and prevention.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with APIVoid:

- IP Reputation
- ThreatLog Domain Query
- Domain Reputation
- URL Screenshot
- URL Reputation
- Domain Age
- Site Trustworthiness
- Parked Domain
- URL Status
- HTTP Tracker
- Email Verify
- DNS Lookup
- DNS Propagation
- SSL Info
- URL to HTML
- URL to PDF

Prerequisites

- You must have the network access through APIVoid
- You must have the APIVoid API key.

Configuration

Configuring APIVoid

- 1. Register to APIVoid. After logging, the API key is available.
- 2. Click My API Keys and copy the API key.

Configuring SOAR

- 1. Click Configuration > Integration > Create Integration.
- 2. Click Create. In Configuration Editor specify following values to create a credential:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, APIVoid Credential).			API Key that you copied from APIVoid portal.

- 3. Click **Save** to save the integration definition.
- 4. Navigate to Configuration>Customization Library and edit APIVoid Advanced Action Script Default Template.
- 5. Select the integration that you have added in the **Integrations** menu.
- 6. Click **Save** to complete the integration.
- 7. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.
- 1. IP Reputation

Enrichment capability for retrieving reputation value of given IP address.

Following table presents the IP reputation enrichment capability details:

Capabilities


Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
IP	IP address to retrieve reputation.	Network Address Host	Yes	Yes

Output:

Case Scope: N/A

Configuration Page 81 of 594

Human Readable Output:



2. ThreatLog Domain Query

Enrichment capability to query a domain for ThreatLog.

Following table presents the ThreatLog Domian Query enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Domain	Host to query	HOST	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output



Capabilities Page 82 of 594

3. Domain Reputation

Enrichment capability to retrieve Domain Reputation.


Following table presents the **Domain Reputation** enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Domain	Host to query	HOST	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output:



4. URL Screenshot

Enrichment capability to take a screenshot for given URL by APIVoid.

Following table presents the **URL Screenshot** enrichment capability details:


Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
URL	URL to take screenshot.	URL	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output:

Capabilities Page 83 of 594



5. URL Reputation

Enrichment capability to retrieve URL reputation.

Following table presents the URL Reputation enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
URL	URL to retrieve reputation.	URL	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output:



6. Domain Age

Enrichment capability to retrieve domain age information.

Following table presents the **Domain Age** enrichment details:


Capabilities Page 84 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Domain	Domain to retrieve age information.	HOST	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output:



7. Site Trustworthiness

Enrichment capability to retrieve site trustworthiness score / information Following table presents the **Site Trustworthiness** enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Host	Host to retrieve site trustworthiness information.	HOST	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output:

Capabilities Page 85 of 594



8. Parked Domain

Enrichment capability to retrieve information for parked domain.


Following table presents the **Parked Domain** enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Domain	Domain to retrieve information.	HOST	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output:



9. URL Status

Enrichment capability to retrieve URL Status information.

Following table presents the URL Status enrichment capability details:

Capabilities Page 86 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
URL	URL to retrieve status.	URL	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output:



10. HTTP Tracker

Enrichment capability for tracking http requests per URL.

Following table presents the HTTP Tracker enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
URL	URL to track http requests.	HOST	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output:

Capabilities Page 87 of 594



11. Email Verify

Enrichment capability that verifies given E-mail address.


Following table presents the **Email Verify** enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Email Address	Email Address to verify.	EMAIL_ ADDRESS	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output:



12. DNS Lookup

Enrichment capability to lookup for DNS per given host.

Following table presents the DNS Lookup enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
HOST	Host or domain to lookup.	HOST	Yes	Yes


Capabilities Page 88 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Lookup Type	DNS Lookup type. Can be one of the following: "dns-a", "dns-aaaa", "dns-mx", "dns-ns", "dns-dmark", "dns-ptr", "dns-txt", "dns-any", "dns-cname", "dns-soa", "dns-srv", "dns-caa".	ENUM	No	Yes

Output:

Case Scope: N/A

Human Readable Output:



13. DNS Propagation

Enrichment capability to check for DNS of the given host.

Following table presents the DNS Propagation enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Email Address	Host or domain to lookup.	HOST	Yes	Yes
Lookup Type	DNS Lookup type. Can be one of the following: "A", "AAAA", "NS", "MX", "TXT", "SRV", "PTR", "SOA", "CNAME", "SPF", "CAA".	ENUM	No	Yes

Output:

Case Scope: N/A

Human Readable Output:

Capabilities Page 89 of 594



14. SSL Info

Enrichment capability to retrieve SSL information.

Following table presents the **SSL Info** enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
HOST	Host or domain to lookup.	HOST	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output:



15. URL to HTML

Following table presents the **URL to HTML** enrichment capability details:


Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
URL	URL to retrieve HTML.	URL	Yes	Yes

Output:

Case Scope: N/A

Capabilities Page 90 of 594

Human Readable Output:



16. URL to PDF

Enrichment capability to retrieve PDF file from URL.

Following table presents the **URL to PDF** enrichment capability details:


Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
URL	URL to retrieve PDF.	URL	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output:

Capabilities Page 91 of 594



Capabilities Page 92 of 594

Integration Guide for Anomali ThreatStream

Integration Overview

Anomali ThreatStream is a Threat Intelligence Platform that enables businesses to integrate security products and leverage threat data to defend against cyber threats.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Anomali ThreatStream:

- Domain Reputation
- Email Reputation
- File Reputation
- Get Incident Details
- · Get Intelligence
- Get Investigation Details
- IP Reputation
- List Incidents
- List Investigations
- Report Indicator
- Create Investigation
- Close Investigation
- Update Investigation

Use Case: Investigating Phishing Campaigns

SOAR, when integrated with Anomali ThreatStream, helps campaigns that investigate and mitigate phishing. When a phishing report email comes from a user, SOAR extracts the indicators such as IP address, URLs and attachments in the message and creates an incident on the Incident Management Service Desk. SOAR then checks with Anomali ThreatStream, to know if this is a known attack and whether these indicators were previously analyzed.

This investigation can be either performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites


- SOAR connects to Anomali ThreatStream API via HTTPS. Access to https://api.threatstream.com/(443/tcp port) is required.
- An API key is required for SOAR to connect to Anomali ThreatStream Service.

Configuring Anomali ThreatStream

- 1. Log in to https://ui.threatstream.com/.
- 2. Navigate to **Settings** > **My Profile** to get the API Key.



Note: This key is required by SOAR to access the platform for queries.



Configuring SOAR

- Configuration > Credentials > Create Credential.
- 2. Fill the Credential Editor form with the following details:
 - a. Internal Credential:

Parameter	Value
Туре	Internal credential
Name	Display name of credential set (For example, Anomali ThreatStream Credentials)
Username	Your username on Anomali ThreatStream platform
Password	Empty
Private Key	API key you have obtained from Anamoli ThreatStream Platform

Configuration Page 94 of 594


b. Credential Store:

Parameter	Value
Туре	External credential
Name	Name of the credential with full path of the safe on store

- 3. Configuration > Integrations > Create Integration.
- 4. Fill the configuration form with the following parameter values:

Parameter	Value
Name	Display name of Anomali ThreatStream integration on SOAR
Туре	Anomali ThreatStream
Address	Address of the integration (https://api.threatstream.com).
Configuration	You need to specify the following configuration parameters:
	<pre># Integration ID of the proxy integration to use when connecting to # current integration. # If not provided, ATAR will try to use a direct connection. #proxy.id=123</pre>
Credential	Name of the credential set you have just created on step 2. (For example, Anomali ThreatStream Credentials)
Trust Invalid SSL Certificates	No selection required
Require Approval From	Select user(s) from list to ask her/his approval before executing actions on this integration.
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.

Configuration Page 95 of 594




- 5. Click **Save** to complete integration.
- 6. Click **Test** to test the integration.

Additoinal Notes

- Anomali ThreatStream integration on SOAR is an Advanced Script and content of the default script is accessible under Configuration > Customization Library.
- While defining the integration for the first time, you might encounter the following warning message, which is the expected behavior for this type of integration.

Additoinal Notes Page 96 of 594



Additoinal Notes Page 97 of 594

Integration Guide for Arbor Networks APS

Integration Overview

Arbor Networks APS is an in-line Distributed Denial of Service(DDoS) protection solution.

Integration Capabilities

ArcSight has the following integration capabilities with Arbor Networks APS:

- Block IP
- · Block access to IP

Use Case: Blocking malicious IP on peripheral

ArcSight SOAR integrates with Arbor Networks APS to block malicious IP addresses detected while responding to an incident. SOAR can block both the incoming and outgoing traffic either automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to Arbor Networks APS' API via HTTPS. By default, the API interface works on 443/tcp port. So access permission to this port is required.
- An API access token needs to be created for SOAR to connect to Arbor Networks APS.

Configuring Arbor Networks APS

- 1. Log in to Arbor Networks APS device.
- 2. Add a new API token.

admin@arbos: /# serv aaa local apitoken generate admin ATAR_INTEGRATION
 Added token: jwP9JcmZYz4I9QH0LpkDA_n5nj_DNHifc6Iwsq0P



Note: SOAR uses the generated token as the credential password and user name as admin.

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Fill the Credential Editor form with the following parameter values:

a. Internal Credential:

Parameter	Value
Туре	Internal credential
Name	Display name of the credential set (For example, Arbor APS Credential)
Username	admin
Password	API Token you have created for SOAR on Arbor Networks APS device
Private Key	Empty

b. Credential Store:

Parameter	Value
Туре	Extrenal credential
Name	Name of the credential with pull path of the safe on store

- 3. Configuration > Integrations > Create Integration.
- 4. Fill the configuration form with the following parameter values:

Parameter	Value
Name	Display name of Arbor Networks APS integration on SOAR
Туре	Arbor Networks APS
Address	Address of the integration (the format should be http (s]://1.1.1:1234 or http[s]://abc.example.com:1234)
Password	API Token you have created for SOAR on Arbor Networks APS device
Credential	Name of the credential set you have just created on step 2. (For example, Arbor APS Credential)
Trust Invalid SSL Certificates	Select this if device's certificate is self-signed or not recognized by browsers
Require Approval From	Select user(s) from list to ask her/his approval before executing actions on this integration
Notify	Select user(s) from the list to notify when ATAR performs an action on this ntegration

Configuring SOAR Page 99 of 594

- 5. Click **Test**. The following pop up will be displayed if your credential and address are valid.
- 6. Click Save to complete integration.

Integration Guide for AWS Network Firewall

Integration Overview

AWS Network Firewall is a managed service that makes it easy to deploy essential network protections for all of your Amazon Virtual Private Clouds (VPCs). AWS Network Firewall's flexible rules engine allows you to define firewall rules that provide fine-grained control over network traffic, such as blocking outbound Server Message Block (SMB) requests to prevent the spread of malicious activity. AWS Network Firewall's stateful firewall can incorporate context from traffic flows, like tracking connections and protocol identification, to enforce policies such as preventing your VPCs from accessing domains using an unauthorized protocol.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with AWS Network Firewall:

- Create Stateful Rule Group
- Create Stateless Rule Group
- Add Stateful Rule
- Add Stateless Rule
- Delete Rule Group
- Delete Stateful Rule
- Delete Stateless Rule
- List Firewalls
- List Rule Groups
- List Firewall Policies
- Get Firewall Policies
- Get Firewall Rule Group

Prerequisites

 ArcSight SOAR connects to AWS Network Firewall API using HTTPS. Access to https://aws.amazon.com/network-firewall is required. Access key ID and Secret Access key are required for ArcSight SOAR to connect to AWS Network Firewall.

Configuration

Configuring AWS Network Firewall

- 1. Log in to Amazon AWS.
- Navigate to My Security Credentials and select Identity Access Management (IAM) service.
- Click Access Management > Users > Add User to add an IAM user.
- 4. Select Access Type as Programmatic Access.
- 5. You can skip the next steps until Access Key and Secret Access Key are displayed.



Download the credentials as the Secret Access Key is not displayed post this step.

6. Add the following action permissions if you require admin permissions for this service or contact your AWS cloud support:

```
"network-firewall:ListTagsForResource",
"network-firewall:DeleteRuleGroup",
"network-firewall:DescribeLoggingConfiguration",
"network-firewall:CreateRuleGroup",
"network-firewall:DescribeRuleGroupMetadata",
"network-firewall:DescribeFirewall",
"network-firewall:UpdateRuleGroup",
"network-firewall:ListRuleGroups",
"network-firewall:DescribeRuleGroup",
"network-firewall:DescribeFirewallPolicy",
"network-firewall:ListFirewalls",
"network-firewall:TagResource",
"network-firewall:DescribeResourcePolicy",
"network-firewall:DeleteFirewall",
"network-firewall:ListFirewallPolicies"
]
```

Configuration Page 101 of 594

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor:**

Туре	Name	Username	Password	Private Key
Internal Credential	Display name of credential set (for example, Amazon Network Firewall Credentials).	Empty	Access Key	Secret Key

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration Form:**

Parameter	Value			
Name	Display name of the integration			
Туре	Amazon Network I	Firewall		
Address		egration should follow the format ewall.amazonaws.com:443		
	For specific region, the integration should follow the format https://network-firewall.region.amazonaws.com			
Configuration	Specify the followi	ng configuration parameter values:		
	Region	Region is required for retrieving the correct endpoint for current integration. For example: ap-southeast-1		
	proxy.id	Integration ID of the proxy to use current intergration. For example: Proxy.id=12345		
Credential	Credential that has	s been defined for this integration under the Credentials		
Trust Invalid SSL Certificates	Select this option if the firewall's web certificate is self-signed or if it is not recognized by browsers			
Require Approval From	Select user(s) from list who can provide approval before executing actions on this integration			
Notify	Select user(s) from an action on this in	the list who can provide approval when SOAR performs		

5. Click Save.

Configuring SOAR Page 102 of 594

- 6. Navigate to Configuration > Customization Library and edit Amazon Network Firewall Advanced Action Script Default Script Template.
- 7. Select the integration that you have created in step 4 from the **Integrations** drop-down menu and click **Save**.
- 8. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. Create Stateful Rule Group

Action capability for creating a Stateful Rule Group for blocking IP address.

• Rollback: No

• Duplicate Control: No

The following table presents the **Create Stateful Rule Group** action capabilities details:

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is no-rollback.	N/A	N/A	No
Rule Group Name	Name of the Rule Group	String	No	No
Action	Action to be taken (PASS,DROP,ALERT)	String	No	Yes
Header Protocol	Header Protocol (TCP,HTTP,ICMP and so on)	String	No	Yes
Capacity	Capacity	Integer	No	Yes
Header Source	IP Address	String	No	Yes
Header Source Port	Source Port	String	No	Yes
Header Destination	IP Address	String	No	Yes
Header Destination Port	Destination Port	String	No	Yes
Direction	Direction (FORWARD,ANY)	String	No	Yes
Rule Order	Rule Order to be executed	String	No	Yes

Output:

N/A

Human Readable Output

Capabilities Page 103 of 594

N/A

2. Create Stateless Rule Group

Action capability for creating a Stateless Rule Group for blocking IP address.

• Rollback: No

• Duplicate Control: No

The following table presents the **Create Stateless Rule Group** action capabilities details:

Input Parameter	Description	Туре	Scope Rescticted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Roll Back mode	Time to rollback this action. Default is no-rollback	N/A	N/A	No
Rule Group Name	Rule Group Name	String	No	Yes
Rule Group Action	Action to be taken (aws:PASS,aws:DROP)	String	No	Yes
Source Address Definition	IP address,range of IP address	String	No	Yes
Destination Address Definition	IP address,range of IP address	String	No	Yes
Header Destination Port	Destination Port	String	No	Yes
Priority	Priority for execution	Integer	No	Yes
Capacity	Capacity	Integer	No	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

3. Add Stateful Rule

Action capability for adding a Stateful rule to an existing Rule Group for blocking IP address.

• Rollback: Yes

• Duplicate Control: Yes

The following table presents the Add Stateful Rule action capabilities details:

Capabilities Page 104 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integraion	Name of the third party integration	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is no-rollback	String	N/A	No
Rule Group Name	Rule Group Name	String	No	Yes
Rule Group Action Name	Action to be taken (PASS,DROP,ALERT)	String	No	Yes
Header Protocol	Hearder Protocol(TCP, HTTP, ICMP and so on)	String	No	Yes
Header Source	IP Address	String	No	Yes
Header Source Port	Source Port	String	No	Yes
Header Destination	IP Address	String	No	Yes
Header Destination Port	Destination Port	String	No	Yes
Direction	Direction(FORWARD,ANY)	String	No	Yes
Rule Order	Rule Order to be executed	String	No	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

4. Add Stateless Rule

Action capability for adding a Stateless Rule to an existing Rule Group for blocking IP address.

• Rollback: Yes

• Duplicate Control: Yes

The following table presents the **Add Stateless Rule** action capabilities details:

Capabilities Page 105 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is no-rollback	String	N/A	No
Rule Group Name	Rule Group Name	String	No	Yes
Action	Action to be taken (aws:PASS,aws:DROP)	String	No	Yes
Source Address Definition	IP Addess, Range of IP Address	String	No	Yes
Destination Address Definition	IP Addess, Range of IP Address	String	No	Yes
Priority	Priority for execution	String	No	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

5. Delete Rule Group

Action capability for deleting Rule Group from existing Rule Group.

• Rollback: No

• Duplicate Control: Yes

The following table presents the **Delete Rule Group** action capabilities details:

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is norollback.	N/A	N/A	No
Rule Group Name	Rule Group Name	String	No	Yes
Туре	Type (STATEFUL or STATELESS)	String	No	Yes

Output:

Case Scope

N/A

Human Readable Output

Capabilities Page 106 of 594

N/A

6. Delete Stateful Rule

Action capability for deleting a Stateful Rule from an existing Rule Group.

• Rollback: No

• Duplicate Control: No

The following table presents the **Delete Stateful Group** action capabilities details:

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is norollback.	N/A	N/A	No
Rule Group Name	Rule Group Name	String	No	Yes
Sid	Sid	Integer	No	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

7. Delete Stateless Rule

Action capability for deleting a Stateless Rule from an existing Rule Group.

• Rollback: No

• Duplicate Control: No

The following table presents the **Delete Stateless Group** action capabilities details:

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is norollback.	N/A	N/A	No
Rule Group Name	Rule Group Name	String	No	Yes
Priority	Priority for execution	Integer	No	Yes

Output:

Case Scope

Capabilities Page 107 of 594

N/A

Human Readable Output

N/A

8. List Firewalls

Enrichment capability for retrieving a list of firewall for the specified VPC identifiers.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Max result	Max result	Integration	N/A	Yes
VPC IDs	VPC identifiers	String	N/A	No

Output:

Case Scope

N/A

Human Readable Output

9. List Rule Groups

Enrichment capability for retrieving a list of rule groups.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Max result	Max result	Integration	N/A	Yes
Scope	Scope(ACCOUNT,MANAGED)	String	N/A	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

10. List Firewall Policies

Enrichment capability for retrieving a list of firewall policies.

Capabilities Page 108 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Max result	Max result	Integration	N/A	Yes

Case Scope

N/A

Human Readable Output

N/A

11. Get Firewall Policy

Enrichment capability for retrieving the details of a firewall policy.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Firewall Policy Name	Firewall Policy Name	String	N/A	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

12. Get Firewall Rule Group

Enrichment capability for retrieving the details of a firewall rule group.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integeration	N/A	Yes
Max Results	Max Results	Integer	N/A	Yes
Scope	Scope(ACCOUNT,MANAGED)	String	N/A	Yes

Output:

Case Scope

N/A

Capabilities Page 109 of 594

Human Readable Output N/A

Integration Guide for Azure Network Security Groups

Integration Overview

Azure Network Security Groups is a service that is used to filter network traffic to and from Azure resources in an Azure virtual networks. A network security group contains security rules that allow or deny inbound network traffic to, or outbound network traffic from, several types of Azure resources. For each rule, you can specify source and destination, port, and protocol.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Azure Network Security Groups:

- Get Network Security Group
- List All Network Security Group
- List Network Security Group in Resource Group
- Create Network Security Group
- Create Network Security Group Rule
- Add Network Security Group Tag
- Remove Network Security Group Tag

Prerequisites

ArcSight SOAR connects to Microsoft Azure Network Security API using HTTPS. Access to Azure Portal (https://login.live.com) is required.

Configuration

Configuring Microsoft Azure Network Security

- 1. Log in to https://portal.azure.com and Navigate to Azure Active Directory service.
- Click App Registration > New Registration. Complete the ArcSight SOAR application registration by specifying the following parameter values in the Register an application form:

Name	Supported Account types	Redirected URL
ArcSight SOAR	Accounts in this organizational directory only (Default Directory for single tenant only)	https://localhost/soar

Select your application and Click Add a certificate or secret > New Client Secret. Add a description and specify the expiry period as 24 months.



Note down the Secret Key along with Client ID as you may need it later.

- a. Click API Permissions > Add a Permission and select Azure Service Management API.
- b. Add the user_impersonation as a permission.
- 4. Navigate to Home > Subscriptions and note down the subscription ID.
- 5. Navigate to Home > Resource groups > IAM > Add Role to add role level permissions.
- 6. Grant following permissions to the users:

Permissions	Description
Microsoft.Network/networkSecurityGroups/read	Gets a network security group definitionAction
Microsoft.Network/networkSecurityGroups/write	Creates a network security group or updates an existing network security groupAction

Configuration Page 111 of 594

Permissions	Description
Microsoft.Network/networkSecurityGroups/securityRules/read	Gets a security rule definition Action
Microsoft.Network/networkSecurityGroups/securityRules/write	Creates a security rule or updates an existing security rule Action

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor**:

Туре	Name	Password	Private Key
Internal Credential	Display name of credential set (for example, Microsoft Azure Network Security).	Client ID of the user that you have created for SOAR on Microsoft Azure Network Security.	Client secret key of the users that you have created for SOAR on Microsoft Azure Network Security.

- 3. Click Configuration > Integrations > Create Integration
- 4. Specify the following parameter values in the **Configuration Form**:

Parameter	Value
Name	Display name of the integration
Туре	Microsoft Azure Network Security
Address	Address of the integration (the format should be https://management.azure.com)

Configuring SOAR Page 112 of 594

Parameter	Value			
Configuration	Specify the following config	uration parameters:		
	tenant.id	Tenant Id on Microsoft Azure. For example: tenant.id = 57faef05-5f3f-4147-a5e1- 5ecd93902c3a		
	subscription	Subscription ID on Microsoft Azure. For example, subscription = 7ee609fd-4deb4156-826e-7d1796f6e3e7		
	version	Microsoft Azure Network Security API version . For example: version= 2021-05-01		
	proxy.id ID of the proxy integration if you access Microsoft Azu through a web proxy device. For example: proxy.id = 12345			
Credential	Credential that has been defined for this integration under Credential menu.			
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.			

- 5. Click Save.
- 6. Navigate to Configuration > Customization Library and edit Amazon Network Firewall Advanced Action Script Default Script Template.
- 7. Select the integration that you have created in step 4 from the **Integrations** drop-down menu and click **Save**.
- 8. Click **Test**, and **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

Get Network Security Group
 Enrichment capability for retrieving a network security group in a resource group.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Network Security Group Name	Name of the network security group	String	N/A	Yes
Resource Group Name	Resource group of the user that you have created in Microsoft Azure Network Security Group	String	N/A	Yes

Output:

Capabilities Page 113 of 594

Case Scope

N/A

Human Readable Output

N/A

2. List All Network Security Group

Enrichment capability for retrieving all network security groups from a resource group.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Network Security Group Name	Name of the network security group	String	N/A	Yes
Resource Group Name	Resource group of the user in Microsoft Azure Network Security Group	String	N/A	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

3. List Network Security Group in Resource Group

Enrichment capability for listing all network security group in a particular resource group.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Network Security Group Name	Name of the network security group	String	N/A	Yes
Resource Group Name	Resource group of the user in Microsoft Azure Network Security Group	String	N/A	Yes

Output:

Case Scope

N/A

Human Readable Output

Capabilities Page 114 of 594

4. Create Network Security Group

Action capability for creating a network security group in a particular resource group.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
inNetwork Security Group Name	Network Security Group Name	String	N/A	Yes
Resource groups Name	Resource group of the users in Microsoft Azure Network Security Group.	String	N/A	Yes
Location	Location of the user.	String	N/A	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

5. Create Network Security Group Rule

Action capability for creating a network security group rule in resource group.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Network Security Group Name	Name of the network security group name	String	N/A	Yes
Resource Group Name	Resource group of the users in Microsoft Azure Network Security Group.	String	N/A	Yes
Name	Unique Rule Name	String	N/A	Yes
Protocol	TCP, UDP, ICMP, ESP, AH, or Any	String	N/A	Yes
Source Address Prefix	"*" for all default or 0.0.0.0/0 or AzureLoadBalancer	String	N/A	Yes
Destination Address Prefix	"*" for all default or 0.0.0.0/0 or AzureLoadBalancer	String	N/A	Yes
Source Port Range	0-65535	String	N/A	Yes
Destination Port Range	0-65535	String	N/A	Yes

Capabilities Page 115 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Priority	A number in the range 100-4096 to assign a priority. Rules are processed in priority order, with lower numbers processed before higher numbers	String	N/A	Yes
Direction	Whether the rule applies to inbound, or outbound traffic	String	N/A	Yes
Access	Allow or deny.	String	N/A	Yes
Location	Location of the user	String	N/A	Yes

Case Scope

N/A

Human Readable Output

N/A

6. Add Network Security Group Tags

Action capability for updating a network security group tag in the specified resource group.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Network Security Group Name	Network Security Group Name	String	N/A	Yes
Resource group Name	Resource group of the user in Microsoft Azure Network Security Group.	String	N/A	Yes
Tag Name	Resource Tag Key	String	N/A	Yes
Tag Value	Resource Tag Value	String	N/A	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

7. Remove Network Security Group Tags

Action capability for Updating network security group tag in the specified resource group.

Capabilities Page 116 of 594

Input Parameter	Description	Type	Scope Restricted (Yes/No)	Required (Yes/No)
Network Security Group Name	Network Security Group Name	String	N/A	Yes
Resource group Name	Resource group of the user in Microsoft Azure Network Security Group.	String	N/A	Yes
Tag Name	Resource Tag Key	String	N/A	Yes
Tag Value	Resource Tag Value	String	N/A	Yes

Case Scope

N/A

Human Readable Output

N/A

Capabilities Page 117 of 594

Integration Guide for Bind RPZ DNS

Integration Overview

ArcSight SOAR uses BIND DNS servers to block malicious domains using incident scope.

Integration Capabilities

Action

Block

Configuration

Prerequisites

- You must enable the DNS Zone Transfer on the server as SOAR uses DNS Zone Transfer Protocol to connect to the BIND DNS server.
- Remote Name Daemon Control (RNDC)


Configuring SOAR

- 1. To create the integration, navigate to **Configuration > Integrations**.
- 2. Specify the following parameter values in the Integration Editor window:

Parameter	Value
Name	Display name of the integration
Туре	BIND RPZ DNS
Address	Address of the integration (the format must be 1.1.1.1).

Parameter	Value
Configuration	You must specify the following configuration parameters:
	ZONE: Name of the RPZ configured on the BIND server
	BLOCK_IP: IP address to which malicious domains need to be redirected
	TTL: Time-to-live for the DNS record
	KEY_NAME: Name of the RNDC key
Credential	Specify the Credential that was defined for this integration under the Credentials menu
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or is not recognized by browsers.
Require Approval From	Select users from list who can provide approval before executing action on this integration
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration

Configuring SOAR Page 119 of 594



- 3. Click **Test**. The following pop up will be displayed if your credential and address are valid.
- 4. Click **Save** to complete integration.

Integration Guide for BMC Helix ITSM

Integration Overview

BMC Helix ITSM is a comprehensive Cognitive Service Management cloud offering, that consists of robust cognitive capabilities such as intelligent chatbots and predictive capabilities.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with BMC Helix ITSM:

- Create Incident
- · Update Incident
- Get an Incident
- Close Incident
- · Add Work Note to Incident

Prerequisites

You must have HTTPS access as ArcSight SOAR connects to BMC Helix API through this service.

Configuration

Configuring BMC Helix ITSM

To configure a service and get a jwt token from the BMC Helix platform endpoint, complete the following steps:



Your service can use the token to call ITSM APIs under its own identity.

- 1. Login to create an authorization key used in all subsequent calls.
- 2. In the login page, specify the following details:



Client creates a POST call and passes the user name, password, and Auth String in the Request headers using the /x-www-form-urlencoded content type.

Body Parameters for the JWT (JSON Web Tokens) Token generation:

Parameter	Description	Data Type	Required
Username	< username>	String	Yes
Password	< password>	String	Yes

Additional Configurations:

Configuration Parameters	Description
proxy.id	Proxy device to be used while communicating with the remote system's API
cache.reusing.duration	Default cache-reuse parameter
list.name	List name that is used for mapping ArcSight SOAR cases to MC Helix ITSM incidents. For example, list.name=bmcMapList

Prerequisites Page 121 of 594

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credentials.
- 2. Specify the following parameters values in the Credential Editor form.

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, BMC Helix Credentials).	Your username from BMC Helic	Your password from BMC Helic	Empty

- 3. Click Configuration > Integrations > Upload plugin
- 4. Select your integration plugin zip file and click Save.
- 5. Select the integration that you have added to the Integrations menu.
- 6. Click Save to complete the integration.
- 7. Click Test. A successful message is displayed if the credential and address are valid.

Integration Capabilities:

1. Create Incident

Action capability to create incident records with severity, priority, descriptions etc.

· Rollback: No

• Duplicate Control: No

Request headers:

Parameter	Value	Required
Authorization	AR-JWT <token generated=""></token>	Yes

Input Parameters:

Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
Urgency	The level if incident. The level, for example, can be critical, low or high.	Array	No	Yes
Impact	The type of issue.	Array	No	Yes
Service Type	The type of service incident. The type, for example, can be 'User Service Restoration.	Array	No	Yes
Description	Description of the incident.	String	No	Yes

Output:

Configuring SOAR Page 122 of 594

Case Scope: N/A

Human Readable Output: N/A

2. Update Incident

Action capability to update the incident.

• Rollback: No

• Duplicate Control: No

Request headers:

Parameter	Value	Required
Authorization	AR-JWT <token generated=""></token>	Yes

Input Parameters:

Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
Request ID	RequestID Of An IncidentOn HPD:IncidentInterface	String	No	Yes
Status	The status of the incident (Ex Status:"Resolved"	Array	No	Yes
Urgency	The level if incident. The level, for example, can be critical, low or high.	Array	No	Yes
Impact	The type of issue.	Array	No	Yes
Status Reason	The status of the reason.	Array	No	Yes
Description	Description of the incident.	String	No	No

Output:

Case Scope: N/A

Human Readable Output: N/A

3. Get an Incident

Enrichment capability to fetch the incident details for a given incident ID.

Request headers:

Parameter	Value	Required
Authorization	AR-JWT <token generated=""></token>	Yes

Input Parameters:

Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
Incident Number	Incident number Of An IncidentOn HPD:IncidentInterface	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output:

Кеу	Value
Request ID	INC00000005318 INC00000005318
Incident Number	INC00000005587
Submitter	Sam_Agent
Submit Date	2023-03-03T11:32:12.000+0000
Assignee Login ID	Arthur Agent
Reported Date	2023-03-03T11:32:12.000+0000
Responded Date	2023-03-03T11:32:12.000+0000
Last Modified By	Sam_Agent
Last Modified Date	2023-03-03T12:24:32.000+0000
Last Resolved Date	2023-03-03T12:16:36.000+0000
Close Date	2023-03-03T12:16:36.000+0000
Chatria	Clood

Status	Closed
Status History	N/A
Assignee Groups	15032;'Sam_Agent';
Department	BMCOpsMonitoring Dept
Site Group	United States
Region	Americas
Entry ID	INC00000005318
Customer Login ID	Sam_Agent
Description	Changed Status
Company	BMCOpsMonitoring
Country	United States
State Province	Texas
City	Houston
Last Name	Agent
First Name	Sam
Contact Client Type	Office-Based Employee
VIP	No

VIP	No
Contact Sensitivity	Standard
Street	2103 CityWest Blvd.
Zip/Postal Code	77042-2828
Internet E-mail	N/A
Corporate ID	N/A
Phone Number	###
Service Type	Infrastructure Restoration
Status Reason	Automated Resolution Reported
Detailed Decription	N/A
Resolution	Closed Incident
Urgency	4-Low
Impact	2-Significant/Large
Priority	Low
Reported Source	Systems Management

4. Close Incident

Action capability to update existing incident.

• Rollback: No

• Duplicate Control: No

Request headers:

Parameter	Value	Required
Authorization	AR-JWT <token generated=""></token>	Yes

Input Parameters:

Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
Request ID	RequestID Of An IncidentOn HPD:IncidentInterface	String	No	Yes
Resolution Note	Detailed note of the updating incident	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

5. Add Work note to Incident

Action capability to create a work note to existing incident.

Rollback: No

• Duplicate Control: No

Request headers:

Parameter	Value	Required
Authorization	AR-JWT <token generated=""></token>	Yes

Input Parameters:

Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
Incident Number	Incident number of work note	String	No	Yes
Work Note	Work note for the Incident	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

Integration Guide for BMC Helix Remedyforce

Integration Overview

BMC Helix Remedyforce is a cloud service management solution on Salesforce for IT service operations. It improves service delivery with incident and asset management capabilities.

Integration Capabilities

SOAR has the following integration capabilities with BMC Helix Remedyforce:

- Add Client Note to Incident
- Add Client Note to Service Request
- Close Incident
- Close Service Request
- Create Incident
- Create Service Request
- Update Incident

- Update Service Request
- · Get Incident Details
- Get Service Request Details
- List Request Definition Questions
- List Request Definitions

Configuration

Configuring BMC Helix Remedyforce

- You must have access to HTTPS as the ArcSight SOAR connects to https://na1.salesforce.com API through this service.
- BMC Helix Remedyforce requires a Username, Password, and Security Token for access.
- Users must have API access enabled.

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the Credential Editor:

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, BMC Helix Remedyforce Credentials)
Username	<username></username>
Password	<pre><password></password></pre>
Private Key	<security token=""></security>

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of BMC Helix Remedyforce Integration on SOAR
Туре	Advanced Scriptable Device
Address	Address of the Integration (address should be in the format(https://na1.salesforce.com)

Parameter	Value
Configuratio	Specify the following configuration parameters:
n	# Integration ID of the proxy integration to use when connecting to current integration.
	# If not provided, ArcSight SOAR will try to use a direct connection.
	<pre>#proxy.id=123</pre>
	# Name of the list mapping SOAR Case IDs to Salesforce IDs of incidents and service requests
	list.name=SOAR_to_Remedyforce_List
Credential	Name of the credential set created in step 2 (For example, BMC Helix Remedyforce Credentials)
Trust Invalid SSL Certificates	Select this if the certificate of the engine is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an enrichment on this integration

- 5. Click **Test** to test whether the configuration and credentials used can successfully authenticate.
- 6. Click **Save** to complete the integration.
- 7. Click Configuration > Lists > Create List.

Parameter	Value
List Name	Name of list corresponding to list.name in configuration (ie. SOAR_to_Remedyforce_List)

8. Specify the following in the **List Editor** form:

Туре	Column Name
Keyword	Кеу
Keyword	Salesforce ID

Capabilities

1. Add Client note to Incident

Action capability for adding a client note to an incident.

Capabilities Page 129 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Summary	Summary of the note	String	No	Yes
Notes	Note to add to the incident	String	No	Yes

Case Scope

N/A

Human Readable Output

N/A

2. Add Client Note to Service Request

Action capability for adding a client note to a service request.

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Summary	Summary of the note	String	No	Yes
Notes	Note to add to the incident	String	No	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

3. Close Incident

Action capability to close an incident given its status.

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Status	Status of the incident	Dropdown menu with the following options: CLOSED, CLOSED/NO CONTACT, COMPLETED, REJECTED	No	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

4. Close Service Request

Action capability to create a service request.

Capabilities Page 130 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Status	Status of the incident	Dropdown menu with the following options: CLOSED CLOSED/NO CONTACT COMPLETED REJECTED	No	Yes

Case Scope

N/A

Human Readable Output

N/A

5. Create Incident

Action capability to create a new incident.

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Client Username	Username of the client for which the incident is created	Email Address	No	Yes
Account	Name of the account for the incident	Dropdown menu with options: • Account A • Account B • Account C	No	No
Status	Status of the incident	Dropdown menu with options: IN PROGRESS PENDING ACCEPTED ASSIGNED OPENED	No	No

Capabilities Page 131 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Category	Category of the incident	Dropdown menu with the options: • HR-Separation - Disable Systems Access • Email Distribution • Human Resource Inquiries • Building Access	No	No
Impact	Impact of the incident	Dropdown menu with the options: HIGH, MEDIUM, LOW	No	No
Urgency	Urgency of the incident	Dropdown menu with the options: • HIGH • MEDIUM • LOW	No	No
Queue	Name of the queue to assign the incident to	Dropdown menu with the options: Change Management Client Services Application Development Desk Side Support	No	No
Staff Username	Username of the staff to assign the incident to.	Email Address	No	No
Description	Description of the incident	String	No	No
Due Date Time	Date time when the incident is due, can be static (format yyyy-mm-dd HH:MM:SS) or relative (ex: 1d, 2h, 3m)	String	No	No

Capabilities Page 132 of 594

Case Scope

N/A

Human Readable Output

N/A

6. Create Service Request

Action capability to create a service request.

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Request Definition ID	Salesforce ID of the request definition.	String	No	Yes
Request Definition Questions	Questions and answers for the request definition in the format questionID1=value1;questionID2=value2	String	No	No
Client Username	Username of the client for which the service request is created	Email Address	No	Yes
Account	Name of the account for the service requested	Dropdown menu with options: • Account A • Account B • Account C	No	No
Status	Status of the service requested	Dropdown menu with options: • IN PROGRESS • PENDING • ACCEPTED • ASSIGNED • OPENED	No	No

Capabilities Page 133 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Category	Category of the service requested	Dropdown menu with the options: • HR-Separation - Disable Systems Access • Email Distribution • Human Resource Inquiries • Building Access	No	No
Impact	Impact of the service request	Dropdown menu with the options: • HIGH • MEDIUM • LOW	No	No
Urgency	Urgency of the service request	Dropdown menu with the options: • HIGH • MEDIUM • LOW	No	No
Queue	Name of the queue to which the service request is assigned	Dropdown menu with the options: Change Management, Client Services, Application Development, Desk Side Support	No	No
Staff Username	Username of the staff to which the service request is assigned	Email Address	No	No
Description	Description of the service request	String	No	No
Due Date Time	Date time when the service request is due, can be static (format yyyy-mm-dd HH:MM:SS) or relative (ex: 1d, 2h, 3m)	String	No	No

Case Scope

Capabilities Page 134 of 594

N/A

Human Readable Output

N/A

7. Update Incident

Action capability to acquire the client username, account, status, category, impact, urgency, queue, staff username, description, and due date time and updates the incident. At least one of the following parameter must be updated:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Client Username	(Optional) Username of the client for which the service request is created	Email Address	No	Yes
Account	Name of the account	Dropdown menu with options:Account AAccount BAccount C	No	No
Status	Status of the incident	Dropdown menu with options: IN PROGRESS PENDING ACCEPTED ASSIGNED OPENED	No	No
Category	Category of the incident	 Dropdown menu with the options: HR-Separation - Disable Systems Access Email Distribution Human Resource Inquiries Building Access 	No	No
Impact	Impact of the incident	Dropdown menu with the options: • HIGH • MEDIUM • LOW	No	No

Capabilities Page 135 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Urgency	Urgency of the incident	Dropdown menu with the options:	No	No
Queue	Name of the queue to which the service request is assigned	 Dropdown menu with the options: Change Management Client Services Application Development Desk Side Support 	No	No
Staff Username	Username of the staff to which the incident is assigned	Email Address	No	No
Description	Description of the incident	String	No	No
Due Date Time	Date time when the service request is due, can be static (format yyyy-mm-dd HH:MM:SS) or relative (ex: 1d, 2h, 3m)	String	No	No

Case Scope

N/A

Human Readable Output

N/A

8. Update Service Request

Action capability that takes the client email address, status, category, impact, urgency, queue, staff username, description, and due date time and updates the service request. At least one of the following parameters must be updated:

Capabilities Page 136 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Client Username	(Optional) Username of the client to which the service request is created	Email Address	No	Yes
Account	Name of the account for the service requested	Dropdown menu with options: • Account A • Account B • Account C	No	No
Status	Status of the service request	Dropdown menu with options: IN PROGRESS PENDING ACCEPTED ASSIGNED OPENED	No	No
Category	Category of the service request	Dropdown menu with the options: • HR-Separation - Disable Systems Access • Email Distribution • Human Resource Inquiries • Building Access	No	No
Impact	Impact of the service request	Dropdown menu with the options: • HIGH • MEDIUM • LOW	No	No
Urgency	Urgency of the service request	Dropdown menu with the options: • HIGH • MEDIUM • LOW	No	No

Capabilities Page 137 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Queue	Name of the queue to which the service request is assigned	Dropdown menu with the options: Change Management Client Services Application Development Desk Side Support	No	No
Staff Username	Username of the staff to which the incident is assigned	Email Address	No	No
Description	Description of the service request	String	No	No
Due Date Time	Date time when the service request is due, can be static (format yyyy-mm-dd HH:MM:SS) or relative (ex: 1d, 2h, 3m)	String	No	No

9. Get Incident Details

Enrichment capability to retrieve incident details given by the Salesforce ID. Salesforce ID will be retrieved from the list on the SOAR.

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	BMC Helix Remedyforce	Integration	N/A	Yes


Output:

Case Scope

Action	Туре	Category/Value
N/A	N/A	N/A

Human Readable Output:

Capabilities Page 138 of 594



10. Get Service Request Details

Enrichment capability to retrieves service request details given the Salesforce ID. Salesforce ID will be retrieved from the list on the SOAR.

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	BMC Helix Remedyforce	Integration	N/A	Yes


Output:

Case Scope:

Action	Туре	Category/value
N/A	N/A	N/A

Human Readable Output

Capabilities Page 139 of 594



11. List Request Definition Questions

Enrichment capability to list the questions associated with a request definition.

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	BMC Helix Remedyforce	Integration	N/A	Yes
Request Definition ID	Salesforce ID of the request definition	String	No	Yes

Output:

Case Scope:

Action	Туре	Category/Value
N/A	N/A	N/A

Human Readable Output:

Capabilities Page 140 of 594

Question Id	Question Prompt	Required	Input Values
	# of CPU's needed	true	Option: Allocate 1 CPU to new system, Value: 1, Default: true Option: Allocate 2 CPUs to new system, Value: 2, Default: false Option: Allocate 4 CPUs to new system, Value: 4, Default: false
	Memory required	true	Option: Allocate 512 MB memory to new system, Value: 512, Default: true Option: Allocate 1 GB memory to new system, Value: 1024, Default: false Option: Allocate 2 GB memory to new system, Value: 2048, Default: false Option: Allocate 4 GB memory to new system, Value: 4096, Default: false
	Operating System Requested	true	Option: Install Windows 7 on new system, Value: WIN7, Default: true Option: Install Linux Redhat on new system, Value: Linux, Default: false
	Other details:	false	Enter text

12. List Request Definitions

Enrichment capability to list all available request definitions that can be used for service request creation.

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	BMC Helix Remedyforce	Integration	N/A	Yes

Output:

Case Scope

Action	Туре	Category/Value
N/A	N/A	N/A

Human Readable Output:

Name	ld	Description
I need a server for a project		Request for a new project server
Request a Copy/License of AutoCAD 2015		Use this to request a copy of Autodesk AutoCAD 2015 to be installed on your computer. You will be charged for the cost of the license associated with the software install.
Cannot Access Imagine		N/A
Request Employee Separation (Off-boarding / Termination)		Starts the separation process as an employee leaves the organization.
Client Services: Request for Change		Need a report? Marketing materials? An enhancement request for one of our solutions?

Capabilities Page 141 of 594

Integration Guide for Carbon Black Response (EDR)

Integration Overview

Carbon Black Response (EDR)is a next-generation antivirus and end point detection response application. It's sophisticated detection combines custom and cloud-delivered threat intel, automated watchlists, and integrations with other platforms to efficiently scale hunt across the enterprise. It consolidates threat intelligence for your environment to automatically detect suspicious behavior.

Integration Capabilities

- Block Hash
- Unblock Hash
- Quarantine
- Unquarantine
- Computer Info
- Download Binary
- Get Binary Metadata
- List Process Connections
- Process Event Details
- Search Binaries
- Search Processes

Use Case: Investigating and Blocking Malware Spread

ArcSight SOAR integrates with Carbon Black Response (EDR), to help investigation and mitigation of malware attacks. When a suspicious file or malware is detected, SOAR lets you to search malware across endpoints, isolates PCs from network, and blocks relevant hashes. This investigation can either be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- Access to port 443/tcp as SOAR connects to Carbon Black Response(EDR) API through HTTPS.
- An API key is required for SOAR to connect to Carbon Black Response(EDR).

Configuring Carbon Black Response(EDR)

- 1. Log in to Carbon Black Server.
- 2. Navigate to **User Profile > API Token** and make a note of the API key.

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the **Crenetial Editor** form with the following parameter values:
 - a. Internal credential:

Parameter	Value
Туре	Internal credential
Name	Display name of the credential set (For example, Carbon Black Credential)
Username	Empty
Password	Empty
Private Key	API Key obtained from Carbon Black Response (EDR)

b. Credential Store:

Parameter	Value
Туре	External credential
Name	Name of the credential with full path of the safe on store.


3. Click Configuration > Integrations > Create Migration.

Prerequisites Page 143 of 594

4. Specify the **Configuration form** with the following parameter values:

Parameter	Value	
Name	Display name of Carbon Black Response (EDR) integration on SOAR	
Туре	Carbon Black Response	
Address	Address of the integration (in the format: https://192.168.2.26)	
Configuration	Specify the following configuration parameters:	
	<pre># Integration ID of the proxy integration to use when connecting to # current integration. # If not provided, SOAR will try to use a direct connection. #proxy.id=123</pre>	
Credential	Name of the credential set created on step 2. (For example, Carbon Black Credentials)	
Trust Invalid SSL Cerificates	Not Applicable	
Require Approval From	Select users from list who can provide approval before executing actions on this integration.	
Notify	Select users from the list to notify when SOAR performs an action on this integration	

Configuring SOAR Page 144 of 594




- 5. Navigate to Configuration > Customization Library and edit Carbon Black Response Advanced Action Script Default Template.
- 6. Select the integration that you have added to Integrations menu.
- 7. Click Save to complete the integration.
- 8. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Additional Notes

- Carbon Black Response integration on SOAR is an Advanced Script, and the content of default script is accessible under Configuration > Customization Library.
- While defining the integration for the first time, you will encounter the following warning message, which is expected behavior for this type of integration.

Additional Notes Page 145 of 594



Additional Notes Page 146 of 594

Integration Guide for Check Point R80

Integration Overview

Check Point R80 is an integrated solution for advanced threat prevention and security management.

This integration was tested with Check Point R80.20.

Integration Capabilities

- · Block Email Sender
- Block Hash
- Block Host
- Block IP
- Block URL

Prerequisites

You must have access to HTTPS as the ArcSight SOAR connects to Check Point Smart Console API through this service.

Configuration

Configuring Check Point R80

- Login to Management Console and navigate to Manage & Settings > Blades >
 Management API Advanced Settings and select All IP addresses that can be used for GUI clients in the Access Settings section.
- 2. Restart the API service by executing the following command in the command prompt: api restart
- 3. SOAR requires standard read/write access for the necessary policy and objects. To install policy automatically, the user must have the rights in its permission profile. You must

configure the required access rights for SOAR user as follows:

Туре	Permission
Access Control	 Policy Data Loss Prevention Access Control Objects and Settings Install Policy
Threat Prevention	 Policy Layers Policy Exceptions Profiles Protections Install Policy
Management	Management API Login
Others	Common Objects

4. Create an **Object Group** to be used by SOAR. The ArcSight SOAR adds the objects that you want to block in the Object Group.

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following values in the **Credential Editor**:

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set, for example, Check Point R80 Credentials.
Username	User that you have created for SOAR on Check Point R80
Password	Password of the user you have created for SOAR on Check Point R80
Private Key	Empty

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following values in the Configuration Form:

Parameter	Value
Name	Display name of the integration.
Туре	Check Point R80 Next Generation Firewall.
Address	Address of the integration (the format must be 10.0.0.1 or abc.example.com)

Configuring SOAR Page 148 of 594

Parameter	Value			
Configuration	Specify the follow	Specify the following configuration parameters:		
	group.name	Object Group's name created in Check Point configuration steps. For example:		
		group.name = SOAR		
	products	Possible values are AV (Anti Virus) for external threats and AB (Anti Bot) for internal threats. Please put " " separator for more than one product. For example:		
		Product = AV AB		
	install.policy	If you would like to install policy automatically, set this variable true:		
		<pre>install.policy = true</pre>		
	policy.package	Policy which SOAR installs on target systems. Required if install.policy is true. For example:		
		policy.package = standard		
	targets	Name of the target gateways. Required if install.policy is true. Please use " $\ $ " as separator if you have more than one target. For example:		
		targets = CP_Cluster		
	access	Required for blocking IP addresses on access policy. Required if install.policy is true.		
		access = true		
	threat.prevention	Required for blocking indicators on Threat Prevention policy (Domain, Email, Hash, URL). Required if install.policy is true.		
		threat.prevention = true		
	proxy.id	ID of the Proxy integration if you access Check Point R80 through a web proxy device. For example:		
		proxy.id = 12345		
Credentials	Credential that h	Credential that has been defined for this integration under the Credentials menu.		
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or is not recognized by browsers.			
Require Approval From	Select user(s) fro integration	Select user(s) from list to ask her/his approval before executing actions on this integration		
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration			

5. Click **Show Additional Parameters** checkbox and select the frequency of policy install in **Maintenance** dropdown.

Configuring SOAR Page 149 of 594



As the firewall might get overloaded, in case of frequent attacks or misconfiguration, thus, SOAR does not install the policy after every action. Instead, you can define the frequency of the policy install in **Maintenance** menu by either selecting pre-defined values or by defining a custom Cron expression for scheduling. The ArcSight SOAR uses spring-framework's Cron expression format. For the format and similar example, refer to the Spring Framework-Cron Expression

- 6. Click **Test**. An **Integration Successful** message is displayed if your credential and address are valid.
- 7. Click Save to complete the integration.

Capabilities

1. Block Email Sender

Action capability for blocking malicious email addresses.

• Rollback: Yes

• Duplicate Control: Yes



Only supported on AV product. AB product doesn't support this capability.

Input Parameter	Description	Туре	Scope Restricted Yes/No	Required Yes/No
Integration	Name of the third party integration	Integration	N/A	Yes
Rollback	Time to rollback this action. Default is no-rollback.	N/A	N/A	No
Email Address	Email address to be blocked	Email Address	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

2. Block Hash

Action capability for blocking hash values of malicious files.

• Rollback: Yes

• Duplicate Control: Yes

Capabilities Page 150 of 594



Only supported on AV product. AB product doesn't support this capability.

Input Parameter	Description	Туре	Scope Restricted Yes/No	Required Yes/No
Integration	Name of the third party integration	Integration	N/A	Yes
Rollback	Time to rollback this action. Default is no-rollback.	N/A	N/A	No
Hash	Hash to be blocked	Hash	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

3. Block Host

Action capability for blocking malicious hosts.

• Rollback: Yes

• Duplicate Control: Yes



Only supported on AV product. AB product doesn't support this capability.

Input Parameter	Description	Туре	Scope Restricted Yes/No	Required Yes/No
Integration	Name of the third party integration	Integration	N/A	Yes
Rollback	Time to rollback this action. Default is no-rollback.	N/A	N/A	No
Host	Host to be blocked	Host (It is mentioned as domain object on Check Point)	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

4. Block IP

Action capability for blocking malicious IP addresses.

Capabilities Page 151 of 594

• Rollback: Yes

• Duplicate Control: Yes



Only supported on AV product. AB product doesn't support this capability.

Input Parameter	Description	Туре	Scope Restricted Yes/No	Required Yes/No
Integration	Name of the third party integration	Integration	N/A	Yes
Rollback	Time to rollback this action. Default is no-rollback.	N/A	N/A	No
IP Address	IP address to be blocked	Network Address	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

5. Block URL

Action capability for blocking URLs.

• Rollback: Yes

• Duplicate Control: Yes



Only supported on AV product. AB product doesn't support this capability.

Input Parameter	Description	Туре	Scope Restricted Yes/No	Required Yes/No
Integration	Name of the third party integration	Integration	N/A	Yes
Rollback	Time to rollback this action. Default is no-rollback.	N/A	N/A	No
URL	URL to be blocked	URL	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

Capabilities Page 152 of 594

Integration Guide for Check Point SandBlast

Integration Overview

Check Point SandBlast provides advanced threat protection against known threats, zero-day malware, and sophisticated attacks.

Integration Capabilities

Threat Emulation capability prevents infections from undiscovered exploits, zero-day and targeted attacks by inspecting files, and running them in a virtual sandbox to discover malicious behavior.

ArcSight SOAR has the following integration capabilities with Check Point SandBlast:

Threat Emulation & AV Scan

Use Case: Investigating suspicious file

With Check Point SandBlast integration, during the investigation of an incident, SOAR can send a suspicious file to Check Point SandBlast to emulate threats and run an anti virus scan for the file. This investigation can either be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- Make sure you have access to 443/tcp port as SOAR connects to Check Point SandBlast's
 API through HTTPS. If cloud-based threat emulation service is used, the API interface works
 on https://te.checkpoint.com/api/bla/bla
- If a local gateway is used, typically access permission to 18194/tcp port is required.
- An API key is required for SOAR to connect to Check Point SandBlast.

Configuring Check Point SandBlast

1. If you are using cloud-based threat emulation service, contact Check Point to get the API key.

2. If you are using local gateway, the following link provides you with the document for creating API key:

http://supportcontent.checkpoint.com/solutions?id=sk113599

Configuring SOAR

- 1. Configuration > Integrations > Create Integration.
- 2. Fill the **Credential Editor** form with the following parameter values:
 - a. Internal Credential:

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, Check Point SandBlast Credential)
Username	Empty
Password	Empty
Private Key	API key you have created for SOAR on local gateway or you have obtained from Check Point.

b. Credential Store:


Parameter	Value
Туре	External credential
Name	Name of the credential with full path of the safe on store

- 3. Configuration > Integrations > Create Integration.
- 4. Fill the configuration form with the following parameter values:

Parameter	Value
Name	Display name of Check Point SandBlast integration on SOAR
Address	Address of the integration (the format must be https://192.168.1.1:18194 or https://te.checkpoint.com)
Credential	Name of the credential set you have just created on step 2. (For example, Check Point SandBlast Credential).
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or is not recognized by browsers.

Configuring SOAR Page 154 of 594

Parameter	Value
Configuration	Specify the following configuration parameters:
	<pre># Set local_instance true if you use local gateway. local_instance=false# configure how far (in minutes) into the past this enrichment will look. cache.reusing.duration=60 # Set proxy id if necessary for SOAR to reach the SandBlast instance. proxy.id=123</pre>
Require Approval Form	Select user(s) from list to ask her/his approval before executing actions on this s.
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.



- 5. Click **Test**. The following pop up will be displayed if your credential and address are valid.
- 6. Click **Save** to complete integration.

Configuring SOAR Page 155 of 594

Integration Guide for CiscoASA Firewall

Cisco ASA is a security technology that combines firewall, antivirus, intrusion prevention and virtual private network (VPN) capabilities. It provides proactive threat defence and stops attacks before they spread in the network.

Integration Capabilities

- Block Host
- Block IP

Prerequisites

- You must have access to 443/tcp port for HTTPS as the ArcSight SOAR connects to Cisco ASA Firewall REST-API interface through this service.
- SOAR must have a user account to connect to Cisco ASA Firewall.

Configuration

Configuring Cisco ASA Firewall

- 1. Log in to Cisco ASA Firewall device command line console.
- 2. Create a user account with privilege level 15 as follows:

```
# configure terminal
# username soar password choose_a_complex_password privilege 15
```

3. Enable the **REST API** services by running the following commands:

```
# rest-api image
# rest-api agent
```

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor** form.

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, Cisco ASA Firewall Credential).	User you have created for SOAR on Cisco ASA Firewall.	Password of the user you have created for SOAR on Cisco ASA Firewal.	Empty.

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form.

Parameter	Value		
Name	Display name of the integration.		
Туре	Cisco ASA Firewall		
Address	Address of the integrat	ion (the format should be https://10.0.0.1)	
Configuration	Specify the following co	onfiguration parameters:	
	NETWORK_OBJECT_ GROUP_NAME_FOR_ IP	IP Object Group name used by SOAR. For example: NETWORK_OBJECT_GROUP_NAME_FOR_IP=SOAR_IP_LIST .	
	NETWORK_OBJECT_ GROUP_NAME_FOR_ DOMAIN	FQDN Object Group name used by SOAR. For example: NETWORK_OBJECT_GROUP_NAME_FOR_DOMAIN=SOAR_ DOMAIN_LIST.	
	proxy.id	ID of the Proxy integration if you access Cisco ASA Firewall through a web proxy device. For example: proxy.id = 12345	
Credential	Credential that has bee	en defined for this integration in the Credentials menu.	
Trust Invalid SSL Certificates	Select this if firewall's web certificate is self-signed or is not recognized by browsers.		
Require Approval From	Select user(s) from list to ask the approval before executing actions on this integration.		
Notify	Select user(s) from the integration.	list to notify when SOAR performs an action on this	

- 5. Click **Save** to save the integration definition.
- 6. Navigate to Configuration>Customization Library and edit Cisco ASA Firewall Advanced Action Script Default Template.

Configuring SOAR Page 157 of 594

- 7. Select the integration that you have added in the Integrations menu.
- 8. Click **Save** to complete the integration.

Capabilities

1. Block Host

Action capability for blocking malicious host.

• Rollback: Yes

• Duplicate Control: Yes

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the 3rd party integration	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is no-rollback	N/A	N/A	No
FQDN	Host to be blocked	Host (It is written as domain object on Cisco ASA Firewall)	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

2. Block IP

Action capability for blocking malicious IP addresses.

• Rollback: Yes

• Duplicate Control: Yes

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the 3rd party integration.	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is no-rollback.	N/A	N/A	No
IP Address	IP address to be blocked	Network Address	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

Capabilities Page 158 of 594

Integration Guide for Cisco Firepower Management Center

Integration Overview

Cisco Firepower Management Center (formerly Sourcefire Firepower Management Center) is an administrative center node of the Firepower Threat Defense systems and manages critical Cisco network security solutions. It provides complete and unified management over firewalls, application control, intrusion prevention, URL filtering, and advanced malware protection.

This integration is tested with Cisco Firepower Management Center version 6.3.0 (build83).

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Cisco Firepower Management Center:

- Block IP
- Block URL

Prerequisites


You must have access to HTTPS as the ArcSight SOAR connects to Cisco Firepower Management Center REST API through this service.

Configuration


Configuring Cisco Firepower Management Center

- Login to Management Center and navigate to System > Configuration > REST API
 Preferences and enable REST API.
- Navigate to System > Users > User Roles and create a new role with the following permissions:

- Object Manager>Modify Object Manager
- Deploy Configuration to Devices



3. Navigate to **System > Users > Users** and create a new user account with user role that you have created in the previous step.



4. Navigate to **Objects** > **Object Management** and create two object groups with the following configurations.

Name	Description	Allow Overrides
SOAR_BLOCK_IP	Object Group for IPs blocked by ArcSight SOAR.	True
SOAR_BLOCK_URL	Object Group for URLs blocked by ArcSight SOAR.	True



Note: You can use these object groups in required rules.

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor** form.

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, Cisco FMC Credential).	User you have created for SOAR on Cisco Firepower Management Center.	Password of the user that you have created for SOAR on Cisco Firepower Management Center.	

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form.

Parameter	Value			
Name	Display name of the integrati	Display name of the integration.		
Туре	Cisco Firepower Managemen	t Center.		
Address	Address of the integration (th	ne format must be https://10.10.20.40).		
Configuration	Specify the following configu	ration parameters:		
	proxy.id	ID of the Proxy integration if you access Cisco Firepower Management Center through a web proxy device. For example: proxy.id = 12345		
	network.object.group.name	Name of the object group SOAR adds IP addresses into. network.object.group.name = SOAR_BLOCK_IP		
	url.object.group.name	Name of the object group SOAR adds IP addresses into. url.object.group.name=SOAR_BLOCK_URL		
Credential	Credential that has been defined for this integration under the Credentials menu.			

Configuring SOAR Page 161 of 594

Parameter	Value
Trust Invalid SSL Certificates	Select this if web server's certificate is self-signed or is not recognized by browsers.
Require Approval From	Select user(s) from list to ask the approval before executing actions on this integration.
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.

5. Click **Show Additional Parameters** checkbox and select the frequency of policy install in **Maintenance** dropdown.



As the devices managed by Cisco Firepower Management Center might get overloaded, in case of frequent attacks or misconfiguration, thus, SOAR does not deploy the changes after every action. Instead, you can define the frequency of the deployments in Maintenance menu by either selecting pre-defined values or by defining a custom Cron expression for scheduling.

The ArcSight SOAR uses spring-framework's Cron expression format. For the format and similar example, refer to the Spring Framework-Cron Expression.

- 6. Click **Save** to save the integration definition.
- 7. Navigate to Configuration>Customization Library and edit Cisco Firepower Management Center Advanced Action Script Default Template.
- 8. Select the integration that you have added to **Integrations** menu.
- 9. Click **Save** to complete the integration.
- 10. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. Block IP

Action capability for adding an IP to given object group.

• Rollback: Yes

• Duplicate Control: No

This table presents the **Block IP** action capability details:

Capabilities Page 162 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is no-rollback	N/A	N/A	No
IP	IP address to be added to object group	Network Address	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

2. Block URL

Action capability for adding an URL to given object group.

• Rollback: Yes

• Duplicate Control: No

This table presents the **Block URL** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is no-rollback	N/A	N/A	No
URL	URL to be added to object group	URL	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

Capabilities Page 163 of 594

Integration Guide for Cisco Identity Service Engine

Integration Overview

The Cisco Identity Services Engine (ISE) offers a network-based approach for adaptable, trusted access everywhere, based on the context. It provides intelligent, integrated protection through intent-based policy and compliance solutions. This integration has been tested with Cisco Identity Services Engine 2.3.0.238 version.

Integration Capabilities

ArcSight SOAR has the following integration capability with Cisco Identity Services Engine:

Action:

Block MAC Address

Configuration

Prerequisites

Make sure to check the following prerequisites:

- Access to 443/tcpport as SOAR connects to Identity Services Engine API through HTTPS.
- An user account for SOAR to connect to Identity Services Engine

Configuring Cisco Identity Services Engine

1. Create a user account and the user must be a member of MnT Admin.

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential
- 2. Fill the Credential Editor form with following parameter values:

a. Internal Credential:

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, Cisco ISE credentials)
Username	User you have created for SOAR on Cisco Identity Services Engine
Password	Password of the user that you have created for SOAR on Cisco Identity Services Engine.
Private Key	Empty

b. Credential Store:

Parameter	Value
Туре	External Credential
Name	Name of the credential with pull path of the safe on store.

- 3. Click Configuration > Integrations > Create Integration.
- 4. Fill the configuration form with the following parameter values:

Parameter	Value	
Name	Display name of Cisco Identity Services Engine integration on SOAR	
Туре	Cisco Identity Services Engine	
Address	Address of the integration (the format must be https://192.168.2.3)	
Credential	Name of the credential set you have just created on step 2 (For example, Cisco ISE Credentials)	
Trust Invalid SSL Certificates	Select this if Firewall's certificate is self-signed or is not recognized by browsers	
Configuration	You must specify the following configuration parameters.	
	serverHost =	
Require Approval From	Select user(s) from list to ask her/his approval before executing actions on this integration	
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.	

- 5. Click **Test**. The following pop up will be displayed if your credential and address are valid.
- 6. Click **Save** to complete integration.

Configuring SOAR Page 165 of 594

Integration Guide for Cisco Ironport Email Security

Integration Overview

Cisco Ironport Email Security is one of Cisco Ironport products to prevent phishing, business email compromise, ransomeware and spam. This integration has been tested with Cisco Ironport Email Security 11.0.0-264 version.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Cisco Ironport Email Security:

- Block sender IP/Host
- Block email that includes a keyword
- Block sender email

Use Case: Stopping phishing campaigns

With this integration, SOAR can block emails based on sender, IP address or a keyword while responding to cyber-attacks. Blocking can be either performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

Make sure to check the following prerequisites:.

- Access to 22/tcp port as SOAR connects to Cisco Ironport Email Security via SSH.
- A user account for SOAR to connect to Cisco Ironport Email Security.

Configuring Cisco Ironport Email Security

1. To access the **Cisco Inroport Email Security resources**, create a user account with minimum **operator** role.

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Fill the Credential Editor form with the following parameter values:
 - a. Internal Credential:

Parameter	Value	
Туре	Internal Credential	
Name	Display name of credential set (For example, Cisco Firepower Manageme Credentials)	
Username	User you have created for SOAR on on Cisco Firepower Management Center	
Password	Password of the user that you have created for SOAR on Cisco Firepower Management Center.	
Private Key	Empty	

b. Credential Store:

Parameter	Value
Туре	External Credential
Name of the credential with pull path of the safe on store.	

- 3. Click Configuration > Integrations > Create Integration.
- 4. Fill the configuration form with the following parameter values:


Parameter	Value
Name	Display name of Cisco Ironport Email Security integration on SOAR
Туре	Cisco Ironport Email Security
Address	Address of the integration (the format must be 192.168.200.43)
Credential	Name of the credential set you have just created on step 2 (For example, Cisco Ironport Credentials)
Require Approval From	Select user(s) from list to ask her/his approval before executing actions on this integration
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.

- 5. Click **Save** to complete integration.
- 6. Click **Test** to test the integration.

Additional Notes

Configuring SOAR Page 167 of 594

- Cisco Ironport Email Security integration on SOAR is an Advanced Action Script, and you can access the content of the default script under **Configuration** > **Customization Library**.
- While defining integration for the first time, you might encounter the following warning message, which is the expected behavior for this type of integration.



Integration Guide for Cisco Umbrella

Integration Overview

Cisco Umbrella provides resolution of threats to cloud protection. Cisco paragliding provides flexible cloud protection when and how you ask for it. It combines various security features into one solution, helping you to optimize your data on incident response and rapidly improve safety across devices and locations.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Cisco Umbrella:

- Get Domain Status
- Get Security Score Information
- Get Risk Score
- Get WHOIS Domain
- Get Related Domain
- Get Co-occurrences
- Get Passive DNS Record

Prerequisites

You must have HTTPS access as ArcSight SOAR connects to Cisco Umbrella API through this service.

Configuration

Configuring Cisco Umbrella

API requires Token authentication which can be extracted from the dashboard.

- 1. Navigate to Investigate > API Keys > Create New Token.
- 2. Enter a token name and click Create.



The generated token includes the email address of the person who created it and the token creation date. To revoke the token, click the delete icon.



You can use any number of valid Investigate API access tokens to authorize and Investigate API requests.

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the Credential Editor form:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, Cisco Umbrella Credentials)	N/A	N/A	Bearer {token}

- 3. Click Configuration > Integrations > Upload plugin.
- 4. Select your integration plugin zip file and click Save.
- 5. Select the integration that you have added to the Integrations menu.
- 6. Click Save to complete the integration.
- 7. Click Test. A successful message is displayed if the credential and address are valid.

Prerequisites Page 169 of 594

Integration Capabilities

1. Get Domain Status

Enrichment capability to look up the status, and security and content category IDs for the domain.

Input Parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Domain	A domain name. For example, 'microfocus.com'.	HOST, UNKNOWN, KEYWORD	Yes	Yes

Default Parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
showLabels	Include the showLabels query parameter to display the human-readable or named category labels in the response.	Boolean	No	No

Output:

Case Scope:

N/A

Human Readable:

Key	Value
Status	safe
Security Categories	N/A
Content Categories	["Software/Technology", "Business Services", "Computers and Internet"]

2. Get Security Score Information

Enrichment capability to list multiple scores or security features of a domain Input Parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Domain	A domain name. For example, 'microfocus.com'.	HOST, UNKNOWN, KEYWORD	Yes	Yes


Output:

Case Scope:

N/A

Human Readable :

Key	Value
DGA Score	0
Perplexity	0.11194989638754399
Entropy	1.9219280948873625
Secure Rank2	0
Page Rank	0
Asn Score	0
Prefix Score	0
RIP Score	0
Popularity	100
Fastflux	false
Geo Diversity	[["US", 0.5409], ["ES", 0.0879], ["CA", 0.0519], ["GB", 0.0473], ["IN", 0.0356], ["BR", 0.0299], ["AU", 0.0212], ["MX", 0.0159], ["DE", 0.0158], ["FR", 0.0133], ["NL", 0.0126], ["JP", 0.0101], ["IT", 0.0085], ["SG", 0.006], ["DK", 0.0036], ["L", 0.0036], ["PL", 0.0035], ["HK", 0.0034], ["ID", 0.0032], ["PH", 0.0031], ["SE", 0.003], ["CN", 0.0027], ["AR", 0.0026], ["PL", 0.0026], ["ES", 0.0026], ["HV", 0.0026], ["BE", 0.0025], ["CH", 0.0024], ["SA", 0.0024], ["NO", 0.0025], ["BE", 0.0021], ["VN", 0.0019], ["AE", 0.0018], ["AT", 0.0017], ["TH", 0.0017], ["CZ", 0.0017], ["CL", 0.0017], ["KR", 0.0017], ["EG", 0.0015], ["TW", 0.0015], ["RU", 0.0015], ["TW", 0.0015], ["RO", 0.0015], ["RO", 0.0016], ["RO", 0.0006], ["SE", 0.0016], ["RO", 0.0006], ["SE", 0.0006], ["SE", 0.0006], ["PR", 0.0006], ["PR", 0.0006], ["PR", 0.0006], ["TR", 0.0006],



TLD Geo Diversity	N/A
Geo Score	0
KS Test	0
Attack	N/A
Threat Type	N/A
Found	true
Found	true

3. Get Risk Score

Enrichment capability to get the risk score for a domain. The risk score is scaled from 0 to 100, with 100 being the highest risk and 0 being no risk at all.

Input Parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Domain	A domain name. For example, 'microfocus.com'.	HOST, UNKNOWN, KEYWORD	Yes	Yes

Output:

Case Scope:

Action	Туре	Category / Value
Domain	Scope Item Property	Cisco Umbrella Risk Score

Human Readable Output:



4. Get WHOIS Domain

Enrichment capability to fetch WHOIS information for the specified domain Input Parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Domain	A domain name without wildcard and including top-level domain (TLD)	HOST, UNKNOWN, KEYWORD	Yes	Yes

Output:

Case Scope:

N/A

Key	Value
Whois Servers	whois.markmonitor.com
Addresses	["170 w. tasman dr."]
Administrative Contact Name	Domain Administrator
Administrative Contact Email	infosec@cisco.com
Technical Contact Email	infosec@cisco.com
Technical Contact Fax	14085264575
Name Servers	["ns1.cisco.com", "ns2.cisco.com", "ns3.cisco.com"]
Administrative Contact City	San Jose
Registrant Name	MarkMonitor, Inc.
Domain Name	cisco.com
Technical Contact Country	UNITED STATES
RegistrarIANAID	292
Updated	2022-04-13
Status	["clientDeleteProhibited clientTransferProhibited clientUpdateProhibited serverDeleteProhibited serverTransferProhibited serverUpdateProhibited"]
Registrar Name	MarkMonitor, Inc.
Technical Contact Organization	Cisco Technology Inc.
Emails	["infosec@cisco.com"]
Audit Updated Date	2023-03-06 00:19:37 UTC
Record Expired	false

5. Get Related Domain

Enrichment capability to get a list of domain names that have been frequently requested around the same time (up to 60 seconds before or after) as the given domain name, but that are not frequently associated with other domain names.

Input Parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Domain	A domain name. For example, 'microfocus.com'.	HOST, UNKNOWN, KEYWORD	Yes	Yes

Output:

Case Scope:

N/A

Domain	Number Of Client Ip Requests
site.com	447
google.com	375
sfdcopens.com	328
salesforcescrt.com	285
trailblazer.me	248
salesforce-sitesa.com	247
yahoo.com	239
salesforce.com	224
meraki.com	223
sdfc.sh	219
salesforce-scrt.com	202
trailhead.com	187
salesforce-hub.com	131

6. Get Co-occurrences

Enrichment capability to list the co-occurrences for the specified domain. Input Parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Domain	A domain name. For example. 'cisco.com'	HOST, UNKNOWN, KEYWORD	Yes	Yes

Output:

Case Scope:

N/A

Domain	Value
visuaforce.com	0.1395325916662083
trailhead.com	0.12338393401066777
sdlc.sh	0.0940698919293961
stdcopens.com	0.085611988091635
site.com	0.0765182794794976
salesforce-sitesa.com	0.07137240765308193
salesforce-scrt.com	0.06680765715826874
salesforce-hub.com	0.0674292465481571
salesforce-experience.com	0.05971431124816412
salesforce-communities.com	0.05116082433262011
salesforcescrt.com	0.03937267908814215
salesforce.com	0.02866262043139404
lightning.com	0.027756049323472236
force-user-content.com	0.019588843799334343
forceusercontent.com	0.016911967447479512
traiblezer.me	0.012054556521978586

7. Get Passive DNS Record

Enrichment capability returns the Resource Record (RR) data for DNS responses, and categorization data, where the answer (or data) is the domain(s).

Input Parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Domain	A domain name. For example, 'cisco.com'.	HOST, UNKNOWN, KEYWORD	Yes	Yes

Query Parameters:


Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
limit	The number of records to return in the collection. The default limit is 500 records. The maximum number of records returned for all requests to the endpoint is 10,000.	integer	No	Yes
offset	A number that represents an index into the collection. By default, the offset is 0 (the first record).	integer	No	No
sortorder	Sort records by ascending (asc) or descending (desc) order. By default, the records are returned in descending order.	string	No	No
sortby	Sort records by one of the following fields: minTtl, maxTtl, firstSeen, or lastSeen.	string	No	No
recordType	The type of records. For example: 'A', 'CNAME', 'NS', 'MX'. Use commas to separate multiple types of record.	string	No	No
includefeatures	Specify 'true' to add feature sections to the response. The default value is 'false'.	boolean	No	No
minFirstSeen	Returns only records with firstSeen >= minFirstSeen.	integer	No	No
maxFirstSeen	Returns only records with firstSeen <= maxFirstSeen.	integer	No	No
minLastSeen	Returns only records with lastSeen >= minLastSeen.	integer	No	No

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
maxLastSeen	Returns only records with lastSeen <= maxLastSeen.	integer	No	No
sortCategories	Comma-separated list of security categories or 'All'. 'All' stands for all security categories. Records which have at least one of these security categories will be first in the ordering. The rest of the sorting parameters are applied within the records with and without any of the security categories.	string	No	No
requiredCategories	Filter for records with security categories. The case-sensitive security category strings are Drive-by Downloads/Exploits, Mobile Threats, Dynamic DNS, High Risk Sites and Locations, Command and Control, Malware, Phishing, Newly Seen Domains, Potentially Harmful, DNS Tunneling VPN, and Cryptomining. Use commas to separate multiple security category strings.	string	No	No

Output:

Case Scope:

N/A



Integration Guide for CrowdStrike Falcon

Integration Overview

CrowdStrike is a cloud based cybersecurity tool that allows organizations to leverage its lightweight agent. The agent is an all-encompassing EDR and antivirus software.

Integration Capabilities

- Isolate Machine
- Unisolate Machine
- Add Comment to Detection
- Update Detection Status
- Assign Detection
- · Get IOC Details
- Get Hosts by IOC
- Get Process by IOC

- List Host Vulnerabilities
- Get Host Details

Prerequisites

- ArcSight SOAR connects to https://falcon.crowdstrike.com/login/ APIs through HTTPS.
 Access to this service is required.
- CrowdStrike requires an API key for access.

Configuration

Configuring CrowdStrike

- CrowdStrike requires a Client ID and Client secret for access.
- Users with the Falcon Administrator role can create a Client ID and Client secret from https://falcon.crowdstrike.com/ after logging in with valid credentials.

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the Credential Editor:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, CrowdStrike Falcon).	Empty	Client ID created on CrowdStrike Falcon	Client Secret for the Client ID created on CrowdStrike Falcon

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the Configuration Form:

Parameter	Value
Name	Display name of the integration
Туре	Advanced Scriptable Device
Address	Address of the integration (the format should be https://api.crowdstrike.com/)

Prerequisites Page 179 of 594

Parameter	Value		
Configuratio n	Specify the following configuration parameters:		
	Specify the following configuration parameters: # Integration ID of the proxy integration to use when connecting to current integration. # If not provided, ArcSight SOAR will try to use a direct connection. #proxy.id=123 # Maximum number of results to return from the API # If not provided, the integration will gather all results #max.result.count = 100		
Credential	Credential that has been defined for this integration under Credential menu.		
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or not recognized by browsers. Not selected.		
Require Approval From	Select user(s) from the list to ask their approval before executing enrichments on this integration.		
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.		

- 5. Select the integration that you have added in the Integrations menu.
- 6. Click **Save** to complete the integration.
- 7. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. Isolate Machine

Action capability for isolating a machine.

• Rollback: Yes

• Duplicate Control: Yes

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Host	Network address, hostname or agent ID of the machine.	Network Address Computer Name Keyword Unknown	Yes	Yes

Output:

Case Scope

N/A

Human Readable Output

Capabilities Page 180 of 594

N/A

2. Unisolate Machine

Action capability to unisolate a machine.

• Rollback: Yes

• Duplicate Control: Yes

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Host	Network address, hostname or agent ID of the machine.	Network Address Computer Name Keyword Unknown	Yes	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

3. Add Comment to Detection

Action capability for adding a comment to a detection.

Rollback: No

• Duplicate Control: No

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Detection ID	CrowdStrike Detection ID.	Unknown	Yes	Yes
Comment	Comment added to the detection.	String	No	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

4. Update Detection Status

Action capability for updating detection status.

• Rollback: No

Capabilities Page 181 of 594

• Duplicate Control: No

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Detection ID	CrowdStrike Detection ID.	Unknown	Yes	Yes
Status	Status from the following drop down menu options: New, In Progress, Closed, True Positive, False Positive, Ignored.	String	No	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

5. Assign Detection

Action capability for assigning a detection to a user.

• Rollback: No

• Duplicate Control: No

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required(Yes/No)
Detection ID	CrowdStrike Detection ID.	Unknown	Yes	Yes
Email Address	User email	String	No	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

6. Get IOC Details

Enrichment capability used to get the details of an IOC.

Capabilities Page 182 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the 3rd party integration.	Integration	N/A	Yes
IOC	SHA256 or MD5 hash value, network address or domain.	Hash Network Address Host URL	Yes	Yes
Do not Use Cache	SOAR does not use cached results if this box is checked.	Boolean	N/A	No

Output:

Case Scope

Action	Туре	Category/Value
Set	Scope Item Property	CrowdStrike Severity

Human Readable Output

N/A

7. Get Hosts by IOC

Enrichment capability used to retrieve hosts where the IOC has been observed.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the 3rd party integration.	Integration	N/A	Yes
IOC	SHA256 or MD5 hash value, network address or domain.	Hash Network Address Host URL	Yes	Yes
Do not Use Cache	SOAR does not use cached results if this box is checked.	Boolean	N/A	No

Output:

Case Scope

Action	Туре	Category/Value
Set	Scope Item/Related	Hostname (Computer Name)

Human Readable Output

N/A

Capabilities Page 183 of 594

8. Get Process by IOC

Enrichment capability used to retrieve the process name of the IOC on the devices where the IOC has triggered a detection.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the 3rd party integration.	Integration	N/A	Yes
Hash	SHA256 or MD5 hash value, network address or domain.	Hash	Yes	Yes
Host	Network address, hostname or agent ID of the machine.	Network Address Computer Name Keyword Unknown	Yes	No
Do not Use Cache	SOAR does not use cached results if this box is checked.	Boolean	N/A	No

Output:

Case Scope

Action	Туре	Category/Value
Set	Scope Item Property	CrowdStrike Process Name

Human Readable Output

N/A

9. List Host Vulnerabilities

Enrichment capability used to list the vulnerabilities on a host.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the 3rd party integration.	Integration	N/A	Yes
Status	Status from the following options: All, Open, Closed, Reopen, Expired	String	No	Yes

Capabilities Page 184 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Host	Network address, hostname or agent ID of the machine.	Network Address Computer Name Keyword Unknown	Yes	No
Do not Use Cache	SOAR does not use cached results if this box is checked.	Boolean	N/A	No

Output:

Case Scope

Action	Туре	Category/Value
None	None	None

Human Readable Output

N/A

10. Get Host Details

Enrchment capability used to get the details of a host.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the 3rd party integration.	Integration	N/A	Yes
Host	Network address, hostname or agent ID of the machine.	Network Address Computer Name Keyword Unknown	Yes	No
Do not use cache	SOAR does not use cached results if this box is checked.	Boolean	N/A	No

Output:

Case Scope

Action	Туре	Category/Value
Set	Scope Item/Related	Hostname (Computer Name)

Human Readable Output

N/A

Capabilities Page 185 of 594

Integration Guide for Cyberark Central Credential Provider

Integration Overview

CyberArk Application Identity Manager is a central credential provider that stores passwords and other credentials used by systems, applications, and scripts by eliminating embedded credentials. SOAR might use encrypted credentials stored on its database and CyberArk AIM vault to connect to other systems and applications while investigating and responding to an incident.

Configuration

Prerequisites

- Make sure to check the access to CyberArk Application Identity Manager API as SOAR connects to it through HTTPS.
- Define a new application for SOAR on CyberArk's PVWA (Password Vault Web Access)
 Interface.

Configuring CyberArk Application Identity Manager

- Log in to Password Vault Web Access interface as a user with Manage Users authorization permission.
- 2. Navigate to Applications and click Add Application.
- 3. Fill the Add Application form with the following parameter values:

Parameter	Value	
Name	Specify SOAR as the unique name (ID) of the application.	
Description	Specify a short description of the application (For example, Application for Automated Threat Analysis&Response)	
Business Owner	Specify contact information about the application's Business owner	
Location	Specify the location of the application in the Vault hierarchy. Note: If the location is not selected, the application gets added to the user location who creates it.	

- 4. To specify unlimited number of machines and Windows OS users for a single application, select **Allow extended authentication restrictions**.
- 5. Navigate to Allowed Machines and specify the application's Allowed Machines.



Note: This information enables the Credential Provider to check only applications that run from specified machines can access their passwords.

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Fill the **Credential Editor** form with the following parameter values:
 - a. Internal Credential:

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, CyberArk AIM Credential)
Username	Application Name you have created on CyberArk Password Vault Web Access
Password	Empty
Private Key	Empty

- 3. Click Configurations > Integrations > Create Integration.
- 4. Fill the Configuration form with the following details:

Parameter	Value
Name	Display name of CyberArk AIM integration on SOAR
Туре	CyberArk Central Credential Provider
Address	Address of the integration (the format must be https://192.168.1.1:1234 or https://abc.example.com:1234)
Credential	Name of the credential set you have just created on step 2 (For example, CyberArk AIM Credential).
Trust Invalid SSL Certificates	Select this if device's certificate is self-signed or is not recognized by browsers
Require Approval From	Select user(s) from list to ask her/his approval before executing actions on this integration
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration

5. Click **Save** to complete integration.

Configuring SOAR Page 187 of 594

6. Click **Test** to test the integration.

Additional Notes

Following are the steps to use CyberArk AIM as central credential store:

- 1. Navigate to Configuration > Parameters.
- 2. Modify the ExternalCredentialStoreIntegrationID parameter value to ID of the CyberArk AIM integration that you have defined in the above procedure.
- 3. To define the new name for a credential:
 - a. Navigate to Configuration > Credentials.
 - b. Select External Credential from the drop down and it automatically uses CyberArk AIM integration.



Note: The name of the credential must be the same as the account name defined in CyberArk. Make sure to follow the naming convention of SOAR as Safe and Folder separated by | character. Else, SOAR automatically searches all Safes for the given credential name.

Additional Notes Page 188 of 594

Integration Guide for CYMRU Malware Hash Registry Query

Integration Overview

CYMRU is a look-up service that checks if the hash code is malware. If the hashcode belongs to malware, then the latest timestamp of the malware and the rough antivirus package detection rate is returned. ArcSight SOAR uses CYMRU Malware Hash Registry Query to query computed MD5 or SHA-1 hash of a file to check for malware.

Integration Capabilities

Action

Hash registry query

Configuration

Configuring CYMRU Malware Hash Registry Query


1. Make sure SOAR has access to CYMRU Malware Hash Registry Query integration's API as it connects to it through HTTPS.

Configuring SOAR

- 1. To create the integration, navigate to Configuration > Integrations.
- 2. Specify the following parameter values in the Integrations Editor:

Parameter	Value
Name	Display name of the integration
Туре	CYMRU malware hash registry query
Address	Address of the integration (in the following format http[s]://malware.cymru.hash.com)

Parameter	Value
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or is not recognized by browsers.
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an action on this integration.



- 3. Click **Test** to test the integration.
- 4. Click **Save** to complete the integration.

CyberRes Galaxy Threat Acclerator

Integration Overview

CyberRes Galaxy Threat Accelerator Program (GTAP) Plus is a Threat Intelligence feed, available as a subscription service from Micro Focus CyberRes. Please talk to your Sales Representative to request a 60-day evaluation license or purchase an annual subscription. The license key provided will be the MISP API key that will be used in the CyberRes Galaxy Threat Accelerator (GTAP) Plus integration.

Integration Capabilities

- Domain Reputation
- File Reputation
- IP Reputation
- URL Reputation

Prerequisites

ArcSight SOAR connects to "https://threatfeed.cyberres.com" APIs through HTTPS. Access to this service is required.

Configuring CyberRes Galaxy Threat Accelerator

You need to get the API key from CyberRes.

Configuring SOAR

- 1. Click Configuration > Integration > Upload Plugin and upload the plugin zip file.
- 2. Edit the configuration to modify the name in the Configuration Form.
- 3. Click Configuration > Credentials and edit the credential.

Туре	Internal credential
Name	Display name of credential set (i.e CyberRes Galaxy Threat Accelerator Credentials)
Username	Empty
Password	Empty
Private Key	API key

4. Click **Configuration > Scope Item Property** and Create 2 new scope item property definitions with the following properties:

Property Visible Name	Data Type
CyberRes Galaxy Domain Reputation	TEXT
CyberRes Galaxy File Reputation	TEXT
CyberRes GalaxyIP Reputation	TEXT
CyberRes Galaxy URL Reputation	TEXT

Capabilities

1. Domain Reputation

Enrichment capability for retrieving details of domain reputation.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Domain	Domain to be queried from CyberRes Galaxy Threat Accelerator	Host	Yes	Yes
Do not use cache	SOAR does not use cached results if this box is checked.	Boolean	N/A	No

Output:

Case Scope

Action	Туре	Category/value
Set	Scope Item Property	CyberRes Galaxy Domain Reputation

Human Readable Output

2. File Reputation

Enrichment capability for retrieving details of file hash and reputation.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Hash	Hash to be queried from CyberRes Galaxy Threat Accelerator	Host	Yes	Yes
Do not use cache	SOAR does not use cached results if this box is checked.	Boolean	N/A	No

Output:

Case Scope:

Action	Туре	Category/value
Set	Scope Item Property	CyberRes Galaxy File Reputation

Human Readable Output

Capabilities Page 192 of 594

3. IP Reputation

Enrichment capability for retrieving IP Address details and reputation.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
IP Address	IP Address to be queried from CyberRes Galaxy Threat Accelerator	Network Address	Yes	Yes
Do not use cache	SOAR does not use cached results if this box is checked.	Boolean	N/A	No

Output:

Case Scope

Action	Туре	Category/value
Set	Scope Item Property	CyberRes Galaxy IP Reputation

Human Readable Output

4. URL Reputation

Enrichment capability for retrieving URL details and reputation.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
URL	URL to be queried from CyberRes Galaxy Threat Accelerator	URL	Yes	Yes
Do not use cache	SOAR does not use cached results if this box is checked.	Boolean	N/A	No

Output:

Case Scope

Action	Туре	Category/value
Set	Scope Item Property	CyberRes Galaxy URL Reputation

Human Readable Output

Capabilities Page 193 of 594

Integration Guide for CyThreat Threat Intelligence

Integration Overview

CyThreat provides cyber threat intelligence data. These data feeds are enriched with subject and event-based reports as compiled by STM analysts.

CyThreat collects data from various open and commercial sources (deep/dark web, social media, blogs, forums, etc.) automatically. This allows the detection of the activities of the threat actors, proactive prevention of cyber-attacks before they occur and also allows applications to take preventive measures.

SOAR can seek benefit from CyThreat intelligence from both Integration and as Alert Source.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with CyThreat Threat Intelligence:

- Domain Query
- Hash Query
- IP Query

Alert Source Capability

ArcSight SOAR has the following alert source capability with CyThreat Threat Intelligence:

Consume Threat Intelligence feeds from CyThreat(default)

Prerequisites

- You must have access to HTTPS as the ArcSight SOAR connects to CyThreat API through this service.
- API token and password to connect to CyThreat Threat Intelligence API.

Configuration

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameters in the **Credential Editor** form:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, CyThreat Credentials).	Empty	API password that you have received from CyThreat service.	API token that you have received from the CyThreat service.

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the Configuration Form.

Parameter	Value		
Name	Display name of the CyThreart integration.		
Туре	CyThreat		
Address	Address of the integration (the format should be https://cti.stm.com.tr).		
Configuration	Specify the following configuration parameters:		
	proxy.id ID of the Proxy integration if you access https://cti.stm.com.tr through a web proxy device. For example: proxy.id = 12345		
Credential	Credential that has been defined for this integration under the Credentials menu.		
Trust Invalid SSL Certificates	Select this if web server's certificate is self-signed or is not recognized by browsers. The SSL certificate of CyThreat service is going to known by SOAR, so you do not need to check this box.		
Require Approval From	Select user(s) from list to ask the approval before executing actions on this integration.		
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.		

- 5. Click **Save** to save the integration definition.
- 6. Navigate to Configuration>Customization Library and edit CyThreat Advanced Action Script Default Script Template.
- 7. Select the integration that you have added to Integrations menu.
- 8. Click **Save** to complete the integration.

Configuration Page 195 of 594



Note: Steps 7-9 are required only for Advanced Action Script Default Templates.

- 9. Navigate to Configuration > Integrations > CyThreat integration.
- 10. Click **Test**. **Integration Successful** message is displayed if the credential and address are valid.

Configuring CyThreat as an Alert Source

- 1. Navigate to Configuration > Alert Source > Create Alert Source Configuration.
- 2. Select CyThreat Threat Intelligence and specify the following parameters in the Alert Source Configuration Editor:

Parameter	Value
Name	Display name of the CyThreart alert source.
Туре	CyThreat Threat Intelligence
Address	https://cti.stm.com.tr/api/
Alert Severities	Arrangement table of severity mapping.
enable.ip.risk.source	Uncomment and change to true to consume IP Source.
enable.domain.risk.source	Uncomment and change to true to consume Domain Source.
enable.hash.risk.source	Uncomment and change to true to consume Hash Source.
enable.usom.blacklist.source	Uncomment and change to true to consume Usom Blacklist Source.
ip.min.risk	SOAR is not going to create case if risk level of the incoming alarm is below of the value.
domain.min.risk	SOAR is not going to create case if risk level of the incoming alarm is below of the value.
hash.min.risk	SOAR is not going to create case if risk level of the incoming alarm is below of the value.
proxy.id	ID of the Proxy integration if you access https://cti.stm.com.tr through a web proxy device. For Example: proxy.id = 12345.
days.to.look.back.at.initial.sync	How far (in days) into the past SOAR will look for remote incidents at the initial sync task.
Credential	Name of the credential set created on step 2 Configuring SOAR part (For example, CyThreat Credentials).
Visible Alert Fields	Field names from the alert if you want to show them on case.
Trust Invalid SSL Certificates	The SSL certificate of CyThreat service is going to known by SOAR, so you do not need to check this box.

- 3. Click **Test**. The **Alert Source tested successfully** message is displayed if your credentials are valid
- 4. Click Save.

Integration Capabilities

1. Domain Query

Enrichment capability for retrieving domain information.

The following table presents the **Domain Query** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Domain	Domain that you want to query.	Host	Yes	No

Output:

Case Scope: N/A

Human Readable Output: Yes

2. Hash Query

Enrichment capability for retrieving hash information.

The following table presents the **Hash Query** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Hash	Hash value that you want to query.	Hash	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: Yes

3. IP Query

Enrichment capability for retrieving domain information.

The following table presents the **IP Query** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
IP	Ip that you want to query.	Host	Network Address	Yes

Output:

Case Scope: N/A

Human Readable Output: Yes

Integration Guide for DomainTools

Integration Overview

DomainTools is a leading provider of Whois and other DNS profile data for threat intelligence enrichment. It is a part of Datacenter Group (DCL and SA). DomainTools data helps security analysts investigate malicious activity on their networks.

Integration Capabilities

- Get Domain Profile
- Get Domain Reputation
- Get Domain Risk
- Domain Hosting History
- Recent Domain
- Reverse IP Lookup
- Reverse IP Whois
- Whois Lookup
- Iris Investigate

Configuration

Configuring DomainTools

 You must have access to HTTPS as the ArcSight SOAR connects to DomainTools API through this service.

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the Credential Editor:

Туре	Name	Username	Password	Private Key
Internal Credential	Display name of credential set (for example, DomainTools Credentials)	Valid API username	Valid API Key to authenticate the DomainTools APIs	N/A

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the Configuration Form:

Parameter	Value			
Name	Display name of the	Display name of the integration		
Туре	DomainTools			
Address	Address of the integr	ration (https://api.domaintools.com)		
Configuration	Specify the following configuration parameter values:			
	ID of the Proxy integration if you access DomainTools through a web proxy device. For example, proxy.id = 12345			
Credential	Credential that has b	een defined for this integration under the Credential menu		
Trust Invalid SSL Certificates	Select this option if the web server's certificate is self-signed or if it is not recognized by browsers			
Require Approval From	Select user(s) from list who can provide approval before executing actions on this integration			
Notify	Select user(s) from the on this integration	he list who can provide approval when SOAR performs an action		

Configuration Page 199 of 594

- 5. Click **Save** to save the integration definition.
- 6. Navigate to Configuration > Customization Library and edit DomainTools Advanced Action Script Default Template.
- 7. Select the integration that you have added to Integrations menu.
- 8. Click **Save** to complete the integration
- 9. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. Get Domain Profile

Enrichment capability for retrieving the basic domain name registration details and a preview of additional data available from DomainTools membership and report products.

Input Parameter	Description	Туре	Scope Restricted(Yes/No)	Required (Yes/No)
Integration	Name of the third-party integration	Integration	N/A	Yes
Domain	Domain name to be queried	HOST UNKNOWN KEYWORD	Yes	Yes

Output:

Case Scope

N/A

Human Readable Output:

Capabilities Page 200 of 594

Key	Value
Registrant Name	REDACTED FOR PRIVACY
Registrant Domains	36356545
Registrant Product Url	https://reversewhois.domaintools.com/?all(]=REDACTED+FOR+PRIVACY&none()=
Server IP Address	141.193.213.20
Server Other Domains	41968
Server Product Url	https://reverseip.domaintools.com/search/?q=domaintools.com
Registration Created	1998-08-02
Registration Expires	2027-08-01
Registration Updated	2020-01-09
Registration Registrar	eNom, LLC
Registration Statuses	["clientTransferProhibited"]
Name Servers	["Server: DNS1.P04.NSONE.NET, Product URL: https://reversens.domaintools.com/search/? q=DNS1.P04.NSONE.NET", "Server: DNS2.P04.NSONE.NET, Product URL: https://reversens.domaintools.com/search/?q=DNS2.P04.NSONE.NET", "Server: DNS3.P04.NSONE.NET, Product URL: https://reversens.domaintools.com/search/? q=DNS3.P04.NSONE.NET", "Server: DNS4.P04.NSONE.NET, Product URL: https://reversens.domaintools.com/search/?q=DNS4.P04.NSONE.NET"]
History	["Registrar - Earliest_Event: 2002-04-12, Events: 4, Product_URL: https://research.domaintools.com/", "IP Address - Events: 91, Years: 11, Product_URL: https://research.domaintools.com/", "IP Address - Events: 91, Years: 11, Product_URL: https://research.domaintools.com/", "Name Server - Events: 7, Years: 18, Product_URL: https://research.domaintools.com/", "Name Server - Events: 7, Years: 18, Product_URL: https://research.domaintools.com/", "Whois - Records: 6139, Earliest_Event: 2001-10-26, Product_URL: https://research.domaintools.com/"]
SEO Score	NA
SEO Product Url	https://research.domaintools.com/seo-browser/?domain=domaintools.com
Website Response Code	NA
Website Title	N/A
Website Server	N/A
Website Meta	NA
Website Product Url	https://whois.domaintools.com/domaintools.com

2. Get Domain Reputation

Enrichment capability for retrieving domain details and reputation.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third-party integration	Integration	N/A	Yes
Domain	Domain name to be queried for which the risk score is desired	HOST, UNKNOWN, KEYWORD	Yes	Yes


Output:

Case Scope:

Capabilities Page 201 of 594

Action	Туре	Category/Value
Set	Scope item Property	Risk Score

Human Readable Output:



3. Get Domain Risk

Enrichment capability for deeper investigation of individual domains and to retrieve the risk score.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third-party integration	Integration	N/A	Yes
Domain	Domain name to be queried for which the risk score is desired	HOST, UNKNOWN, KEYWORD	Yes	Yes

Output:

Case Scope

Action	Туре	Category/Value
Set	Scope item Property	Risk Score

Human Readable Output:



4. Domain Hosting History

Enrichment capability for retrieving a list of changes that have occurred in a Domain Name's registrar, IP address, and name servers. IP and name server's events include the value before and after the change and indicate the type of action that triggered the event.

Capabilities Page 202 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third-party integration	Integration	N/A	Yes
Domain	Domain name to be queried to get hosting history	HOST, UNKNOWN, KEYWORD	Yes	Yes

Output:

Case Scope

N/A

Human Readable Output:

Date	Туре	Action	Details
2002-10-03	Registrar	N/A	Registrar: Alldomains, Registrar Tag: Alldomains
2006-04-10	Registrar	N/A	Registrar: MarkMonitor, Registrar Tag: eMarkMonitor
2004-04-24	IP	New	Previous: N/A, New: 216.239.57.99
2004-05-08	IP	Change	Previous: 216.239.57.99, New: 66.102.7.99
2004-05-15	IP	Change	Previous: 66.102.7.99, New: 216.239.57.99
2004-05-22	IP	Change	Previous: 216.239.57.99, New: 216.239.51.99
2004-05-29	IP	Change	Previous: 216.239.51.99, New: 216.239.53.99
2004-06-19	IP	Change	Previous: 216.239.53.99, New: 216.239.57.99
2004-07-17	IP	Change	Previous: 216.239.57.99, New: 66.102.7.99
2004-07-24	IP	Change	Previous: 66.102.7.99, New: 216.239.57.99
2004-08-29	IP	Change	Previous: 216.239.57.99, New: 66.102.7.99

5. Recent Domain

Enrichment capability to search for domain names that match your specific search string. Unlike Domain suggestions, Domain Search finds currently registered or previously registered domain names that are either currently registered or have been registered in the past under one of the major gTLDs (.com, .net, .org, .info, .us, or .biz) many countries code TLDs, or the new gTLDs.

Capabilities Page 203 of 594


Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third-party integration	Integration	N/A	Yes
Query	Query string for the search	Host Unkown Keyword	Yes	Yes

Output:

Case Scope

N/A

Human Readable Output:



6. Reverse IP Lookup

Enrichment capability to retrieve a list of domain names that share the same Internet host (I.e., the same IP address).

Capabilities Page 204 of 594



The users can request an IP address or a domain name. It is recommended to provide a domain name, and if a domain name is provided the system would return a list of all domains that share the same IP address.


Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third-party integration	Integration	N/A	Yes
Domain	Domain name to be queried for which the risk score is desired	HOST UNKNOWN KEYWORD	Yes	Yes

Output:

Case Scope

N/A

Human Readable Output:



7. Reverse IP Whois

Enrichment capability to retrieve a list of IP ranges that are owned by an organization.

Capabilities Page 205 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third-party integration	Integration	N/A	Yes
Query	Name of the organization to be queried	String	Yes	Yes

Output:

Case Scope

N/A

Human Readable Output:

Range	Record Ip	Record Date	Organization	Country	Server
199.30.228.0/22	199.30.228.13	2022-11-16	DomainTools, LLC	US	whois.arin.net
64.246.187.40/30	64.246.187.40	2022-10-13	DomainTools, LLC	US	whois.arin.net
64.246.165.48/30	64.246.165.50	2022-11-10	DomainTools, LLC	US	whois.arin.net
66.249.16.0/23	66.249.16.0	2022-10-05	Name Intelligence, Inc.	US	whois.arin.net
216.145.14.140/30	216.145.14.140	2022-10-08	DomainTools, LLC	US	whois.arin.net
64.246.165.8/30	64.246.165.8	2022-10-15	DomainTools, LLC	US	whois.arin.net
67.135.38.72/29	67.135.38.72	2022-10-12	DomainTools, LLC	US	whois.arin.net
63.150.103.144/29	63.150.103.147	2022-10-26	DomainTools, LLC	US	whois.arin.net

8. Whois Lookup

Enrichment capability to retrieve the ownership record for a domain name or IP address with basic registration details.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third-party integration	Integration	N/A	Yes
Domain	Domain name to be queried.	HOST UNKNOWN KEYWORD	Yes	Yes

Output:

Case Scope

N/A

Human Readable Output:

Capabilities Page 206 of 594

Кеу	Value
Registrant	REDACTED FOR PRIVACY
Registration Created	1998-08-02
Registration Expires	2027-08-01
Registration Updated	2020-01-09
Registration Registrar	eNom, LLC
Registration Statues	["clientTransferProhibited"]
Name Servers	["DNS1.P04.NSONE.NET", "DNS2.P04.NSONE.NET", "DNS3.P04.NSONE.NET", "DNS4.P04.NSONE.NET"]
Whois Date	2022-11-16
Whois Record	Domain Name: domaintools.com Registry Domain ID: 1697312_DOMAIN_COM-VRSN Registrar WHOIS Server: WHOIS.ENOM.COM Registrar URL: WWW.ENOM.COM Updated Date: 2020-01-09723-06-29-002 Creation Date: 1998-08-02704-00-000.002 Registrar Registration Expiration Date: 2027-08-01704-00-000.002 Registrar: ENOM, INC. Registrar IANA ID: 48 Domain Status: clientTransferProhibited https://www.icann.org/eppitclientTransferProhibited Registrant Name: REDACTED FOR PRIVACY Registrant Organization: REDACTED FOR PRIVACY Registrant Street: REDACTED FOR PRIVACY Registrant Street: Registrant Ctry. REDACTED FOR PRIVACY Registrant Country: US Registrant Phone: REDACTED FOR PRIVACY Registrant Fax: REDACTED FOR PRIVACY Registrant Email: https://lieredaccess.com/contact/e4e03487-86e0- 4e34-bc3d-723c615024e9 Admin Name: REDACTED FOR PRIVACY Admin Organization: REDACTED FOR PRIVACY Admin Street: REDACTED FOR PRIVACY Admin Street: Admin City: REDACTED FOR PRIVACY Admin Street: REDACTED FOR PRIVACY Admin Street: Admin Postal Code: REDACTED FOR PRIVACY Admin Extent Province: REDACTED FOR PRIVACY Admin Pone: REDACTED FOR PRIVACY Admin Prone Ext. Admin Fax: REDACTED FOR PRIVACY Admin Pone: REDACTED FOR PRIVACY Admin Prone Ext. Admin Fax: REDACTED FOR PRIVACY Admin Email: REDACTED FOR PRIVACY Tech Name: REDACTED FOR PRIVACY Tech Organization: REDACTED FOR PRIVACY Tech Street: REDACTED FOR PRIVACY Tech Street: Tech City: REDACTED FOR PRIVACY Tech Street: REDACTED FOR PRIVACY Tech Phone: REDACTED FOR PRIVACY Tech Street: REDACTED FOR PRIVACY Tech Phone: REDACTED FOR PRIVACY Tech Street: REDACTED FOR PRIVACY Tech Phone: REDACTED FOR PRIVACY Tech Street: REDACTED FOR PRIVACY Tech Postal Code: REDACTED FOR PRIVACY Tech Street: REDACTED FOR PRIVACY Tech Postal Code: REDACTED FOR PRIVACY Tech Street: REDACTED FOR PRIVACY Tech Postal Code: REDACTED FOR PRIVACY Tech Street: REDACTED FOR PRIVACY Tech Postal Code: REDACTED FOR PRIVACY Tech Street: REDACTED FOR PRIVACY Tech Postal REDACTED FOR PRIVACY Tech Prone Ext. Tech Fax: REDACTED FOR PRIVACY Tech Postal R
Record Source	domaintools.com

9. Iris Investigate

Enrichment capability is ideally suited for investigating and orchestrating use cases at a human scale.

These are typically triggered on-demand by an analyst seeking additional context on a single indicator, with the best result available for investigations.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third-party integration	Integration	N/A	Yes
Domain	Domain name to be queried.	HOST UNKNOWN KEYWORD	Yes	Yes

Output:

Case Scope

N/A

Capabilities Page 207 of 594

Human Readable Output:

Key	Value
Domain	domaintoels.com
Domain Risk	["zerolist: 0", "OverAll Risk Score: 0"]
Whois Url	https://whois.domaintools.com/domaintools.com
Adsense	N/A
Alexa	3954
Popularity Rank	3763
Active	true
Google Analytics	N/A
Admin Contact	country: REDACTED FOR PRIVACY, org: REDACTED FOR PRIVACY, org: REDACTED FOR PRIVACY, phone: N/A, street: REDACTED FOR PRIVACY, name: REDACTED FOR PRIVACY, state: REDACTED FOR PRIVACY, postal: REDACTED FOR PRIVACY, fax: N/A, email: N/A
Billing Contact	country: N/A, org: N/A, city: N/A, phone: N/A, street: N/A, name: N/A, state: N/A, postal: N/A, fax: N/A, email: N/A
Registrant Contact	country: us, org: REDACTED FOR PRIVACY, city: REDACTED FOR PRIVACY, phone: N/A, street: REDACTED FOR PRIVACY, name: REDACTED FOR PRIVACY, state: WA, postal: REDACTED FOR PRIVACY, fax: N/A, email: N/A
Technical Contact	country: REDACTED FOR PRIVACY, org: REDACTED FOR PRIVACY, org: REDACTED FOR PRIVACY, phone: N/A, street: REDACTED FOR PRIVACY, name: REDACTED FOR PRIVACY, state: REDACTED FOR PRIVACY, postal: REDACTED FOR PRIVACY, fax: N/A, email: N/A
Create Date	1998-08-02
Expiration Date	2027-08-01
Email Domain	["nsone.net", "enom.com"]
SOA Email	["hostmaster@nsone.net"]
SSL EMAIL	NA
Additional Whois Email	["abuse@enom.com"]
IP	["address: 141.193.213.21, isp: WPEngine Inc., country_code: us, asn: [209242]", "address: 141.193.213.20, isp: WPEngine Inc., country_code: us, asn: [209242]"]

Capabilities Page 208 of 594

Integration Guide for DNS Service

Integration Overview

DNS Server is used to resolve and translate the IP addresses, host names and queries to various DNS records.

Integration Capabilities

SOAR has the following integration capabilities with DNS Server.

• DNS Lookup

Configuration

Prerequisites

Make sure SOAR has access to DNS Server through 53/udp port

Configuring DNS Service


• No specific configuration is needed on DNS Server.

Configuring SOAR

- 1. Click Configuration > Integrations > Create Integrations.
- 2. Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of DNS Server integration on SOAR.
Туре	DNS Service
Address	Address of the integration (in the format: 192.168.2.53)

Parameter	Value
Trust Invalid SSL Certificates	Not applicable
Require Approval From	Select users from the list who can provide approval before executing actions on this integration. As SOAR only executes enrichment on DNS Server, leave it empty
Notify	Select users from the list to notify when SOAR performs an action on this integration. As SOAR only executes enrichment on DNS Server, leave it empty



- 3. Click **Test**. The following pop up will be displayed if your credential and address are valid.
- 4. Click **Save** to complete integration.

Configuring SOAR Page 210 of 594

Integration Guide for EmailRep

Integration Overview

EmailRep consists of crawlers, scanners and enrichment services that collect data from email addresses, domains, and internet personas.

EmailRep uses hundreds of data points from social media profiles, professional networking sites, dark web credential leaks, data breaches, phishing kits, phishing emails, spam lists, open mail relays, domain age and reputation, and deliverability to predict the risk on an email address.

This integration enables ArcSight SOAR to report and query an email address.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with EmailRep:

- Email Query
- Report Email

Prerequisite

An API key is required for accessing EmailRep.

Configuring SOAR

- Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor** form:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, EmailRep Credentials).			API Key

3. Click **Configuration > Integration > Create Integrations** Specify the following parameter values in the **Configuration** form:

Parameter	Value	Value	
Name	Display na	Display name of the integration.	
Туре	EmailRep		
Address	Address of	the integration (https://emailrep.io).	
Configuration	Specify the	e following configuration parameters:	
	proxy.id ID of the Proxy integration if you access EmailRep through a device. For example, proxy.id = 12345		
Credential	Credential that has been defined for this integration under the Credentials menu.		
Trust Invalid SSL Certificates	Select this if web server's certificate is self-signed or is not recognized by browsers.		
Require Approval From	Select user(s) from list to ask the approval before executing actions on this integration.		
Notify	Select user integration	r(s) from the list to notify when SOAR performs an action on this n.	

- 4. Click **Save** to save the integration definition.
- 5. Navigate to Configuration>Customization Library and edit Emailrep Advanced Action Script Default Template.
- 6. Select the integration that you have added to Integrations menu.
- 7. Click **Save** to complete the integration.
- 8. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. Email Query

Enrichment capability for getting reputation of email addresses.

The following table presents the **Email Query** enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Email Address	Email address to be queried.	Email Address	Yes	Yes
Do not Use Cache	SOAR does not use cached results if this box is checked.	Checkbox	N/A	No

Output:

Capabilities Page 212 of 594

Case Scope:

Action	Туре	Category/ Value
Set	Scope item value	EmailRep Suspicious
Set	Scope item value	EmailRep Reputation

Human Readable Output:



- 2. Report Email
- 3. Action capability for reporting malicious email addresses.
 - Rollback: No
 - Duplicate Control: Yes



Note: This capability requires Professional or Enterprise API membership to EmailRep.

The following table presents **Report Email** action capability details:

Output:

	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is no-rollback.	N/A	N/A	No
Email Address	Email address to be reported.	Email Address	Yes	Yes
Tag	Report tag.	String	N/A	No
Description	Description/ reason to report.	String	No	Yes

Case Scope: N/A

Human Readable Output: N/A

Capabilities Page 213 of 594

Integration Guide for EnCase Endpoint Security

Integration Overview

EnCase Endpoint Security detects, validates and prioritizes unknown threats, assess the scope and impact of a compromise, and returns devices to a trusted state. With EnCase Endpoint Security, you can:

- Collect, aggregate and baseline all endpoint activity
- Proactively address the gaps in your security framework
- Detect unknown risks or threats even before data exfiltration has begun
- Respond to any events for validation and triage
- Perform manual or automated incident response with forensic-level investigations of endpoints
- Automate the recovery of endpoints to a trusted state through remediation

Integration Capabilities

ArcSight SOAR has the following integration capabilities with EnCase Endpoint Security:

- List Investigations
- Find Hosts with IOCs
- Standard Agent Timeline (Snapshot)
- Collect Memory
- Create Snapshot
- Find Hosts with Items of Interest
- Get Investigation Job Status
- Get Event Status
- Collect Data Pre Defined Filter
- Collect Data -Custom Filter
- Isolate
- Reconnect
- Create Event
- Remediate

Prerequisites

You must have access to HTTPS as the ArcSight SOAR connects to Encase API through this service.

Configuration

Configuring EnCase Endpoint Security

• Authentication: Encase REST APIs supports authentication using an Integration Key.

Integration Key Authentication

- To authenticate using an Integration Key, a new Integration Account needs to be created in the Account Management page of the web application.
- The Integration Key can be viewed or regenerated from the Manage Integration Key action.
- The Base URL for Integration Key APIs is: http(s)://server:port/integration. The Integration Key should be passed in a Request Parameter called Key.

Authentication Parameters

Request Headers:

Parameters	Datatype	Description	Required
Key	string	The Encase REST API Key	Yes

Configuration Parameter	Description
proxy.id	Proxy device to be used while communicating with the remote system's API
cache.reusing.duration	Default cache-reuse parameter
investigation.name	Default case name we want to create in Encase. For Example: SOAR

Additional Configuration:



In the Address configuration, replace the server-port with your server-port. For example: https://<server_name>:<server_port>

where,

<server_name>: Name of the server
<server_port>: Port number of the server

Prerequisites Page 215 of 594

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credentials.
- 2. Specify the following parameters values in the Credential Editor form.

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, Encase v1 Credentials).	N/A	N/A	The Encase REST API v1 Key

- 3. Click Configuration > Integrations > Upload plugin
- 4. Select your integration plugin zip file and click Save.
- 5. Select the integration that you have added to Integrations menu.
- 6. Click Save to complete the integration.
- 7. Click **Test.** an Integration Successful message is displayed if the credential and address are valid.

Integration Capabilities:

1. List Investigations:

Enrichment ca	apability to	get the	list of	Investigations.
---------------	--------------	---------	---------	-----------------

Input Parameters:

N/A

Output:

Case Scope:

N/A

Configuring SOAR Page 216 of 594

Human Readable Output:

2. Find Hosts with IOCs

The Enrichment capability queues a search for file-based indicators of compromise.

Input Parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Target IP addresses, FQDNs or hostnames	The name of the target address, FQDNs or hostnames	["COMPUTER_NAME", "HOST", "NETWORK_ ADDRESS"]	Yes	No
Target IP ranges, IP addresses, FQDNs or hostnames	The rage of IP address, FQDNs or hostnames	String	No	No

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Name of existing filter	Filter name for search	String	Yes	Yes
Stop the search after the first hit	Whether to stop or not after the first search	Boolean	Yes	Yes

Case Scope:

N/A

Human Readable Output

3. Standard Agent Timeline (Snapshot)

The enrichment capability triggers a collection of automatic snapshots which are then stitched together to create a timeline.

Input Parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Target IP addresses, FQDNs or hostnames	The name of the target address, FQDNs or hostnames	["COMPUTER_NAME", "HOST", "NETWORK_ ADDRESS"]	Yes	No
Target IP ranges, IP addresses, FQDNs or hostnames	The rage of IP address, FQDNs or hostnames	String	No	No

Output:

Case Scope:

N/A

Human Readable Output

4. Collect Memory

The enrichment capability triggers a collection of physical memory to an evidence file(.E01 or .RAW) which can later be analysed in a memory forensics tool such as Volatility.

Input Parameter

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Memory Output Format	Memory Out put format like "RAW", "E01"	String	No	Yes
Target IP addresses, FQDNs or hostnames	The name of the target address, FQDNs or hostnames	["COMPUTER_NAME", "HOST", "NETWORK_ ADDRESS"]	Yes	No
Target IP ranges, IP addresses, FQDNs or hostnames	The rage of IP address, FQDNs or hostnames	String	No	No

Case Scope: N/A

Human Readable Output

5. Create Snapshot

The enrichment capability is used to queue a new snapshot of the specified targets within a specified investigation. A snapshot captures the state of a machine at a given time, including the running processes, open ports, network cards, and logon information.

Input Parameter

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Target IP addresses, FQDNs or hostnames	The name of the target address, FQDNs or hostnames	["COMPUTER_NAME", "HOST", "NETWORK_ ADDRESS"]	Yes	No
Target IP ranges, IP addresses, FQDNs or hostnames	The rage of IP address, FQDNs or hostnames	String	No	No

Case Scope: N/A

Human Readable Output

6. Find Hosts with Items of Interest

The Enrichment capability queues a scan of your network for indicators including running processes, loaded DLLs, network connections, DNS cache entries, and more. This search relies only on live snapshots, as opposed to forensically searching filesystems. This search can efficiently sweep large IP ranges.

Input Parameter

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Target IP addresses, FQDNs or hostnames	The name of the target address, FQDNs or hostnames	["COMPUTER_NAME", "HOST", "NETWORK_ ADDRESS"]	Yes	No
Target IP ranges, IP addresses, FQDNs or hostnames	The rage of IP address, FQDNs or hostnames	String	No	No
MD5 and SHA1 Hashes of Interest	MD5 and SHA1 Hashes of Interest	Hash	Yes	No
IP Addresses of Interest	IP Address	["NETWORK_ADDRESS"]	Yes	No
Domains of Interest	Domains of Interest	["HOST"]	Yes	No
URLs of Interest will derive Domain Name	List of URLs	["URL"]	Yes	No

Case Scope: N/A

Human Readable Output

7. Get Investigation Job Status

The enrichment capability I is used to get the status of an investigation job.

Input Parameter

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Valid Job Type	Valid Job Type to get the status	String	No	Yes
Job ID	Job ID to get the status	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output

8. Get Event Status

The Enrichment Capability I is used to get the status of an event created using the CreateEvent API


Input Parameter

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Job ID	Job ID to get the status	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output:



9. Collect Data - Pre Defined Filter

The enrichment capability queues a file collection using any existing web or desktop filter.

Input Parameter

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Target IP addresses, FQDNs or hostnames	The name of the target address, FQDNs or hostnames	["COMPUTER_NAME", "HOST", "NETWORK_ ADDRESS"]	Yes	No
Target IP ranges, IP addresses, FQDNs or hostnames	The rage of IP address, FQDNs or hostnames	String	No	No
Name of existing filter	Name of existing filter	String	No	Yes
Endpoint Investigator Case Collection	Endpoint Investigator Case Collection value need to select	Boolean	No	Yes
Endpoint Investigator Case Name	Case Name	String	No	No
Endpoint Investigator Base Case Folder	Base Case Folder Name	String	No	No
Endpoint Investigator Case Backup Location	Endpoint Investigator Case Backup Location path	String	No	No
Endpoint Investigator Case Maximum Backup Size (GB)	Endpoint Investigator Case Maximum Backup Size (GB)	Number	No	No

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Endpoint Investigator Case Backup Every Interval	Endpoint Investigator Case Backup Every Interval	String	No	Yes
Endpoint Investigator Case Number. Use SOAR Case Number?	Endpoint Investigator Case Number. Use SOAR Case Number?	Number	No	Yes
Endpoint Investigator User Defined Case Number	If SOAR Case Number not used specify a case number	Number	No	No
Endpoint Investigator Case Examiner Name	Name of person doing the investigation.	String	No	No
Endpoint Investigator Case Description	Endpoint Investigator Case Description	String	No	No

Case Scope: N/A

Human Readable Output

10. Collect Data -Custom Filter

The enrichment capability queues a file collection using user-supplied EnDef filter Input Parameter

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Target IP addresses, FQDNs or hostnames	The name of the target address, FQDNs or hostnames	["COMPUTER_NAME", "HOST", "NETWORK_ ADDRESS"]	Yes	No
Target IP ranges, IP addresses, FQDNs or hostnames	The rage of IP address, FQDNs or hostnames	String	No	No
EnDefFilter	Name of existing filter	Is supported only for application/json	No	Yes
Endpoint Investigator Case Collection	Endpoint Investigator Case Collection value need to select	Boolean	No	Yes
Endpoint Investigator Case Name	Case Name	String	No	No

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Endpoint Investigator Base Case Folder	Base Case Folder Name	String	No	No
Endpoint Investigator Case Backup Location	Endpoint Investigator Case Backup Location path	String	No	No
Endpoint Investigator Case Maximum Backup Size (GB)	Endpoint Investigator Case Maximum Backup Size (GB)	Number	No	No
Endpoint Investigator Case Backup Every Interval	Endpoint Investigator Case Backup Every Interval	String	No	Yes
Endpoint Investigator Case Number. Use SOAR Case Number?	Endpoint Investigator Case Number. Use SOAR Case Number?	Number	No	Yes
Endpoint Investigator User Defined Case Number	If SOAR Case Number not used specify a case number.	Number	No	No
Endpoint Investigator Case Examiner Name	Name of person doing the investigation.	String	No	No
Endpoint Investigator Case Description	Endpoint Investigator Case Description	String	No	No

Case Scope: N/A

Human Readable Output

11. Isolate

The Action capability used to isolate an endpoint, which prevents an endpoint from communicating across the network

Input Parameter

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
A single target name that can be: HostName, IP Address, or FQDN	A single target name that can be: HostName, IP Address, or FQDN	["COMPUTER_NAME", "HOST", "NETWORK_ ADDRESS"]	Yes	Yes

Output

Case Scope: N/A

Human Readable Output:



12. Reconnect

The Action capability s used to reconnect a previously isolated endpoint (using Isolate) back to the network.

Input Parameter

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
A single target name that can be: HostName, IP Address, or FQDN	A single target name that can be: HostName, IP Address, or FQDN	["COMPUTER_NAME", "HOST", "NETWORK_ ADDRESS"]	Yes	Yes

Output

Case Scope: N/A

Human Readable Output:



13. Create Event

The Action capability is used by SIEMs or other security software to queue a new snapshot of the specified target, and it subsequently create a new event to be triaged within EnCaseEndpoint Security. A snapshot captures the state of a machine at a given time, including the running processes, open ports, network cards, and logon information. Input Parameter

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Source	Source	String	No	Yes
Comment	Comment	String	No	No
Id	Id	String	No	Yes
Score Enter a value between 1 and 100. 1-30 = assess, 31-69 = suspicious, 70-100 = malicious	Sore value	Number	No	Yes
A single target name that can be: HostName, IP Address, or FQDN	A single target name that can be: HostName, IP Address, or FQDN	["COMPUTER_ NAME", "HOST", "NETWORK_ ADDRESS"]	Yes	Yes

Case Scope: N/A

Human Readable Output:

```
a few seconds ago - commented

Jobld:68663, Source:Swarna Source, Comment:Test CommentId:Score:36, Targets:ir518w-win10

a few seconds ago - Create Event action for Score Enter a value between 1 and 100. 1-30 = asses s, 31-69 = suspicious, 70-100 = malicious: 36, Target IP addresses, FQDNs or hostnames: ir518 w-win10, Source: Swarna Source, Id: Test Id, Comment: Test Comment on EnCase Endpoint Securit y1 created by S swarna dash (waiting for execution)
```

14. Remediate

The action capability queues a remediation of processes and files using a combination of hash and size.

Input Parameter

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Remediation Option	Remediation Option	String	No	Yes
Target IP ranges, IP addresses, FQDNs or hostnames	Target IP ranges, IP addresses, FQDNs or hostnames	String	No	No
A single target name that can be: HostName, IP Address, or FQDN	A single target name that can be: HostName, IP Address, or FQDN	["COMPUTER_NAME", "HOST", "NETWORK_ ADDRESS"]	Yes	Yes
MD5 Hashes		["HASH"], ["MD5"]	Yes	Yes

Case Scope: N/A

Human Readable Output:

a few seconds ago - Remediate action for Remediation Option: Kill running processes only (optimized for IP ranges), Target IP addresses, FQDNs or hostnames: ir518w-win10, MD5 Hashes: 07411 F169FBCE7CC3C3E4830779EAFDD on EnCase Endpoint Security1 executed successfully by

S swarna dash

a few seconds ago - Remediate action for Remediation Option: Kill running processes only (optimized for IP ranges), Target IP addresses, FQDNs or hostnames: ir518w-win10, MD5 Hashes: 07411 F169FBCE7CC3C3E4830779EAFDD on EnCase Endpoint Security1 created by S swarna dash (waiting for execution)


a few seconds ago - commented

Jobld:68668, InvestigationId:79, InvestigationUrl:https://vm-ehutnyk.eastus.cloudapp.azure.com:4421/#/investigation/79?view=6, Remediation Option ID:1, Remediation Option Level:Kill running processes only (optimized for IP ranges), Hashes:{'Md5': u'07411F169FBCE7CC3C3E4830779EAFDD'}, Targets:ir518w-win10

Integration Guide for ESB Karar

- 1. To create the alert source, click **Configuration > Alert Source**.
- 2. Specify the following parameter values in the **Configuration Editor**:

Parameter	Value
Name	Display name of the alert source
Туре	ESB Karar
Address	Address of the alert source. (in the format imap[s]://host:port/FOLDER).
Configuration Content	esb.imap.host= esb.imap.port= esb.imap.secure=true esb.imap.folder=INBOX esb.mail.from=info@esb.org.tr
Credential	Credential defined for this alert source under the Credentials menu
Visible Alert Field	- details.description - details.allowed



- 3. Click **Test**. The following pop up will be displayed if your credential and address are valid.
- 4. Click **Save** to complete integration.

Integration Guide for F5 Big-IP Advanced Firewall Manager

Integration Overview

Big IP AFM protects the network against incoming threats, even the most massive and complex DDoS attacks.

Big IP AFM keeps bad traffic away from some specific network addresses and protects the data center against DDoS attacks, and other network or application attacks. It also brings visibility and control to SSH, and SSL connections, providing against back door threats that use the SSH channel for data breaches and app attacks.

Integration Capabilities

Action

• Add address to specific address list

Configuration

Configuring F5 Big-IP Advanced Firewall Manager


 Make sure SOAR has access to F5 Big-IP Advanced Firewall Manager integration's API as it connects to it using HTTPS.

Configuring SOAR

- 1. To create the integration, navigate to **Configuration > Integrations**.
- 2. Specify the following parameter values in the Integrations Editor form.

Parameter	Value
Name	Display name of integration
Туре	F5 Big-IP Advanced Firewall Manager
Address	Address of the integration (in the format 1.1.1.1:1234 or
	abc.example.com:1234)

Parameter	Value
Credential	Credential that was defined for this integration under the Credentials menu
Trust Invalid SSL Certificates	Select this if device's certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration



- 3. Click **Test**. The following pop up will be displayed if your credential and address are valid.
- 4. Click **Save** to complete integration.

Integration Guide for FireEye HX

Integration Overview

FireEye HX is an endpoint threat detection and prevention solution. ArcSight SOAR integrates with FireEye HX through REST API to give enrichment and action capabilities to the users.

Integration Capabilities

Enrichment

- IoC Scan: HX can scan a given scope item in a target system and return information.
- Detailed System Information: HX can gather a target system information.
- **Script Execution:** HX supports different forensic data gathering scripts. These are XML formatted files that exist on HX installation. If customer wishes, they can import these script like files into Customization Library and then execute them through SOAR.

Action

Quarantine: HX quarantines a target system and reverts the quarantine if required.

Configuration

Configuring FireEye HX

- Make sure API services are enabled and create a api_admin user. To enable the service, please see product documentation
- Access to the port number defined in the HX during installation as SOAR connects to FireEye HX.
- Define required access control rules if SOAR and FireEye HX are segregated.

Configuring SOAR

SOAR configuration is standard and users need to specify **Name**, **Address** and **Credential fields**. Rest of the fields can be changed as required.




Note: Configuration field must not be changed by users.

- 1. To create the integration, navigate to **Configuration > Integrations**.
- 2. Specify the following parameter values in the Integration Editor form:

Parameter	Value
Name	Display name of the integration
Туре	FireEye HX
Address	Address of the alert source (in the format http[s]://1.1.1.1:3000 or http[s]://abc.example.com:3000)
Configuration	Specify the following configuration parameter: server.address.suffix=/hx/api/v3
Credential	Credential defined under the Credentials menu
Trust Invalid SSL Certificates	Select this if device's certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an action on this integration

Configuring SOAR Page 232 of 594



- 3. Click **Test** to test the integration.
- 4. Click **Save** to complete integration.

Configuring SOAR Page 233 of 594

Integration Guide for Forcepoint Cloud Services

Integration Overview

SOAR works with Forcepoint Cloud Services to report uncategorized sites.

Integration Capabilities

Action

Report

Configuration

Configuring Forcepoint Cloud Services


- Make sure SOAR has access to HTTPS as it connects to Forcepoint Cloud Services URL https://www.websense.com).
- A user account on Forcepoint/WebSense to use the **Sitelookup** tool.

Configuring SOAR

- 1. To create the integration, navigate to Configuration > Integrations.
- 2. Specify the following parameter values in the Integrations Editor.

Parameter	Value
Name	Display name of the integration
Туре	Forcepoint Cloud Services
Address	Address of the integration (in the format
	http[s]://abc.example.com:3000)
Credential	Credential defined for this integration under the Credentials menu.

Parameter	Value
Trust Invalid SSL Certificates	Select this if device's certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an action on this integration



- 3. Click **Test** to test the integration.
- 4. Click **Save** to complete the integration.

Configuring SOAR Page 235 of 594

Integration Guide for Forcepoint Content Gateway

Integration Overview

Forcepoint Web Content Gateway is a web proxy and cache that analyzes HTTP(S) requests in real-time and passes the traffic to Filtering Service for policy enforcement.

Integration Capabilities

ArcSight SOAR has the following integration capability with Forcepoint Web Content Gateway:

• Block Access to IP Addresses, URLs and Hostnames

Use Case: Blocking Phishing Domains

SOAR checks the inbox of user's email, for phishing reports and automatically creates an incident record on the service desk. During the investigation, SOAR extracts the malicious IP addresses, domains, and URLs in the message body and blocks access to Forcepoint Web Content Gateway. This can either be performed automatically within a playbook or manually by an analyst.

Also, SOAR uses threat intelligence (TI) feeds as an Alert Source and automatically blocks malicious domains/IP addresses reported by TI source on Forcepoint Web Content Gateway before any attack occurs.

Configuration

Prerequisites

- Current version of Forcepoint Web Content Gateway.
- Access to HTTPS as SOAR connects to Forcepoint Web Content Gateway Policy API
- Access to 15873/tcp port

Configuring Facepoint Web Content Gateway

Forcepoint Management API does not get installed by default. To complete the
integration, install this service on the server or appliance. Also, the configuration steps
differ with the usage of the server. For the complete instructions, see Management API

Installation Guide.

2. After installing Management API components, use the Forcepoint Security Manager to configure the account used for authentication. To enable the communication, see *Enabling communication between Management API clients and servers* in the Management API Installation Guide.

Configuring SOAR

- 1. Click Configurtion > Credentials > Create Credential.
- 2. Specify the following parameter values in the Credential Editor form:
 - a. Internal credential:

Parameter	Value
Туре	Internal credential
Name	Display name of the credential set (For example, Forcepoint WCG Credentials)
Username	Username configured on Forcepoint Management API
Password	Password for the user configured on Forcepoint Management API.
Private Key	Empty

b. Credential Store:


Parameter	Value
Туре	External credential
Name	Name of the credential with pull path of the safe on store.

- 3. Click Configuration > integrations > Create Integration.
- 4. Specify the following configuration parameter values in the **Configuration form**:

Parameter	Value
Name	Display name of Forcepoint Web Content Gateway integration on SOAR
Туре	Forcepoint Web Content Gateway
Address	Address of the integration (in the format
	https://192.168.2.99:15:15873).

Configuring SOAR Page 237 of 594

Parameter	Value	
Configuration	Specify the following configuration parameters:	
	# The Category name cannot include any of the following characters: # * < > { } ~ ! \$ % & @ # . " \ & + = ? / ; : , # SOAR is going to automatically add new category name if it doesn't exist categoryName=SOAR_BLOCK	
Credential	Name of the credential set created on step 2. (For example, Forcepoint WCG Credentials)	
Trust Invalid SSL Cerificates	Select this if Engine's certificate is self-signed or is not recognized by browsers.	
Require Approval From	Select users from the list who can provide approval before executing actions on this integration.	
Notify	Select users from the list to notify when SOAR performs an action on this integration	



- 5. Click **Test**. The following pop up will be displayed if your credentials and address are valid.
- 6. Click **Save** to complete integration.

Configuring SOAR Page 238 of 594

Additional Notes

• The categoryName you provide in the Configuration section is API-Managed but not managed by UI. If the category does not exist on the device, SOAR creates it automatically.

Configuring SOAR Page 239 of 594

Integration Guide for ForeScout CounterACT NAC

Integration Overview

ForeScout CounterACT NAC provides virtual insight into any device connected across the enterprise and gives a single-pane-of-glass perspective. ForeScout discovers devices in real-time, then classifies, assesses, and monitors these devices. Also, this platform provides agent-less control and continuous monitoring across heterogeneous environments. Enables to trigger actions to notify, monitor, and remediation.

Integration Capabilities

SOAR has the following integration capability with ForeScout CounterACT NAC:

Action Capabilities

Assign Policy to Host

Enrichment Capabilities

- Host information query by Network Address
- Host information query by Username
- Host information query by MAC Address
- Host information query by Computer Name

Use Case: Isolating Mal-behaving PC

SOAR integrates with ForeScout CounterACT NAC, while responding to an incident it applies a policy to mal-behaving computers and prevents further spread of the attack. A policy to the host can either be applied automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- Current version of ForeScout CounterACT NAC
- Access to SSH protocol(22/tcp port) as SOAR connects to ForeScout CounterACT NAC using SSH protocol.

- Access to 443/tcp port as enrichment plugin connects to ForeScout CounterACT NAC server
- A shell user account needs to be created for SOAR to connect to ForeScout


CounterACT NAC

Configuring ForeScout CounterACT NAC


- 1. Login to ForeScout CounterACT NAC appliance.
- 2. Create a shell account by executing the following command in the command prompt:
 - \$ useradd -s /bin/bash -m -d /home/soar soar
 - \$ passwd atar
- 3. To allow new user to execute fstool command without the need to enter the password, add the following line to sudo configuration (/etc/sudoers)

```
soar ALL=(root) NOPASSWD: /usr/local/forescout/bin/fstool
```

4. To use enrichment capabilities, add or use an existing web management user with the following permission:



- 5. Login to Forescout Management Interface.
- 6. Enable CEF service.



- 7. Navigate to **Policy** and edit one of the existing policies or create a new one.
- 8. To edit condition of a rule, add "SIEM Message" as Criteria and select desired action.



Note: Make a note or save the SIEM message to use while configuring SOAR.

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor** form:
 - a. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, ForeScout CounterACT NAC Credential)
Username	Username created for SOAR on ForeScout CounterACT NAC
Password	Password of the user that was created for SOAR on ForeScout CounterACT NAC
Private Key	Empty

b. Internal Credential

Configuring SOAR Page 243 of 594

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, ForeScout CounterACT NAC Credential)
Username	Username created for SOAR on ForeScout CounterACT NAC for web management user (2.2.3).
Password	Password of the user you have created for SOAR on ForeScout for web management user (2.2.3).
Private Key	Empty



Note: Make a note or save the credential ID to use it in device configuration (2.3.4).

c. Credential Store:

Parameter	Value	
Туре	External Credential	
Name	Name of the credential with pull path of the safe on store.	


3. Click Confingration > Integrations > Create Integration.

Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of Database Server integration on SOAR
Туре	ForeScout CounterACT NAC
Address	Address of the integration (in the format 192.168.1.1)
Configurati	Specify the following configuration parameters.
on	<pre># Supported versions are: v1 (for version 8.0) and v2 (for version 8.1.3). Default version is v1 #version= # Siem messages should be separate with comma # For Example: # policy.siem.messages=MSG1,MSG2,MSG3 policy.siem.messages= # please provide the credential id if the ForeScout query page has a # different username & password webui_credential_id=(Credential id that you made a note in step 2.3.4)</pre>
Credential	Name of the credential set created on step 2. (For example, ForeScout CounterACT NAC Credential)

Configuring SOAR Page 244 of 594

Parameter	Value
Trust Invalid SSL Certificates	Select this if device's certificate is self-signed or is not recognized by browsers
Require Approval from	Select users from the list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an action on this integration.




- 4. Click **Save** to complete integration.
- 5. Click **Test**to test the integration.

Additional Notes

• ForeScout CounterACT NAC integration is an Advanced Script, and the content of the default script is accessible under **Configuration** > **Customization** Library.

Additional Notes Page 245 of 594

• While defining the integration for the first time, you might encounter the following warning message, which is the expected behavior for this type of integration.



Integration Guide for Fortinet Forti Manager V2

Integration Overview

FortiManager is a management tool for Fortify Firewalls. It can manage multiple firewalls in a row from its central user interface.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Forti Manager:

- Add to Address Group
- List Devices
- List Firewall Address Groups
- List Firewall Addresses

Prerequisites

- You must have access to HTTPS as the ArcSight SOAR connects to Forti Manager IP through this service.
- You must have a super user credentials.

Configuration

Configuring Forti Manager

SSH to FortigateManager with admin user credential and execute the following command on ssh terminal:

```
FW # config system admin user
(user)# edit admin
(admin)# set rpc-permit read-write
```

Configuring SOAR

- 1. Click Configuration > Integration > Create Integration.
- 2. In Configuration Editor, select FortiManager in the Type list.
- 3. Click **Create** to create a new credential and specify the following parameters in the **Credential Editor** form:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, Fortin Manager Credentials).	FortiManager Username	FortiManager Password	Empty

- Check the Clear Text Accesscheckbox .
- 5. Click **Save** to save the integration definition.
- 6. Navigate to Configuration>Customization Library and edit FortiManager Advanced Action Script Default Template.
- 7. Select the integration that you have added to Integrations menu.
- 8. Click **Save** to complete the integration.
- Click Test. Integration Successful message is displayed if the credential and address are valid.

Capabilities

- 1. Add To Address Group
- Adds Ip address to given group for specified ADOM.
 The following table presents the Add To Address Group action capability details:

Configuration Page 247 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
IP	A valid IP Address to retrieve data.	Network Address Host	Yes	Yes
ADOM	Administrative Domain.	String	No	Yes

Case Scope: N/A

Human Readable Output: N/A

3. List Firewall Address Groups

4. List of firewall address groups on FortiManager.

The following table presents the List Firewall Address Groups action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
ADOM	Administrative Domain.	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output:



- 5. List Firewall Addresses
- 6. List of Firewall Addresses on FortiManager.

The following table presents the List Firewall Addresses action capability details:


Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
ADOM	Administrative Domain.	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output:

Capabilities Page 248 of 594



Capabilities Page 249 of 594

Integration Guide for Fortinet FortiAnalyzer

Integration Overview

Fortinet FortiAnalyzer is a central log collection and analysis tool for Fortinet products. SOAR can query FortiAnalyzer (FAZ) for scope items to enrich incident data and to search the past events for emerging threats.

Integration Capabilities

ArcSight SOAR has the following enrichment capabilities with Fortinet FortiAnalyzer:

- Accepted Traffic Logs: This query returns accepted traffic logs to or from the selected scope item and the time frame might be between 1 hour to 12 hours.
- URL Access Logs: This query returns the events that record access to the selected URL and the time frame might be between 1 hour to 12 hours.

Configuring Fortinet FortiAnalyzer

Web services must be enabled on the network interface to which the client connects.

- To enable web services for an interface, navigate to System Settings > Network >
 Interface.
- 2. Select **Edit** for the interface for which you need to enable the web services.
- 3. In the Administrative Access section, select Web Service.
- 4. Select **OK** to apply the changes.
- 5. Create a user with a custom profile.



Note: This user profile requires access to Log View/FortiView/NOC - SOC component and ADOM's SOAR.

Configuring SOAR

- Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor** form:

a. Internal credential:

Parameter	Value
Туре	Internal credential
Name	Display name of the credential set (For example, Fortinet FortiAnalyzer)
Username	API Key created on Fortinet FortiAnalyzer
Password	API Password for the key created on Fortinet FortiAnalyzer
Private Key	Empty

b. Credential Store:


Parameter	Value
Туре	External credential
Name	Name of the credential with pull path of the safe on store

3. Click Configuration > integrations > Create Integration.

4. Specify the following configuration parameter values in the **Configuration form**:

Parameter	Value
Name	Display name of Fortinet FortiAnalyzer integration on SOAR
Туре	Fortinet FortiAnalyzer
Address	Address of the integration (in the following format: 1.1.1.1 or http[s]://abc.example.com)
Credential	Name of the credential set created on step 2 (for example, Fortinet FortiAnalyzer Credentials)
Configuration	Specify the following configuration parameters: maxNumMatches: Define the number of results SOAR shows per page of query adom: ADOM's SOAR query to get logs from
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an action on this integration

Configuring SOAR Page 251 of 594



- 5. Click **Test** to test the integration.
- 6. Click **Save** to save the integration.

Configuring SOAR Page 252 of 594

Integration Guide for Fortinet FortiDDoS

Integration Overview

FortiDDoS is a network behavior anomaly (NBA) prevention system that detects and blocks attacks that intend to disrupt network service (distributed denial of service (DDoS) attacks) by over utilizing server resources.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with FortiDDoS:

Block IP and Hostname

Use Case: Blocking malicious IP on peripheral

SOAR integrates with FortiDDoS to block malicious IP addresses detected while responding tp an incident. Blocking can be performed automatically within a playbook or manually by an analyst.

Configuration


Prerequisites

- FortiDDoS version 4.7 and 5.1
- Access to tcp port 443 as SOAR connects to FortiDDoS' API using HTTPS
- An administrator user account for SOAR to connect to FortiDDoS

Configuring FortiDDoS

- To add a new SOAR user with the required access profile permissions, navigate to System > Admin > Access Profile.
- In the Access profile form, select Global Settings and Protection profiles with Read & Write permissions.
- 3. Navigate to System > Admin > Administrator.

- 4. To add an administrator with the profile created in the previous step, select **Enable** for **Allow API Access**.
- (Optional) To specify Remote Authentication and Idle timeout values, navigate to Centralized Management > Admin.



6. Click Save to save the changes.

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the **Credential Editor** with the following parameter values:
 - a. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, FortiDDoS Credentials)
Username	User created on FortiMail for SOAR
Password	Password of the user that was created for SOAR on FortiMail
Private Key	Empty

b. Credential Store:


Parameter	Value
Туре	External Credential
Name	Name of the credential with pull path of the safe on store

Configuring SOAR Page 254 of 594

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of FortiDDoS integration on SOAR
Туре	FortiDDoS
Address	Address of the integration (in the following format: https://192.168.3.99)
Configuration	Specify the following configuration parameters:
	<pre># Supported API versions are: v1 (for 4.x versions) and v2 (for 5.x versions). Default api.version=v2 #proxy.id=123</pre>
Credential	Name of the credential set created on step 2 (For example, FortiDDoS Credentials)
Trust Invalid SSL Certificates	Select this if Integrations's certificate is self-signed or is not recognized by browsers.
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an action on this integration

Configuring SOAR Page 255 of 594



- 5. Click **Test** to test the integration.
- 6. Click **Save** to complete the integration.

Configuring SOAR Page 256 of 594

Integration Guide for Fortinet FortiGate API

Integration Overview

Fortinet FortiGate is an industry leading next generation security platform.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Fortinet FortiGate API:

- Action
- Block IP
- Block FQDN
- Block URL

Use Case: Blocking malicious artifacts detected through alerts

SOAR automatically executes playbooks and blocks malicious artifacts on FortiGate platform. The artifacts IP, Domain and URL can be blocked using SOAR.

Configuration

Prerequisites

- Access to tcp port 443 as SOAR connects to Fortinet FortiGate API using HTTPS
- A user account with necessary permissions on the FortiGate platform

Configuring Fortinet FortiGate

- 1. To create a user, navigate to **System > Administrators**.
- Click Create New and select REST API Admin.
- 3. Specify the following values in the New REST API Admin form:

Username: <SOAR user name>

Trusted Hosts: A subnet that covers SOAR's API address






Note: Use the IP address that SOAR uses and 0.0.0.0/0 must not be used as an IP address.

- 4. To create a profile, click + in the **Admin Profile** window.
- 5. Select **Read/Write** persmissions for the following groups:

Firewall > Address

Security > Web Filter



6. Click **OK** to save the profile and save the API key.

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the **Credential Editor** with the following parameter values:
 - a. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, Fortinet FortiGate Credentials)
Username	Empty
Password	Empty
Private Key	Enter the API Key generated by FortiGate




Note:Fortinet FortiGate requires private key and External Credential is not used.

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of Fortinet FortiGate integration on SOAR
Туре	Fortinet FortiGate 6.0
Address	Address of the firewall
Configuration	Specify the following configuration parameters: group.name: Group name for adding objects to be blocked. This Address Group will be created on FortiGate and then can be used in policies as the admin see fit policy.names: Policy names to be used to block URL. ' ' is used as separator for policies and SOAR writes the URL to all the policies defined
Credential	Name of the credential set that was created on step 2 (For example, Fortinet FortiGate Credentials)
Trust Invalid SSL Certificates	Select this if Integrations's certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration

Configuring SOAR Page 260 of 594



5. Click Save to complete the integration.

Additional Notes

• The API Key to work properly requires access to HTTPS and for security reasons as well.



• If you have multiple policies on the integration configuration and if one of the policy's URL filter is disabled, SOAR with Fortinet integration displays no specific error message. In such case, you might encounter the following error message:

None of policy names in t he configuration are present in the Fortinet FortiGate server.

Additional Notes Page 261 of 594

Integration Guide for Fortinet FortiMail

Integration Overview

Fortinet FortiMail secure email gateway utilizes the latest technologies and security services from FortiGuard Labs to protect from common and advanced threats while integrating robust data protection capabilities to avoid data loss.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with FortiMail:

- Add to Block List
- Block

Use Case: Blocking malicious sender

SOAR integrates with FortiMail to block malicious email addresses detected while responding to an incident. The blocking can either be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites


- FortiMail version 6.2.2(GA) and later
- Access to tcp port 443 as SOAR connects to FortiMail API using it
- An administrator user account for SOAR to connect to FortiMail

Configuring FortiMail


 By default, REST-API service is disabled on FortiMail. To enable it, use the following CLI command:

```
config system global
set rest-api enable
end
```

- 2. Navigate to System > Administrator > Admin Profile.
- 3. Select Policy, Block/Safe List with Read-Write support and create an admin profile in the Admin Profile form.



- 4. Navigate to System > Administrator > Administrator.
- 5. Create a new administrator account with the profile that you have created in the previous step.



Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the Credential Editor with the following parameter values:
 - a. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, FortiMail Credentials)
Username	User created on FortiMail for SOAR
Password	Password of the user created on FortiMail for SOAR
Private Key	Empty


b. Credential Store:

Parameter	Value
Туре	External Credential
Name	Name of the credential with pull path of the safe on store

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form:

Configuring SOAR Page 264 of 594

Parameter	Value
Name	Display name of FortiMail integration on SOAR
Туре	FortiMail
Address	Address of the integration (in the following format: https://192.168.3.100)
Configuration	Specify the following configuration parameters: #proxy.id=5433
Credential	Name of the credential set created on step 2 (For example, FortiMail Credentials)
Trust Invalid SSL Certificates	Select this if Integrations's certificate is self-signed or is not recognized by browsers.
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an action on this integration



5. Click **Test** to test the integration.

Configuring SOAR Page 265 of 594

6. Click **Save** to complete the integration.

Additional Notes

Add to Block List capability uses the Security > System > Blocklist, whereas Block capability uses the Policy > Access Control.

Additional Notes Page 266 of 594

Integration Guide for Fortinet FortiManager

Integration Overview

Fortinet FortiManager is a centralized management unit for Fortinet family devices. It provides best compliance practices and workflow automation. This integration has been tested with Fortinet FortiManager v5.6.2-build1631 180124 (GA) firmware version.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with FortiManager:

- Block file on an connected Fortinet family device (For example, Fortinet NGFW, Fortinet FortiMail, etc)
- Block IP address on an connected Fortinet family device (For example, Fortinet NGFW, Fortinet FortiMail, etc)
- Block username on an connected Fortinet family device (For example, Fortinet NGFW)
- Block email on an connected Fortinet family device (For example, Fortinet FortiMail)

Use case: Mitigating Compromised Account Cases

SIEM, with the help of intelligence sources, creates an alarm. It compromises the suspected email accounts of the employees. SOAR integrates with Fortinet FortiManager and automatically blocks the outgoing emails and the incoming and outgoing traffic. This blocking can either be performed automatically within a playbook or manually by an analyst.


Prerequisites

- Access to tcp port 443 as SOAR connects to Fortinet FortiManager using HTTPS
- A user account for SOAR to connect to Forti Manager


Configuration

Configuring FortiManager

- 1. Navigate to System Settings > Admin > Administrators.
- To create a profile with Super_User account, specify the following values in the New Administrator form:
 - Username: <SOAR username>
 - Admin Type: Local
 - New Password: <Specify the password>
 - Confirm Password:< Confirm the password entered in the Password field>
 - Admin Profile: Super User



- 3. Navigate to System Settings > Network.
- 4. Enable the Web Service in the Administrative Access.



Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the Credential Editor:
 - a. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, Forti Manager Credentials)
Username	User that was created for SOAR on Forti Manager
Password	Password of the user that was created for SOAR on Forti Manager
Private Key	Empty

b. Credential Store:


Parameter	Value
Туре	External Credential
Name	Name of the credential with pull path of the safe on store

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of FortiMail integration on SOAR
Туре	Forti Manager
Address	Address of the integration (in the following format: https://192.168.2.2:8080)

Configuring SOAR Page 269 of 594

Parameter	Value
Credential	Name of the credential set created on step 2 (For example, Forti Manager Credentials)
Trust Invalid SSL Certificates	Select this if Forti Manager's certificate is self signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an action on this integration



- 5. Click **Test** to test the integration.
- 6. Click **Save** to complete the integration.

Additional Notes

Commands to be run on Forti Gate firewall devices are defined as Advanced Action Script. To access the default scripts navigate to **Configuration > Customization Library**.

Additional Notes Page 270 of 594

Integration Guide for Fortinet FortiSandbox

Integration Overview

Fortinet Sandbox is a zero-day malware behavior analysis system. It enables organizations to defend against advanced threats such as ransomware by integrating various Fortinet technologies and other security products. Or is used as an extension to their on-premise security architectures to leverage complete control. This integration has been tested with Fortinet FortiSandbox 3.1.0 version.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Fortinet Sandbox:

- Query File Hash
- · Analyze File
- Analyze URL

Use Case: Investigating Suspicious Files

During the investigation of a suspicious endpoint behavior, SOAR integrated with Fortinet Sandbox analyzes the behavior of potential malware and hashes and URLs detected on suspicious network traffic. This investigation can either be performed automatically within a playbook or manually by an analyst.


Configuration

Prerequisites


- Access to tcp port 443 as SOAR connects to Fortinet Sandbox API using HTTPS
- A user account is required for SOAR to connect to Fortinet Sandbox

Configuring Fortinet Sandbox

- Navigate to System > Admin Profiles.
- Create an Admin Profile with Read/Write permission for SCAN INPUT and select Enable for JSON API.



- 3. Navigate to System > Administrators.
- 4. Create an **Administrator** account with the profile that is created in the previous step and specify the following values:
 - Administrator: SOAR_LABS
 - Password: <Specify the password>
 - Confirm Password: <Confirm the password spcified in the Password field>
 - Type: Select Local
 - · Admin Profile: <Specify the profile name>



Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the Credential Editor:
 - a. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, Fortinet Sandbox Credentials)
Username	User that was created on Fortinet Sandbox for SOAR
Password	Password of the user that was created for SOAR on Fortinet Sandbox
Private Key	Empty


b. Credential Store:

Parameter	Value
Туре	External Credential
Name	Name of the credential with pull path of the safe on store

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form:

Configuring SOAR Page 273 of 594

Parameter	Value
Name	Display name of Fortinet Sandbox integration on SOAR
Туре	Fortinet Sandbox
Address	Address of the integration (in the following format: https://192.168.2.75)
Configuration	Specify the following configuration parameters: #proxy.id=5442
Credential	Name of the credential set created on step 2 (For example, Fortinet Sandbox Credentials)
Trust Invalid SSL Certificates	Select this if Web UI's certificate certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Not Applicable



5. Click **Test** to test the integration.

6. Click **Save** to complete the integration.

Configuring SOAR Page 274 of 594

Additional Notes

Fortinet Sandbox supports the following compressed file types:

.tar, .z, .xz, .gz, .tar.gz, .tgz, .zip, .bz2, .tar.bz2, .tar.Z, .7z, .rar, .lzh, .ace

Integration Guide for FraudGuard

FraudGuard is a service designed to provide an easy way to validate usage by continuously collecting and analyzing real-time internet traffic. Utilizing just a few simple API endpoints we make integration as simple as possible and return data such as: Risk Level, Threat Type, Geo Location

Integration Capabilities

- Geo Lookup
- Get Host Reputation
- Get IP Reputation
- Add to Custom Blacklist
- Add to Custom Whitelist
- Delete From Custom Blacklist
- Delete From Custom Whitelist

Prerequisites

You must have access to HTTPS as the ArcSight SOAR connects to FraudGuard API through this service.

Configuring FraudGuard

- 1. Navigate to https://api.fraudguard.io.
- 2. Create a user account by setting your username and password.

Configuring SOAR

- 1. Click Configurations > Credentials > Create crendentials.
- 2. Specify the following parameter values in the **Credential Editor**:
 - Internal Credential

Parameter	Value
Туре	Internal credential
Name	Display name of credential set(i.e, FraudGuard credentials)
Username	Username that you have noted from the service
Password	Password that you have noted from the service
Private Key	Empty

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form:

Parameter	Value		
Name	Display name of FraudGuard integration on SOAR.		
Туре	FraudGuard		
Address	https://api.fraudguard.io		
Configuration	Specify the following	configuration parameters:	
	proxy.id	ID of the Proxy integration if you access Fraudguard through a web proxy device. For example: proxy.id = 12345	
	cache.reusing.duration	configure how far (in minutes) into the past this enrichment will look.	
Credential	Credential that has been defined for this integration under the credentials menu.		
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration		

- 5. Click **Save** to save the integration definition.
- 6. Navigate to Configuration > Customization Library" and edit Fraudguard Action Script Default Template.
- 7. Select the integration you have added to Integrations dropdown menu.
- 8. Click **Save** to complete the integration.

Configuring SOAR Page 276 of 594

Capabilities

1. Geo Lookup

Enrichment capability for lookup of IP address.

Input Parameter	Description	Туре	Scope Restricted(Yes/No)	Required (Yes/No)
Integration	Name of the 3rd party integration	Integration	N/A	Yes
IP Address	Scoped variable to store IP address	String	N/A	Yes

Output:

Case Scope

N/A

Human Readable Output

Yes

2. Get Host Reputation

Enrichment capability for get host reputation and details.

Input Parameter	Description	Туре	Scope Restricted(Yes/No)	Required (Yes/No)
Integration	Name of the 3rd party integration	Integration	N/A	Yes
Hostname	Scoped Parameter to store host address.	String	N/A	Yes

Output:

Case Scope

N/A

Human Readable Output

Yes

3. Get IP Reputation

Enrichment capability for Getting IP details from fraudguard.

Capabilities Page 277 of 594

Input Parameter	Description	Туре	Scope Restricted(Yes/No)	Required (Yes/No)
Integration	Name of the 3rd party integration	Integration	N/A	Yes
IP Address	Scoped Parameter IP Address.	String	N/A	Yes

Case Scope

N/A

Human Readable Output

Yes

4. Add to Custom Blacklist

Action capability for Adding an IP to blacklist.

Rollback: Yes

Input Parameter	Description	Туре	Scope Restricted(Yes/No)	Required (Yes/No)
Rollback Mode	Time to rollback this action. Default is norollback.	N/A	N/A	No
IP Address	IP Address to be added to the blacklist eg: 0.0.0.0/0	String	N/A	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

5. Add to Custom Whitelist

Action capability for Adding an IP to whitelist.

• Rollback: Yes

Capabilities Page 278 of 594

Input Parameter	Description	Туре	Scope Restricted(Yes/No)	Required (Yes/No)
Rollback Mode	Time to rollback this action. Default is no- rollback.	N/A	N/A	No
IP Address	IP Address to be added to the whitelist eg: 0.0.0.0/0	String	N/A	Yes

Case Scope

N/A

Human Readable Output

N/A

6. Delete From Custom Blacklist

Action capability for Deleting an IP from blacklist.

• Rollback: Yes

Input Parameter	Description	Туре	Scope Restricted(Yes/No)	Required (Yes/No)
Rollback Mode	Time to rollback this action. Default is no- rollback.	N/A	N/A	No
IP Address	IP Address to be removed from the blacklist eg: 0.0.0.0/0	String	N/A	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

7. Delete From Custom Whitelist

a. Action capability for Deleting an IP from whitelist.

• Rollback: Yes

Capabilities Page 279 of 594

Input Parameter	Description	Туре	Scope Restricted(Yes/No)	Required (Yes/No)
Rollback Mode	Time to rollback this action. Default is no- rollback.	N/A	N/A	No
IP Address	IP Address to be removed from the whitelist eg: 0.0.0.0/0	String	N/A	Yes

Case Scope

N/A

Human Readable Output

N/A

Capabilities Page 280 of 594

Integration Guide for FTP Server

Integration Overview

ArcSight SOAR uses FTP Servers to put or transfer files to remote machines using incident scope.

Integration Capabilities

Action

• Put File

Configuration

Prerequisites


- Access to File Transfer Protocol or SFTP as SOAR connects to FTP Server using it
- · A user's credential

Configuring SOAR

- 1. To create the integration, navigate to **Configuration > Integrations**.
- 2. Specify the following parameter values in the Integrations Editor form.

Parameter	Value
Name	Display name of the integration
Туре	FTP Server
Address	Address of the integration (in the format: 1.1.1.1 or abc.example.com)

Parameter	Value
Configuration	Specify the following configuration parameters:
	connection.port is the listening port of the FTP/SFTP service running. connection.protocol could be FTP or SFTP. remote.file.filename.appenduuid specifies whether the UUID will be appended to the filename. It can be either "true" or "false". remote.folder is the folder relative to the FTP home directory.
Credential	Credential that was defined for this integration under the Credentials menu
Trust Invalid SSL Certificates	Select this if device's certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an action on this integration



Configuring SOAR Page 282 of 594

- 3. Click **Test** to test the integration.
- 4. Click $\bf Save$ to complete integration.

Configuring SOAR Page 283 of 594

Integration Guide for Have I Been Pwned

Integration Overview

Have I Been Pwned is a web service that allows to check if the emails/usernames are exposed as part of previous data breaches.

This integration supports Have I Been Pwned API v3.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Have I Been Pwned:

- Check Pwned Accounts
- Check Pwned Pastes
- Check Pwned Domains

Prerequisites

Have I Been Pwned requires an API key for access.

Configuration

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor** form:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (i.e., Have I Been Pwned Credentials)			API Key

3. Click Configuration > Integrations > Create Integration.

4. Specify the following parameter values in the **Configuration Form**:

Parameter	Value	
Name	Display name of the integration	
Туре	Have I Been Pwned	
Address	Address of the integration (https://haveibeenpwned.com/)	
Configuration	Specify the following configuration parameters:	
	proxy.id Access the ID of the Proxy integration Have I Been Pwned through a web proxy device. For example: proxy.id = 12345	
Credential	Credential that has been defined for this integration under the Credentials menu.	
Trust Invalid SSL Certificates	Select this if web server's certificate is self-signed or is not recognized by browsers.	
Require Approval From	Since there is no action capability in this plugin, please leave it empty.	
Notify	Since there is no action capability in this plugin, please leave it empty.	

- 5. Click **Save** to save the integration definition.
- 6. Navigate to Configuration>Customization Library and edit Have I Been Pwned Advanced Action Script Default Template.
- 7. .Select the integration you have added to **Integrations** menu.
- 8. Click **Save** to complete the integration.
- 9. Click **Test**. **Integration Successful** message is displayed if your credential and address are valid.

Capabilities

1. Check Pwned Accounts

Enrichment capability for gathering pwned account details.

The following table presents the **Check Pwned Accounts** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes
Email Address	Email address to be queried	Email Address Username Keyword Unknown	Yes	Yes
Do not Use Cache	SOAR does not use cached results if this box is checked	Checkbox	N/A	No

Capabilities Page 285 of 594

Case Scope: N/A

Human Readable Output:

Breach	Date	Description
Anti Public Combo List	2016-12-16	In December 2016, a huge list of email address and password pairs appeared in a "combo list" referred to as "Anti Public" The list contained 458 million unique email addresses, many with multiple different passwords hacked from various online systems. The list was broadly circulated and used for "credential stuffing" that is attackers employ it in an attempt to identify other online systems where the account owner had reused their password. For detailed background on this incident, read Password reuse, credential stuffing and another billion records in Have I Been Pwned .
Apollo	2018-07-23	In July 2018, the sales engagement startup Apollo left a database containing billions of data points publicly exposed without a password /a>. The data was discovered by security researcher Vinny Troia /a> who subsequently sent a subset of the data containing 126 million unique email addresses to Have I Been Pwned. The data left exposed by Apollo was used in their "revenue acceleration platform" and included personal information such as names and email addresses as well as professional information including places of employment, the roles people hold and where they're located. Apollo stressed that the exposed data did not include sensitive information such as passwords, social security numbers or financial data. The Apollo website has a contact form /a> for those looking to get in touch with the organisation.

2. Check Pwned Domains

Enrichment capability for gathering pwned domain details.

Following is the **Check Pwned Domains** enrichment capability details.

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes
Domain	Domain to be queried	Domain Keyword Unknown	Yes	Yes
Do not Use Cache	SOAR does not use cached results if this box is checked	Checkbox	N/A	No

Output:

Capabilities Page 286 of 594

Case Scope: N/A

Human Readable Output:

Breach	Domain	Date	Description
Acneorg	acne.org	2014-11-25	In November 2014, the acne website acne.org suffered a data breach that exposed over 430k forum members' accounts. The data was being actively traded on underground forums and included email addresses, birth dates and passwords.

3. Check Pwned Pastes

Enrichment capability for listing the paste sites that pwned account is mentioned.

Following is the **Check Pwned Pastes** enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes
Email Address	Email address to be queried	Email Address Username Keyword Unknown	Yes	Yes
Do not Use Cache	SOAR does not use cached results if this box is checked	Checkbox	N/A	No

Output:

Human Readable Output:

Source	Paste Title	ld	Date
AdHocUrl	www.pemiblanc.com	http://www.pemiblanc.com/test.txt	
Pastebin	Braydooon	SvZR2M9L	2014-05-12T22:05:00Z
Pastebin	aibudgoadgb	jdDgA26z	2014-07-04T22:07:00Z
Pastebin	something	z6fMvVdt	2014-07-12T21:07:00Z
Pastebin	WARZ ACCOUNTS	4jytVNct	2014-12-05T01:12:00Z
Pastebin	Funny Passwords	mUKY4AL5	2014-12-30T19:15:00Z
Pastebin		1a33mzkW	2015-01-06T08:56:00Z
Pastebin	//3x0// R I=3G5	SFCp5Dxc	2015-02-12T19:02:00Z
Pastebin	//3x0// R I=3G5.	WKpdpyEM	2015-02-12T19:03:00Z
Pastebin	10k+ US Combolist	Qm1yQmVb	2015-07-12T03:33:10Z
Pastebin		1v22W7TG	2018-08-12T15:19:16Z

Capabilities Page 287 of 594

Integration Guide for Generic HTTP SMS Gateway

Integration Overview

ArcSight SOAR uses Generic HTTP SMS (Short Message Service) Gateway to send SMS.

Integration Capabilities

None

Configuration

Configuring Generic HTTP SMS Gateway

- Access to File HTTPS service as SOAR uses it to connect to Generic HTTP SMS Gateway
- A SOAR user account

Configuring SOAR

- 1. To create the integration, navigate to Configuration > Integrations.
- 2. Specify the following parameter values in the Integrations Editor form.

Parameter	Value
Name	Display name of the integration
Туре	Generic HTTP SMS Gateway
Address	Address of the integration (in the following format: 1.1.1.1 or abc.example.com)

Parameter	Value			
Configuration	Specify the following configuration parameters:			
	<pre>http.method = POST http.auth.enabled = false params.jobID = \${credential.privateKey} params.url = http://dev.swh.soarlabs.io/atar/ params.username = \${credential.username} params.text = \${text} params.gsmNumber = \${recipient} http.header.User-Agent = SOAR http.header.Content-Type = application/x-www-form-urlencode sms.stripCountryCode = +90</pre>			
Credential	Credential that was defined for this integration under the Credentials menu			
Trust Invalid SSL Certificates	Select this if device's certificate is self-signed or is not recognized by browsers			
Require Approval From	Select users from the list who can provide approval before executing actions on this integration			
Notify	Select users from the list to notify when SOAR performs an action on this integration			

- 3. Click Test to test the integration.
- ${\bf 4.} \quad {\bf Click} \ {\bf Save} \ {\bf to} \ {\bf complete} \ {\bf integration}.$

Configuring SOAR Page 289 of 594

Integration Guide for HTTP Proxy

Integration Overview

ArcSight SOAR uses HTTP proxies to access HTTP services. Some integration plugins are capable of accessing resources on the Internet or other networks through a proxy device configuration. See the respective integration guides for configuring the proxy.

Configuration

Prerequisites

- · Access to proxy service for SOAR
- A user account to connect to proxy if proxy authentication enabled

Configuring HTTP Proxy

HTTP Proxy software must be configured to get the access to SOAR. You can consult the system to know the HTTP Proxy used in the network.

Configuring SOAR

- Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the Credential Editor:

Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (for example, HTTP Proxy Credentials)
Username	User that was created on HTTP proxy software for SOAR
Password	Password of the user that was created on HTTP proxy software for SOAR
Private Key	Empty

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form:

Parameter	Value			
Name	Display name of HTTP Proxy integration on SOAR			
Туре	HTTP Proxy			
Address	Address of the integration (in the following format: https://192.168.1.3:8081)			
Configuration	Specify the following configuration parameters:			
	<pre># Supported values: basic, ntlm, none # For NTLM, username in credential should be specified like: username@domain authentication.type=basic # URL to use when testing availability of this proxy integration. # Defaults to the value of HttpProxyCheckURL configuration parameter.</pre>			
Credential	Name of the credential set created on step 2 (For example, HTTP Proxy Credentials)			
Trust Invalid SSL Certificates	Select this if Web UI's certificate certificate is self-signed or is not recognized by browsers			
Require Approval From	Select users from the list who can provide approval before executing actions on this integration			
Notify	Select users from the list to notify when SOAR performs an action on this integration			

- 5. Click **Test** to test the integration.
- 6. Click **Save** to complete the integration.

Additional Notes

For SOAR to perform Automatic Update Checks, navigate to **Configuration > Parameters** and set ProxyIntegrationIdForAutomaticUpdateCheck.

Configuring SOAR Page 291 of 594

Integration Guide for IBM Security X-Force

Integration Overview

IBM X-Force Exchange is a cloud-based threat intelligence platform that enables users to research security threats, search attack indicators, aggregate actionable intelligence, and collaborate with peers.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with IBM X-Force Exchange:

- DNS Records
- IP Report
- · Malware for File Hash
- Send File for Analysis
- URL Report

Use Case: Investigating Phishing Campaigns

SOAR follows the user's email inbox for phishing reports and automatically creates an incident record on its service desk. While investigating the attack, SOAR extracts the sender address, IP address, URLs in the message body, files in the attachment, and checks with IBM X-Force Exchange if these attacks are previously analyzed. This investigation can either be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites


- Access to https://api.xforce.ibmcloud.com (443/tcp port) for SOAR to connect to IBM X-Force Exchange API
- An API key for SOAR to connect to IBM X-Force Exchange

Configuring IBM X-Force Exchange

- 1. Log in to https://exchange.xforce.ibmcloud.com.
- 2. To create a new API key, navigate to **Settings > API Access**.



Note: Save the generated API key and the password.



Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the Credential Editor:
 - a. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, IBM X-Force Exchange Credentials)
Username	API Key created on IBM X-Force Exchange
Password	API Password for the key created on IBM X-Force Exchange
Private Key	Empty

b. Credential Store:


Parameter	Value		
Туре	External Credential		
Name	Name of the credential with pull path of the safe on store		

3. Click Configuration > Integrations > Create Integration.

4. Specify the following parameter values in the **Configuration** form:

Parameter	Value				
Name	Display name of IBM X-Force Exchange integration on SOAR				
Туре	IBM X-Force Exchange				
Address	Address of the integration (https://api.xforce.ibmcloud.com)				
Configuration	Specify the following configuration parameters:				
	<pre># Integration ID of the proxy integration to use when connecting # to current integration. # If not provided, SOAR will try to use a direct connection. #proxy.id=123 # configure how far (in minutes) into the past this enrichment will look. cache.reusing.duration=60</pre>				
Credential	Name of the credential set created on step 2 (For example, IBM XForce Exchange Credentials)				
Trust Invalid SSL Certificates	Select this if Web UI's certificate is self-signed or is not recognized by browsers				
Require Approval From	Select users from the list who can provide approval before executing actions on this integration				
Notify	Select users from the list to notify when SOAR performs an action on this integration				

Configuring SOAR Page 294 of 594



- 5. Click **Test** to test the integration.
- 6. Click **Save** to complete the integration.

Configuring SOAR Page 295 of 594

Integration Guide for Infoblox DNS Firewall

Integration Overview

Infoblox DNS Firewall defends DNS servers from the comprehensive range of DNS-based attacks while maintaining service availability and business continuity. The Grid Manager web interface provides access to the appliance for network and IP address management.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Infoblox DNS Firewall:

- Block IP address (No Data)
- Block IP Address (No Such Domain)
- Block Host (No Data)
- Block Host (No Such Domain)
- Substitute DNS A Record

Use Case: Blocking malicious IP addresses on DNS

SOAR integrates with Infoblox DNS firewall to block malicious IP addresses and hosts on DNS firewall to stop malware attacks and protect users. These actions can either be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- Infoblox NIOS 8.4 version
- Access to tcp port 443 as SOAR connects to Infoblox DNS Firewall API
- A SOAR user account to connect Infoblox DNS Firewall

Configuring Infoblox DNS Firewall

- Navigate to Administration > Administrators > Admins.
- 2. To add an account, specify the following values in the Add Administrator Wizard:

Authentication Type: Local

Login: <Specify the username>

Password: <Specify the password>

Confirm Password: <confirm the password specified in Password field>

Admin Group: Select admin-group

3. To create a new Response Policy Zone, navigate to **Data Management** > **DNS** > **Response**

Policy Zones.

Configuring SOAR

1. Click Configuration > Credentials > Create Credential.

2. Specify the following parameter values in the **Credential Editor**:

a. Internal Credential

Parameter	Value		
Туре	Internal Credential		
Name	Display name of credential set (For example, Infoblox DNS FW Credentials)		
Username	User created for SOAR on Infoblox DNS FW		
Password	API Password for the key created for SOAR on Infoblox DNS FW		
Private Key	Empty		

b. Credential Store:

Parameter	Value		
Туре	External Credential		
Name	Name of the credential with pull path of the safe on store		


3. Click Configuration > Integrations > Create Integration.

Configuring SOAR Page 297 of 594

4. Specify the following parameter values in the **Configuration** form:

Parameter	Value				
Name	Display name of Infoblox DNS Firewall integration on SOAR				
Туре	Infoblox DNS Firewall				
Address	Address of the integration (in the following format: https://192.168.2.53)				
Configuration	Specify the following configuration parameters:				
	<pre># Name of View under which rp_zone is located. view=default # Name of Response Policy Zone that SOAR will write block rules rp_zone=mitigated.local # Default name and value of extensible attrbute which SOAR uses to write comment for block extensible.attribute.name= extensible.attribute.value= # IP address that SOAR uses to substitute in DNS A records. substitute.ip.address=127.0.0.1 #proxy.id=5442</pre>				
Credential	Name of the credential set created on step 2 (For example, Infoblox DNS FW Credentials)				
Trust Invalid SSL Certificates	Select this if Web UI's certificate is self-signed or is not recognized by browsers				
Require Approval From	Select users from the list who can provide approval before executing actions on this integration				
Notify	Select users from the list to notify when SOAR performs an action on this integration.				

Configuring SOAR Page 298 of 594



- Click **Test** to test the integration.
- 6. Click **Save** to complete the integration.

Additional Notes

Infoblox DNS Firewall allows blocking IP and host with only one rule type (either No Data or No Such Domain). If you try to block an IP or host that already got blocked with another rule type, you might get an error.

Integration Guide for Intezer

Integration Overview

Intezer is a malware analysis tool that automates alert triage, incident response and threat hunting.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Intezer:

- Analyze Hash
- Get Sub-Analyses
- · Get File Metadata
- Code Reuse Families
- · Get Related Files

Prerequisites

- ArcSight SOAR connects to the https://analyze.intezer.com/ API through HTTPS. Access to this service is required.
- Intezer requires an API key for access.

Configuration

Configuring Intezer

- Intezer requires an API key for access.
- Users can obtain an API key from intezer.com after logging in with valid credentials.

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the Credential Editor:

Туре	Name	Username	Password	Private Key
Internal Credential	Display name of credential set (for example Intezer).	Empty	Empty	API Key created on Intezer

3. Click Configuration > Integrations > Create Integration

4. Specify the following parameter values in the **Configuration Form**:

Parameter	Value
Name	Display name of the integration.
Туре	Intezer.
Address	Address of the integration (the format must be https://s3.amazonaws.com).
Configuratio	Specify the following configuration parameters:
n	<pre># Integration ID of the proxy integration to use when connecting to current integration. # If not provided, ArcSight SOAR will try to use a direct connection. #proxy.id=123 # configure how far (in minutes) into the past this enrichment will look. #cache.reusing.duration=20</pre>
Credential	Name of the credential set created in step 2. (i.e. Intezer Credentials).
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or not recognized by browsers. Not selected.
Require Approval From	Select user(s) from list to ask the approval before executing actions on this integration.
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.

- 5. Click Save.
- 6. Navigate to Configuration > Customization Library and edit Intezer Advanced Action Script Default Script Template.
- 7. Select the integration that you have created in step 4 from the **Integrations** drop-down menu and click **Save**.
- 8. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. Analyze Hash

Enrichment capability for retrieving details of a file hash.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the 3rd party integration.	Integration	N/A	Yes
Hash	SHA256, SHA1, or MD5 hash value.	Hash	Yes	Yes

Capabilities Page 301 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Do not Use Cache	SOAR does not use cached results if this box is checked.	Boolean	N/A	No

Case Scope

Action	Туре	Category/Value
Add	Scope Item	Intezer Hash Value (SHA1, SHA256, MD5)
Set	Scope Item Property	Intezer Verdict
Set	Scope Item Property	Intezer Malware Family

Human Readable Output

2. Get Sub-Analyses

Enrichment capability for retrieving all sub-analyses of an Intezer analysis ID.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the 3rd party integration.	Integration	N/A	Yes
Analysis ID	Intezer analysis ID. Can be retrieved from the human readable output of the 'Analyze Hash' enrichment.	String	No	Yes
Do not Use Cache	SOAR does not use cached results if this box is checked.	Boolean	N/A	No

Output:

Case Scope

N/A

Human Readable Output

3. Get File Metadata

Enrichment capability for retrieving the file metadata for an Intezer analysis ID and subanalysis ID.

Capabilities Page 302 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the 3rd party integration.	Integration	N/A	Yes
Analysis ID	Intezer analysis ID. Can be retrieved from the human readable output of the 'Analyze Hash' enrichment.	String	No	Yes
Sub-Analysis ID	Intezer sub-analysis ID. Can be retrieved from the human readable output of the 'Get Sub-Analyses' enrichment.	String	No	Yes
Do not Use Cache	SOAR does not use cached results if this box is checked.	Boolean	N/A	No

Case Scope

Action	Туре	Category/Value
None	N/A	N/A

Human Readable Output

4. Code Reuse Families

Enrichment capability for retrieving the malware family code reuse data for an Intezer analysis ID and sub-analysis ID.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the 3rd party integration.	Integration	N/A	Yes
Analysis ID	Intezer analysis ID. Can be retrieved from the human readable output of the 'Analyze Hash' enrichment.	String	No	Yes
Sub-Analysis ID	Intezer sub-analysis ID. Can be retrieved from the human readable output of the 'Get Sub-Analyses' enrichment.	String	No	Yes

Output:

Case Scope

Action	Туре	Category/Value
None	N/A	N/A

Human Readable Output

5. Get Related Files

Capabilities Page 303 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the 3rd party integration.	Integration	N/A	Yes
Analysis ID	Intezer analysis ID. Can be retrieved from the human readable output of the 'Analyze Hash' enrichment.	String	No	Yes
Sub-Analysis ID	Intezer sub-analysis ID. Can be retrieved from the human readable output of the 'Get Sub-Analyses' enrichment.	String	No	Yes
Family ID	Intezer family ID. Can be retrieved from the human readable output of the 'Code Reuse Families' enrichment.	String	No	Yes

Case Scope

N/A

Human Readable Output

Capabilities Page 304 of 594

Integration Guide for Invictus USTA ThreatIntelligence

Integration Overview

Invictus USTA is a threat intelligence service which delivers cyber-threat insights in real time.

Integration Capabilities

- Ingest Threat Intelligence Feed as Alert
- Check Identity Leak
- Check Stolen Client Account
- Check Domain Info
- Check Hash Info
- Check IP Info
- Check URL Info
- Submit Bad Sender
- Submit Referer URL

Use Case: Blocking malicious URLs and IPs before they harm

ArcSight SOAR integrates with USTA intelligence feed to block malicious entities on your perimeter protection before they harm.

Use Case #2: Investigating Fraud and ID Theft

SOAR integrates with USTA Threat Intelligence to investigate fraud cases, possible ID theft, and cases of client account compromises.

Configuration

Prerequisites

- Access to https://usta01.invictuseurope.com/api/ (443/tcp port) for SOAR to connect to USTA API
- An API Key for SOAR to connect to Invictus USTA API

Configuring Invictus USPA

Invictus USTA requires no specific configuration.

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the Credential Editor:
 - a. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example,Invictus USTA Credentials)
Username	Empty
Password	Empty
Private Key	API Key obtained from Invictus USTA platform

b. Credential Store:

Parameter	Value
Туре	External Credential
Name	Name of the credential with pull path of the safe on store

Configuring Invictus USTA as Alert Source

- 1. Click Configuration > Alert Source > Create Alert Source Configuration.
- 2. Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of Invictus USTA Alert Source on SOAR
Туре	USTA
Address	Address of the Invictus USTA Threat Intelligence Service (https://usta01.invictuseurope.com/api/)
Alert Severities	Mapping of alert severity values to SOAR incident severities

Parameter	Value
Configuration	Specify the following configuration parameters:
ŭ	<pre># Ignore events older than specified date. If empty, date based filtering is disabled. # Example: filterOlderThanDate=2017-01-01 filterOlderThanDate=2020-01-10 # Integration ID of the proxy integration to use when connecting to current source. # If not provided, SOAR will try to use a direct connection. #proxy.id=5523</pre>
Credential	Name of the credential set just created. (For example, Invictus USTA Credentials)
Trust Invalid SSL Certificates	Select this if Web UI's certificate is self-signed or is not recognized by browsers
Visible Alert Fields	Define the alarm fields to be displayed on Incident Management Service Desk

- 3. Click **Test** to test the integration.
- 4. Click **Save** to complete the integration.

Configuring Invictus USTA as Integration

- 1. Click Configuration > Integrations > Create Integration.
- 2. Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of Invictus USTA integration on SOAR
Туре	USTA
Address	Address of the Invictus USTA Threat Intelligence Service (https://usta01.invictuseurope.com)
Configuration	Specify the following configuration parameters:
	<pre># Integration ID of the proxy integration to use when connecting to current source. # If not provided, SOAR will try to use a direct connection. #proxy.id=5523#proxy.id=5523</pre>
Credential	Name of the credential set created on step 2 (For example, Invictus USTA Credentials)

Trust Invalid SSL Certificates	Select this if Web UI's certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an action on this integration.

- 3. Click **Test** to test the integration.
- 4. Click **Save** to complete the integration.

Additional Notes

USTA permits connection requests from specific network addresses for each customer. Hence, make sure to check the access permission by USTA before integration.

Additional Notes Page 308 of 594

Integration Guide for IPInfo

Integration Overview

IPinfo is a solution for IP data which offers both free and paid API tokens to put IP geolocation, ASN, IP to company, mobile carrier, and many more.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with IPinfo:

IP Query

Configuration

Prerequisites

- You must have access to HTTPS as ArcSight SOAR connects to IPinfo through this service.
- IPinfo requires an API key for access.

Configuring SOAR

- Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor** form:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, IPinfo Credential).			Access token

- a. Click Configuration > Integrations > Create Integration.
- b. Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of the integration.
Туре	IPinfo.io
Address	Address of the integration (the format should be https://ipinfo.io).

Parameter	Value		
Configuration	Specify the	e following configuration parameters:	
	proxy.id	ID of the Proxy integration if you access ipinfo.io through a web proxy device. For example: proxy.id = 12345	
Credential	Credential that has been defined for this integration under the Credentials menu.		
Trust Invalid SSL Certificates	Select this if web server's certificate is self-signed or is not recognized by browsers.		
Require Approval From	Select user(s) from list to ask the approval before executing actions on this integration.		
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.		

- c. Click **Save** to save the integration definition.
- d. Navigate to Configuration>Customization Library and edit IPinfo Advanced Action Script Default Template.
- e. Select the integration that you have added to Integrations menu.
- f. Click **Save** to complete the integration.
- g. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

a. IP Query

Enrichment capability for retrieving information regarding an IP.

The following table presents the IP Query enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
IP	Network address to be queried from IPInfo .	Network Address	Yes	Yes
Do not Use Cache	SOAR does not use cached results if this box is checked.	Boolean	N/A	No


Output:

Case Scope:

Capabilities Page 310 of 594

Enrichment	Туре	Category/ Value
None	N/A	N/A

Human Readable Output:



Capabilities Page 311 of 594

Integration Guide for Jira

Integration Overview

Jira is an ITSM service that provides issue management to users.

Unlike our other plugins, this plugin consists of two modules. One was developed as a custom script in SOAR to perform actions on Jira, and the other as an add-on in Jira to perform actions on the SOAR product. We aimed that both products keep each other informed of certain changes on each other. SOAR is using Jira API to perform operations on Jira, and Jira is using our newly developed SOAR API to perform operations on SOAR through the add-on we developed. Issue creation must be initiated with SOAR, so we can mark the issue and track it both sides.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Jira:

- Create Issue
- Send Comment
- Update Issue
- Update Issue Status


Prerequisites

You must have access to HTTPS as the ArcSight SOAR connects to Jira API through this service and Jira connects to SOAR through this service.

Configuration

Configuring SOAR

- 1. Navigate to ITOM Management and click the Three dots button for deployment and select Reconfigure.
- 2. Click **SOAR** tab. On the **REST API** fields, specify values for one of them and keep a note of it, as shown in the following figure:





Note: You can note down the Client Id Suffix and Client Secret values to be used later.

- 3. Click Save
- 4. Navigate to SOAR application and click Configuration > Credentials > Create Credential.
- 5. Specify the following parameter values in the Credential Editor:

Parameter	Value
Туре	Internal credential.
Name	Display name of credential set (for example, Jira Credentials)
Username	Jira User Username.
Password	Jira User Password.
Private Key	

- 6. Click Save.
- 7. Click Configuration > Lists > Create List. Give the list a name (for example, jiraLookup).



Note: SOAR is going to map SOAR cases and Jira issues on this list for both sides.

- 8. Click Save
- 9. Click Configuration > Integration > Create Integration
- 10. Specify the following parameter values in the Configuration Form:

Parameter	Value
Name	Display name of Jira integration on SOAR.
Туре	Jira
Address	Address of the integration (for example, https://192.168.200.231:8080).
proxy.id	ID of the Proxy integration if accessing the jira service through a web proxy device. For Example: proxy.id = 12345.
list.name	Parameter must be equal to list name that is given at step 8. (for example, list.name=jiraLookup).

Configuring SOAR Page 313 of 594

Parameter	Value
Credential	Name of the credential set created on step 5(for example, Jira Credentials).
Trust Invalid SSL Certificates	Select this if service's certificate is self-signed or is not recognized by browsers.
Required Approval From	Select users from the list who can provide approval before executing actions on this integration.
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.

- 11. Click Save.
- 12. Navigate to Configuration > Customization Library > Open Jira Script.
- 13. Select integration that is newly created in the Integrations field.
- 14. Click **Save** to complete the integration.
- 15. Click **Test**, an **Integration Successful** message is displayed if the address and credential are valid.

Configuring Jira

- 1. Navigate to Jira Administration Manage apps.
- 2. Click **Upload app** and choose the Jira add-on jar file that is provided. After the installation completion, the plugin is visible in the **User-installed** apps.



Note: You can also download the Jira add-on jar file from Marketplace.

- Click Configure. Specify the values for Base URL, Client ID, Client Secret (as noted during creating an API user in Configuring SOAR part) and SOAR username (SOAR needs a JIRA user to access Jira service).
- 4. Click Save.



Note: Now you can start creating issue on Jira by Create Issue capability on SOAR.

Capabilities

1. Create Issue

Action capability for creating issue on Jira.

The following table presents the **Create Issue** action capability details:

Configuring Jira Page 314 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Project Key	Key of the project that you want to create issue in it.	Text	No	Yes
Issue Type	Type of the issue.	Text	No	Yes
Summary	Summary of the issue.	Text	No	Yes
Description	Description of the issue.	Text	No	Yes

Case Scope: N/A

Human Readable Output: N/A

2. Send Comment

Action capability for sending comment to related issue.

The following table presents the **Send Comment** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Comment	Comment that you want to add to the issue.	Text	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

3. Update Issue

Action capability for updating attributes of the issue

The following table presents the **Update Issue** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Summary	Summary of the issue.	Text	No	No
Description	Description of the issue.	Text	No	No
Assignee	Assignee of the issue.	Text	No	No
Priority	Priority of the issue.	Text	No	No

Output:

Case Scope: N/A

Human Readable Output: N/A

4. Update Issue Status

Action capability for updating status of the issue.

The following table presents the **Update Issue Status** action capability details:

Capabilities Page 315 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Status	Status of the issue	ComboBox (Elements of the combobox are changeable by the script code)	No	Yes

Case Scope: N/A

Human Readable Output: N/A



Note: We are supporting Update Status, Update Severity, Update Description, Update Subject and Add Comment capabilities through SOAR application. If the Jira user changes any of the related items in the Jira issue, and if that issue description contains SoarCaseId then the prepared API requests are sent to SOAR.

SOAR then adds the SOAR CaseId into description-field during the creation of the Jira Issue. The Add-On uses this SoarCaseId for SOAR API requests.

Capabilities Page 316 of 594

Integration Guide for JDBC(Database) Server

Integration Capabilities

ArcSight SOAR has the following integration capability with database servers:

JDBC Query

Use Case: Querying HR Database

With this integration, while investigating an incident SOAR can run a query on HR database to see if they are logged on the user on a suspicious endpoint. This can either be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- A database listener or service for SOAR to access.
- Create a DB user account for SOAR to run the SQL queries.

Configuring Database Server

Please contact database administrator for user account and access permissions.

Configuring SOAR

- Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor**:

a. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, JDBC Credentials)
Username	User account that was configured on database server
Password	Password for user account that was configured on database server
Private Key	Empty


b. Credential Store

Parameter	Value
Туре	External Credential
Name	Name of the credential with pull path of the safe on store.

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form:

Parameter	Value	
Name	Display name of Database Server integration on SOAR	
Туре	Database Server	
Address	Address of the integration (in the format	
	jdbc:driverName://192.168.3.10:5432/databaseName).	
Configuration	Specify the following configuration parameters:	
	<pre># For MySQL: db.driverClass=com.mysql.jdbc.Driver # For Oracle: db.driverClass=oracle.jdbc.OracleDriver # For PostgreSQL: db.driverClass=org.postgresql.Driver # For MSSQL Server: db.driverClass=com.microsoft.sqlserver.jdbc.SQLServerDriver db.driverClass= db.driverClass=org.postgresql.Driver # Absolute path where you put the JDBC driver's JAR file. db.driverPath= # configure how far (in minutes) into the past this enrichment will look. cache.reusing.duration=30</pre>	
Credential	Name of the credential set created on step 2. (For example, Database Server Credentials).	
Trust Invalid SSL Certificates	Select this if device's certificate is self-signed or is not recognized by browsers	
Require Approval from	Select users from the list who can provide approval before executing actions on this integration	
Notify	Select users from the list to notify when SOAR performs an action on this integration.	

Configuring SOAR Page 318 of 594



- 5. Click **Test**. The following pop up will be displayed if your credential and address are valid.
- 6. Click **Save** to complete integration.

Configuring SOAR Page 319 of 594

Integration Guides for Kannel SMS Gateway

Integration Overview

Kannel is an open source SMS Gateway which is used widely for sending in either single or bulk SMS(Short Message Service). Kannel links HTTP based services to various SMS centers using various protocols.

Integration Capabilities

Supported Action Capabilities

Kannel SMS Gateway allows user notifications using SMS messages which was set when creating the Playbook involving this integration.

Configuration

Configuring Kannel SMS Gateway

Configure the integration to send SMS messages.


Configuring SOAR

Following are the steps to create the integration:

- 1. Navigate to Configuration > Parameters.
- 2. Configure SMS Device to be used as the ID of Kannel SMS Gateway integration.
- 3. To configure the integration, navigate to **Configuration > Integrations**.
- 4. Specify the following parameter values in the Integration Editor:

Parameter	Value
Name	Display name of Kannel SMS Gateway integration on SOAR
Туре	Kannel SMS Gateway

Parameter	Value
Address	Address of the integration (in the following format: 1.1.1.1:1234)
Configuration	sms.sender= <specify configured="" device="" field="" in="" sms="" the="" value=""></specify>
Credential	Name of the credential set created on step 2
Trust Invalid SSL Certificates	Select this if Integrations's certificate is self-signed or is not recognized by browsers.
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an action on this integration



- 5. Click **Test** to test the integration.
- 6. Click **Save** to complete the integration.

Configuring SOAR Page 321 of 594

Integration Guide for Kaspersky Security Center

Integration Overview

ArcSight SOAR is capable of communicating with Kaspersky Security Center through WinRM and Powershell to block hashes, add tags to hosts, run tasks, move hosts to groups and retrieve information about various management objects.

Integration Capabilities

- Block (blacklist) SHA-256 or MD5 hash, with rollback support
- Add tag to host, with rollback support
- Move host to group
- Run task
- Retrieve host information

Configuration

Configuration on Kaspersky Security Center

- To define a Kaspersky Security Center installation as an integration on your SOAR, following integration specific configuration should be performed.
 - SOAR should be able to access the server with Kaspersky Security Center through WinRM on the network; usually with TCP port 5985 or 5986 (if SSL is enabled on WinRM). See WinRM Integration Guide for details on how to configure WinRM access.
 - A local or domain administrator user account is required execute various capabilities.
 - 32-bit version of Windows Scripting Host (which is available on a default Windows installation) is required to execute built-in scripts, which is usually located at C:\Windows\SYSWOW64\cscript.exe.

Configuring SOAR

- While creating this integration via Integrations tab of Configuration menu:
- Name: Display name of the integration.
- Address: Address of the integration. Format of the address should be

IP, IP:port, dns.hostname.localnet, or dns.hostname.localnet:port for HTTP;

or prefixed with https:// if HTTPS/SSL listener was enabled on WinRM.

• Credential: Credential that has been defined for this integration under the Credentials menu.

Optional configuration

- blockhash.categoryname: Category name to add block hashes into; if unspecified defaults to SOAR. If specified category name doesn't exist, it will be automatically created.
- path.cscriptexe: Location of the 32-bits version of the cscript.exe on server.

If unspecified, defaults to "C:\\Windows\\SysWOW64\\cscript.exe".



Note: The backslashes must be escaped and double-backslash is required.

Overriding built-in scripts

SOAR allows overriding built-in scripts using Customization Library. Create a new customization of **Basic plugin script**, take note of its ID, and set the value of the script you'd like to override in the integration configuration by specifying its identifier as specified below:

Parameter Name	Description	
enrichment.gettasknames	Retrieve names of tasks available for Run task capability	
enrichment.getgroupnames	Retrieve names of groups available for Move host to group capability	
enrichment.gettagnames	Retrieve names of tags available for Add tag to host capability	
enrichment.hostinfo	Retrieve host information enrichment script	
execute.blockhash	Block hash capability	
rollback.blockhash	Rollback block hash capability	
execute.addtag	Add tag capability	

Configuring SOAR Page 323 of 594

Parameter Name	Description
rollback.addtag	Rollback add tag capability
execute.movesystem	Move host to group capability
execute.runtask	Run task capability

Important points

- When these parameters are specified, built-in scripts will be ignored and the customization with specified ID will be used instead as the script. All scripts should target Windows Scripting Host with Javascript language, unless a different/compatible interpreter is specified in path.cscriptexe parameter in integration configuration. See [https://support.kaspersky.com/9291](Kaspersky Enterprise Security Administration Kit Automation10) for reference on using its COM/ActiveX API.
- SOAR's implementation is sensitive to the expected output of these scripts; overriding a
 capability with a script that doesn't write expected output to stdout may break existing
 functionality.
- Scripts are automatically evaluated as StringTemplate and various parameters are injected into the template for block hash, run task, move host into group, add tag and host information capabilities. See built-in scripts below for example usage and [http://www.stringtemplate.org](String Template Website) for more details on how to make use of the ST engine.

Example:

4214 is the ID of the customization to override this capability.

execute.runtask=4214

Built-in Tasks

Get Task Names

```
function obj(name) {
  return new ActiveXObject("klakaut.KlAk" + name);
}
try {
  var oConnectProps = obj("Params"), oAdmServer = obj("Proxy"),
  oSrvView = obj("SrvView"),
  oTasks = obj("Tasks2"), item, enumObj;
  oConnectProps.Add("Address", "127.0.0.1:13291");
  oAdmServer.Connect(oConnectProps);
```

Get Task Names Page 324 of 594

```
oTasks.AdmServer = oSrvView.AdmServer = oAdmServer;
enumObj = new Enumerator(oTasks.EnumTasks(-1));
WScript.Echo('[OK] [BEGIN]');
for (; !enumObj.atEnd(); enumObj.moveNext()) {
  item = enumObj.item();
  WScript.Echo(item.item('TASK_UNIQUE_ID') + '=' + item.item('DisplayName'));
  }
  WScript.Echo('[END]');
} catch (e) {
  WScript.Echo("[Error] " + e.number + " occured !!! " + e.description);
}
```

Get Group Names

```
function obj(name) {
return new ActiveXObject("klakaut.KlAk" + name);
function EnumerateGroups(oSubgroupsEnum) {
var enumObj = new Enumerator(oSubgroupsEnum);
for (;!enumObj.atEnd();enumObj.moveNext()) {
var oObj = enumObj.item();
WScript.Echo(oObj.Item("id") + '=' + oObj.Item("name"));
if (oObj.Check("groups")) {
EnumerateGroups(oObj.Item("groups"));
}
}
}
try {
var oConnectProps = obj("Params"), oAdmServer = obj("Proxy"),
oGroups = obj("Groups");
oConnectProps.Add("Address", "127.0.0.1:13291");
oAdmServer.Connect(oConnectProps);
oGroups.AdmServer = oAdmServer;
WScript.Echo('[OK] [BEGIN]');
EnumerateGroups(oGroups.GetSubgroups(oGroups.GroupIdGroups, 0));
WScript.Echo('[END]');
} catch (e) {
WScript.Echo("[Error] " + e.number + " occured !!! " + e.description);
}
```

Get Group Names Page 325 of 594

Get Tag Names

```
function obj(name) {
return new ActiveXObject("klakaut.KlAk" + name);
try {
var oConnectProps = obj("Params"), oAdmServer = obj("Proxy"),
oTagsControl = obj("TagsControl"), oProps = obj("Params"), oTags,
enumObj;
oConnectProps.Add("Address", "127.0.0.1:13291");
oAdmServer.Connect(oConnectProps);
oTagsControl.AdmServer = oAdmServer;
oTagsControl.Prop("ListName") = "HostsTags";
oTags = oTagsControl.GetAllTags(oProps);
WScript.Echo('[OK] [BEGIN]');
if (oTags != null) {
enumObj = new Enumerator(oTags);
for (; !enumObj.atEnd(); enumObj.moveNext()) {
WScript.Echo(enumObj.item() + "=" + enumObj.item());
}
WScript.Echo('[END]');
} catch (e) {
WScript.Echo("[Error] " + e.number + " occured !!! " + e.description);
```

Host Information Enrichment

```
function obj(name) {
  return new ActiveXObject("klakaut.KlAk" + name);
}
function ip2long(IPaddress) {
  var ip = IPaddress.match(/^(\d+)\.(\d+)\.(\d+)\.(\d+)\*/);
  return ip ? (+ip[1] << 24) + (+ip[2] << 16) + (+ip[3] << 8) + (+ip[4]) :
  null;
}
function long2ip(1) {
  return ((1 >> 24) & 255) + "." + ((1 >> 16) & 255) + "." + ((1 >> 8) & 255) +
  "." + (1 & 255);
}
function coll() {
  var ret = obj("Collection"), len = arguments.length, args = arguments;
  if (len == 1) {
   args = arguments[0].split('|');
   len = args.length;
}
```

Get Tag Names Page 326 of 594

```
ret.SetSize(len);
for (var i=0; i<len; i++) {
ret.SetAt(i, (arguments.length == 1 ? "KLHST_WKS_" : "") + args[i]);
}
return ret;
function g(a, e) {
var r = e.item('KLHST_WKS_' + a);
if (r === undefined) {
r = '';
return r;
var rtpState = ["Unknown", "Stopped", "Suspended", "Starting", "Running",
"Running (Maximum protection)", "Running (Maximum speed)",
"Running (Recommended settings)", "Running (Custom settings)",
"Failure"];
function getStatus(v) {
var r = [];
if ((v \& 1) == 1) {
r.push("Visible");
if ((v \& 4) == 4) {
r.push("Agent:Installed");
if ((v \& 8) == 8) {
r.push("Agent:Alive");
if ((v & 16) == 16) {
r.push("Real-Time-Protection:Installed");
return r.join(",");
}
try {
var oConnectProps = obj("Params"), oAdmServer = obj("Proxy"),
oHosts = obj("Hosts"), c=0;
oConnectProps.Add("Address", "127.0.0.1:13291");
oAdmServer.Connect(oConnectProps);
oHosts.AdmServer = oAdmServer;
var fieldsToReturn = "LAST_VISIBLE|STATUS|RTP_STATE|LAST_UPDATE|LAST_
FULLSCAN
WINHOSTNAME | WINDOMAIN | OS_NAME | OS_VER_MAJOR | OS_VER_MINOR | IP_LONG | PRODUCT_TAG_
NAME";
var ftr = fieldsToReturn.split('|');
var enumObj = new Enumerator(oHosts.FindHosts("(KLHST_WKS_IP_LONG=" +
ip2long('%host%') + ")", coll(fieldsToReturn), coll()));
WScript.Echo('[OK]');
for (; !enumObj.atEnd(); enumObj.moveNext()) {
```

```
var e = enumObj.item();
WScript.Echo('[' + c++ + ']' +
'LAST_VISIBLE=' + Date.parse(g('LAST_VISIBLE', e)) +
'|LAST_UPDATE=' + Date.parse(g('LAST_UPDATE', e)) +
'|LAST_FULLSCAN=' + Date.parse(g('LAST_FULLSCAN', e)) +
'|WINHOSTNAME=' + g('WINHOSTNAME', e) +
'|WINDOMAIN=' + g('WINDOMAIN', e) +
'|OS=' + g('OS_NAME', e) + ' (' + g('OS_VER_MAJOR', e) + '.' +
g('OS_VER_MINOR', e) + ')' +
'|IP=' + long2ip(g('IP_LONG', e)) +
'|RTP_STATE=' + rtpState[g('RTP_STATE', e)] +
'|STATUS=' + getStatus(g('STATUS', e)) +
'|PRODUCT_TAG_NAME=' + g('PRODUCT_TAG_NAME', e)
);
}
WScript.Echo("[END] Retrieved information for " + c + " hosts.");
WScript.Echo("[Error] " + e.number + " occured !!! " + e.description);
}
```

Block Hash Action Capability

```
var hashes = [%hashes: {h | "%h%"}; separator=", "%];
function obj(name) {
return new ActiveXObject("klakaut.KlAk" + name);
try {
var oConnectProps = obj("Params"), oAdmServer = obj("Proxy"),
oCategory = obj("FileCategorizer"), oFields2Return = obj("Collection"),
oSrvView = obj("SrvView");
oConnectProps.Add("Address", "127.0.0.1:13291");
oAdmServer.Connect(oConnectProps);
oCategory.AdmServer = oSrvView.AdmServer = oAdmServer;
oFields2Return.SetSize(2);
oFields2Return.SetAt(0, "id");
oFields2Return.SetAt(1, "name");
var enumObj = new Enumerator(oSrvView.GetChunkAccessor
('customcategories',
'(name = "*")', oFields2Return, obj("Collection"))), catFound = null;
for (; !enumObj.atEnd(); enumObj.moveNext()) {
var item = enumObj.item();
if (item.item('name') === '%categoryname%') {
catFound = item.item('id');
// dump("", "", item, false);
// dump("", "", oCategory.GetCategory(item.item('id')), false);
```

```
var oCatToAdd, oInclProps, i, oCatProps = obj("Params"), oCatData = catFound
oCategory.getCategory(catFound) : null, oInclusions = catFound ?
oCatData.Item('inclusions') : obj("Collection");
for (i=0; i<hashes.length; i++) {</pre>
oInclProps = obj("Params");
oInclProps.Add('ex_type', 3);
oInclProps.Add(hashes[i].length == 32 ? 'str' : 'str2', hashes[i]);
oInclProps.Add('str_op', 0);
oInclusions.SetSize(oInclusions.Count + 1);
oInclusions.setAt(oInclusions.Count - 1, oInclProps);
}
if (!catFound) {
oCatProps.Add('name', '%categoryname%');
oCatProps.Add('CategoryType', 0);
oCatProps.Add('inclusions', oInclusions);
oCatToAdd = oCategory.CreateCategory(oCatProps);
WScript.Echo("[OK] [CREATED] Added " + hashes.length +
' hashes to newly created category: %categoryname%');
} else {
oCategory.UpdateCategory(catFound, oCatData);
WScript.Echo("[OK] [UPDATED] Added " + hashes.length +
' hashes to existing category: %categoryname% its current size is: '
+ oInclusions.Count);
} catch (e) {
WScript.Echo("[Error] " + e.number + " occured !!! " + e.description);
```

Rollback of block hash capability

```
var hashes = [%hashes: {h | "%h%"}; separator=", "%];
function obj(name) {
  return new ActiveXObject("klakaut.KlAk" + name);
}
try {
  var oConnectProps = obj("Params"), oAdmServer = obj("Proxy"),
  oCategory = obj("FileCategorizer"), oFields2Return = obj("Collection"),
  oSrvView = obj("SrvView");
  oConnectProps.Add("Address", "127.0.0.1:13291");
  oAdmServer.Connect(oConnectProps);
  oCategory.AdmServer = oSrvView.AdmServer = oAdmServer;
  oFields2Return.SetSize(2);
  oFields2Return.SetAt(0, "id");
  oFields2Return.SetAt(1, "name");
```

```
var enumObj = new Enumerator(oSrvView.GetChunkAccessor('customcategories',
'(name = "*")', oFields2Return, obj("Collection"))), catFound = null;
for (; !enumObj.atEnd(); enumObj.moveNext()) {
var item = enumObj.item();
if (item.item('name') === '%categoryname%') {
catFound = item.item('id');
}
if (!catFound) {
WScript.Echo("[OK] [DOESNTEXIST] Category %categoryname% doesn't exist,
no need to remove anything.");
} else {
var oCatData = oCategory.getCategory(catFound),
oInclusions = oCatData.Item('inclusions'),
oNewInclusions = obj("Collection"), i, j, k=0;
for (j=0; j<oInclusions.Count; j++) {</pre>
for (i=0; i<hashes.length; i++) {</pre>
var incl = oInclusions.Item(j);
if (incl.Item('str') !== hashes[i] && incl.Item('str2') !== hashes[i]) {
oNewInclusions.SetSize(oNewInclusions.Count + 1);
oNewInclusions.setAt(oNewInclusions.Count - 1, incl);
} else {
k++;
}
oCatData.Item('inclusions') = oNewInclusions;
oCategory.UpdateCategory(catFound, oCatData);
WScript.Echo("[OK] [UPDATED] Removed " + k + " of " + hashes.length +
' hashes from category: %categoryname% its current size is: ' +
oNewInclusions.Count);
}
} catch (e) {
WScript.Echo("[Error] " + e.number + " occured !!! " + e.description);
}
```

Add tag to host capability

```
function obj(name) {
  return new ActiveXObject("klakaut.KlAk" + name);
}
function ip2long(IPaddress) {
  var ip = IPaddress.match(/^(\d+)\.(\d+)\.(\d+)\.(\d+)\$/);
  return ip ? (+ip[1] << 24) + (+ip[2] << 16) + (+ip[3] << 8) + (+ip[4]) :
  null;
}</pre>
```

```
try {
var oConnectProps = obj("Params"), oAdmServer = obj("Proxy"),
oTagsControl = obj("TagsControl"), oHosts = obj("Hosts"),
oFields2Return = obj("Collection"), enumObj, taggedHosts = 0;
oConnectProps.Add("Address", "127.0.0.1:13291");
oAdmServer.Connect(oConnectProps);
oTagsControl.Prop("ListName") = "HostsTags";
oTagsControl.AdmServer = oHosts.AdmServer = oAdmServer;
oFields2Return.SetSize(1);
oFields2Return.SetAt(0, "KLHST_WKS_HOSTNAME");
enumObj = new Enumerator(oHosts.FindHosts("(KLHST_WKS_IP_LONG=" +
ip2long('%host%') +
")", oFields2Return, obj("Collection")));
for (; !enumObj.atEnd(); enumObj.moveNext()) {
var oTagArrayItem = obj("Params");
oTagArrayItem.Add("KLTAGS_VALUE", "%tag%");
oTagArrayItem.Add("KLTAGS_SET", true);
var oTagArray = obj("Collection");
oTagArray.SetSize(1);
oTagArray.SetAt(0, oTagArrayItem);
var oHostsArrayItem = obj("Params");
oHostsArrayItem.Add("KLTAGS_ITEM_ID", enumObj.item().item('KLHST_
WKS HOSTNAME'));
oHostsArrayItem.Add("KLTAGS TAGS", oTagArray);
var oHostsArray = obj("Collection");
oHostsArray.SetSize(1);
oHostsArray.SetAt(0, oHostsArrayItem);
var oSetTagsCallProps = obj("Params");
oSetTagsCallProps.Add("KLTAGS_FULL_REPLACE", false);
oTagsControl.SetTags(oHostsArray, oSetTagsCallProps);
taggedHosts++;
}
WScript.Echo("[OK] Added '%tag%' to " + taggedHosts + " hosts.");
} catch (e) {
WScript.Echo("[Error] " + e.number + " occured !!! " + e.description);
```

Rollback of Add Tag to Host Capability

```
function obj(name) {
  return new ActiveXObject("klakaut.KlAk" + name);
}
function ip2long(IPaddress) {
  var ip = IPaddress.match(/^(\d+)\.(\d+)\.(\d+)\*/);
  return ip ? (+ip[1] << 24) + (+ip[2] << 16) + (+ip[3] << 8) + (+ip[4]) :
  null;</pre>
```

```
}
try {
var oConnectProps = obj("Params"), oAdmServer = obj("Proxy"),
oTagsControl = obj("TagsControl"), oHosts = obj("Hosts"),
oFields2Return = obj("Collection"), enumObj, tagRemovedHosts = 0,
removedTagCount;
oConnectProps.Add("Address", "127.0.0.1:13291");
oAdmServer.Connect(oConnectProps);
oTagsControl.Prop("ListName") = "HostsTags";
oTagsControl.AdmServer = oHosts.AdmServer = oAdmServer;
oFields2Return.SetSize(1);
oFields2Return.SetAt(0, "KLHST_WKS_HOSTNAME");
enumObj = new Enumerator(oHosts.FindHosts("(KLHST_WKS_IP_LONG=" +
ip2long('%host%') + ")", oFields2Return, obj("Collection")));
for (; !enumObj.atEnd(); enumObj.moveNext()) {
var hostId = enumObj.item().item('KLHST_WKS_HOSTNAME');
var oHostIds = obj("Collection");
oHostIds.setSize(1);
oHostIds.SetAt(0, hostId);
var oExistingTagArray = oTagsControl.GetTags(oHostIds, obj("Params"));
var oTagArray = obj("Collection");
removedTagCount = 0;
for (var i = 0; i < oExistingTagArray.Count; i++) {</pre>
var oTagEntry = oExistingTagArray.Item(i);
var oTagValues = oTagEntry.Item("KLTAGS_TAGS");
for (var j = 0; j < oTagValues.Count; j++) {
var tag = oTagValues.Item(j);
if (tag != '%tag%') {
oTagArray.SetSize(oTagArray.Count + 1);
var oTagArrayItem = obj("Params");
oTagArrayItem.Add("KLTAGS_VALUE", tag);
oTagArrayItem.Add("KLTAGS_SET", true);
oTagArray.SetAt(oTagArray.Count - 1, oTagArrayItem);
} else {
removedTagCount++;
}
}
var oHostsArrayItem = obj("Params");
oHostsArrayItem.Add("KLTAGS_ITEM_ID", hostId);
oHostsArrayItem.Add("KLTAGS_TAGS", oTagArray);
var oHostsArray = obj("Collection");
oHostsArray.SetSize(1);
oHostsArray.SetAt(0, oHostsArrayItem);
var oSetTagsCallProps = obj("Params");
oSetTagsCallProps.Add("KLTAGS_FULL_REPLACE", true);
oTagsControl.SetTags(oHostsArray, oSetTagsCallProps);
```

```
if (removedTagCount > 0) {
  tagRemovedHosts++;
}
}
WScript.Echo("[OK] Removed '%tag%' from " + tagRemovedHosts + "
  hosts.");
} catch (e) {
WScript.Echo("[Error] " + e.number + " occured !!! " + e.description);
}
```

Move system to group capability

```
function obj(name) {
return new ActiveXObject("klakaut.KlAk" + name);
function ip2long(IPaddress) {
var ip = IPaddress.match(/^(\d+)\.(\d+)\.(\d+)\.(\d+));
return ip ? (+ip[1] << 24) + (+ip[2] << 16) + (+ip[3] << 8) + (+ip[4]) :
null;
}
try {
var oConnectProps = obj("Params"), oAdmServer = obj("Proxy"),
oHosts = obj("Hosts"), oFields2Return = obj("Collection"), enumObj,
hostsToMove = obj("Collection");
oConnectProps.Add("Address", "127.0.0.1:13291");
oAdmServer.Connect(oConnectProps);
oHosts.AdmServer = oAdmServer;
oFields2Return.SetSize(1);
oFields2Return.SetAt(0, "KLHST_WKS_HOSTNAME");
enumObj = new Enumerator(oHosts.FindHosts("(KLHST WKS IP LONG=" +
ip2long('%host%') + ")", oFields2Return, obj("Collection")));
for (; !enumObj.atEnd(); enumObj.moveNext()) {
hostsToMove.SetSize(hostsToMove.Count + 1);
hostsToMove.SetAt(hostsToMove.Count - 1,
enumObj.item().item('KLHST_WKS_HOSTNAME'));
oHosts.MoveHostsToGroup(parseInt('%group%'), hostsToMove);
WScript.Echo("[OK] " + hostsToMove.Count + " hosts moved to group
#%group%");
} catch (e) {
WScript.Echo("[Error] " + e.number + " occured !!! " + e.description);
```

Run task capability

```
function obj(name) {
return new ActiveXObject("klakaut.KlAk" + name);
try {
var oConnectProps = obj("Params"), oAdmServer = obj("Proxy"),
oTasks = obj("Tasks2"), item, enumObj, taskFound=false;
oConnectProps.Add("Address", "127.0.0.1:13291");
oAdmServer.Connect(oConnectProps);
oTasks.AdmServer = oAdmServer;
enumObj = new Enumerator(oTasks.EnumTasks(-1));
for (; !enumObj.atEnd(); enumObj.moveNext()) {
item = enumObj.item();
if (item.item('TASK_UNIQUE_ID') == '%task%') {
oTask = oTasks.GetTask(parseInt('%task%'));
oTasks.RunTask(parseInt('%task%'));
taskFound = oTask;
}
WScript.Echo(taskFound ? '[OK] Task #%task%:' + taskFound.item
('DisplayName') +
 successfully started.' : '[ERROR] Specified task #%task% was not found.');
} catch (e) {
WScript.Echo("[Error] " + e.number + " occured !!! " + e.description);
}
```

Run task capability Page 334 of 594

Integration Guide for MAY Siber Scop NET

Integration Overview

MAY Siber Scop NET is a NAC platform that provides visibility to any connected device across the network by integrating switches, routers and firewalls. This integration has been tested with MAY Siber Scop NET 7.1.17 version.

Integration Capabilities

ArcSight SOAR has the following integration capability with MAY Siber Scop NET:

Block

Use Case: Isolating Mal-behaving PC

With MAY Siber Scop NET integration, while responding an incident ATAR may block malbehaving computers' network access in order to contain the attack and prevent further spread of the attack. Blocking the host can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to MAY Siber Scop NET API via HTTPS. Typically it runs on 443/tcp port. So access to this service is required.
- An API key is required for SOAR to connect to MAY Siber Scop NET.

Configuring MAY Siber Scop NET

Login to MAY Siber Scop NET and create Web service key under **Settings > Global Settings > Web Service Key** menu.

Configuring SOAR

- 1. Navigate to Configuration > Credentials and click Create Credential.
- Fill the Credential Editor form as follows:

a. Internal Credential:

Туре	Name	Username	Password	Private Key
Internal credential.	Display name of credential set (i.e., MAY Siber Scop NET Credential).	Empty.	Web Service Key you have created for ATAR on MAY Siber Scop NET.	Empty.

b. Credential Store:

Туре	Name
External credential.	Name of the credential with pull path of the safe on store.

- 3. Navigate to Configuration > Integrations and click Create Integration.
- 4. Fill the configuration form as follows:

Parameter	Value
Name:	Display name of MAY Siber Scop NET integration on SOAR.
Туре:	MAY Siber Scop NET.
Address:	Address of the integration (the format should be https://1.1.1.1 or https://abc.example.com).
Configuration:	You need to specify the following configuration parameters:
	<pre># Blocked by message customization # \$incident. for incident, \$rule. for rule ,\$alert. for alert # \$incident. for incident, \$rule. for rule ,\$alert. for alert # \$incident. for incident, \$rule. for rule ,\$alert. for alert # \$incident.serial\$ for incident serial, \$incident.subject\$ for incident # subject # \$rule.id\$ for rule id, \$rule.name\$ for rule name # for customize reasons followings can be uncomment #block.reason=Blocked by ATAR - \$incident.serial\$ \$incident.subject\$ #rollback.reason=Rollbacked by ATAR - \$incident.serial\$ \$incident.subject\$</pre>
Credential:	Name of the credential set you've just created on step 2. (i.e., MAY Siber Scop NET Credential).
Trust Invalid SSL Certificates:	Select this if Engine's certificate is self-signed or not recognized by browsers. Not selected.
Require Approval From:	Select user(s) from list to ask her/his approval before executing actions on this integration.
Notify:	Select user(s) from the list to notify when ATAR performs an action on this integration.

- 5. When you click the **Test** button a success message is displayed.
- ${\it 6. \ \, Click \, \textbf{Save} \, to \, complete \, integration.}$

Configuring SOAR Page 336 of 594

Integration Guide for McAfee ePolicy Orchestrator

Integration Overview

McAfee ePolicy Orchestrator (ePO) is a management server for McAfee products which are used to protect endpoints from malware and network threats. It provides a centralized management console to simplify and accelerate the security effectiveness with visibility and control from device to cloud. This integration has been tested with McAfee ePolicy Orchestrator NET 5.10 version.

Integration Capabilities

- SOAR has the following integration capabilities with McAfee ePolicy Orchestrator:
- Assign Policy
- Apply Tag
- Host Information
- Move Host
- Run Task
- Set TIE Reputation

Use Case: Examining suspicious endpoint

With this integration, during the investigation of an incident SOARmay start an on-demand scan on a suspicious endpoint and may force new policy or move host to other place in system tree regarding scan result. This can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to McAfee ePolicy Orchestrator API through HTTPS. Typically it runs on 8443/tcp port. So access to this service is required.
- An user account is required for SOAR to connect McAfee ePolicy Orchestrator.

Configuration on McAfee ePolicy Orchestrator

1. Navigate to **User Management > Permission** Sets and create a permission set for SOAR with the following permissions:

Endpoint Security Threat Prevention	View and change task settings
McAfee Agent	View and change policy settings
McAfee TIE Reputations	View and change reputations
Queries and Reports	Use public groups.
Systems	Edit System Tree groups and systems & Apply, exclude, and clear tags
System Tree access	Can search on the following nodes and portions of the System
Tree	My Organization & Can access the following nodes and portions of the System

- View and change policy settings for the products that you want SOAR to chance policies for (for example: Endpoint Security Threat Prevention, Endpoint Security Firewall, Active Response, etc.)
- Navigate User Management > Users and create a user with permission set you in previous step.

Configuring SOAR

- 1. Navigate to Configuration > Credentials and click Create Credential.
- 2. Fill the Credential Editor form as follows:
 - a. Internal Credential:

Туре	Name:	Username:	Password:	Private Key:
Internal credential.	Display name of credential set (i.e., McAfee ePO Credentials).	Username you have configured on McAfee ePolicy Orchestrator.	Password for the user you have configured on McAfee ePolicy Orchestrator.	Empty.

b. Credential Store:

Туре:	Name:
External credential.	Name of the credential with pull path of the safe on store.

3. Navigate to Configuration > Integrations and click Create Integration.

4. Fill the configuration form as follows:

Parameter	Value
Name	Display name of McAfee ePolicy Orchestrator integration on ATAR.
Туре	McAfee ePolicy Orchestrator.
Address	Address of the integration (the format should be https://192.168.2.100:8443).
Configuration	You need to specify the following configuration parameters. For the first integration these values can be left as is:
	<pre>system.move.autoSort=false clienttask.run.retryAttempts = clienttask.run.retryIntervalInSeconds = clienttask.run.abortAfterMinutes = clienttask.run.useAllAgentHandlers = clienttask.run.stopAfterMinutes= clienttask.run.randomizationInterval = policy.assignToSystem.resetInheritance=</pre>
Credential	Name of the credential set you've just created on step 2. (i.e., McAfeeePO Credentials).
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed ornot recognized by browsers.
Require Approval From	Select user(s) from list to ask her/his approval beforeexecuting actions on this integration.
Notify	Select user(s) from the list to notify when SOARperforms an action on thisintegration.

- 5. When you click the **Test** button a success message is displayed.
- 6. Click **Save** to complete integration.

Configuring SOAR Page 339 of 594

Integration Guide for McAfee Network Security Platform (IPS)

Integration Overview

McAfee Network Security Platform is an intrusion prevention system (IPS) to identify malicious network traffic and stops never-before-seen attacks for which no signatures exist. This integration has been tested with McAfee Network Security Platform 9.2.7.22 version.

Integration Capabilities

SOAR has the following integration capabilities with McAfee Network Security Platform:

- Blacklist MD5 Hash
- Quarantine IP address

Configuration

Prerequisites

- SOAR connects to McAfee Network Security Platform's API via HTTPS. By default McAfee Network Security Platform REST-API interface works on 443/tcp port. So access permission to this port is required.
- A user account is required for SOAR to connect McAfee Network Security Platform.

Configuration on McAfee Network Security Platform (IPS)

- 1. Navigate to Manager > Users and Roles > Users and create a user account with Super User role. In order to access API, Super User role is needed.
- Navigate to Devices and note the device/sensor names.

Configuring SOAR

- 1. Navigate Configuration > Credentials and click Create Credential.
- 2. Fill the Credential Editor form as follows:
 - a. Internal Credential:

Туре	Name	Username	Password	Private Key
Internal credential.	Display name of credential set (i.e., McAfee NSP Credentials).	User you have created for SOAR on McAfee Network Security Platform.	Password of the user you have created for SOAR on McAfee Network Security Platform.	Empty.

b. Credential Store:

Туре	Name
External credential.	Name of the credential with pull path of the safe on store.

- 3. Navigate to Configuration > Integrations and click Create Integration.
- 4. Fill the configuration form as follows:

Parameter	Value
Name	Display name of McAfee Network Security Platform integration on SOAR.
Туре	McAfee Network Security Platform.
Address	Address of the integration (the format should be https://192.168.2.2).
Credential	Name of the credential set you've just created on step 2. (i.e., McAfee NSP Credentials).
Trust Invalid SSL Certificates	Select this if Platform's certificate is self-signed or not recognized by browsers.
Configuration	You need to specify the following configuration parameters.
	<pre># Name of ISP Devices/Sensors. SENSOR_NAME=SENSOR #proxy.id=5442</pre>
Require Approval From	Select user(s) from list to ask her/his approval before executing actions on this integration.
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.

- 5. When you click on the **Test** button a success message is displayed.
- 6. Click **Save** to complete integration.

Configuring SOAR Page 341 of 594

Integration Guide for McAfee Web Gateway

Integration Overview

McAfee Web Gateway is a web filtering solution which utilizes both reputation and categorybased filtering and protection against zero-day malware as well. This integration has been tested with McAfee Web Gateway 7.7.2.8.0 version.

Integration Capabilities

SOAR has the following integration capability with McAfee Web Gateway:

Block URL

Use Case: Blocking access to malicious URL

SOAR can integrate with McAfee Web Gateway to block malicious URLs detected while responding an incident. Blocking can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to McAfee Web Gateway's API through HTTPS. By default McAfee Web Gateway REST-API interface works on 4712/tcp port. So access permission to this port is required.
- A user account for SOAR to connect to McAfee Web Gateway.

Configuration on McAfee Web Gateway

- 1. Navigate to **Accounts** menu and add a new Role to be used for SOAR user. The new role should have at least "Rest-Interface Accessible" permission.
- 2. Navigate through Accounts menu and add an Internal Administrator Account with the role you have created in previous step.
- 3. Create a Wildcard Expression List under Policy > Lists.

- 4. Create a new rule and enable it under **Policy** > **Rule Sets** > **URL Filtering** menu to use list created in previous step. Rule criteria should be:
 - URL.Host matches in list ATARBlock
- 5. Save changes.

Configuration on SOAR

- 1. Navigate Configuration > Credentials and click Create Credential.
- 2. Fill the Credential Editor form as follows:
 - a. Internal Credential:

Туре	Name	Username	Password	Private Key
Internal credential.	Display name of credential set (i.e., McAfee Web GW Credential).	User you have created for SOAR on McAfee Web Gateway.	Password of the user you have created for SOAR on McAfee Web Gateway.	Empty.

b. Credential Store:

Туре	Name
External credential.	Name of the credential with pull path of the safe on store.

- 3. Navigate Configuration > Integrations and click Create Integration.
- 4. Fill the configuration form as follows:

Parameter	Value
Name	Display name of McAfee Web Gateway integration on SOAR
Туре	McAfee Web Gateway
Address	Address of the integration (the format should be 192.168.1.1:4712)
Configuration	You need to specify the following configuration parameters:
	<pre># Use the McAfee Web Gateway management interface to create the # list in Policy -> Rule set -> URL filtering section. SOAR will use # specified list name when adding blocked items. block.list.name=ATARBlock</pre>
Credential	Name of the credential set you've just created on step 2. (i.e., McAfeeWeb GW Credential)

Parameter	Value
Trust Invalid SSL Certificates	Select this if the certificate of the engine is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an enrichment on this integration

- 5. On Integration editor, click **Show Additional Parameters** checkbox and set **ConnectionLimit** to "1". Because of a limitation of McAfee Web Gateway, this value should never be greater than "1".
- 6. When you click the **Test** button the following popup should be displayed if yourcredential and address is valid.
- 7. Click **Save** to complete integration.

Integration Guide for McAfee Web Gateway v2

Integration Overview

McAfee Web Gateway is a web filtering solution which utilizes both reputation and category-based filtering and protection against zero-day malware as well.

Integration Capabilities

SOAR has the following integration capability with McAfee Web Gateway v2:

- Add Entry to List
- Remove Entry from List
- Get List Entries
- Get List Entry Details
- Get Lists

Configuration

Configuring McAfee Web Gateway v2

- Configure the **Username** and **Password** for McAfee Web Gateway v2.
- Enable REST-Interface accessible permission for the administrator role.

Configuring SOAR

- 1. Navigate Configuration > Credentials and click Create Credential.
- 2. Specify the following parameter values in the Credential Editor form:

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example,McAfee Web Gateway v2 Credential)
Username	<username></username>
Password	<password></password>
Private Key	Empty

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the Configuration form:

Parameter	Value
Name	Display name of McAfee Web Gateway v2 integration on SOAR
Туре	Advanced Scriptable Device
Address	https://{base_url:port}

Parameter	Value
Configuratio n	Specify the following configuration parameters:
	## Please use the McAfee Web Gateway management interface to create the list.
	# ArcSight SOAR will use the specified list name when no List parameter is specified
	# for the enrichment and action capabilities.
	default.list.name=ATARBlockList
	# Integration ID of the proxy integration to use when connecting to current integration.
	# If not provided, ArcSight SOAR will try to use a direct connection.
	<pre>#proxy.id=123</pre>
	# Maximum number of results to return from the API.
	# If not provided, the integration will gather all results.
	#max.result.count=100
Credential	Name of the credential set that you just created in step 2. (i.e., McAfeeWebGateway v2 Credentials)
Trust Invalid SSL Certificates	Select this if the certificate of the engine is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an enrichment on this integration

5. Click **Show Additional Parameters** and specify the following parameters in the Configuration form.

Parameter	Value
Batch Size	1
Connection Limit	1

- 6. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.
- 7. Click **Save** to complete the integration.

Configuring SOAR Page 346 of 594

Capabilities

1. Add Entry to List

Action capability to take the List name/ID to be added, Value to be added, and Description of the entry being added, and adds entry to the list. An asterisk can be added to the beginning and/or end of the value.

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Value	Entry value to add to the list	Network Address, Host, URL, Keyword, Unknown	Yes	Yes
List	Name or ID of the list. If not specified, the default list in the configuration will be used.	String	No	No
Description	Description of the list entry	String	No	No
Prefix Asterix	Add asterisk to the beginning of the 'Value' input	Checkbox	No	No
Suffix Asterix	Add asterisk should be added to the end of the 'Value' input	Checkbox	No	No

Output:

Case Scope

N/A

Human Readable Input

N/A

2. Remove Entry from list

Action capability that takes the List name/ID and the Value of the entry to remove, then removes the entry from the list. An asterisk can be added to the beginning and/or end of the value.

Capabilities Page 347 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Value	Entry value to remove from the list	Network Address, Host, URL, Keyword, Unknown	Yes	Yes
List	Name or ID of the list. If not specified, the default list in the configuration will be used.	String	No	No
Prefix Asterix	Add asterisk to the beginning of the Value input	Checkbox	No	No
Suffix Asterix	Add asterisk to the end of the Value input	Checkbox	No	No



Note: Suffix Asterix parameter is optional.

Output:

Case Scope:

N/A

Human Readable Output

N/A

3. Get List Entries

Takes the List name and returns the entries.

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	McAfee Web Gateway v2	N/A	No	Yes
List	Name or ID of the list If not specified, the default list in the configuration will be used	String	No	No

Output:

Case Scope

Capabilities Page 348 of 594

Action	Туре	Category/Value
N/A	N/A	N/A

Human Readable Output:

Entry	Description
217.94.215.154	Potentially malicious IP from Germany (source: Abuse IPDB)
43.155.113.200	Potentially malicious IP from Hong Kong (source: Abuse IPDB)
173.231.197.16	Potentially malicious IP from United States (source: Abuse IPDB)
20.19.121.168	Potentially malicious IP from France (source: Abuse IPDB)
41.57.134.48	Potentially malicious IP from South Africa (source: Abuse IPDB)

4. Get List Entry Details

Takes the entry Value and List and retrieves the entry details.

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	McAfee Web Gateway v2	N/A	No	Yes
Value	Entry value to fetch details	Network Address, Host, URL, Keyword, Unknown	Yes	Yes
List	Name or ID of the list If not specified, the default list in the configuration will be used	String	No	No

Output:

Case Scope

Action	Туре	Category/Value
N/A	N/A	N/A

Human Readable Output:

Capabilities Page 349 of 594

Field	Value
List ID	com.scur.type.ip.4552
List Title	Allowed Clients
List Type	ip
Entry Value	8.8.8.8
Entry Description	Google IP

5. **Get Lists**

Enrichment capability that takes the list types and retrieves all available lists for the list type specified.

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	McAfee Web Gateway v2	N/A	No	Yes
Туре	Type of the list	Type of the list such as All, IP, IP Range, Number, Regex, String	No	Yes

Output:

Case Scope:

Action	Туре	Category/Value
N/A	N/A	N/A

Human Readable Output:

ld	Title	Туре
com.scur.type.regex.272	ATARBlockList	regex
com.scur.type.string.263	ATARBlock	string
com.scur.list.applcntrl.data_analy tics	Data Analytics	applcontrol
5145	Category Blocklist	category
5146	Upload Media Type Blocklist	mediatype

Capabilities Page 350 of 594

Integration Guide for Micro Focus Arcsight ESM

See Integrating SOAR with ESM

Integration Guide for Micro Focus ArcSight Intelligence

See Integrating SOAR with Intelligence.

Integration Guide for Micro Focus ArcSight Logger

Integration Overview

ArcSight Logger is a log management solution for compliance, efficient log search, and secure storage.

Integration Capabilities

ArcSight SOAR has the following integration capability with Micro Focus ArcSight Logger:

Search Query

Use Case: Investigating Cyber-attacks

Integrated with Micro Focus ArcSight Logger, ATAR queires logs collected from various enterprise systems to enrich incident ticket, and improve analyst's understanding of incident.

Configuration

Prereqisites

- Currently SOAR supports Micro Focus ArcSight Logger version 6.3.1.7874.0 and later.SOAR
 connects to Micro Focus ArcSight Logger API using HTTPS. By default REST-API interface
 works on 443/tcp port. So access permission to this port is required.
- A user account is required for ATAR to connect Micro Focus ArcSight Logger.

Configuration on Micro Focus ArcSight Logger

 Click System Admin > Users/Groups > User Management and add a user account with Default Logger Search Group.

Configuring SOAR

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the Credential Editor:

a. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, ArcSight Logger Credentials)
Username	User you have created for ATAR on Micro Focus ArcSight Logger.
Password	Password of the user you have created for ATAR on Micro Focus ArcSight Logger.
Private Key	Empty

b. Credential Store:

Parameter	Value
Туре	External Credential
Name	Name of the credential with pull path of the safe on store

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of Micro Focus ArcSight Logger integration on SOAR
Туре	Micro Focus ArcSight Logger
Address	Address of the integration (the format must be https://192.168.12.6)
Configuration	Specify the following configuration parameters:
	<pre>events.pageLength=10000 # configure how far (in minutes) into the past this enrichment will look. #cache.reusing.duration=20 # local search enabling parameter for Search Query capability. # If this is set false, ATAR will perform searches on all nodes. #local.search.enabled=false # use master session while fetching events from peers for Search Query. # If this is set true, ATAR will use the same session ID while performing # searches on the other nodes. #reuse.master.session=false # peers credential list (if master session won't be shared) # peer address and credential ID values must be separated with : # additional peer-credential pairs must be separated with #peer.credential.list=1.1.1.1:CredentialId 2.2.2.2:CredentialId</pre>
Credential	Name of the credential set created on step 2 (For example, ArcSight Logger Credentials)
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or is not recognized by browsers

5. Click **Test** to test the integration.

Configuring SOAR Page 353 of 594

6. Click **Save** to complete the integration.

Additional Notes

- In order to execute queries on Micro Focus ArcSight Logger, you should create query scripts with ArcSight Logger Query type under Configuration -> Customization Library.
- SOAR extracts scope items on columns defined as Artifact in the query script. For example, // Artifact: deviceCustomNumber1Label | KEYWORD | RELATED

Configuring SOAR Page 354 of 594

Integration Guide for Microsoft Active Directory

Integration Overview

Microsoft Active Directory is an umbrella title for directory-based identity related services that Microsoft developed for the Windows domain networks.

ArcSight SOAR has the following integration capabilities with Microsoft Active Directory:

- Add user to a group
- Remove user from a group
- Lock user acoount
- Get user information
- Get user's groups
- Get group list
- Get group information
- Get computer information
- List computers on domain
- Fetch a domain object

Use Case: Compromised user account

During the investigation of the attack SOAR can ask Microsoft Active Directory the details of theuser account suspicious to be compromised, check the groups account belongs to, locks the account, fetches her/his manager's information and send a notification e-mail to manager if needed.

This can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to Microsoft Active Directory using LDAPS protocols. Access to 636/tcp
- port is required.
- A domain user account is required for SOAR to connect Microsoft Active Directory.

Configuration on Microsoft Active Directory

- Create a user account on Domain Controller with no password expiry.
- Add this user into "Account Operators" group. Members of this group can manage groups and accounts on domain except domain admins.

Configuring SOAR

- 1. Navigate Configuration > Credentials and click Create Credential.
- 2. Fill the Credential Editor form as follows:

a. Internal Credential:

Туре	Name:	Username	Password	Private Key
Internal credential.	Display name of credential set (i.e., Microsoft AD Credentials).	User you have created for SOAR on Microsoft Active Directory (the format should be username@domain).	Password of the user you have created for SOAR on Microsoft ActiveDirectory.	Empty.

b. Credential Store:

Туре	Name
External credential.	Name of the credential with pull path of the safe on store.

- 3. Navigate to Configuration > Integrations and click Create Integration.
- 4. Fill the configuration form as follows:

Parameter	Value
Name	Display name of Microsoft Active Directory integration on SOAR.
Туре	Microsoft Active Directory.
Address	Address of the integration (the format should be 192.168.2.2:636).

Parameter	Value
Configuration	You need to specify the following configuration parameters.
	<pre># SOAR will search objects under LDAP searchbase specified. # Format should be "DC=EXAMPLE,DC=COM" ldap.searchbase=DC=EXAMPLE,DC=COM # LDAP domain should be like "example.com" ldap.domain=example.com # LDAP NT domain name should be like "EXAMPLE" ldap.ntdomain=EXAMPLE # Username for LDAP service availability check. # SOAR will try to bind LDAP service as this user. ldap.checkavailabilityuser=testuser01@example.com # configure how far (in minutes) into the past this enrichment will look. cache.reusing.duration=30</pre>
Credential	Name of the credential set you've just created on step 2. (i.e., Microsoft AD Credentials).
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or not recognized by browsers.
Require Approval From	Select user(s) from list to ask her/his approval before executing actions on this integration.
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.

- 5. Click on the **Test** button.
- 6. Click **Save** to complete integration.

Configuring SOAR Page 357 of 594

Integration Guide for Microsoft Azure Active Directory

Integration Overview

Azure Active Directory (Azure AD) is Microsoft's cloud-based identity and access management service. It helps users to sign-in and access both external and internal resources, for example Microsoft 365, Azure portal, SaaS applications and many more.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Azure Active Directory:

- Add User to Group
- Disable User
- Enable User
- Get User Details
- Get User's Manager
- List Groups
- List User's Groups
- List Users
- Remove User from Group
- Revoke Sessions
- Create Group
- Delete Group
- List Delegated Permissions

Prerequisites

You must have access to HTTPS as the ArcSight SOAR connects to Azure Active Directory API through this service.

Configuration

Configuring Microsoft Azure

- 1. Log in to Azure Portal and navigate to Azure Active Directory service.
- 2. Click **App Registrations** tab to create a new registration with the following values:

Name	Supported Account Types	Redirect URL
ArcSight SOAR	Accounts in the organizational directory (Default Directory only - Single tenant)	(Web) https://localhost/soar

- 3. Navigate to Add a certificate or secret> Client secretto create a client secret. Add ArcSight SOAR as description and specify the expiry period as 24 months.
- 4. Note down the Secret Key value and Client ID.
- 5. Navigate to API Permissions and add the following permissions:

Permission Type	Permission	Description
Delegated	Directory Access as user All	Access directory as the signed in user
Application	Directory Read write All	Read and write directory data
Application	User Read write All	Read and write all users' full profiles.

6. Click **Yes** to grant admin consent for **Default Directory**.

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor** form:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, Azure AD Credentials).		Client ID of the application (for example, ArcSight SOAR) that you registered on Azure portal.	Secret Key

3. Click Configuration > Integrations > Create Integration.

Configuration Page 359 of 594

4. Specify the following parameter values in the **Configuration** form:

Parameter	Value			
Name	Display name of the integration.			
Туре	Microsoft Azure Active Directory.			
Address	Address of the integration (for example, https://graph.microsoft.com/v1.0).			
Configuration	Specify the following configuration parameters:			
	list.name	Tenant ID on Microsoft Azure tenant.id = ff1f0000-c600-4500-0038- 9d400000000		
	proxy.id	ID of the Proxy integration if you access Microsoft Azure Active Directory through a web proxy device. For example, proxy.id = 12345		
Credential	Credential that has been defined for this integration under the Credentials menu.			
Trust Invalid SSL Certificates	Select this if	Select this if web server's certificate is self-signed or is not recognized by browsers.		
Require Approval From	Select users from the list who can provide approval before executing actions on this integration			
Notify	Select users from the list to notify when SOAR performs an enrichment on this integration			

- 5. Click **Save** to save the integration definition.
- 6. Navigate to Configuration>Customization Library and edit Microsoft Azure Active Directory Advanced Action Script Default Template.
- 7. Select the integration that you have added to Integrations menu.
- 8. Click **Save** to complete the integration
- 9. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. Add User to Group

Action capability for adding a user to given AD group.

• Rollback: Yes

• Duplicate Control: No

The following table provides the **Add User to Group** action capability details:

Capabilities Page 360 of 594

Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third-party integration.	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is no-rollback.	N/A	N/A	No
User	Username to be added to group	Username Email Address Keyword Unknown	Yes	Yes
Group ID	Target group ID	String	No	Yes

Case Scope: N/A

Human Readable Output: N/A

2. Disable User

Action capability for disabling user account by blocking the sign-in procedure.

• Rollback: Yes

• Duplicate Control: No

The following table provides the **Disable User** action capability details:

Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third-party integration.	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is no-rollback.	N/A	N/A	No
User	Username to be disabled.	Username Email Address Keyword Unknown	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

3. Enable User

Action capability for enabling user account by removing sign-in block.

• Rollback: Yes

• Duplicate Control: No

Capabilities Page 361 of 594

The following table provides the **Enable User** action capability details:

Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third-party integration.	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is no-rollback.	N/A	N/A	No
User	Username to be enabled	Username Email Address Keyword Unknown	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

4. Get User Details

Enrichment capability for retrieving user details.

The following table provides the **Get User Details** enrichment capability details:

Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third-party integration.	Integration	N/A	Yes
User	User to be queried from Active Directory	Username Email Address Keyword Unknown	Yes	Yes

Output:

Case Scope:

Action	Туре	Category/ Value
None	N/A	N/A

Human Readable Output:

Capabilities Page 362 of 594



5. Get User's Manager

Enrichment capability for retrieving user's manager.

The following table provides the Get User's Manager enrichment capability details:

Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third-party integration.	Integration	N/A	Yes
User	User to be queried for manager's information.	Username Email Address Keyword Unknown	Yes	Yes

Output:

Case Scope:

Action	Туре	Category/ Value
None	N/A	N/A

Human Readable Output:



6. List Groups

Enrichment capability for retrieving AD group list.

The following table provides the List Groups enrichment capability details:

Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third-party integration.	Integration	N/A	Yes

Output:

Capabilities Page 363 of 594

Case Scope:

Action	Туре	Category/ Value
None	N/A	N/A

Human Readable Output:



7. List User's Groups

Enrichment capability for retrieving the list of groups for a specified username.

The following table provides the List User's Group enrichment capability details:

Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third-party integration.	Integration	N/A	Yes
User	User to be queried for group memberships.	Username Email Address Keyword Unknown	Yes	Yes

Output:

Case Scope:

Action	Туре	Category/ Value
None	N/A	N/A

Human Readable Output:



8. List Users

Enrichment capability for retrieving list of users.

The following table provides the **List Users** enrichment capability details:

Capabilities Page 364 of 594

Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third-party integration.	Integration	N/A	Yes

Case Scope:

Action	Туре	Category/ Value
None	N/A	N/A

Human Readable Output:



9. Remove User from Group

Action capability for removing a user from given AD group.

• Rollback: Yes

• Duplicate Control: No

The following table provides the Remove Users Group action capability details:

Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third-party integration.	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is no-rollback.	N/A	N/A	No
User	Username to be removed from group	Username Email Address Keyword Unknown	Yes	Yes
Group ID	Target group ID	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

Capabilities Page 365 of 594

10. Revoke Sessions

Action capability to revoke all the refresh action of the user and session tokens issued to applications, by resetting the **signInSessionsValidFromDateTime** user property to the current date.

This forces the user to sign in to those applications again.

• Rollback: No

• Duplicate Control: Yes

The following table presents the **Revoke Sessions** enrichment capabilities details:

Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third-party integration.	Integration	N/A	Yes
Rollback Mode	Time to rollback this action. Default is no-rollback.	N/A	N/A	No
User	Username to be forced to revoke (terminate) sign-in sessions.	Username Email Address Keyword Unknown	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

11. Create Group

Action capability for creating a new group from a given AD.

• Rollback: No

• Duplicate Control: No

The following table provides the **Create Group** action capability details:

Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of third-party integration	Integration	N/A	Yes
Group Nickname	The mail alias for the group, unique for Microsoft 365 groups in the organization. Maximum length is 64 characters. This property can contain only characters in the ASCII character set 0 - 127 except the following: @ () \ [] ";:.<>, SPACE.	String	No	Yes

Capabilities Page 366 of 594

Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Group Name	The name to display in the address book for the group. Maximum length: 256 characters	String	No	Yes
Description	A brief description about the group	String	No	Yes

Case Scope: N/A

Human Readable Output: N/A

12. Delete Group

Action capability to delete a group from a given AD.

• Rollback: No

• Duplicate Control: Yes

The following table provides the **Delete Group** action capability details:

Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third-party integration	Integration	N/A	Yes
Group Nickname	Nickname of the group to be queried from Active Directory	String	No	Yes

Output:

Case Scope:

N/A

Human Readable Output:

N/A

13. List Delegated Permissions

Enrichment capability to list delegated permissions.

The following table represents the **List Delegated Permissions** enrichment capabilities details:

Capabilities Page 367 of 594

Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third-party integration	Integration	N/A	Yes
User	User to be queried from Active Directory	Username Email Address Keyword Unknown	Yes	Yes

Case Scope: N/A

Human Readable Output:

Client Id	Consent Type	Principal Name	Resource Name	Scope
346054c8-18cf-419a-9414- 917c1b6a14a0	Principal	hirenpatel@sacuman.onmicro soft.com	Microsoft Graph	Directory.AccessAsUser.All openid profile offline_access

Integration Guide for Microsoft Defender for CloudApps

Integration Overview

Microsoft Defender for Cloud Apps is a Cloud Access Security Broker (CASB) that supports various deployment modes including log collection, API connectors, and reverse proxy. It provides visibility, control over data travel, and sophisticated analytics to identify and combat cyber threats across all your Microsoft and third-party cloud services.

Integration Capabilities

- Close Alert as Benign
- Close Alert as False Positive
- Close Alert as True Positive
- Get Alert by ID
- Get Entity Details
- List Activities
- List Activities by IP

- List Activities by User
- · List Activities by User Domain
- List Alerts
- List Alerts by IP
- List Alerts by Severity
- List Alerts by Status
- List Entities
- List IP Ranges
- Mark Alert as Read
- Mark Alert as Unread

Prerequisites

ArcSight SOAR connects to login.microsoft.com and *.portal.cloudappsecurity.com APIs through HTTPS. Access to these services is required.

Configuration

Configuring Microsoft Defender for CloudApps

- 1. Log in to portal.azure.com.
- Navigate to Azure Active Directory service > App Registrations to create a New Registration with the following values:

Name	Supported Account Types	Redirected URL
ArcSight SOAR	Accounts in this organizational directory only (Default Directory only - Single tenant)	https://localhost/soar (web)



If you have already defined an application for other integrations and want to use it, you can skip steps 1-4.

3. Click Add a certificate or secret to create a new Client Secret for the application you have registered and specify the following fields:

Description	Expiry
ArcSight SOAR	24 months

4. Note down the Secret Key along with Client ID.

Prerequisites Page 369 of 594

5. Navigate to **API Permissions** and add the following permissions from Microsoft Cloud App Security:

Permission Type	Permission	Description
Application	Investigation.manage	Manage alerts, activities, policies, and other investigation-related information
Application	Investigation.read	View alerts, activities and policies

- 6. Grant admin consent for Default Directory.
- 7. Log in to **Defender for cloudsApps** portal and click on ? icon. Under **About**, please note the portal URL value (for example, https://<tenant_id><tenant_ region>.portal.cloudappsecurity.com"). This will be used as Integration address.

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Fill the **Crdential Editor** form with following parameter values:

Туре	Internal credential
Name	Display name of credential set (i.e, Microsoft Defender for Cloud Apps Credentials)
Username	<empty></empty>
Password	Client ID of the application (i.e., ArcSight SOAR) you've registered on Azure Portal.
Private Key	Secret Key

- 3. Click Configuration > Integrations > Create Integration.
- 4. Fill the configuration form with the following parameter values:

Parameter	Value
Name	Display name of the Integration
Туре	Microsoft Defender for CloudApps
Address	Address of the integration (https:// <tenant_id><tenant_ region="">.portal.cloudappsecurity.com)</tenant_></tenant_id>

Configuring SOAR Page 370 of 594

Parameter	Value		
Configuration	Specify the following configuration parameter:		
	tenant.id	Tenant ID on Microsoft Azure tenant.id = ff1f0000-c600-4500-0038- 9d4000000000	
	proxy.id	ID of the Proxy integration if you access Cisco Firepower Management Center through a web proxy device. For example: proxy.id = 12345	
	cache.reusing.duration	Configure how far (in minutes) into the past this enrichment will look. cache.reusing.duration=20	
Credential	Credential that has been defined for this integ	ration under the Credentials menu.	
Trust Invalid SSL Certificates	Select this if web server's certificate is self-signed or is not recognized by browsers		
Require Approval From	Select user(s) from list to ask her/his approval before executing actions on this integration		
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration		

- 5. Click **Save** to save the integration definition.
- 6. Navigate to Configuration > Customization Library and edit Microsoft Defender for Cloud Apps Advanced Action Script Default Template.
- 7. Select the integration you have added to Integrations dropdown menu.
- 8. Click **Save** to complete the integration
- 9. Edit the integration under **Configuration** > **Integrations** and Click **Test**. A Integration Successfull message will be displayed if your credential and address are valid.



Steps 6-8 are required only for Advanced Action Script Default Templates.

Capabilities

1. Close Alert as Benign

Action capability for closing security alert as benign on Microsoft Defender for Cloud Apps portal.

• Rollback: No

• Duplicate Control: No

Capabilities Page 371 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Alert ID	Alert ID on Defender for Cloud Apps portal.	String	No	Yes
Comment	Comment added to the alert on Defender for Cloud Apps portal	String	No	Yes
Reason	Closing reason added to the alert on Defender for Cloud Apps portal	String Actual severity is lower Confirmed with end user Triggered by test Other	No	Yes

Case Scope

N/A

Human Readable Output

N/A

2. Close Alert as False Positive

Action capability for closing security alert as false positive on Microsoft Defender for Cloud Apps portal

• Rollback: No

• Duplicate Control: No

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Alert ID	Alert ID on Defender for Cloud Apps portal.	String	No	Yes
Comment	Comment added to the alert on Defender for Cloud Apps portal	String	No	Yes
Reason	Closing reason added to the alert on Defender for Cloud Apps portal	String Alert is not accurate Not of interest Too many similar alerts Other	No	Yes

Output:

Case Scope

N/A

Capabilities Page 372 of 594

Human Readable Output

N/A

3. Close Alert as True Positive

Action capability for closing security alert as true positive on Microsoft Defender for Cloud Apps portal

• Rollback: No

• Duplicate Control: No

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Alert ID	Alert ID on Defender for Cloud Apps portal.	String	No	Yes
Comment	Comment added to the alert on Defender for Cloud Apps portal	String	No	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

4. Mark Alert as Read

Action capability for marking the security alert as read.

• Rollback: No

• Duplicate Control: No

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes
Alert ID	Alert ID on Defender for Cloud Apps portal	String	No	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

5. Mark Alert as Unread

Action capability for marking the security as unread.

• Rollback: No

Capabilities Page 373 of 594

• Duplicate Control: No

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes
Alert ID	Alert ID on Defender for Cloud Apps portal	String	No	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

6. Get Alert by ID

Enrichment capability for querying & retrieving security alert details by alert ID.

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes
Alert ID	Alert ID on Defender for Cloud Apps portal.	String	No	Yes

Output:

Case Scope

Action	Туре	Category/Value
None	N/A	N/A

Human Readable Output

Кеу	Value
Title	Logon from a risky IP address
Description	Activity policy 'Logon from a risky IP address' was triggered by 'Ahmet Ozturk (onmicrosoft.com)'
Severity	High
Status	Read
Resolution Status	Open
Stories	["Threat Detection"]
Evidence	N/A
Intent	["Unknown"]
Entities	[("abel": "Logon from a risky IP address", "type": "policyRule", "policyType": "AUDIT", "id": "62/t88504556622Tr0d 12at2":), ("entityType": 2, "em": "onnicrosoft.com", "label": "Ahmet Ozturk", "ype": "account", "pa": "onnicrosoft.com", "saas": 11161, "inst": 0, "id": "d9ace94f-e0ce-4a3a- 9921-2680111168a0"), ("label": "onnicrosoft.com", "type": "user", "id": onnicrosoft.com"), ("label": "Microsoft Defender for Cicula dype, "type": "service", "id": 20595), (), ("label": "AU, "type": "country", "id": "AU") }
Threat Score	40
Alert Id	63046032c48ddd33f77278e2
Alert Time	2022-08-23T05:05:51.0Z
Alert Timestamp	1661231151874

Capabilities Page 374 of 594

7. List IP Ranges

Enrichment capability for getting list of IP Ranges defined. Query returns maximum 100 items.

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes

Output:

Case Scope

Action	Туре	Category/Value
None	N/A	N/A

Human Readable Output

ld	Name	Category	Subnets	Location	Tags	Last Modified
62fb849edf907614b4a52a16	Sydney-HQ	VPN	[New York and Transcolute]	{ "latitude": -25.72810364, "countryCode": "AU", "name": "Australia", "countryName": "Australia", "longitude": 134.4901886 }	["Custom_tag1", "Custom_tag2"]	2022-08-18T13:16:38.0Z
62fe31e6199de67916075ae8	Risky IP Ranges	Risky	[THE HER LEGAT, THE RESE HART]		N/A	2022-08-18T12:34:46.0Z

8. Get Entity Details

Enrichment capability for retrieving entity details.

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes
Entity	Entity queried on Defender for Cloud Apps portal. It is represented as a dictionary with the entity ID, SaaS, and instance details. For example: {"id":"3fa9f28b-eb0e-463a-ba7b- 8089fe9991e2","saas":11161,"inst":0}	Username Keyword Unknown	Yes	Yes

Output:

Case Scope

Action	Туре	Category/Value
None	N/A	N/A

Human Readable Output

Capabilities Page 375 of 594

Кеу	Value
Name	Neil Young
Email	neil.young@
Role	User
Groups	["External users"]
Domain	prinquisi
Organization	N/A
Threat Score	N/A
App. Name	Okta Dev-14556012
Status	Active

9. List Activities

Enrichment capability for getting list of activities in given time range. Results are ordered by create time from newest to oldest. Query returns maximum 100 items.


Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes
Time Range	Time range filter for query	Time range. Relative: e.g. Last 5 days Absolute: e.g. 2022- 08-14 15:10 - 2022-08- 14 15:32	N/A	Yes

Output:

Case Scope

Action	Туре	Category/Value
None	N/A	N/A

Human Readable Output:



Capabilities Page 376 of 594

10. List Activities by IP

Enrichment capability for getting list of activities by IP address in given time range. Results are ordered by create time from newest to oldest. Query returns maximum 100 items.

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes
IP Address	Client IP address to filter activities	Network Address	Yes	Yes
Time Range	Time range filter for query	Time range. Relative: e.g. Last 5 days Absolute: e.g. 2022- 08-14 15:10 - 2022-08- 14 15:32	N/A	Yes

Output:

Action	Туре	Category/Value
None	N/A	N/A

Human Readable Output:

Activity Date	App. Name	Description	User	Client Ip	Device Type	ld
2022-09-07T02:33:38.0Z	Microsoft Azure	GetEntities Microsoft.Management: resource 	509e4652-da8d-478d-a730- e9d4a1996ca4	52.	N/A	b9fa206917fca3284f584e29168 6e8ab53bce9c0373f1c9db1b92 8f1b02ee4e3
2022-09-07T02:33:38.0Z	Microsoft Azure	GetEntities Microsoft.Management: resource GetEntities Microsoft.Management 	509e4652-da8d-478d-a730- e9d4a1996ca4	52.	N/A	4cf8491d4934c8a7rc070312c4 017db4eaecea615b6f42b89e8e d5423d442f62
2022-09-06T14:33:37.0Z	Microsoft Azure	GetEntities Microsoft.Management: resource 	509e4652-da8d-478d-a730- e9d4a1996ca4	52.	N/A	17776964be7af0ff01a11b16782 4c15ef10ac735b1a52ae0a1d9d dda2132e2bb
2022-09-06T14:33:37.0Z	Microsoft Azure	GetEntities Microsoft.Management: resource cosoft.Management 	509e4652-da8d-478d-a730- e9d4a1996ca4	52.	N/A	df614fe388a02bd3dc3d77f3764 c1e5dbab4a34d99f680b074239 de6a8a5d79d
2022-09-06T02:33:38.0Z	Microsoft Azure	GetEntities Microsoft.Management: resource d>>/providers/Microsoft.Management d>> Succeeded	509e4652-da8d-478d-a730- e9d4a1996ca4	52.	N/A	8f730d550d44de6ce2cffb128da d22426c92c990c02ed5a43461 89bc18972015

11. List Activities by User

Enrichment capability for getting list of activities for a username in given time range. Results are ordered by create time from newest to oldest. Query returns maximum 100 items.

Capabilities Page 377 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes
Username	Username to filter activities.	Username Email Address Keyword Unknown	Yes	Yes
Time Range	Time range filter for query	Time range. Relative: e.g. Last 5 days Absolute: e.g. 2022- 08-14 15:10 - 2022-08- 14 15:32	N/A	Yes

Action	Туре	Category/Value
None	N/A	N/A

Human Readable Output



12. List Activities by User Domain

Enrichment capability for getting list of activities for a user domain in given time range. Results are ordered by create time from newest to oldest. Query returns maximum 100 items.

Capabilities Page 378 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes
User Domaiin	User domain to filter activities.	Host Keyword Unknown	Yes	Yes
Time Range	Time range filter for query	Time range. Relative: e.g. Last 5 days Absolute: e.g. 2022- 08-14 15:10 - 2022-08- 14 15:32	N/A	Yes

Case Scope

Action	Туре	Category/Value
None	N/A	N/A

Human Readable Output



13. List Alerts

Enrichment capability for getting list of security alerts created in given time range. Results are ordered by create time from newest to oldest. Query returns maximum 100 items.

Capabilities Page 379 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes
Time Range	Time range filter for query	Time range. Relative: e.g. Last 5 days Absolute: e.g. 2022- 08-14 15:10 - 2022-08- 14 15:32	N/A	Yes

Case Scope

Action	Туре	Category/Value
None	N/A	N/A

Human Readable output

Alert Date	Title	Description	Severity	Status	Risk Category	Intent	ld
2022-08-26T12:57:13.0Z	System alert: Okta (Okta Dev-14556012) App connector error	The Okta (Okta Dev- 14556012) App connector has not been working properly for more than 72 hours. This may be due to a timeout in the connection test or a connection problem with the app.	High	Open	N/A	["Unknown"]	6308c32cab79f53e82b7a8 df
2022-08-24T00:57:05.0Z	System alert: Okta (Okta Dev-14556012) App connector error	The Okta (Okta Dev- 14556012) App connector has not been working properly for more than 12 hours. This may be due to a timeout in the connection test or a connection problem with the app.	High	Open	N/A	["Unknown"]	63057763bb527f38df6cb7f 4
2022-08-23T05:05:51.0Z	Logon from a risky IP address	Activity policy 'Logon from a risky IP address' was triggered by 'Ahmet Ozturk (onmi crosoft.com)'	High	Open	["Threat Detection"]	["Unknown"]	63046032c48ddd33f77278 e2
2022-08-23T03:45:20.0Z	Logon from a risky IP address	Activity policy 'Logon from a risky IP address' was triggered by 'Ahmet Ozturk (High	Open	["Threat Detection"]	["Unknown"]	63044d51092d0a774ca41 22c

14. List Alerts by IP

Enrichment capability for getting list of security alerts with the specified IP field, created in given time range. Results are ordered by create time from newest to oldest. Query returns maximum 100 items.

Capabilities Page 380 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes
IP Address	IP Address to filter alerts	Network Address	Yes	Yes
Time Range	Time range filter for query	Time range. Relative: e.g. Last 5 days Absolute: e.g. 2022- 08-14 15:10 - 2022-08- 14 15:32	N/A	Yes

Case Scope

Action	Туре	Category/Value
None	N/A	N/A

Human Readable output

Alert Date	Title	Description	Severity	Status	Risk Category	Intent	ld
2022-09-08T08:09:55.0Z	Logon from a risky IP address	Activity policy 'Logon from a risky IP address' was triggered by 'Ahmet Ozturk (Ionmi crosoft.com)'	High	Open	["Threat Detection"]	["Unknown"]	6319a356bb28275c55bda ba9
2022-09-08T06:49:30.0Z	Logon from a risky IP address	Activity policy 'Logon from a risky IP address' was triggered by 'Ahmet Ozturk (onmi crosoft.com)'	High	Open	["Threat Detection"]	["Unknown"]	6319907cefed093ba6a1a8 47
2022-09-08T01:17:58.0Z	Logon from a risky IP address	Activity policy "Logon from a risky IP address' was triggered by 'Ahmet Ozturk (onmi crosoft.com)'	High	Open	["Threat Detection"]	["Unknown"]	631942c81ef9c55bbe34a7 51
2022-09-07T15:49:29.0Z	Logon from a risky IP address	Activity policy "Logon from a risky IP address' was triggered by 'Ahmet Ozturk (onmi crosoft.com)'	High	Open	["Threat Detection"]	["Unknown"]	6318bd8aafff392edc75306 6
2022-09-07T14:47:58.0Z	Logon from a risky IP address	Activity policy "Logon from a risky IP address' was triggered by 'Ahmet Ozturk (onmi crosoft.com)'	High	Open	["Threat Detection"]	["Unknown"]	6318af1e9335c0397f3997 84

15. List Alerts by Severity

Enrichment capability for getting list of security alerts with the specified severity value, created in given time range. Results are ordered by create time from newest to oldest. Query returns maximum 100 items.

Capabilities Page 381 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes
Alert Severity	Alert severity set by vendor/provider	String High Medium Low Informational	No	Yes
Time Range	Time range filter for query	Time range. Relative: e.g. Last 5 days Absolute: e.g. 2022-08-14 15:10 – 2022- 08-14 15:32	N/A	Yes

Case Scope

Action	Туре	Category/Value
None	N/A	N/A

Human Readable Output

Alert Date	Title	Description	Severity	Status	Risk Category	Intent	ld
2022-08-22T04:45:02.0Z	Logon from a risky IP address	Activity policy "Logon from a risky IP address' was triggered by 'Ahmet Ozturk (onmi crosoft.com)'	High	Open	["Threat Detection"]	["Unknown"]	630309d07b8da932bcd4a 961
2022-08-22T03:24:26.0Z	Logon from a risky IP address	Activity policy 'Logon from a risky IP address' was triggered by 'Ahmet Ozturk (onmi crosoft.com)'	High	Open	["Threat Detection"]	["Unknown"]	6302f6ec8afe46488b0b35 8d
2022-08-22T02:03:54.0Z	Logon from a risky IP address	Activity policy "Logon from a risky IP address' was triggered by 'Ahmet Ozturk (onmi crosoft.com)'	High	Open	["Threat Detection"]	["Unknown"]	6302e40b824aab20473cf0 72
2022-08-22T00:43:13.0Z	Logon from a risky IP address	Activity policy 'Logon from a risky IP address' was triggered by 'Ahmet Ozturk (onmi crosoft.com)'	High	Open	["Threat Detection"]	["Unknown"]	6302d12384381753eb19d 204
2022-08-21T11:12:19.0Z	Logon from a risky IP address	Activity policy "Logon from a risky IP address" was triggered by 'Ahmet Ozturk ("" onmi crosoft.com)"	High	Open	["Threat Detection"]	["Unknown"]	630213148e36546156e44 ad1

16. List Alerts by Status

Enrichment capability for getting list of security alerts with the specified status value, created in given time range. Results are ordered by create time from newest to oldest. Query returns maximum 100 items.

Capabilities Page 382 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes
Alert Status	Alert resolution status	String Benign Dismissed False Positive Open Resolved True Positive	No	Yes
Time Range	Time range filter for query	Time range. Relative: e.g. Last 5 days Absolute: e.g. 2022- 08-14 15:10 - 2022-08- 14 15:32	N/A	Yes

Case Scope

Action	Туре	Category/Value
None	N/A	N/A

Human Readable Output



17. List Entities

Enrichment capability for getting list of entities. Query returns maximum 100 items.


Capabilities Page 383 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration	Integration	N/A	Yes

Case Scope

Action	Туре	Category/Value
None	N/A	N/A

Human Readable Output



Integration Guide for Microsoft Defender Endpoint

Integration Overview

Microsoft Defender for Endpoint is an enterprise endpoint security platform designed to help enterprise networks prevent, detect, investigate, and respond to advanced threats.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Micro Focus ArcSight Intelligence:

- · Get Alert by ID
- Get Domain Statistics
- Get File Information
- Get File Related Machines
- Get File Statistics

- Get Installed Software
- Get IP Statistics
- Get Logon Users
- Get Machine Details
- List Alerts
- List Alerts by Severity
- List Alerts by Status
- List File Related Alerts
- List Machines
- List User Related Alerts
- Add Machine Tag
- Assign Alert
- Isolate Machine
- Remove Machine Tag
- Restrict Code Execution
- Stop & Quarantine File
- Integrate Machine
- Unrestrict Code Execution
- Update Alert Classification
- Update Alert Comment
- Update Alert Determination
- Update Alert Status

Prerequisites

ArcSight SOAR connects to Microsoft Defender API using HTTPS. Access to Microsoft portal login.microsoft.com is required.

Configuring Microsoft Defender

1. Log in to https://portal.azure.com and Navigate to Azure Active Directory service.



If an application is defined for other integrations, skip steps 1-3 to use it.

2. Click **App Registration** > **New Registration**. Complete the ArcSight SOAR application registration by specifying the following parameter values in the Register an application

Prerequisites Page 385 of 594

form:

Name	Supported Account Types	Redirected URL
ArcSight SOAR	Accounts in this organizational directory only (Default Directory for single tenant only)	https://localhost/soar

3. Select your application and Click **Add a certificate or secret > New Client Secret**. Add a description and specify the expiry period as 24 months.



Note down the Secret Key value along with Client ID and tenant ID.

4. Click API Permissions > Add a Permission and select Windows Defender API. Add the following permissions from WindowsDefender ATP:

Permission Type	Permission	Description
Application	Alert.Read.All, File.Read.All, Machine.Isolate, Machine.Read.All, Machine.RestrictEx, User.Read.All, Alert.ReadWrite.All, Ip.Read.All,Url.Read.All,Machine.StopAndQuarantine, Machine.Scan	Read and update your organisation's security events.

5. Click **Yes** to grant admin consent for Default Directory.

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the **Configuration Form**:

Parameter	Value
Name	Display name of the credential set
Туре	Internal credential
Username	Empty
Password	client_id of the application created above for SOAR on Azure portal.
Private Key	Secret key of the application created above for SOAR on Azure portal.

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration Form**:

Parameter	Value
Name	Display name of the integration
Туре	Microsoft Defender for Endpoint
Address	Address of the integration ((the format should be https://api.securitycenter.microsoft.com)

Configuring SOAR Page 386 of 594

Parameter	Value			
Configuration	Specify the following configuration param	eters:		
	proxy.id	ID of the Proxy integration if you access Microsoft Azure through a web proxy device. For example: proxy.id = 12345		
	tenant.id	Global Unique Identifier (GUID) for your Microsoft 365 Tenant.		
	cache.reusing.duration	Configure how far (in minutes) into the past this enrichment will look.		
Credential	Credential that has been defined for this integration under the Credentials menu			
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration			

- 5. Click Save.
- 6. Navigate to Configuration > Customization Library and edit Microsoft Defender for Endpoint Advanced Action Script Default Template
- 7. Select the integration that you have created in step 4 from the **Integrations** drop-down menu and click **Save**.
- 8. Click **Test**, and **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. Get Alert by ID

Enrichment capability for getting details of an alert by Alert ID.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Alert ID	Alert ID that has been created by the User.	String	N/A	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

2. Get Domain Statistics

Enrichment capability for retrieving statistics on a domain.

Capabilities Page 387 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Domain	Host that you have created from case scope	String	Yes	Yes

Case Scope

N/A

Human Readable Output

N/A

3. Get File Information

Enrichment Capability for getting file details

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
File Hash	SHA1 & SHA256 file hash from case scope	String	Yes	Yes

Output:

Case Scope

Human Readable Output

4. Get File Related Machines

Enrichment capability for Retrieving a collection of machines related to a given file hash

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
File Hash	SHA1 file hash from case scope	String	Yes	Yes

Output:

Case Scope

Human Readable Output

Capabilities Page 388 of 594

N/A

5. Get File Statistics

Enrichment capability for Retrieving the statistics for given file.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
File Hash	SHA1 file hash from case scope	String	Yes	Yes

Output:

Case Scope

Human Readable Output

N/A

6. Get Installed Software

Enrichment capability for Retrieving a collection of installed software related to a given device ID.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
IP Address	Network Address from case scope	String	Yes	Yes

Output:

Case Scope

Human Readable Output

N/A

7. Get IP Statistics

Enrichment capability for Retrieving the statistics for given IP.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
IP Address	Network Address from case scope	String	Yes	Yes

Capabilities Page 389 of 594

Case Scope

Human Readable Output

N/A

8. Get Logon Users

Enrichment capability for Retrieving collection of logged on users on a specific device

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
IP Address	Network Address from case scope	String	Yes	Yes

Output:

Case Scope

Human Readable Output

N/A

9. Get Machine Details

Enrichment capability for retrieving machine details for given IP address.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
IP Address	Network Address from case scope	String	Yes	Yes

Output:

Case Scope

Human Readable Output

N/A

10. List Alerts

Enrichment capability for retrieving a collection of alerts in a given time-range.

Capabilities Page 390 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Time range	Time range	String	No	Yes

Case Scope

N/A

Human Readable Output

N/A

11. List Alerts by Severity

Enrichment Capability for retrieving a collection of alerts for a given severity value in a given time-range.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Time range	Time range	String	No	Yes
Severity	Severity of the alert	String	No	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

12. List Alerts by Status

Enrichment Capability for retrieving a collection of alerts for a given status value in a given time-range.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Time range	Time range	String	No	Yes
Alert Status	Alert Status	String	No	Yes

Capabilities Page 391 of 594

Case Scope

N/A

Human Readable Output

N/A

13. List File Related Alerts

Enrichment capability for retrieving a collection of alerts related to a given file hash.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Domain	Domain host from case scope	String	Yes	Yes

Output:

Case Scope

Human Readable Output

N/A

14. List Machines

Enrichment capability for retrieving a list of machines that have communicated with Microsoft

Defender for Endpoint cloud.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

15. List User Related Alerts

Enrichment capability for retrieving a collection of alerts related to a given username.

Capabilities Page 392 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Username	Username from case scope	String	Yes	Yes

Case Scope

Human Readable Output

N/A

16. List Machines By Tag

Enrichment capability for finding machines by a given tag.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Tag	Input Tag	String	Yes	Yes

Output:

Case Scope

Human Readable Output

N/A

17. Add Machine Tag

Action capability for adding a tag to specific machine.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
IP Address	Network address from case scope	Network Address	Yes	Yes
Tag	Input Tag	String	Yes	Yes

Output:

Case Scope

Human Readable Output

N/A

18. Assign Alert

Action capability for assigning an alert.

Capabilities Page 393 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Alert ID	Alert ID	String	No	Yes
Assignee	Assignee	String	No	Yes

Case Scope

N/A

Human Readable Output

N/A

19. Isolate Machine

Action capability for isolating device from accessing external network.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
IP Address	Network address from case scope	Network Address	Yes	Yes
Comment	Comment	String	No	Yes

Output:

Case Scope

Human Readable Output

N/A

20. Remove Machine Tag

Action capability for removing a tag from a specific machine.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
IP Address	Network address from case scope	Network Address	Yes	Yes
Tag	Input Tag	String	No	Yes

Output:

Case Scope

Human Readable Output

N/A

21. Restrict Code Execution

Action capability for restricting execution of all applications on the device except a

Capabilities Page 394 of 594

predefined set.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
IP Address	Network address from case scope	Network Address	Yes	Yes

Output:

Case Scope

Human Readable Output

N/A

22. Stop & Quarantine File

Action capability for stopping execution of a file on a device and deleting it.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
IP Address	Network address from case scope	Network Address	Yes	Yes
File Hash (SHA1)	File Hash (SHA1) from case scope	String	Yes	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

23. Unisolate Machine

Action capability for releasing machine from isolation.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
IP Address	Network address from case scope	Network Address	Yes	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

Capabilities Page 395 of 594

24. Unrestrict Code Execution

Action capability for removing app restrictions on a device.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
IP Address	Network address from case scope	Network Address	Yes	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

25. Update Alert Classification

Action capability for updating alert classification.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Alert ID	Alert ID	String	No	Yes
Alert Classification	Alert classification	String	No	Yes

Output:

Case Scope

Human Readable Output

N/A

26. Update Alert Comment

Action capability for adding comment to an alert.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Alert ID	Alert ID	String	No	Yes
Alert Comments	Alert comment	String	No	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

Capabilities Page 396 of 594

27. Update Alert Determination

Action capability for updating an alert determination.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Alert ID	Alert ID	String	No	Yes
Alert Determination	Alert determination	String	No	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

28. Update Alert Status

Action capability for updating alert status.

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Alert ID	Alert ID	String	No	Yes
Alert Status	Alert status	String	No	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

Capabilities Page 397 of 594

Integration Guide for Micro Focus IT Service Manager

Integration Overview

Micro Focus Service Manager is an IT Service Management (ITSM) Tool that uses the Information Technology Infrastructure Library (ITIL) framework to provide a web interface for corporate changes, releases and interactions (request fulfillment) that is supported by a service catalog and Configuration Management Database (CMDB).

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Micro Focus IT Service Manager:

- Close Incident
- Create Incident
- Update Incident

Prerequisites

You must have access to HTTPS as the ArcSight SOAR connects to Micro Focus IT Service Manager API through this service.

Configuration

Configuring Micro Focus IT Service Manager

1. Create a user on IT Service Manager with admin role. This user must be able to and consume the rest APIs of the IT Service Manager.

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the Credential Editor form.

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, Micro Focus IT Service Manager Credentials).	Username of the created user on Micro Focus IT Service Manager.	Password of the created user on Micro Focus IT Service Manager.	

- 3. Click **Configuration** > **Lists** > **Create List**. The list must have two columns with the type keyword. Add a name to the list and save it. The name of the list is used during integration configuration.
- 4. Click Configuration > Integrations > Create Integration.
- 5. Specify the following parameter values in the Configuration form.

Parameter	Value				
Name	Display name	Display name of the integration.			
Туре	Micro Focus	IT Service Manager			
Address		licro Focus IT Service Manager integration (for example, 3.165.82:13080).			
Configuration	Specify the f	ollowing configuration parameters:			
	list.name	List name that is used for mapping ArcSight SOAR cases to Micro Focus IT Service Manager incidents. For example, list.name=mfitsmMapList			
	proxy.id ID of the Proxy integration if you access Micro Focus IT Service Manager through a web proxy device. For example, proxy.id = 12345				
Credential	Credential th	nat has been defined for this integration under the Credentials menu.			
Trust Invalid SSL Certificates	Select this if	web server's certificate is self-signed or is not recognized by browsers.			
Require Approval From	Select user(s) from list to ask the approval before executing actions on this integration.				
Notify	Select user(s integration.) from the list to notify when SOAR performs an action on this			

- 6. Click **Save** to save the integration definition.
- 7. Navigate to Configuration>Customization Library and edit Micro Focus IT Service Manager Advanced Action Script Default Template.
- 8. Select the integration that you have added to Integrations menu.

Configuring SOAR Page 399 of 594

- 9. Click **Save** to complete the integration.
- 10. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. Create Incident

Action capability for creating incident on Micro Focus IT Service Manager

Rollback: No

Duplicate Check: Yes

The following table presents the **Create Incident** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Category	Category information of created incident.	Enum	No	Yes
Description	MF ITSM Incident Description.	Text	No	Yes
Title	Incident Title	Text	No	Yes
Service	Service Type	Enum	No	Yes
Impact	Incident Impact	Enum	No	Yes
Urgency	Incident Urgency	Enum	No	Yes
Status	Incident Status	Enum	No	No
Alert Status	Incident Alert Status	Text	No	No
Area	Incident Area	Text	No	No
Subarea	Incident Subarea	Text	No	No
Assignment Group	Incident Assignee	Text	No	No
Affected CI	Incident Affected CI	Text	No	No
Company	Incident Company	Text	No	No
Phase	Incident Phase	Text	No	No

2. Close Incident

Action capability for closing incident on Micro Focus IT Service Manager.

Rollback: No

Duplicate Check: Yes

The following table presents the **Close Incident** action capability details:

Capabilities Page 400 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Solution	Solution Note	Text	No	Yes

3. Update Incident

Action capability for updating incident on Micro Focus IT Service Manager.

Rollback: No

Duplicate Check: No

The following table presents the update incident action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Description	MF ITSM Incident Description.	Text	No	Yes
Title	Incident Title	Text	No	Yes
Service	Service Type	Enum	No	Yes
Impact	Incident Impact	Enum	No	Yes
Urgency	Incident Urgency	Enum	No	Yes
Status	Incident Status	Enum	No	No
Alert Status	Incident Alert Status	Text	No	No
Area	Incident Area	Text	No	No
Subarea	Incident Subarea	Text	No	No
Assignment Group	Incident Assignee	Text	No	No
Affected CI	Incident Affected CI	Text	No	No
Company	Incident Company	Text	No	No
Phase	Incident Phase	Text	No	No

Capabilities Page 401 of 594

Integration Guide for Micro Focus UCMDB

Integration Overview

Micro Focus Universal Configuration Management Database (UCMDB) generates and maintains a Configuration Management Database of information technology items. It includes a mechanism for automated discovery of IT infrastructure components, such as computers and network devices.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Micro Focus UCMDB:

- Expose CI Information
- Get Cl
- · Get Related CIs

Prerequisites

You must have access to HTTPS as the ArcSight SOAR connects to Micro Focus UCMDB API through this service.

Configuration

Configuring Micro Focus UCMDB

Create a user with privileges to use REST API. The username and password of the user is used as credential in the ArcSight SOAR.

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential
- 2. Specify the following parameter values in the Credential Editor form:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, Micro Focus UCMDB Credentials).	Username	Password	

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form:

Parameter	Value				
Name	Display name of the inte	Display name of the integration.			
Туре	Micro Focus UCMDB				
Address	URL of UCMDB (ie. https	://cms.smax.swdemos.net:8443)			
Configuration	Specify the following configuration parameters:				
	cache.reusing.duration	Configure how far (in minutes) into the past this enrichment will look. For example, cache.reusing.duration=20			
	max.result.count Maximum result count for Get Observed Attack Techniques capability.For example: max.result.count=200				
	proxy.id ID of the Proxy integration if you access Micro Focus UCMDB through a web proxy device. For example, proxy.id = 12345				
Credential	Credential that has been menu.	defined for this integration under the Credentials			
Trust Invalid SSL Certificates	Select this if web server's certificate is self-signed or is not recognized by browsers.				
Require Approval From	Select user(s) from list to ask the approval before executing actions on this integration.				
Notify	Select user(s) from the li integration.	st to notify when SOAR performs an action on this			

- 5. Click **Save** to save the integration definition.
- 6. Navigate to Configuration>Customization Library and edit Micro Focus UCMDB Advanced Action Script Default Template.
- 7. Select the integration that you have added to Integrations menu.
- 8. Click **Save** to complete the integration.

Configuring SOAR Page 403 of 594

9. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. Expose CI Information

Enrichment capability for information related to the CIs of a certain type.

The following table presents the **CI Enrichment** capability details:


Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	No	Yes
Layout	The comma seperated columns that are displayed in the output, for example, display_label, name, description, node_role	Text	No	Yes
Туре	The CI Type. For example, node, sqlserver, unix.	Text	No	Yes
Column	The value of this column is checked against the value you provided, for example, application_ip or name	Text	No	No
Value	Value, that is going to used during filtering.	Scopeltem	Yes	No

Output:

Case Scope:

Action	Туре	Category/ Value
Add	Scope Item	Keyword(Related)

Human Readable Output:



2. Get CI

Enrichment capability for returning details of a CI.

Capabilities Page 404 of 594

The following table presents the **Get CI** enrichment capability details:


Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	No	Yes
ID	CI id. If provided this value will be used regardless of the IP and Type values.	Keyword	Yes	No

Output:

Case Scope:

Action	Туре	Category/ Value
None	N/A	N/A

Human Readable Output:



3. Get Related CIs

Enrichment capability for returning the details of the CIs related to the specified CI. The following table presents the **Get Related CI** enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	No	Yes
ID	CI id. If provided this value will be used no matter type or ip provided or not.	Keyword	Yes	Yes
Туре	The string that represents the name of a valid configuration item type from the UCMDB. The name of the CI Type can be found inside the CI Type Manager.	Text	No	Yes


Output:

Capabilities Page 405 of 594

Case Scope:

Action	Туре	Category/ Value
None	N/A	N/A

Human Readable Output:



Capabilities Page 406 of 594

Integration Guide for Microsoft Exchange

Integration Overview

Exchange Server is a mail server developed by Microsoft.

SOAR has the following integration capabilities with Microsoft Exchange Server:

- Delete email
- Mark email
- · Quarantine email

Use Case: Deleting already delivered phishing emails

SOAR can follow email inboxes for user's phishing reports and automatically creates an incident record on its service desk. During the investigation of the attack SOAR can extract the sender address and subject and using these values performs a search on Microsoft Exchange Server to mark or delete already delivered malicious messages. This can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to Microsoft Exchange Web Service API via HTTPS. So access to 443/tcp port is required.
- A user account with impersonation role is required for SOAR to connect Microsoft Exchange.

Configuration on Microsoft Exchange

- 1. Login to Microsoft Exchange admin center and add a user mailbox for SOAR.
- 2. Open Exchange Management Shell and give the user Application Impersonation role using the following command:

```
New-ManagementRoleAssignment \
   -Name:<impersonation Assignment Name> \
   -Role:ApplicationImpersonation \
   -User:<account name>
```

Configuration on SOAR

- 1. Navigate Configuration > Credentials and click Create Credential.
- 2. Specify the parameter values in the **Credential Editor** form as follows:

a. Internal Credential:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (i.e., Microsoft Exchange Credentials).	User you have configured SOAR on Microsoft Exchange (the format should be username@domain).	Password of the user you have configured for SOAR on Microsoft Exchange.	Empty

b. Credential Store:

Type: External credential.

Name: Name of the credential with pull path of the safe on store.

- 3. Navigate toConfiguration -> Integrations and click Create Integration.
- 4. Specify the parameter values in the **Configuration** form as follows:

Address	Configura tion	Credenti al	Trust Invalid SSL Certificated	Require Approval from	Notify	Require Approv al from	Notify
Display name of Microso ft Exchang e integrat ion on SOAR.	Microsoft Exchange	Address of the integrati on (the format should be 192.168. 2.8).	You need to specify the following configuration parameters requests.impersonation.d isable=false requests.cookies.enable=true mail.store.protocol=exch ange mail.incoming.pollerperi od=10000 mail.incoming.folder=Inb ox	Name of the credenti al set you've just created on step 2. (i.e., Microsof t Exchange Credenti als).	Select this if certifica te used on Exchan ge Server is self- signed or not recogni zed by browse rs.	Select user(s) from list to ask her/his approva I before executi ng actions on this integrat ion	Select user(s) from the list to notify when SOAR perform s an action on this integration.

- 5. Click **Test** to test the integration.
- 6. Click Save to complete integration.

Additional Notes

- To customize warning messages for Quarantine and Mark actions, edit the following parameters under **Configuration** > **Parameters**:
 - $^{\circ} \ \ MSExchange Mark Warning Text$
 - MSExchangeQuarantineWarningText
- To customize the mail folder to be used for Quarantine actions, edit the following parameter under **Configuration** > **Parameters**:
 - MSExchangeQuarantineEMailBox
- In some environments with multiple CAS deployments Exchange uses a request cookie to track the environment. The requests.cookies.enable configuration can help track the cookie so that SOAR won't have any mismatch and Subscription was not found error. It is by default true and should stay that way in most environments.

Additional Notes Page 409 of 594

Integration Guide for Microsoft Office365 Exchange EWS

Integration Overview

Exchange Server EWS provide access to mailbox data stored in Exchange Online, Exchange Online as part of Office 365, and on-premises versions of Exchange starting with Exchange Server 2007, and enable you to manage that information according to the requirements of your organization.



Note: This is the new version of Microsoft Exchange integration and old one will be phased out.

Users are encouraged to use this integration.

ArcSight SOAR has the following integration capabilities with Microsoft Exchange EWS:

- Block Email Sender
- Delete Email
- Delete Attachment
- Get Attachments
- Get Emails
- Search Emails

Use Case: Deleting already delivered phishing emails

SOAR follows email inboxes for user's phishing reports and automatically creates an incident record on its service desk. During the investigation of the attack ATAR can extract the sender address and subject and using these values performs a search on Microsoft Exchange Server to delete already delivered malicious messages and block malicious senders. This can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to Microsoft Exchange Web Service API using HTTPS. So access to 443/tcp port is required.
- A user account with the following permissions is required for SOAR to connect MS Exchange EWS Server:

- ApplicationImpersonation (Authorized to make operations for other users' accounts)
- MailboxSearch (Authorized to search all mailboxes).

Configuration on Microsoft Exchange

- 1. Login to Microsoft Exchange Admin Center (For example, https://exchangeserver/ecp) and add a user mailbox for SOAR.
- 2. Navigate to **Permissions** > **Cloud Migrator Impersonation**, edit and add user account you have created in first step to "Members" to give Account Impersonation permission.
- 3. Navigate to **Permissions > Discovery Management**, edit and add user account you have created in first step to "Members" to give Mailbox Search permission

Using OAuth2 with Microsoft Exchange online Integrtations

You can use the OAuth authentication service provided by Azure Active Directory to enable your EWS Managed API applications to access Exchange Online in Office 365. To use OAuth with your application complete the following:

- 1. Register the application for OAuth2. For more information see Microsoft Documenation.

 After the application registered, it appears in the Application list. Click the application to view details.
- 2. Copy the values for Application(client) ID, Directory(tenant) ID and Client Credentials fields to create credentials in SOAR.



3. Configure the following permissions for registered Application:



Configuring SOAR

1. Navigate Configuration > Credentials and click Create Credential.

Fill the Credential Editor form as follows:

a. Internal Credential:

Туре	Internal credential.
Name	Display name of credential set (i.e., MS Exchange EWS Credentials).
Username	Application(client) ID value that has been copied from the application.
Password	Client Credentials value that has been copied from the application.
Private Key:	Directory(tenant) IDvalue that has been copied from the application.

b. Credential Store:

Туре	External credential.
Name	Name of the credential with pull path of the safe on store.

- 2. Navigate Configuration > Integrations and click Create Integration.
- 3. Fill the configuration form as follows:

Name:	Display name of Microsoft Exchange EWS integration on ATAR.
Туре:	Microsoft Exchange EWS.
Address:	Address of the integration (the format should be outlook.office365.com or 192.168.2.7).

Configuring SOAR Page 412 of 594

Configurati	You need to specify the following configuration parameters:
on:	# Maximum record number per paginated response. Default value is 1000 page.size=200 # Connect time out in seconds. Default value is 200 connect.timeout=7200 # Request time out in seconds. Default value is 200 request.timeout=7200 # Trash folder name. Default value is Deleted Items #trash.folder= # Junk folder name. Default value is Junk Email #junk.folder= # Maximum record number per paginated attachment detail response. Default value is 10 #attachment.page.size= # Microsoft Exchange Server enrichment API timezone, if not specified GMT will be used as default #timezone= # Maximum number of email id list per request. Default value is 5 #email.id.size= # Maximum record number per paginated item detail response. Default value is 10 #email.page.size= # Maximum email item limit for each enrichment. Default value is 1000 #email.limit= # Maximum attachment item limit for each enrichment. Default value is 100 #attachment.limit= # Authentication methods for the integration. Supported options: Basic, OAuth2, default is Basic #auth.type= Set auth.type=OAuth2in integration configurations to enable OAuth2.
Credential	Select newly created OAuth2 credential for credential field. (i.e., Microsoft Exchange Credentials).
Trust Invalid SSL Certificates	Select this if certificate used on Exchange Server is self-signed or not recognized by browsers.
Require Approval From:	Select user(s) from list to ask approval before executing actions on this integration
Notify	Select user(s) from the list to notify when ATAR performs an action on this integration.

- 4. Click the Test button.
- 5. Click **Save** to complete integration.

Additional Notes

For Delete capability, at least one of the following parameters should be given:

Additional Notes Page 413 of 594

- Email From
- Email Subject
- Email ID
- Attachment ID

And there are 3 deletion methods:

- Hard Delete: Deletes permanently (default)
- Move To Trash: Moves to trash folder (such as Deleted Items folder)
- **Soft Delete:** Moves to dumpster if it is enabled.

Integration Guide for Microsoft Teams

Integration Overview

Microsoft Teams is a messaging and collaboration app for organizations. It allows users to communicate and collaborate in real-time. It also allows users to conduct online meetings and share files among other features for business communications.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Microsoft Teams:

- List Teams
- List Channels
- Create Team
- Create Channel
- List Team Members
- Add Team Member
- Delete Member
- Send Message
- Retrieve Message
- Archive Team
- Unarchive Team

Prerequisites

You must have HTTP access as ArcSight SOAR connects to Microsoft Team API through this service.

Configuration

Configuring Microsoft Teams

To authenticate to Microsoft Teams, you must get a token from the Microsoft identity platform endpoint. Your service can use the token to call Microsoft Graph under its own identity.

- 1. Register your app.
- Add redirect_uri (for send message channel)
- 3. Configure permissions for Microsoft Graph on your app.
- 4. Get administrator consent.
- 5. Get an access token.
- 6. Use the access token to call Microsoft Graph.

Parameters	Description
client_id	The application ID that's assigned to your app. You can find this information in the portal where you registered your app.
client_secret	The client secret that you generated for your app in the app registration portal. The client secret must be URL-encoded before being sent. The Basic auth pattern of instead providing credentials in the Authorization header, per RFC 6749 is also supported.
grant_type	Must be set to client credentials.

7. On the last page, you will see the access key ID and the secret code. Save the details in a secure place.

Authentication Parameters

Request Headers:

Parameters	Datatype	Description	Required
Access Key	string	Access key of the user	Yes
Secret Key	string	Secret Key	Yes

Additional Configuration:

Prerequisites Page 415 of 594

Configuration Parameter	Description
proxy.id	Proxy device to be used while communicating with the remote system's API
cache.reusing.duration	Default cache-reuse parameter
tenant_id	The directory tenant against which the application plans to operate, in GUID or domain-name format.
owner_email.id	The email of a user who has owner access.
redirect.uri	The redirect_uri of your app, where authentication responses can be sent and received by your app. It must exactly match one of the redirect_uris you registered in the portal, but it must be URL-encoded.

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameters values in the Credential Editor form:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, Microsoft Teams credentials)	The application ID (Client_id) that is assigned to your app. You can find this information in the portal where you have registered the app.		

- 3. Click Configuration > Integrations > Upload plugin.
- 4. Select your integration plugin zip file and click Save.
- 5. Select the integration that you have added to the Integrations menu.
- 6. Click Save to complete the integration.
- 7. Click Test. A successful message is displayed if the credential and address are valid.

Integration Capabilities

1. List Teams

Enrichment capability to fetch the list of teams in an organization (tenant). To get a list of all groups in the organization that has Teams, get a list of all groups, and then in code find the ones that have a resourceProvisioningOptions property that contains Team.

Required Permissions

Permission Type	Permissions (from least to most privileged)	
Application	GroupMember.Read.All, Group.Read.All, Directory.Read.All, Group.ReadWrite.All, Directory.ReadWrite.All	

Configuring SOAR Page 416 of 594

Request headers

Header	Value	Required
Authorization	Bearer{Token}	Yes
Content-type	application/json	No

Default Parameters

Parameter	Description	Data Type	Scope Restricted	Required
\$top	This parameter is internally used to get the group item per page (default set it to 999) Eg: /users?\$top=999	Integer	No	No
\$filter	Filters results (rows). (Default is set to `Team`). E.g.: /groups?\$filter=resourceProvisioningOptions/Any(x:x eq 'Team')	String	No	No

Output:

Case Scope

N/A

Human Readable Output

ld	Display Name	Description	Visibility	Mail Enabled	Mail Nickname	Security Enabled
024b4ef1- d630-4932- 84fb- a280602c7185	Microfocus	final test	Public	true	Microfocus	false
03993312- b1b5-466f- 83c6- 69c08a318069	Architecture Team	The team for those in architecture design.	Public	true	ArchitectureTe am	false
0809e34c- dcae-49d8- b2c2- c918c3985cf7	MicroFocus	team	Public	true	MicroFocus78 4	false

2. List Channels

Enrichment capability to get the list of channels either in this team or shared with this team (incoming channels).

Required Permissions:

Permission type	Permissions (from least to most privileged)
Application	Channel.ReadBasic.All, ChannelSettings.Read.All, ChannelSettings.ReadWrite.All

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
Team Display Name	The name of the Team. (Team ID will be fetched internally by using the given team's name).	String	No	Yes

Request headers:

Header	Value	Required
Authorization	Bearer{token}	Yes
Content-type	application/json	No

Output:

Case Scope: N/A

Human Readable Output

Channel Id	Created Date Time	Dispaly Name	Description	Membership Type
19:088e199a9062477 b9afc2b3e42c50964 @thread.tacv2	2022-12- 20T12:21:00.842Z	Microsoft Postman collection	This channel is where we have to collect all microsoft apis endpoints in potsman	standard
19:2c616503f76a403 08c1b24dd1adb209e @thread.tacv2	2022-12- 25T00:28:18.08Z	My Private Channel	This is my first private channels	private
19:2fb57f001ede44e3 b12f4954fea62457@t hread.tacv2	2022-12- 29T09:44:25.411Z	My Channel	This is my first private channels	standard
19:c26838ce37a04d3 a8db56ea146ea44d1 @thread.tacv2	2023-01- 19T12:23:41.352Z	Demo channel	demo channel	standard
19:d00ec51f6ece4ac 2a1b70c7f3788691e @thread.tacv2	2023-01- 24T11:44:44.174Z	Sacumen Microfocus Channel	Only Microfocus realted discussion	standard

3. Create Team

Action capability to create a new team.

• Rollback: No

• Duplicate Control: Yes

Required Permissions:

Permission type	Permissions (from least to most privileged)
Application	Team.Create, Teamwork.Migrate.All, Group.ReadWrite.All**, Directory.ReadWrite.All**



Permissions marked with ** are supported only for backward compatibility. It is recommend that you update your solutions to use an alternative permission listed in the previous table and avoid using these permissions going forward.

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
Display Name	The name of the team.	String	No	Yes
Description	A description for the team.	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

4. Create Channel

Create a new channel in a team, as specified in the request body.

Rollback: No

Duplicate Control: Yes



You can add a maximum of 200 members when you create a private channel.

Required Permissions

Permission type	Permissions (from least to most privileged)
Application	Channel.Create.Group*, Channel.Create,Teamwork.Migrate.All, Group.ReadWrite.All**, Directory.ReadWrite.All**



Permissions marked with ** are supported only for backward compatibility. It is recommend that you update your solutions to use an alternative permission listed in the previous table and avoid using these permissions going forward.

Request headers

Header	Value	Required
Authorization	Bearer {token}	Yes
Content-type	application/json	No

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
Team Display Name	The name of the Team. (Team Id will be identified internally)	String	Yes	Yes
Channel Display Name	Channel name as it will appear to the user in Microsoft Teams. The maximum length is 50 characters.	String	No	Yes
Description	Textual description for the channel.	String	No	Yes

Default Parameters

Parameter	Description	DataType	Scope Restricted	Required
membershipType	The type of channel. Can be set during creation and can't be changed. The possible values are standard, private, unknownFutureValue, shared. The default value is standard. Note that you must use the Prefer: include-unknown-enum-members request header to get the following value in this evolvable enum: shared. (Default is set to `private`.)	String	No	No

Output:

Case Scope: N/A

Human Readable Output: N/A

5. List Team Members

Enrichment Capability to list given team members.

Required Permissions

Permission type	Permissions (from least to most privileged)
Application	TeamMember.Read.Group*,TeamMember.Read.All, TeamMember.ReadWrite.All



Permissions marked with ** are supported only for backward compatibility. It is recommend that you update your solutions to use an alternative permission listed in the previous table and avoid using these permissions going forward.

Request headers

Header	Value	Required
Authorization	Bearer {token}	Yes
Content-type	application/json	No

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
Team Display Name	The name of the team	String	Yes	Yes

Default Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
MaxResults	You can use this parameter to indicate the maximum number of items you want in the response. The default value is 50. The maximum value is 50.	integer	No	No
NextToken	You can use this parameter when paginating results. Set the value of this parameter to null on your first call to the list action. For subsequent calls to the action, fill nextToken in the request with the value of NextToken from the previous response to continue listing data.	String	No	No

Output:

Case Scope: N/A

Human Readable Output

User Id	Name	Email	Team Membership Id	Role
aaccb40a-16e2- 4aad-9457- 0785f45abe3a	deepak.b	deepak.b@mfsac001. onmicrosoft.com	MCMjMSMjMWQ4Yj VmM2UtMWIwMy00Z jk4LWEyNTQtZWM4 OGM1ZGZINTZIIyM5 ZDIyOGFIZC04OTVIL TRKYTMtOTJjMi0wO TM2MWFmZDMyYW EjI2FhY2NINDBhLTE 2ZTItNGFhZC05NDU 3LTA3ODVmNDVhY mUzYQ==	N/A
3b37f154-67f5-4019- a8f0-a9fa54bdb9f2	Akash		MCMjMSMjMWQ4Yj VmM2UtMWlwMy00Z jk4LWEyNTQtZWM4 OGM1ZGZINTZIIyM5 ZDIyOGFIZC04OTVIL TRKYTMtOTJjMi0wO TM2MWFmZDMyYW EjlzNiMzdmMTU0LT Y3ZjUtNDAxOS1hO	N/A

6. Add Team Member

Action capability to add a member to a given team.



The roles property will be empty by default for all members. This property only contains additional qualifiers when relevant - for example, if the member has owner privileges, the roles property contains owner as one of the values. Similarly, if the member is a guest, the roles property contains a guest as one of the values. A basic member should not have any values specified in the roles property.

Rollback: No

Duplicate Control: Yes **Required Permissions:**

Permission type	Permissions (from least to most privileged)
Application	TeamMember.ReadWrite.All

Request headers:

Header	Value	Required
Authorization	Bearer {token}	Yes
Content-type	application/json	No

Default Parameters:

Parameter	Description	DataType	Scope Restricted	Required
@odata.type	It's value should be: `#microsoft.graph.aadUserConversationMember`	String	No	No



Do not add any guest to the team using this action capability as the name only suggests adding a member to the team. If you are trying to add guests, you will get an access denied error.

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
Team Display Name	The name of the team	USERNAME, UNKNOWN, KEYWORD	Yes	Yes
Member Mail	The user object that needs to be added. Eg: `https://graph.microsoft.com/v1.0/users ('8b081ef6-4792-4def-b2c9-c363a1bf41d5')` Internally member id will generate	String. EMAIL_ADDRESS	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

7. Delete Member

Action Capability to delete team members.

Rollback: No

Duplicate Control: No

Required Permissions

Permission type	Permissions (from least to most privileged)
Application	TeamMember.ReadWrite.All

Request headers

Header	Value	Required
Authorization	Bearer {token}	Yes
Content-type	application/json	No

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
Team Display Name	The name of the team	USERNAME, UNKNOWN, KEYWORD	Yes	Yes
Member Display Name	The name of the team member. (The team membership Id will be identified internally).	USERNAME, UNKNOWN, KEYWORD	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

8. Send Message

Action Capability to Send a message in the specified channel.

Rollback: No

Duplicate Control: No



Application permissions are supported for <u>migration</u> only. In the future, Microsoft may require an additional fees to be paid based on the amount of data imported.

Therefore, for the above note, a different authentication mechanism called auth_code flow has been added. Here, the user must perform several steps.

To get auth code url, perform the following:

a. The user must call the Get Auth Code URL enrichment capability.




The Auth URL is present in ArcSight SOAR case timeline.



This has to be done before performing send message in channel action capability.

- b. Copy the Auth URL from ArcSight SOAR case timeline and paste it into a web browser. On pasting this URL, the browser would be redirected to the Permissions page. Check the Consent on behalf of your organization checkbox and click Accept.
- c. After accepting the permissions, the browser will redirect to the **redirect_uri** with a code in the address bar.





Authorization codes typically expire after about 10 minutes.

d. Use the following CURL command to get the **Auth Code**, which is required to get the **Refresh Token**.


```
curl --location --request POST
'https://login.microsoftonline.com/common/oauth2/v2.0/token' \
--header 'Content-Type: application/x-www-form-urlencoded' \
--data-urlencode 'client_id=<client id>' \
--data-urlencode 'scope=https://graph.microsoft.com/mail.read' \
--data-urlencode 'redirect_uri=<redirect_uri>' \
--data-urlencode 'grant_type=authorization_code' \
--data-urlencode 'client_secret=<client secret>' \
--data-urlencode 'code=<auth_code>'
curl -'
```

Parameters for the refresh token generation

Parameters	Description	DataType	Required
client_id	The application ID that is assigned to your app. You can find this information in the portal where you registered your app.	String	Yes
scope	Default set as:-https://graph.microsoft.com/mail.read	String	Yes
client_secret	The client secret that you generated for your app in the app registration portal. The client secret must be URL-encoded before being sent. instead of providing credentials in the Authorization header, per RFC 6749 providing basic auth pattern is also supported.	String	Yes

Parameters	Description	DataType	Required
grant_type	Must be authorization_code for the authorization code flow. Default set it as: Authorization_code	String	Yes
redirect_uri	The redirect_uri of your app, where authentication responses can be sent and received by your app. It must exactly match one of the redirect URIs you registered in the portal .	String	Yes
code	The authorization_code that the app requested. The app can use the authorization code to request an access token for the target resource. Authorization codes are short lived. Typically, they expire after about 10 minutes.	String	Yes

e. Click Credential Editor > Private Key and paste the referesh token value.





This step is only required if and only if the user gets the unauthorized code message while performing **Send message in channel** action capability.

Required Permissions:

Permission type	Permissions (from least to most privileged)	
Delegated	Required permissions already added in authorized code URLs.	

Request headers

Header	Value	Required
Authorization	Bearer {token}	Yes
Content-type	application/json	No

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
Team Display Name	The name of the team	String	No	Yes
Content	The text message to send to channel	String	No	Yes
Channel Display Name	The name of the channel	String	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

9. Retrieve Message

Enrichment Capability to retrieve messages from a given channel.

Permissions for channel:

Permission type	Permissions (from least to most privileged)
Application	ChannelMessage.Read.Group, ChannelMessage.Read.All, Group.Read.All**, Group.ReadWrite.All**



Permissions marked with ** are supported only for backward compatibility. It is recommend that you update your solutions to use an alternative permission listed in the previous table and avoid using these permissions going forward.

Request headers

Header	Value	Required
Authorization	Bearer {token}	Yes
Content-type	application/json	No

Default Request Body Parameters:

Request Body	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
Team Display Name	The name of the team	String	No	Yes
Channel Display Name	Name of the channel	HOST, UNKNOWN, KEYWORD	Yes	Yes

Limitations: Retrieve Message is a Protected API



Microsoft Teams APIs in Microsoft Graph that access sensitive data are considered protected APIs. These APIs require that you have additional validation, beyond permissions and consent, before you can use them. For more information see, Protected APIs. To request access to these protected APIs, fill the request form to connect with the Microsoft support team.

Output:

Case Scope: N/A

Human Readable Output:

ld	Created Date Time	Sender Name	Content	Content Type
1676533857278	2023-02- 16T07:50:57.278Z	Abdul Shuaib	MS Team Auth code required only	text
1674981579526	2023-01- 29T08:39:39.526Z	Abdul Shuaib	yep	text
1674981576704	2023-01- 29T08:39:36.704Z	Abdul Shuaib	See you	text
1674981571583	2023-01- 29T08:39:31.583Z	Abdul Shuaib	thank you bye	text
1674981565070	2023-01- 29T08:39:25.07Z	Abdul Shuaib	Nice to talk with you!!	text
1674981548578	2023-01- 29T08:39:08.578Z	Abdul Shuaib	okay	text

10. Archive Team

Action capability to archive a given team.

Rollback: Yes

Duplicate Control: No **Required Permissions**

Permission type	Permissions (from least to most privileged)
Application	$\label{lem:comp} Team Settings. Read Write. All, Group. Read Write. All **, irectory. Read Wri$



Permissions marked with ** are supported only for backward compatibility. It is recommended that you update your solutions to use an alternative permission listed in the previous table and avoid using these permissions going forward.

Request headers

Header	Value	Required
Authorization	Bearer {token}	Yes
Content-type	application/json	No

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
Team Display Name	The name of the team	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

11. Unarchive Team

Action capability to archive a given team.

Rollback: Yes

Duplicate Control: No **Required Permissions**

Permission type	Permissions (from least to most privileged)
Application	Team Settings. Read Write. Group *, Team Settings. Read Write. All, Group. Read Write. All **, irectory. Read Write. All **



Permissions marked with ** are supported only for backward compatibility. It is recommend that you update your solutions to use an alternative permission listed in the previous table and avoid using these permissions going forward.

Path Parameters:

Path Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
Display Name	The name of the team.	String	No	Yes
Description	A description for the team.	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

Integration Guide for Microsoft Windows DNS Server

Integration Overview

ArcSight SOAR uses Microsoft Windows DNS Server to redirect IP address to another IP address.

SOAR checks connection.secure parameter to connect via WinRM over http or https protocol.

Integration Capabilities

- Action
- Block

Configuration

Configuration on Microsoft Windows DNS Server

- SOAR connects to Microsoft Windows DNS Server's integration API via WinRM services. Therefore SOAR should be able to connect this service.
- WinRM credential is required.

Configuring ATAR

1. While creating this integration via Integrations tab of Configuration menu:

Name: Display name of the integration.

Type: Microsoft Windows DNS Server.

Address: Address of the integration (the format should be http[s]://1.1.1.1:1234).

Credential: WinRM credential is required. Credential that has been defined for this

integration under the Credentials menu.

Configuration: You need to specify the following configuration parameters.

dns.zone.name: Redirected DNS server zone name

dns.block.ip: Redirection address
dns.server.name: DNS server name

#Use https:// instead of http:// on WinRM connection

connection.secure=true : For secure connections, otherwise set to false.
#Parameters:

Windows DNS command execution path.

Trust Invalid SSL Certificates: Select this if Engine's certificate used for the service is self-signed or not recognized by browsers.

Require Approval From: Select user(s) from list to ask her/his approval before executing actions on this integration.

Notify: Select user(s) from the list to notify when ATAR performs an action on this integration.

- 2. Click the **Test** button.
- 3. Click **Save** to complete integration.

Configuring ATAR Page 431 of 594

Integration Guide for Microsoft Windows Services (WinRM)

Integration Overview

Integration Capabilities

- Action
- None

Configuration

Configuration on Microsoft Windows Services

- SOAR connects to Microsoft Windows Service's integration API via WinRM services.
- Therefore SOAR should be able to connect this service.
- WinRM credential is required.

Configuring SOAR

1. While creating this integration via Integrations tab of Configuration menu:

Name: Display name of the integration.

Type: Microsft Windows Services.

Address: Address of the integration (the format should be 1.1.1.1 or abc.example.com).

Configuration: You need to specify the following configuration parameters.

putfile.generateuuid =

putfile.defaultfolder =

connection.secure = true

Credential: Credential that has been defined for this integration under the Credentials menu.

Trust Invalid SSL Certificates: Select this if certificate used for the service is selfsigned or not recognized by browsers.

Require Approval From: Select user(s) from list to ask her/his approval before executing actions on this integration.

Notify: Select user(s) from the list to notify when SOAR performs an action on this integration.

- 2. Click the **Test** button.
- 3. Click **Save** to complete integration.

Configuring SOAR Page 433 of 594

Integration Guide for Microsoft Graph Security

Integration Overview

Microsoft Graph Security is an intermediary service (or broker) that provides a single programmatic interface to connect multiple Microsoft Graph Security providers such as Azure Security Center, Microsoft Defender APT, Microsoft Cloud App. Security, etc. Microsoft Graph Security integration lets you to search and manage security alerts created by those providers. This integration supports Microsoft Graph API v1.0.

Integration Capabilities

- · Assign Alert
- Get Alert by ID
- List Alerts
- List Alerts by Category
- List Alerts by Destination
- List Alerts by Provider
- List Alerts by Severity
- List Alerts by Source IP
- List Alerts by Status
- Update Alert Comment
- Update Alert Feedback
- Update Alert Status

Prerequisites

ArcSight SOAR connects to "login.microsoft.com" and "graph.microsoft.com" APIs through HTTPS. Access to these services is required

.

Configuration

Configuring Microsoft Azure

- Login to https://portal.azure.com and navigate to Azure Active Directory service.
- 2. Create a new registration in App Registrations menu following values.



Note: If an application is defined for other integrations, skip steps 1-3 to use it.

Name	Supported Account Types	Redirect URI
ArcSight SOAR	Accounts in this organizational directory only (Default Directory only - Single tenant)	(Web) https://localhost/soar

- 3. Click **Add a certificate or secret link** and create a new client secret. Specify the description and expiry period as 24 months.
- 4. Note the created Secret Key value along with Client ID.
- 5. Navigate to API Permissions and add the following permissions from Microsoft Graph:

Permission Type	Permission	Description
Application	SecurityEvents, ReadWrite, All.	Read and update your organization's security events.

6. Click Yes to grant admin consent for Default Directory.

Configuring SOAR

- Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor** form:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, Azure AD Credential).		Client ID of the application (for example, ArcSight SOAR) that is registered on Azure Portal.	Secret Key

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of the integration.
Туре	Microsoft Graph Security

Configuration Page 435 of 594

Parameter	Value			
Address	Address of t	Address of the integration (https://graph.microsoft.com/v1.0/security).		
Configuration	Specify the	following configuration parameters:		
	tenant.id Tenant ID on Microsoft Azure tenant.id = ff1f0000-c600-4500-00 9d4000000000			
	proxy.id	ID of the Proxy integration if you access Microsoft Graph Security through a web proxy device. For example, proxy.id = 12345		
Credential	Credential that has been defined for this integration under the Credentials menu.			
Trust Invalid SSL Certificates	Select this if web server's certificate is self-signed or is not recognized by browsers.			
Require Approval From	Select user(s) from list to ask the approval before executing actions on this integration.			
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.			

- 5. Click **Save** to save the integration definition.
- 6. Navigate to Configuration>Customization Library and edit Microsoft Graph Security Advanced Action Script Default Template.
- 7. Select the integration that you have added to Integrations menu.
- 8. Click **Save** to complete the integration.
- 9. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. Assign Alert

Action capability for assigning security alert to a person on Azure Security Center.

• Rollback: No

• Duplicate Control: No

The following table presents the assign alert action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Assign to	Person this alert to be assigned to.	String	No	Yes

Capabilities Page 436 of 594

Case Scope: N/A

Human Readable Output: N/A

2. Get Alert by ID

Enrichment capability for querying & retrieving security alert details by alert ID.

The following table presents the get alert ID enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Alert ID	Alert ID on Azure Security Center.	String	No	Yes


Output:

Case Scope:

Action	Туре	Category/ Value
None	N/A	N/A

Human Readable Output:

Following image provides the Human Readable Output:



3. List Alerts

Enrichment capability for getting list of security alerts created in given time range. Results are based on the alerts creation time, displayed in newest to oldest manner..

The following table presents thelist alerts enrichment capability details:

Capabilities Page 437 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Time Range	Time range filter for query.	Time range. Relative: e.g. Last 5 days Absolute: For example, 2021-08-14 15:10 – 2021-08-14 15:32	N/A	Yes

Case Scope:

Action	Туре	Category/ Value
None	N/A	N/A

Human Readable Output:

Following image provides the **Human Readable Output**:



4. List Alerts by Category

Enrichment capability for getting list of security alerts of a certain category created in given time range. Results are based on the alerts creation time, displayed in newest to oldest manner.

The following table presents the list alert by category enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Alert Category	Category name	String	No	Yes

Capabilities Page 438 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Time Range	Time range filter for query.	Time range. Relative: e.g. Last 5 days Absolute: For example, 2021-08-14 15:10 – 2021-08-14 15:32	N/A	Yes

Case Scope:

Action	Туре	Category/ Value
None	N/A	N/A

Human Readable Output:

Following image provides the **Human Readable Output**:



5. List Alerts by Destination

Enrichment capability for getting list of security alerts with the specified destination field, created in given time range. Results are based on the alerts creation time, displayed in newest to oldest manner.

The following table presents the list alerts by destination enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Destination	Destination Address.	Host Network Address URL .	Yes	Yes
Time Range	Time range filter for query.	Time range. Relative: e.g. Last 5 days Absolute: For example, 2021-08-14 15:10 – 2021-08-14 15:32	N/A	Yes

Output:

Case Scope:

Action	Туре	Category/ Value
None	N/A	N/A

Human Readable Output:

Capabilities Page 439 of 594

Following image provides the **Human Readable Output**:

Created Time	Title	Severity	Status	И
2021-08-20T04:42:24.8891406Z	(SAMPLE ALERT) Potential SQL Injection	high	newAlert	2517728663351108593_e028a31a -2d7a-437a-aa0b-ab4f824ce7c3
2021-08-20T04:42:24.8891406Z	[SAMPLE ALERT] Possible data exfiltration via DNS tunnel (Preview)	low	newAlert	2517728663151108593_7ad617e 3-558b-4407-8d2d-7c3f401f65a1
2021-08-20T04:42:24.8891406Z	[SAMPLE ALERT] MicroBurst exploitation toolkit used to extract keys to your storage accounts (Preview)	high	in Progress	2517728663071108593_7369252 4-d021-43f6-8f9a-e23af4380fb5
2021-08-20T04:42:24.8891406Z	[SAMPLE ALERT] Suspected successful brute force attack	high	inProgress	2517728663331108593_791d8c4 6-46ac-4adb-9cad-6f3aab496c41
2021-08-20T04:42:24.8891406Z	(SAMPLE ALERT) Executable found running from a suspicious location	medium	newAlert	2517728662951264282_a9f1b21a -03ad-4b80-837d-3cb2aec27c70

6. List Alerts by Provider

Enrichment capability for getting list of security alerts originated from the specified security provider, created in given time range. Results are based on the alerts creation time, displayed in newest to oldest manner.

The following table presents the list alerts by provider enrichment capability:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Provider	One of the Microsoft Security Providers.	String Azure Active Directory Identity Protection Azure Advanced Threat Protection Azure Security Center Azure Sentinel Microsoft Cloud App Security Microsoft Defender Advanced Threat Protection	No	Yes
Time Range	Time range filter for query.	Time range. Relative: For example, Last 5 days Absolute: For example, 2021-08-14 15:10 – 2021-08-14 15:32	N/A	Yes

Output:

Case Scope:

Action	Туре	Category/ Value
None	N/A	N/A

Human Readable Output:

Capabilities Page 440 of 594

Following image provides the **Human Readable Output**:

Created Time	Title	Severity	Status	М
2021-08-20T04:42:24.8891406Z	(SAMPLE ALERT) Potential SQL Injection	high	newAlert	2517728663351108593_e028a31a -2d7a-437a-aa0b-ab4f824ce7c3
2021-08-20T04:42:24.8891406Z	[SAMPLE ALERT] Possible data exfiltration via DNS tunnel (Preview)	low	newAlert	2517728663151108593_7ad617e 3-558b-4407-8d2d-7c3f401f65a1
2021-08-20T04:42:24.8891406Z	[SAMPLE ALERT] MicroBurst exploitation toolkit used to extract keys to your storage accounts (Preview)	high	in Progress	2517728663071108593_7369252 4-d021-43f6-8f9a-e23af4380fb5
2021-08-20T04:42:24.8891406Z	[SAMPLE ALERT] Suspected successful brute force attack	high	inProgress	2517728663331108593_791d8c4 6-46ac-4adb-9cad-6f3aab496c41
2021-08-20T04:42:24.8891406Z	(SAMPLE ALERT) Executable found running from a suspicious location	medium	newAlert	2517728662951264282_a9f1b21a -03ad-4b80-837d-3cb2aec27c70

7. List Alerts by Severity

Enrichment capability for getting list of security alerts with the specified severity value, created in given time range. Results are based on the alerts creation time, displayed in newest to oldest manner.

The following table presents the list alerts by severity enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Alert Severity	Alert severity set by vendor/ provider.	String High Medium Low Informational Unknown	No	Yes
Time Range	Time range filter for query.	Time range. Relative: For example, Last 5 days Absolute: For example, 2021-08-14 15:10 – 2021-08-14 15:32	N/A	Yes

Output:

Case Scope:

Action	Туре	Category/ Value
None	N/A	N/A

Human Readable Output:

Following image provides the **Human Readable Output**:

Capabilities Page 441 of 594

Created Time	Title	Severity	Status	ld
2021-08-20T04:42:24.8735717Z	[SAMPLE ALERT] Exposed Kubernetes service detected	medium	newAlert	2517728662731264282_6fadb8e3 -cc13-4633-988f-1bf342f9af94
2021-08-20T04:42:24.8735717Z	[SAMPLE ALERT] Logon from an unusual location	medium	newAlert	2517728662831264282_4a0555a b-14fe-4d8c-97be-f368f0825b35
2021-08-20T04:42:24.8735717Z	[SAMPLE ALERT] Kubernetes events deleted (Preview)	medium	newAlert	2517728663271264282_e4190ac7 -2754-4eaa-beb5-5d3e24e1ae2d
2021-08-20T04:42:24.8735717Z	[SAMPLE ALERT] High volume of operations in a Key Vault	medium	newAlert	2517728662631264282_32ecc7af- 91be-4b28-9ac5-511a271073d2
2021-08-20T04:42:24.8735717Z	(SAMPLE ALERT) Suspicious policy change and secret query in a Key Vault	medium	newAlert	2517728662671264282_e5953fcb -640c-41d1-a685-ec5bd18f05a7

8. List Alerts by Source IP

Enrichment capability for getting list of security alerts with the specified source IP field, created in given time range. Results are based on the alerts creation time, displayed in newest to oldest manner.

The following table presents the list alerts by source IP enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Source IP	Source IP Address.	Network Address	Yes	Yes
Time Range	Time range filter for query.	Time range. Relative: For example, Last 5 days Absolute: For example, 2021-08-14 15:10 – 2021- 08-14 15:32	N/A	Yes

Output:

Case Scope:

Action	Туре	Category/ Value
None	N/A	N/A

Human Readable Output:

Following image provides the **Human Readable Output**:



Capabilities Page 442 of 594

9. List Alerts by Status

Enrichment capability for getting list of security alerts with the specified status value, created in given time range. Results are based on the alerts creation time, displayed in newest to oldest manner.

The following table presents the list alerts by source enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Alert Status	Alert lifecycle status (stage).	String NewAlert InProgess Resolved Unknown	No	Yes
Time Range	Time range filter for query.	Time range. Relative: For example, Last 5 days Absolute: For example, 2021-08-14 15:10 – 2021- 08-14 15:32	N/A	Yes

Output:

Case Scope:

Action	Туре	Category/ Value
None	N/A	N/A

Human Readable Output:

Following image provides the Human Readable Output:



10. Update Alert Comment

Action capability for adding/updating comment feild of the security alert.

• Rollback: No

Duplicate Control: No

Capabilities Page 443 of 594

The following table presents the update alert comments action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Alert ID	Alert ID on Azure Security Center.	String	No	Yes
Alert Comment	Comment to be added to security alert.	String Closed in IPC Closed in MCAS	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

11. Update Alert Feedback

Action capability for adding/updating feedback feild of the security alert.

Rollback: No

• Duplicate Control: No

The following table presents the update alert feedback action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Alert ID	Alert ID on Azure Security Center.	String	No	Yes
Alert Feedback	Comment to be added to security alert.	String Benign Positive False Positive True Positive Unknown	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

12. Update Alert Status

Action capability for updating status of the security alert.

Capabilities Page 444 of 594

• Rollback: No

• Duplicate Control: No

The following table presents the update alert status action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
Alert ID	Alert ID on Azure Security Center.	String	No	Yes
Alert Status	Comment to be added to security alert.	String In Progress New Alert Resolved Unknown	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

Capabilities Page 445 of 594

Integration Guide for MISP

Integration Overview

The MISP threat sharing platform is a free and open source software helping information sharing of threat intelligence including cyber security indicators.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with MISP.

- File Reputation
- IP Reputation
- URL Reputation
- Get Event
- Add Attribute to Event
- Add Tag to Event
- Create Event
- Create Event with Attribute
- Remove Attribute from Event
- Remove Tag from Event

ArcSight SOAR integrates with MISP to gather, store threat information and can query to IoCs. The capabilities can either be performed automatically within a playbook or manually by an analyst.


Configuration

Prerequisites

- Access to tcp port 443 as SOAR connects to MISP using HTTPS
- An API key for SOAR to connect to MISP



Note: To gather the API key for SOAR, navigate to MISP Interface > Event Actions > Automation.



Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the Credential Editor form:
 - a. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, MISP Credentials)
Username	Empty
Password	Empty
Private Key	API Key retrieved from the MISP


- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration form**:

Parameter	Value	
Name	Display name of MISP integration on ArcSight SOAR	
Туре	MISP	
Address	Address of the cloud service, in the following format: https:// <misp_environement_ip></misp_environement_ip>	
Credential	Name of the credential set created in the previous step(For example, MISP Credentials)	

Prerequisites Page 447 of 594

Parameter	Value
Trust Invalid SSL Certificates	Not Applicable
Require Approval From	Select users from the list who can provide approval before executing enrichments on the integration
Notify	Select users from the list to notify when SOAR performs an enrichment on the integration

- 5. Click **Save** to complete the integration.
- 6. Navigate to Configuration > Customization Library.
- 7. In the Customization Editor, Edit MISP Advanced Action Script Default Script Template and for the Integrations field select the integration you saved (for example, MISP Integration).



- 8. Navigate to Configuration > Integrations.
- 9. Click **Edit** for the MISP integration you created.
- 10. Click **Test** to test the integration.

Prerequisites Page 448 of 594

Integration Guide for MxToolBox

Integration Overview

MxToolBox is a service that helps customers to make a query for domains and run the lookups.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with MxToolBox:

- Domain Blacklist Check
- Domain MX Check


Prerequisites

You must have access to HTTPS as the ArcSight SOAR connects to MxToolBox API through this service.


Configuration

Configuring MxToolBox

1. Login to MxToolBox and navigate to **Settings**, as shown in the following figure:



2. Click Automation API Access Settings in the Setting and add a new application.



3. Click API Tab and note the API Key to use on SOAR as shown in the following figure:

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the Credential Editor

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, MxToolBox Credential).			API Key that is noted from the service

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration Form**.

Parameter	Value
Name	Display name of MxToolBox integration on SOAR.
Туре	MxToolBox
Address	https://mxtoolbox.com
proxy.id	ID of the Proxy integration if you access mxtoolbox.com through a web proxy device. For Example: proxy.id = 12345.
Credential	Name of the credential set created on step 2(For example, MxToolBox Credentials).

Configuring SOAR Page 450 of 594

Parameter	Value
Trust Invalid SSL Certificates	The SSL certificate of MxToolBox service is going to known by SOAR, so you do not need to check this box.
Required Approval From	Select users from the list who can provide approval before executing actions on this integration.
Notify	Select users from the list to notify when SOAR performs an action on this integration.

- 5. Click **Save** to save the integration definition.
- 6. Navigate to Configuration > Customization Library > Open MxToolBox Script
- 7. Select integration that is created at step 4 for Integrations field.
- 8. Click Save to complete the integration.
- 9. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. Domain Blacklist Check

Enrichment capability for retrieving blacklist domain information.

The following table provides the **Domain Blacklist Check** enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Domain	Domain that you want to query.	Host	Yes	Yes
Integration	Name of the integration.	Integration	N/A	Yes

Output:

Case Scope: N/A

Human Readable Output: Yes

2. Domain MX Check

Enrichment capability for retrieving MX record information.

The following table provides the **Domain MX Check** enrichment capability details:


Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Domain	Domain that you want to query.	Host	Yes	Yes
Integration	Name of the integration.	Integration	N/A	Yes

Output:

Capabilities Page 451 of 594

Case Scope: N/A

Human Readable Output:



Integration Guide for Netskope v1

Overview of the Plugin

Netskope is a Cloud Security/Security Service Edge (SSE) platform which secures access to the web, cloud services. Netskope provides solutions to help organizations discover, understand, and secure cloud usage across all their users, devices, apps, and data. Their offerings include cloud security posture management, cloud access security broker (CASB), data loss prevention, and threat protection to help organizations safely embrace cloud services and meet compliance requirements.

Supported Integration Capabilities

ArcSight SOAR has the following integration capabilities with Netskope V1:

- List Quarantined Files
- · Allow Quarantined File
- Block Quarantined File

Prerequisites

You must have access to HTTPS, as the ArcSight SOAR connects to Netskope API through HTTPS service.

Configuration

Configuring Netskope

- Authentication: Netskope REST APIs use an auth token to make authorized calls to the API.
 Netskope REST APIs provide access to resources via URI paths. The auth token must be
 used in every REST API call for the tenant. Click Settings > Tools > Rest API v1 to generate
 or revoke a token in the Netskope UI.
- Click Generate New Token and note down the token generated.
- To set the token expiration, click the pencil icon next to the expiration date.
- From the dropdown list, select the number of hours, days, weeks or months to keep the token valid, or to never expire it, and then click **Save**.

Authentication Parameters

Request Headers:

Parameters	Datatype	Description	Required
Access Key	string	The Netskope REST API v1 token	Yes

2. Additional Configuration:

Configuration Parameter	Description
proxy.id	Proxy device to be used while communicating with the remote system's API
cache.reusing.duration	Default cache-reuse parameter



In the Address configuration, replace the tenant-name with your tenant name. Eg:https://alliances.goskope.com

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credentials.
- 2. Specify the following parameter values in the Credential Editor form.

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, Netskope v1	N/A	N/A	The Netskope REST API v1 token
	Credentials).			

Configuration Page 453 of 594

- 3. Click Configuration > Integrations > Upload plugin.
- 4. Select your integration plugin zip file and click Save.
- 5. Select the integration that you have added to the Integrations menu.
- 6. Click **Save** to complete the integration.
- 7. Click **Test**, an Integration Successful message is displayed if the credential and address are valid.

Integration Capabilities:

1. List Quarantined Files

Enrichment capability to get the list of quarantined files.

Input Parameters:

N/A

Default Parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
ор	The operation to be performed. Allowed values: get-files download-url take-action Default value: get-files (Will get list of quarantined files.)	String	No	Yes

Output:

Case Scope:

N/A

Human Readable Output:

2. Block Quarantined File

The action capability to block a quarantined file. This capability deletes the quarantined file.

Rollback: No

Duplicate Control: Yes

Input Parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Quarantine Profile Name	The profile name of the quarantined file.	String	No	Yes
File Name	The name of the quarantined file.	[FILE NAME, UNKNOWN, KEYWORD]	Yes	Yes

Default Parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
ор	The operation to be performed. Allowed values: get-files download-url take-action Default value: `take-action` (Action to be take on a SINGLE quarantined file.)	String	No	Yes
action	Action to be performed on a quarantined file. Allowed values: block allow Default value: `block`	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

3. Allow Quarantined File

The action capability to allow a quarantined file. This capability restores the quarantined

file.

Rollback: No

Duplicate Control: Yes

Input Parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Quarantine Profile Name	The profile name of the quarantined file.	String	No	Yes
File Name	The name of the quarantined file.	[FILE NAME, UNKNOWN, KEYWORD]	Yes	Yes

Default Parameter:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
ор	The operation to be performed. Allowed values: get-files download-url take-action Default value: `take-action` (Action to be take on a SINGLE quarantined file.)	String	No	Yes
action	Action to be performed on a quarantined file. Allowed values: block allow Default value: `allow`	[FILE NAME, UNKNOWN, KEYWORD]	No	Yes

Case Scope: N/A

Human Readable Output: N/A

Integration Guide for Netskope V2

Integration Overview

Netskope is a Cloud Security/Security Service Edge (SSE) platform which secures access to the web and cloud services. Netskope provides solutions to help organizations discover, understand, and secure cloud usage across all their users, devices, apps, and data. The offerings include cloud security posture management, cloud access security broker (CASB), data loss prevention, and threat protection to help organizations safely embrace cloud services and meet compliance requirements.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Netskope V2:

- Search Alerts
- List URL Lists
- Get URL List Details
- Add to URL List
- Remove from URL List

Prerequisites

You must have access to HTTPS as the ArcSight SOAR connects to Netskope API through HTTPS service.

Configuration

Configuring Netskope

1. Authentication:

Netskope REST APIs use an auth token to make authorized calls to the API.Click Settings > Tools > Rest API v2 to create the token for specific APIs.

- 2. Click New Token to create a new token on the REST API v2.
- 3. Enter a token name and the token expiration time, and then click **Add Endpoint** to select the API endpoints to use with the token.
- Specify the privileges for each of the endpoints added.
 Read privileges include GET, and Read+Write privileges include GET, PUT, POST, PATCH, and DELETE.
- ClickSave.
- 6. A confirmation box appears showing whether the token creation was successful. If yes, click **Copy Token** to save it for later use in your API requests.



Add the token to the Netskope-Api-Token header.

Authentication Parameters

Request Headers:

Parameters	Datatype	Description	Required
Access Key	string	The Netskope REST API v2 token	Yes

2. Additional Configuration:

Configuration Parameter	Description
proxy.id	Proxy device to be used while communicating with the remote system's API
cache.reusing.duration	Default cache-reuse parameter
url_list_name	Name of the URL list

Prerequisites Page 457 of 594



Note: Replace tenant-name with your tenant name in the Address configuration

For example: https://alliances.goskope.com

Configuring SOAR

1. Click Configuration > Credentials > Create Credentials.

2. Specify the following parameters values in the Credential Editor form.

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, Netskope v2	N/A	N/A	The Netskope REST API v2 token
	Credentials).			

- 3. Click Configuration > Integrations > Upload plugin.
- 4. Select your integration plugin zip file and click Save.
- 5. Select the integration that you have added to Integrations menu.
- 6. Click Save to complete the integration
- 7. Click **Test**, an Integration Successful message is displayed if the credential and address are valid.

Integration Capabilities:

1. Search Alerts

Enrichment capability to a list of alerts generated by Netskope. You can filter Search Alerts based on the time period.

Required Scopes

Endpoint Name	Required Privilege
/api/v2/events/data/alert	Read



These privileges are specified while creating the REST API Token.

Input Parameters:

Configuring SOAR Page 458 of 594

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Time Range	The relative or absolute time range for the alerts to retrieve. The required starttime and endtime will be calculated internally based on the given Time range.	Integer/ Datetime	No	Yes
Username/User IP Address	Filter alerts by the username or user IP address.	["USERNAME", "NETWORK ADDRESS", "UNKNOWN", "KEYWORD"]	Yes	Yes
Severity	Filter alerts by severity.	String	No	Yes

Default Parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
limit	Maximum number of records to retrieve. Default value is 5000	Integer	No	No
offset	Used to shift the window of alerts if limit is reached. Default value is 0	Integer	No	No

Output:

Case Scope:

N/A

Human Readable Output:

ld	Action	Alert Name	Alert Type	Attack Severity	Timestamp	User	User Ip
a3eae4273b9a8 7e49daa148e	anomaly_detecti on	Suspicious Data Movement	uba	high	2023-01- 03T06:00:04.0Z	Aaron.Etheridge @kkrlogistics.co m	172.31.11.215
762edccd5478e b2228dfaee2	anomaly_detecti on	Suspicious Data Movement	uba	high	2022-12- 27T06:00:04.0Z	Aaron.Etheridge @kkrlogistics.co m	172.31.11.215
74da621548b59 95f33933d63	anomaly_detecti on	Suspicious Data Movement	uba	high	2023-01- 19T06:00:05.0Z	Aaron.Etheridge @kkrlogistics.co m	172.31.11.215
45c20e35d2337 c51d16de877	anomaly_detecti on	Suspicious Data Movement	uba	high	2023-02- 22T06:00:05.0Z	Aaron.Etheridge @kkrlogistics.co m	172.31.11.215
8dc2a1fc1cadcc e379f70004	anomaly_detecti on	Suspicious Data Movement	uba	high	2023-01- 10T06:00:04.0Z	Aaron.Etheridge @kkrlogistics.co m	172.31.11.215
cecede3faa7d08 d9c25295ab	anomaly_detecti on	Suspicious Data Movement	uba	high	2023-02- 06T06:00:05.0Z	Aaron.Etheridge @kkrlogistics.co m	172.31.11.215
ac014e154b812 1e6b3fbb1ad	anomaly_detecti on	Suspicious Data Movement	uba	high	2023-02- 12T06:00:04.0Z	Aaron.Etheridge @kkrlogistics.co m	172.31.11.215
9eeb273f977da1 de2febf8ad	anomaly_detecti on	Suspicious Data Movement	uba	high	2023-02- 07T06:00:06.0Z	Aaron.Etheridge @kkrlogistics.co m	172.31.11.215
b2addf31d256f9 7c99a775d5	anomaly_detecti on	Suspicious Data Movement	uba	high	2023-01- 20T06:00:05.0Z	Aaron.Etheridge @kkrlogistics.co m	172.31.11.215

2. List URL Lists

Enrichment capability to get all applied and pending URL lists.

Required Scopes

Endpoint Name	Required Privilege
/api/v2/policy/urllist	Read



These privileges are specified while creating the REST API Token. $\label{eq:control_eq}$

Input parameters:

N/A

Output:

Case Scope:

N/A

Human Readable Output:

ld	Name	Uris Count	Туре	Modified By	Modified Time	Modified Type	Pending
2	Allowed URLs		exact	aarguelles@lum u.io	2023-02- 13T20:02:11.000 Z	Edited	
5	bannedUrlList1w er		exact	darshit.trivedi@c restdatasys.com	2022-12- 22T00:00:00.000 Z	Edited	
18	CE Fireeye		exact	aarguelles@lum u.io	2023-02- 13T20:02:11.000 Z	Edited	
25	testing		exact	darshit.trivedi@c restdatasys.com	2022-01- 12T00:00:00.000 Z	Edited	
27	root		exact	aarguelles@lum u.io	2023-02- 13T20:02:12.000 Z	Edited	
30	Teting resilient		exact	aarguelles@lum u.io	2023-02- 13T20:02:12.000 Z	Edited	
31	Teting resilient1		exact	aarguelles@lum u.io	2023-02- 13T20:02:12.000 Z	Edited	
32	Resilient URL Lists		exact	aarguelles@lum u.io	2023-02- 13T19:51:46.000 Z	Edited	
37	string111	1	exact	aarguelles@lum u.io	2023-02- 13T20:02:13.000 7	Edited	0

3. Get URL List Details

Enrichment capability to get details of the given URL list by name.

Input Parameters:

Name	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
URL List Name	Name of the URL List.	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output:



4. Add to URL List

Action capability to add a new URL to an existing URL list by updating it.

Rollback: Yes

Duplicate Control: No



Update URL List API is used to implement this feature and it does not support Duplicate

Control.

Required Scopes

Endpoint Name	Required Privilege	
/api/v2/policy/urllist	Read+Write	



These privileges are specified while creating the REST API Token.

Input Parameters:

Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
URL / HOST / IP	The url to be added. Eg: 'www.example.com'	["URL", "HOST", "NETWORK ADDRESS", "UNKNOWN", "KEYWORD"]	Yes	Yes

Default Parameters:

Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
action	The action to be performed on URL list. Default value: append	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

5. Remove from URL List

Action capability to remove a specific URL from an existing URL list by updating it.

Rollback: Yes

Duplicate Control: No



Update URL List API is used to implement this feature and it does not support Duplicate

Required Scopes

Endpoint Name	Required Privilege
/api/v2/policy/urllist	Read+Write



These privileges are specified while creating the REST API Token.

Input Parameters:

Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
URL / HOST / IP	The URL to be removed. Eg: 'www.example.com'	["URL", "HOST", "NETWORK ADDRESS", "UNKNOWN", "KEYWORD"]	Yes	Yes

Default Parameters:

Parameter	Description	Туре	Scope restricted (Yes/No)	Required (Yes/No)
action	The action to be performed on URL list. Default value: replace	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

Integration Guide for Ones BioAffix

Integration Overview

Ones BioAffix is a biometric single sign on (Biometric SSO) and biometric identity verification solution which lets organizations to manage their physical security and access. This integration has been tested with Ones BioAffix 4.20.10.1 version.

Integration Capabilities

ArcSight SOAR has the following integration capability with Ones BioAffix:

- Change User Status (Block & Unblock)
- User Details (Info & Logs)

Use Case: Blocking Suspicious Employees

Integrated with Ones BioAffix ATAR lets users to investigate suspicious employee traffic through building and block access if needed. This can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to Ones BioAffix API via HTTPS. Typically it runs on 8443/tcp* port. So access to this service is required.
- Credentials of administrator is required for SOAR to connect Ones BioAffix.

Configuration on Ones BioAffix

No specific configuration is needed on Ones BioAffix server.

Configuring SOAR

- 1. Navigate Configuration > Credentials and click Create Credential.
- 2. Fill the Credential Editor form as follows:
 - a. Internal Credential:

Type: Internal credential.

Name: Display name of credential set (i.e., Ones BioAffix Credentials)

Username: Administrator username you have on Ones BioAffix.

Password: Password for the administrator user you have on Ones BioAffix.

Private Key: Empty.
b. Credential Store:

Type: External credential.

Name: Name of the credential with pull path of the safe on store.

3. Navigate to Configuration > Integrations and click Create Integration.

4. Fill the configuration form as follows:

Name: Display name of Ones BioAffix integration on ATAR.

Type: Ones BioAffix Server.

Address: Address of the integration (the format should be https://192.168.12.77:8443).

Credential: Name of the credential set you've just created on step 2. (i.e., Ones BioAffix Credentials).

Trust Invalid SSL Certificates: Select this if Engine's certificate is self-signed or not recognized by browsers.

Require Approval From: Select user(s) from list to ask her/his approval before executing actions on this integration.

Notify: Select user(s) from the list to notify when ATAR performs an action on this integration.

- 5. Click the **Test** button.
- 6. Click **Save** to complete integration.

Additional Notes

Due to API behaviour of Ones BioAffix integration, "Date of Birth", "Phone" and "Profile Photo" of users should be set to execute actions.

Additional Notes Page 465 of 594

Integration Guide for Palo Alto Networks AutoFocus

Integration Overview

Palo Alto Networks AutoFocus is a threat intelligence platform which allows to search attack indicators and access to details of them. AutoFocus provides the intelligence, analytics, and context required to understand which attacks require immediate response and take decisive action to prevent future attacks.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Palo Alto Networks AutoFocus:

- Search Email Address
- Search File Hash
- · Search File Name
- Search IP Address
- Search URL

Use Case: Investigating Phishing Campaigns

SOAR integrates with Palo Alto Networks AutoFocus to search attack indicators. SOAR can follow email inboxes for user's phishing reports and automatically creates an incident record on its service desk. During the investigation of the attack SOAR can extract the sender address, IP address, files in the attachment and ask these indicators to Palo Alto Networks AutoFocus if this is a known attack and previously analyzed. This can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to Palo Alto Networks AutoFocus API via HTTPS. Access (https://autofocus.paloaltonetworks.com (443/tcp port) is required.
- An API key is required for SOAR to connect Palo Alto Networks AutoFocus.

Configuration on Palo Alto Networks AutoFocus

No specific configuration is needed. Login to https://autofocus.paloaltonetworks.com and note the API key under **Settings** > **General** menu.

Configuring SOAR

- Navigate Configuration > Credentials and click Create Credential.
- 2. Fill the Credential Editor form as follows:
 - a. Internal Credential:

Type: Internal credential.

Name: Display name of credential set (i.e., PAN AutoFocus Credential).

Username: Empty.
Password: API Key.
Private Key: Empty.

b. Credential Store:

Type: External Credential.

Name: Name of the credential with pull path of the safe on store.

- Navigate Configuration > Integrations and click Create Integration.
- 4. Fill the configuration form as follows:

Name: Display name of Palo Alto Networks AutoFocus integration on SOAR.

Type: Palo Alto Networks AutoFocus.

Address: Address of the integration (https://autofocus.paloaltonetworks.com).

Credential: Name of the credential set you've just created on step 2. (i.e., PAN AutoFocus Credential).

Configuration: You need to specify the following configuration parameters

```
# Integration ID of the proxy integration to use when connecting to
# current integration.
# If not provided, SOAR will try to use a direct connection.
#proxy.id=123
# configure how far (in minutes) into the past this enrichment will look.
# cache.reusing.duration=20
```

Trust Invalid SSL Certificates: Select this if Engine's certificate is self-signed or not recognized by browsers.

Require Approval From: Select user(s) from list to ask approval before executing actions on this integration.

Notify: Select user(s) from the list to notify when SOAR performs an action on this integration.

- 5. The EnrichmentFixedDelay configuration parameter value must be set to less than 120 seconds because of AutoFocus' requirement. Otherwise AutoFocus API cookie will be expired.
- Click the Test button.
- 7. Click **Save** to complete integration.

Integration Guide for Palo Alto Networks Firewall

Integration Overview

Palo Alto Networks Next Generation Firewall is a security technology that combines firewall, antivirus, intrusion prevention, and virtual private network (VPN) capabilities to provide proactive threat defense that stops attacks before they spread through the network. This integration has been tested with Palo Alto Networks NGFW 9.0.1 version.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Palo Alto Firewall (API):

- Block IP
- Block Host
- Block URL
- Disconnect

Use Case: Blocking access to malicious IP addresses and hosts

Integrated with Palo Alto Networks NGFW, SOAR blocks malicious IP addresses and hosts on perimeter while responding cyber-attacks. Blocking can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to Palo Alto Networks NGFW API via HTTPS. Access to 443/tcp port is required.
- An API key is required for SOAR to connect Palo Alto Networks Firewall.

Configuration on Palo Alto Networks Firewall (API)

- 1. Navigate Device menu and create a new Admin Role for SOAR. New role must be restricted to only specific XML API operations. Only required permissions are: "Configuration", "Operational Requests" and "Commit".
- 2. Do not forget to disable all Web UI and Command Line permissions since they are unnecessary.
- 3. Create an Administrator account with SOAR API Role you have created in first step.
- 4. Navigate to Objects > Address Groups and add an address group for IPs to be populated by SOAR actions.
- Similarly add an address group for hosts/FQDNs to be populated by SOAR.
- Navigate **Objects > Custom Objects and add a Custome URL Category to be populated by SOAR.
- 7. Commit all changes.
- 8. To obtain API key run the following request from command line.

```
curl -k -X GET 'https://PaloAlto_NGFW_IP/api/?type=keygen& \
user=atarapi&password=password'
```

Configuring SOAR

- Navigate Configuration > Credentials and click Create Credential.
- 2. Fill the Credential Editor form as follows:
 - a. Internal Credential:

Type: Internal credential.

Name: Display name of credential set (i.e., Palo Alto Firewall Credential).

Username: User you have created for SOAR on Palo Alto NGFW.

Password: Password of the user you have created for SOAR on Palo Alto NGFW.

Prerequisites Page 469 of 594

Private Key: API Key you have created for SOAR.

b. Credential Store:

Type: External credential.

Name: Name of the credential with pull path of the safe on store.

- Navigate Configuration > Integrations and click Create Integration.
- 4. Fill the configuration form as follows:

Name: Display name of Palo Alto Networks Firewall integration on SOAR.

Type: Palo Alto Networks Firewall (API)

Address: Address of the integration (the format should be https://192.168.2.78).

Credential: Name of the credential set you've just created on step 2. (i.e., Palo Alto Firewall Credential).

Trust Invalid SSL Certificates: Select this if web UI's certificate is self-signed or not recognized by browsers.

Configuration: You need to specify the following configuration parameters.

- # Address group to use when blocking IP addresses.
- # This address group should be created in Palo Alto device before use.
 addressgroup.ip=ATAR_BLOCK_IP
- # Address group to use when blocking host names.
- # This address group should be created in Palo Alto device before use.
 addressgroup.host=ATAR BLOCK HOST
- # Custom URL category to use when blocking URLs.
- # This custom URL category should be created in Palo Alto device before use.

custom.url.category=ATAR BLOCK URL

Require Approval From: Select user(s) from list to ask her/his approval before executing actions on this integration.

Notify: Select user(s) from the list to notify when SOAR performs an action on this integration.

- 5. Click on the Test button.
- 6. Click **Save** to complete integration.

Additional Notes

Palo Alto Networks NGFW integration supports multiple "vsys". If your firewall has more than one "vsys" SOAR will ask you to choose one while taking action.

Additional Notes Page 470 of 594

Integration Guide for Palo Alto Networks Panorama

Integration Overview

The Panorama management server provides centralized monitoring and management of multiple Palo Alto Networks next-generation firewalls and of WildFire appliances and appliance clusters. This integration has been tested with Palo Alto Network Panorama 8.1.0 version.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Palo Alto Networks Panorama:

- Block IP address
- Block Host
- Block URL

Use Case: Blocking malicious IP addresses on multiple firewall appliances

With this integration, SOAR can block malicious IP addresses, hosts and URL addresses on multiple firewall devices simultaneously while responding cyber-attacks. This can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to Palo Alto Networks Panorama API using HTTPS. Access to 443/tcp port is required.
- An API key is required for SOAR to connect Palo Alto Networks Panorama.
- If users want to use multiple devicegroup, they should write devicegroup names comma separated, for ex: Ankara, Istanbul, Izmir

Configuration on Palo Alto Networks Panorama

 Navigate to Panorama menu and create a new Admin Role for SOAR. The new role should be restricted to only specific XML API operations. Only required permissions are: "Configuration", "Operational Requests" and "Commit". Do not forget to disable all Web UI and Command Line permissions since they are unnecessary.

- 2. Create an Administrator account with **Custom Panorama Admin** type and SOAR API Role you have created in first step.
- 3. Commit all changes.
- 4. In order to obtain API key run the following request from command line.

```
curl -k -X GET 'https://Panorama_IP/api/?type=keygen& \
user=atarapi&password=password'
```

Configuration on SOAR

- 1. Navigate Configuration > Credentials and click Create Credential.
- 2. Fill the Credential Editor form as follows:
 - a. Internal Credential:

Type: Internal credential.

Name: Display name of credential set (i.e., PAN Panorama Credential).

Username: Empty.

Password: Empty.

Private Key: API Key you have created for SOAR.

b. Credential Store:

Type: External credential.

Name: Name of the credential with pull path of the safe on store.

- 3. Navigate Configuration > Integrations and click Create Integration.
- 4. Fill the configuration form as follows:

Name: Display name of Palo Alto Networks Panorama integration on SOAR.

Type: Palo Alto Networks Panorama.

Address: Address of the integration (https://10.0.2.254).

Credential: Name of the credential set you've just created on step 2. (i.e., PAN Panorama Credential).

Trust Invalid SSL Certificates: Select this if Engine's certificate is self-signed or not recognized by browsers.

Configuration: You need to specify the following configuration parameters.

```
# Device group to use when adding and address object.
# This device group should be created in Palo Alto device before use.
# If users want to use multiple devicegroups, they should write
devicegroup
# names comma separated, for ex: Ankara, Istanbul, Izmir
devicegroup.name=HeadQuarters
# Address group to use when blocking IP addresses.
# This address group should be created in Palo Alto device before use.
addressgroup.ip=ATAR_BLOCK_IP
# Address group to use when blocking host names.
# This address group should be created in Palo Alto device before use.
addressgroup.host=ATAR_BLOCK_HOST
# Custom URL category to use when blocking URLs.
# This custom URL category should be created in Palo Alto device before
use.
custom.url.category=ATAR_BLOCK_URL
```

Require Approval From: Select user(s) from list to ask her/his approval before executing actions on this integration.

Notify: Select user(s) from the list to notify when SOAR performs an action on thisintegration.

- 5. Click the **Test** button.
- 6. Click Save to complete integration.

Integration Guide for Recorded Future

Integration Overview

Recorded Future is a threat intelligence service which collects and analyzes vast amounts of data to deliver relevant cyber threat insights in real time.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Recorded Future:

- Lookup Domain
- Lookup Hash
- Lookup IP Address
- Lookup URL
- Lookup Vulnerability
- Search Entity Lists
- · Search Malware

Use Case: Investigating Phishing Campaigns

SOAR is integrated with Recorded Future, to help investigation and mitigation of phishing campaigns. When a phishing report email comes from user, SOAR extracts the indicators such as IP address, URLs and attachments in message and a new incident is created on SOAR's own Incident Management Service Desk. SOAR then asks these indicators to Recorded Future if this is a known attack and previously analyzed. This can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to Recorded Future API via HTTPS. Access to https://api.recordedfuture.com/v2/ (443/tcp port) is required.
- An API key is required for SOAR to connect Recorded Future service.

Configuration on Recorded Future

Login to https://api.recordedfuture.com/v2/ and create a new API key under user Settings > API Access menu and note the API Key and API Password generated. This token is required by SOAR to access the platform for queries.

Configuring SOAR

- 1. Navigate Configuration > Credentials and click Create Credential.
- 2. Fill the Credential Editor form as follows:

a. Internal Credential:

Type: Internal credential.

Name: Display name of credential set (i.e., Recorded Future Credentials).

Username: API Key you have created on Recorded Future.

Password: API Password for the key you have created on Recorded Future.

Private Key: Empty.

b. Credential Store:

Type: External credential.

Name: Name of the credential with full path of the safe on store.

- 3. Navigate Configuration > Integrations and click Create Integration.
- 4. Fill the configuration form as follows:

Name: Display name of Recorded Future integration on SOAR.

Type: Recorded Future.

Address: Address of the integration (https://api.recordedfuture.com/v2/).

Configuration: You need to specify the following configuration parameters.

```
# Integration ID of the proxy integration to use when connecting to
# current integration.
# If not provided, SOAR will try to use a direct connection.
#proxy.id=123
# configure how far (in minutes) into the past this enrichment will look.
#cache.reusing.duration=20
```

Credential: Name of the credential set you've just created on step 2. (i.e., Recorded Future Credentials)

Trust Invalid SSL Certificates: No need to select.

Require Approval From: Select user(s) from list to ask her/his approval before executing actions on this integration. Since SOAR only executes enrichments on Recorded Future, leave it empty.

Notify: Select user(s) from the list to notify when SOAR performs an action on this integration. Since SOAR only executes enrichments on Recorded Future, leave itempty.

- 5. Click on the **Test** button.
- 6. Click **Save** to complete integration.

Configuring SOAR Page 476 of 594

Integration Guide for Robtex Lookup

1. Integration Overview

Robtex is used for various kinds of research of IP numbers, domain names, etc.

Robtex uses various sources to gather public information about IP numbers, domain names, host names, Autonomous systems, routes, etc. It indexes the data in a big database and provide free access for the data

2. Integration Capabilities

Action

Lookup

Configuration

Configuration on Robtex Lookup

SOAR connects to Robtex Lookup integrations via HTTPS. Therefore ATAR should be able to connect this service.

Configuring SOAR

1. While creating this integration via Integrations tab of Configuration menu:

Name: Display name of Robtex lookup integration on SOAR.

Type: Robtex lookup.

Address: Address of the integration (the address should be https://www.robtex.com).

Configuration: You need to specify the following configuration parameters

```
# Integration ID of the proxy integration to use when connecting to
# current integration.
# If not provided, ATAR will try to use a direct connection.
#proxy.id=123
```

configure how far (in minutes) into the past this enrichment will look.
#cache.reusing.duration=20

Credential: Name of the credential set.

Trust Invalid SSL Certificates: Select this if Engine's certificate is self-signed or not recognized by browsers.

Require Approval From: Select user(s) from list to ask her/his approval before executing actions on this integration.

Notify: Select user(s) from the list to notify when ATAR performs an action on this integration.

- 2. Click the **Test** button.
- 3. Click **Save** to complete integration.

Configuring SOAR Page 478 of 594

Integration Guide for Roksit DNS Firewall

Integration Overview

Roksit DNS Firewall is cloud-based cybersecurity service which provides web security and application control by analyzing DNS traffic.

Integration Capabilities

ArcSight SOAR has the following integration capability with Roksit DNS Firewall:

Block hostname

Use Case: Blocking malicious hosts on DNS

With this integration, SOAR can block malicious hostnames on Roksit DNS Firewall service while responding cyber-attacks. This can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to Roksit DNS Firewall API via HTTPS. So access to https://api.roksit.com (443/tcp port) is required.
- An API key is required to be created for SOAR to connect to Roksit DNS Firewall. Please contact to service provider.

Configuration on Roksit DNS Firewall

• No further configuration is needed.

Configuring SOAR

- 1. Navigate to Configuration > Credentials and click Create Credential.
- Fill the Credential Editor form as follows:
 - a. Internal Credential:

Type: Internal credential.

Name: Display name of credential set (i.e., Roksit DNS FW Credentials).

Username: Empty.

Password: API Key you have obtained from Roksit.

Private Key: Empty. b. Credential Store:

Type: External credential.

Name: Name of the credential with pull path of the safe on store.

3. Navigate to Configuration > Integrations and click Create Integration.

4. Fill the configuration form as follows:

Name: Display name of Roksit DNS Firewall integration on SOAR

Type: Roksit DNS Firewall

Address: Address of the integration (address should be https://api.roksit.com).

Credential: Name of the credential set you've just created on step 2. (i.e., Roksit DNS FW

Credentials)

Trust Invalid SSL Certificates: Select this if Engine's certificate is self-signed or not recognized by browsers.

Require Approval From: Select user(s) from list to ask her/his approval before executing actions on this integration.

Notify: Select user(s) from the list to notify when SOAR performs an action on this integration.

- 5. Click **Save** to complete integration.
- 6. Click **Test** to test the integration.

Additional Notes

- Roksit DNS Firewall integration on SOAR is defined as Advanced Action Script and content of the default script is accessible under **Configuration** > **Customization Library**.
- While defining the integration first time, you get a warning message as follows. For this type of integration this is the expected behaviour.

Configuring SOAR Page 480 of 594

Integration Guide for RSA Security Analytics

Integration Overview

RSA Security Analytics provides real-time visibility into network traffic with full packet capture—on premises, in the cloud and across virtual infrastructure. It helps to detect threats as they traverse in the network, monitor the timing and movement of attackers across the network and reconstruct entire network sessions to support forensic investigations. This integration has been tested with RSA Security Analytics 11.0.0.0 version.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with RSA Security Analytics:

- Network Packet Capture (Time range)
- Network Packet Capture (Relative time)

Use Case: Investigating suspicious cases using packet captures

SOAR integrates with RSA Security Analytics to collect full packet capture for a given timeframe. During the investigation of an incident, SOAR can gather packet-capture from RSA Security Analytics with specified parameters such as offender IP, affected usernames, suspicious end-user machines, etc and put the related pcap file into incident timeline for further analysis and keeping evidence purposes. Collecting pcap files can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to RSA Security Analytics Network Concentrator's API via HTTP/HTTPS.
- By default API interface works on 50105/tcp port. So access permission to this port is required.
- A user account is required to be created for SOAR to connect to RSA Security Analytics Network Concentrator API.

Configuration on RSA Security Analytics Suite

- Login to Security Analytics Suite and navigate to ADMIN > Services and then select Concentrator service and open up Security View by clicking Actions icon.
- 2. Add a new Role to be used for SOAR user. New role should have at least "sdk.content", "sdk.manage" and "sdk.meta" permissions".
- 3. Add a new user with the role you have created in previous step.

Configuring SOAR

- 1. Navigate Configuration > Credentials and click Create Credential.
- 2. Fill the Credential Editor form as follows:
 - a. Internal Credential:

Type: Internal credential.

Name: Display name of credential set (i.e., RSA Security Analytics Credential).

Username: Username you have created for SOAR on RSA Security Analytics Suite.

Password: Password of the user you have created for SOAR on RSA Security Analytics

Suite.

Private Key: Empty.

b. Credential Store:

Type: External credential.

Name: Name of the credential with pull path of the safe on store.

- Navigate Configuration > Integrations and click Create Integration.
- 4. Fill the configuration form as follows:

Name: Display name of RSA Security Analytics integration on SOAR.

Type: RSA Security.

Address: Address of the integration (the format should be http[s]://192.168.1.10:50105 or http[s]://abc.example.com:50105).

Credential: Name of the credential set you've just created on step 2. (i.e., RSA Security Analytics Credential)

Trust Invalid SSL Certificates: Select this if device's certificate is self-signed or not recognized by browsers.

Require Approval From: Select user(s) from list to ask her/his approval before executing actions on this integration.

Notify: Select user(s) from the list to notify when SOAR performs an action on thisintegration.

- 5. Click the **Test** button.
- 6. Click **Save** to complete integration.

Integration Guide for SailPoint

Integration Overview

SailPoint's Identity Security product provides a comprehensive platform for managing and governing accounts, roles, and entitlements across applications, systems, data, and cloud services. It enables organizations to identify risks, monitor behaviors, and refine roles, while providing visibility into access across the entire organization.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with SailPoint:

- Disable Account
- Enable Account
- Get Account Activity
- Get Account Details
- Get Account Entitlements
- Get Account IDs

Configuration

Configuring on SailPoint

- SailPoint requires a Client ID and Client Secret with the ORG ADMIN role for access.
- Users with the ORG_ADMIN role can create a **Client ID** and **Client secret** from https:// {tenant_ name}.api.identitynow.com after logging in with valid credentials.

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the Credential Editor:

Туре	Name	Username	Password	Private Key
Internal Credential	Display name of credential set (for example, SailPoint Credentials).	Empty	Client ID	Client Secret

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration Form:**

Parameter	Value
Name	Display name of SailPoint integration on SOAR
Туре	Advanced Scriptable Device
Address	https://{tenant_name}.api.identitynow.com
Configuratio	Specify the following configuration parameter values:
n	<pre># Integration ID of the proxy integration to use when connecting to current integration. # If not provided, ArcSight SOAR will try to use a direct connection. #proxy.id=123</pre>
	<pre># Maximum number of results to return from the API. # If not provided, the integration will gather all results. #max.result.count = 100</pre>
Credential	Name of the credential set created in step 2. (i.e. SailPoint Credentials).
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or not recognized by browsers. Not selected.
Require Approval From	Select user(s) from list to ask their approval before executing enrichment on this integration.
Notify	Select user(s) from the list who can provide approval when SOAR performs an enrichment on this integration.

- 5. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.
- 6. Click Save.

Configuring SOAR Page 484 of 594

Capabilities

1. Disable Account

Action capability for disabling an account.

The following table presents the **Disable Account** action capabilities details:

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Account ID	ID of the account	Keyword, Unknown	Yes	Yes

Output:

N/A

Human Readable Output

N/A

2. Enable Account

Action capability for enabling an account.

The following table presents the **Enable Account** action capabilities details:

Input Parameter	Description	Туре	Scope Rescticted (Yes/No)	Required (Yes/No)
Account ID	ID of the account	Keyword, Unknown	Yes	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

3. Get Account Activity

Enrichment capability for getting account activity.

The following table presents the **Get Account Activity** enrichment capabilities details:

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	N/A	No	Yes
Username	Identity Username	Unknown, Username, Keyword	Yes	Yes

Capabilities Page 485 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Time Range	Time range picker that filters activities by the time they were created	Relative or absolute time from time range picker	No	Yes
Туре	Type of account activity	List option from drop down menu: All, Access Request, Account Attribute Update, Account State Update, Attribute Synchronization Refresh, Certification, Cloud Automated, Cloud Password Request, Identity Attribute Update, Identity Refresh, Lifecycle Change Refresh, Lifecycle State Change	No	Yes

Case Scope

N/A

Human Readable Output

Capabilities Page 486 of 594

Date	Туре	Operation	Status	Details	ld
2022-10- 05T16:26:32.518 Z	AccountStateUpd ate	ENABLE	PENDING	Requester Name: Target Name:	
2022-10- 05T16:22:35.078 Z	AccountStateUpd ate	DISABLE	PENDING	Requester Name: Target Name:	
2022-10- 04T19:31:52.745 Z	AccountStateUpd ate	ENABLE	PENDING	Requester Name: Target Name:	
2022-10- 04T19:28:50.540 Z	AccountStateUpd ate	DISABLE	PENDING	Requester Name: Target Name:	
2022-09- 29T18:36:23.130 Z	AccountStateUpd ate	ENABLE	PENDING	Requester Name: Target Name:	
2022-09- 29T18:35:08.203 Z	AccountStateUpd ate	DISABLE	PENDING	Requester Name: Target Name:	

4. Get Account Details

Enrichment capability for getting account details.

The following table presents the **Get Account Details** enrichment capabilities details:

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third-party integration	N/A	No	Yes
Account ID	ID of the account	Unknown, Keyword	Yes	Yes

Output:

Case Scope

N/A

Human Readable Output

Capabilities Page 487 of 594

Field	Value
Name	
Account ID	
Created	
Modified	
Source Name	IDN Admin
Source ID	
Identity ID	
Attributes	displayName: givenName: name: honeNumber: familyName: name: id: email: idNowDescription:
Native Identity	
Authoritative	true
Disabled	false
Locked	false
System Account	false
Uncorrelated	false
Manually Correlated	false
Has Entitlements	false

5. Get Account Entitlements

Enrichment capability for getting account entitlements.

The following table presents the **Get Account Entitlements** enrichment capabilities details:

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	N/A	No	Yes
Account ID	ID of the account	Unknown, Keyword	Yes	Yes

Output:

Case Scope

N/A

Capabilities Page 488 of 594

Human Readable Output

Entitlement	Description	Created	Modified	Privileged	Cloud Governed
ORG_ADMIN	Full administrative access to IdentityNow	2021-07- 09T15:38:41.024 Z	2022-09- 28T20:38:13.501 Z	false	false

6. Get Account IDs

Enrichment capability for getting account IDs.

The following table presents the **Get Account IDs** enrichment capabilities details:


Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	N/A	No	Yes
Username	Identity Username	Unknown, Username , Keyword	Yes	No

Output:

Case Scope

Action	Туре	Category/Value
Add	Keyword	Related/ Account ID(s)

Human Readable Output



Integration Guide for SentinelOne

Overview of the Plugin

SentinelOne Singularity platform is an industry-first data lake that seamlessly fuses together the data, access, control, and integration planes of its endpoint protection (EPP), endpoint detection and response (EDR), IoT security, and cloud workload protection (CWPP) into a

centralized platform. With Singularity, organizations gain access to back-end data across the organization through a single solution, providing a cohesive view of their network and assets by adding a real time, autonomous security layer across all enterprise assets.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with SentinelOne:

- Disconnect from Network
- Connect to Network
- Get Agent Status/ Get Endpoint Details
- List Installed Applications
- List Events for Endpoint
- List Groups
- Get Group Details
- Get Hash Reputation
- Move Agent to Group
- Add to Blacklist
- Delete from Blacklist
- Get Blacklist
- List Threats
- · Get Threat Details
- Update Threat
- Add to Exclusion List
- Remove from Exclusion List
- Scan (Full Disk Scan)

Prerequisites

You must have access to HTTPS as ArcSight SOAR connects to SentinelOneAPI through this service.

Configuration

Configuring SentinelOne

API requires Token authentication which can be extracted from dashboard.

- 1. Login to Dashboard https://<instance url>/dashboard.
- Click Profile > get User > API Token Generation erate API extract > Regen.
- 3. Select Regenerate API Token and Extract the Token.



API Token is valid for 6 months, it needs to be regenerated every 6 months.

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the Credential Editor form:

Туре	Name	Username	password	Private Key
Internal credential	Display name of credential set (for example, SentinelOne	N/A	N/A	ApiToken {token}
	Credentials).			

- 3. Click Configuration > Integrations > Upload plugin.
- 4. Select your integration plugin zip file and click on save.
- 5. Select the integration that you have added to Integrations menu.
- 6. Click Save to complete the integration.
- 7. Click Test, an Integration Successful message is displayed if the credential and address are valid.

Integration Capabilities:

1. Disconnect from Network

Use this command to isolate (quarantine) endpoints from the network. The agent can communicate with the Management, which lets you analyze and mitigate threats.

• Rollback: Yes

Duplicate Control: No

Input Parameters

Configuration Page 491 of 594

Parameter	Description	Туре	Scope Restricted	Required
Computer Name/ IP Address	Valid Agent Computer Name or IP Address	COMPUTER NAME, NETWORK ADDRESS, KEYWORD, UNKNOWN	Yes	Yes

Case Scope: N/A

Human Readable Output: N/A

2. Reconnect to Network

After running the **Disconnect from network** on endpoints, analyze the issue, and mitigate threats. Use this command to reconnect to the network all the endpoints that match the filter.

• Rollback: No

• Duplicate Control: No

Input Parameters

Parameter	Description	Туре	Scope Restricted	Required
Computer Name/ IP Address	Valid Agent Computer Name or IP Address	COMPUTER NAME, NETWORK ADDRESS, KEYWORD, UNKNOWN	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

3. GetAgent Status/ Get Endpoint Detail

Fetch the details of the Agent.

Parameter	Description	Туре	Scope	Required
			Restricted	
Computer Name/ IP Address	Valid Agent Computer Name or IP Address	COMPUTER NAME, NETWORK ADDRESS, KEYWORD UNKNOWN	Yes	Yes

Case Scope: N/A

Human Readable Output:

·	
Кеу	Value
Account ID	1504451660558924435
Account Name	Sacumen - A Division of Clarion Technologies Pvt. Ltd
ID	1591167481362742170
UUID	3764e16b-b32f-fee9-cb40-5e41b3a70c67
Group ID	1504451661020297887
Group Name	Default Group
Agent Version	22.3.3.11
Computer Name	Gauri-Inspiron-15-3511
Model Name	Dell Inc. Inspiron 15 3511
OS Arch	64 bit
OS Name	Linux
CPU Count	1
CPU ID	11th Gen Intel(R) Core(TM) i5-1135G7 @ 2.40GHz
Total Memory	15736
Created At	2023-01-05T09:25:45.008751Z
External IP	223.233.82.194
Firewall Enabled	true
Last Active Date	2023-03-02T10:31:35.291301Z
Last Logged In Username	N/A
License Key	N/A
Network Interfaces	[{ "inet": ["192.168.1.8"], "gatewaylp": "192.168.1.1", "gatewayMacAddress":

4. List Installed Applications

Get the installed applications for a specific Agent/Endpoint.

Parameter	Description	Туре	Scope Restricted	Required
Computer Name/ IP Address	Valid Agent Computer Name or IP Address	COMPUTER NAME, NETWORK ADDRESS KEYWOR UNKNOWN	Yes	Yes

Case Scope: N/A

Human Readable Output:

Application Name	Version	Installed Date	Size	Publisher
manpages	5.10-1ubuntu1	2022-04-19T10:03:29Z	1709056	Ubuntu Developers <ubuntu-devel- discuss@lists.ubuntu.com> ;</ubuntu-devel-
openssl	3.0.2-Oubuntu1.8	2023-02-08T07:25:20Z	2102272	Ubuntu Developers <ubuntu-devel- discuss@lists.ubuntu.com> ;</ubuntu-devel-
xserver-common	2:21.1.3-2ubuntu2.7	2023-02-08T07:25:13Z	246784	Ubuntu X-SWAT <ubuntu- x@lists.ubuntu.com></ubuntu-
xserver-xephyr	2:21.1.3-2ubuntu2.7	2023-02-08T07:25:23Z	2670592	Ubuntu X-SWAT <ubuntu- x@lists.ubuntu.com></ubuntu-
xserver-xorg-core	2:21.1.3-2ubuntu2.7	2023-02-08T07:25:13Z	4060160	Ubuntu X-SWAT <ubuntu- x@lists.ubuntu.com></ubuntu-
python3-pkg-resources	59.6.0-1.2ubuntu0.22.04.1	2023-01-24T04:47:55Z	593920	Ubuntu Developers <ubuntu-devel- discuss@lists.ubuntu.com> ;</ubuntu-devel-
python3-setuptools	59.6.0-1.2ubuntu0.22.04.1	2023-01-24T04:47:55Z	1788928	Ubuntu Developers <ubuntu-devel- discuss@lists.ubuntu.com> ;</ubuntu-devel-

5. List Events for Endpoints


Get Deep Visibility results from the query that matches the given event type. Valid values for Event Type are:

Because of some limitation with the SentinelOne account, only the "events" event type is supported.

Input Parameter	Description	Data type	Scope Restricted	Required
Event Type	The event type to query the event. Supported event type: events	string	No	Yes
Time Range	The time range to fetch the events	String	No	Yes

Case Scope: N/A

Human Readable Output:



6. List Groups

Get a list of groups with details of each group.

Input Parameters: N/A

Default Parameters

Parameter	Description	Туре	Scope Restricted	Required
cursor	Cursor position returned by the last request. Use to iterate over more than 1000 items. Example: "YWdlbnRfaWQ6NTgwMjkzODE="	String	No	Yes
limit	Limit number of returned items (1-1000). Example: "10"	Integer	No	Yes

Output:

Case Scope: N/A

Human Readable Output:



7. Get Group Details

Get data of a given Group. To get a Group ID, run **groups**. This command responds with the ID of the Site of the Group, Group name, type (dynamic or static), and similar data. The username provided must have permission for the Site.

Input Parameters

Parameter	Description	Туре	ScopeRestricted	Required
Group Name	Valid group Name to fetch the details	String	No	Yes

Output:

Case Scope: N/A

Human Readable Output



8. **Get Hash Reputation**

Get the reputation of a hash, given the required SHA1. To get a hash, run **threats** (preferably filtered for a Group or Site) and take the file Content Hash value.

Input Parameters

Parameter	Description	Data type	Scope	Required
			Restricted	
Hash Value	A valid hash value	String	Yes	Yes

Output:

Case Scope

Action	Туре	Category/ Value
Set	Scope Item Property	Hash Reputation Rank

Human Readable Output:



9. Move Agent to Group

Move Agents that match the filter to a group. To get the Group ID, run **groups** is required and there can be only one. This will move the matched agents that are on the same site as the given group.

• Rollback: No

• Duplicate Control: No

Input Parameters

Parameter	Description	Туре	Scope Restricted	Required
Group Name	Valid Group Name	String	No	Yes
Computer Name / IP Address	Valid Agent Computer Name	COMPUTER NAME, NETWORK ADDRESS, KEYWORD UNKNOWN	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

10. Add to Blacklist

Action capability to add threats that have a SHA1 hash and that match the filter to the Blacklist of the target scope: Global, Account, Site, or Group.

• Rollback: Yes

• Duplicate Control: Yes

Input Parameters

Parameter	Description	Туре	Scope Restricted	Required
Hash Value	Sha1 Hash Value	string	Yes	Yes
Os Type	Os Type enum = ["linux", "windows", "macos", "windows_legacy"]	Array[String]	No	Yes

Default parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
accountId	Get unique Account id from configuration file.	Array [strings]	No	Yes
type	Select Blacklist type as black hash (This would be default option in blacklist type)	string	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

11. Delete from Blacklist

Action capability to delete the threat from the blacklist.

• Rollback: No

• Duplicate Control: Yes

Parameter	Description	Туре	Scope Restricted	Required
Hash Value	Hash Value of the threat	String	Yes	Yes

Default parameters

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
type	Select Blacklist type as black hash (This would be default option in type)	string	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

12. Get Blacklist

Enrichment capability to get a list of all the items in the blacklist.

Input Parameters: N/A


Default Parameters

Parameter	Description	Туре	Scope Restricted	Required
cursor	Cursor position returned by the last request. Used to iterate over more than 1000 items. Example: "YWdlbnRfaWQ6NTgwMjkzODE="	String	No	No
limit	Limit number of returned item (1-1000) Example: "10"	Integer	No	No

Output:

Case Scope: N/A

Human Readable Output:



13. List Threats

Get data of threats.

Input Parameters: N/A

Default Parameters

Parameter	Description	Туре	Scope Restricted	Required
cursor	Cursor position returned by the last request. Use to iterate over more than 1000 items. Example: "YWdlbnRfaWQ6NTgwMjkzODE="	String	No	Yes
limit	Limit the number of returned items (1-1000). Example: "10"	Integer	No	Yes

Output:

Case Scope: N/A

Human Readable Output:



14. Get a threat's timeline.

Input Parameters

Parameter	Description	Туре	Scope Restricted	Required
Thread Id	Valid Threat ID	String	No	True

Output

Case Scope: N/A

Human Readable Output:

Кеу	Value
Threat ID	1594088535204088378
Threat Name	eicar.com
Threat Classification	Malware
Threat Classification Source	Static
Created At	2023-01-09T10:09:21.761467Z
Updated At	2023-02-22T07:30:05.525940Z
Computer Name	hunters
Confidence Level	malicious
File Path	/home/praveen/Downloads/eicar_com/eicar.com
File Size	68
Site ID	1504451661003520670
Site Name	Default site
Reboot Required	false
Shal	3395856ce81f2b7382dee72602f798b642f14140
Whitening Options	["path", "hash"]
Group Name	Sacumen_test
Account ID	1504451660558924435
Account Name	Sacumen - A Division of Clarion Technologies Pvt. Ltd
Agent OS Name	Linux

15. **Update Threat**

Update the incident details of a threat.

• Rollback: No

• Duplicate Control: No

Input Parameters

Parameter	Description	Туре	Scope Restricted	Required
Thread Id	Valid Threat ID	String	No	Yes
Status	Incident Status Example: "resolved" enum =["unresolved", "in_progress", "resolved"]	string	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

16. Add to Exclusion List

Action capability to create exclusion to make your agents suppress alerts and mitigation for items that you consider to be benign or which you require for interoperability.

• Rollback: Yes

• Duplicate Control: Yes

Input Parameters

Parameter	Description	Туре	Scope Restricted	Required
Hash Value	Valid Hash value	string	Yes	Yes
OS Type	Agent OS type enum =["linux", "macos", "windows", "windows_legacy"]	string	No	Yes

Default parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
accountId	Get unique Account id from configuration file.	Array [strings]	No	No
type	Select Exclusion type as white hash (This would be default option in exclusion type)	string	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

17. Remove from Exclusion List

Every Exclusion opens a possible security hole. If it is decided that an Exclusion (or multiple Exclusions) is not required, use this command to delete it.

• Rollback: No

• Duplicate Control: Yes

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Parameter	Description	Туре	Scope Restricted	Required
Hash Value	Hash value of the exclusion.	string	Yes	Yes

Default parameters:

Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
type	Select Exclusion type as white hash (This would be default option in exclusion type)	string	No	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

18. **Scan**

Command to run a Full Disk Scan on Agents that match the filter.

Full Disk Scan finds dormant suspicious activity, threats, and compliance violations that are then mitigated according to the policy. It scans the local file system. Full Disk Scan does not inspect drives that require user credentials (such as network drives) or external drives. Full Disk Scan does not work on hashes. It does not check each file against the blacklist.

If the Static AI determines that a file is suspicious, the Agent calculates its hash and sees if the hash is in the blacklist. If a file is executed, all aspects of the process are inspected, including hash-based analysis and blacklist checks.

Full Disk Scan can run when the endpoint is offline, but when it is connected to the Management, it can use the most updated cloud data to improve detection.

Rollback: No

• Duplicate Control: No

Input Parameters

Parameter	Description	Туре	Scope Restricted	Required
Computer Name/ IP Address	Valid Agent Computer Name or IP Address	COMPUTER NAME, NETWORK ADDRESS, KEYWORD UNKNOWN	Yes	True

Output:

Case Scope: N/A

Human Readable Output: N/A

Integration Guide for ServiceNow

Integration Overview

ServiceNow allows you to manage digital workflows for enterprise operations.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with ServiceNow:

- Close Incident
- Create Incident
- Update Incident

Prerequisites

You must have access to HTTPS as the ArcSight SOAR connects to ServiceNow API through this service.

Configuration

Configuring ServiceNow

- 1. Create a REST client on SOAR
 - a. Login to SOAR platform.
 - b. Navigate Configurations > REST CLIENTS.
 - c. Create a new **REST client** by providing a description.



You must take a note of your **Client ID** and **Client Secret** as they would be used as username and password during configuring authentication later.

- 2. Create a User
 - a. Login to ServiceNow platform.
 - b. Navigate to User Administration > User.

- c. Click **New** to create a new user and specify the required credentials.Note: This username and password is used during the ArcSight SOAR configuration.
- d. Navigate to **User Administration** > **User** and edit the user you created newly to assign an admin role.

3. Create Rest Messages

- a. Navigate to System Web Services > Outbound > REST Message.
- b. Click **New** to create message and specify the following details in the form:

Form Fields Values		
Name SOAR REST API Requests		
Description	SOAR REST API Requests	
Endpoint	<itom_host_url>/soar-api/api/v1</itom_host_url>	
Authentication tab		
Authentication type	Basic	
Basic Auth Profile	soar credential	

- c. Click the Lookup icon to setup Basic Authentication.
- d. Click **New** and specify the following parameters:

Form Fields	Values
Username	Client ID
Password	Client secret

- e. Click Submit and select the newly created Basic auth profile.
- f. Navigate to System Web Services > Outbound > REST Message and select SOAR REST API Requests.

g. Click **New** and create following HTTP Methods within REST Messages:

i. Update Case on SOAR Method

Form Fields	Values		
Rest Message	SOAR REST API Requests		
Name	Update Case on SOAR		
HTTP Method	Patch		
Endpoint	<itom_host_url>/soar-api/api/v1/case/\${serialId}</itom_host_url>		
Authentication Tab			
Authentication type	Basic		
Basic Auth Profile	SOAR default_profile		
	HTTP Request Tab		
	HTTP Headers Section		
Name	Value		
Content-Type	application/json		
HTTP Query Parameters Section			
Content	\${changes}		

Specify the following details and click **Submit**:

ii. Add Comment to SOAR Case

Specify the following details and click **Submit**:

Form Fields	Values		
Rest Message SOAR REST API Requests			
Name	Add Comment to the SOAR Case		
HTTP Method	Post		
Endpoint	<itom_host_url>/soar-api/api/v1/case-comment</itom_host_url>		
Authentication Tab			
Authentication type	Basic		
Basic Auth profile	SOAR default_profile		
HTTP Request Tab			
HTTP Headers Section			
Name	Value		

Form Fields	Values		
Content-Type	application/json		
HTTP Query Parameters Section			
Content	<pre>{ "serialid":\$(serialid), "comment":"\$(comment)" }</pre>		

4. Create Event Registry

- a. Navigate to Performance Analytics > System > Event Registry.
- b. Click **New** to create an event registry and specify the following details in the form:

Form Fields	Values
Event Name	state_change_soar
Table	Incident[incident]

5. Create Script Action

- a. Navigate to Browse System Policy > Events > Script Actions.
- b. Click **New** to create script action and specify the following details in the form:

Form Fields	Values
Name	Update Case on SOAR
Event name	state_change_soar
Application	Global
Active	<mark checkbox="" this=""></mark>

Add the following script:

```
try {
    r = new sn_ws.RESTMessageV2('SOAR REST API Requests',
    'Update Case on SOAR');
    updated_fields = JSON.parse(event.parm2);
    var serialId = updated_fields["serialId"];
    if (updated_fields["caseProperties"] != {}) {
        r.setStringParameterNoEscape('changes', JSON.stringify
        (updated_fields["caseProperties"]));
        r.setStringParameterNoEscape('serialId', serialId);
        response = r.execute();
        responseBody = response.getBody();
        httpStatus = response.getStatusCode();
    }
    if (updated_fields["caseComment"] != {}) {
```

6. Create Business Rules

- a. Navigate to System Definition > Business Rules.
- b. Click **New** to create business rule and specify the following details in the form:

Form Fields	Values
Name	soar-rule
Table	Incident[incident]
Applic ation	Global
Active	<mark checkbox="" this=""></mark>
Advan ced	<mark checkbox="" this=""></mark>
	When to run tab
When	after
Order	1

Form Fields	Values				
Updat e	<mark checkbox="" this=""></mark>				
	Advanced tab				
Script	Add the following script:				
	<pre>if ((current.operation() == 'update' && current.state.changes() current.description.changes()) current.comments.changes()) { var currentValues = { "caseProperties":{}, "caseComment":{}, "serialId": current.short_description.toString().split("-")[0] }; var previousValues = { "state": previous.state.getDisplayValue(), "description": previous.description.getDisplayValue(), "comments": previous.comments.getJournalEntry(1) }; if (current.comments.changes()){ currentValues["caseComment"]["comment"] = {"value": current.comments.getJournalEntry(1)}; } if (current.state.changes()){ currentValues["caseProperties"]["status"] = {"value": current.state.getDisplayValue()}; } if (current.description.changes()){ currentValues["caseProperties"]["description"] = {"value": current.description.getDisplayValue()}; } gs.eventQueue('state_change_soar', current, JSON.stringify(previousValues), JSON.stringify(currentValues)); }</pre>				

- c. Click Submit.
- 7. Import Certificate (if SOAR has self-signed certificate)
 - a. Navigate to System **Definition > Certificates**.
 - b. Click **New** to create new certificate entry.
 - c. Click the attachment icon below to **upload your certificate file**. Run the following command to create the certificate

```
openssl s_client -connect cdfhost:cdfport 2>/dev/null </dev/null |
sed -ne '/-BEGIN
CERTIFICATE-/,/-END CERTIFICATE-/p'</pre>
```

d. Save the content with .der extension.

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential
- 2. Specify the following parameters in the Credential Editor form:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, ServiceNow Credentials).	Username of the created user on ServiceNow	Password of the created user on ServiceNow	Empty

Check the Cleartext Access option.

- 3. Click **Configuration** > **Lists** > **Create Lists**. The list must two columns with the type **Keyword**. Specify a name for that list and save it. The name of the list is used during integration configuration.
- 4. Click Configuration > Integrations > Create Integration.
- 5. Specify the following parameter values in the Configuration Form.

Parameter	Value			
Name	Display nar	Display name of the integration.		
Туре	ServiceNov	ServiceNow		
Address		Address of the ServiceNow integration (the format should be https://dev107155.service-now.com).		
Configuration	Specify the following configuration parameters:			
	proxy.id ID of the Proxy integration if you access ServiceNow through a web proxy device. For example: proxy.id = 12345 .			
	list.name	List name that is used for mapping ArcSight SOAR cases to ServiceNow incidents. For example, list.name=servicenowMapList		
Credential	Credential	Credential that has been defined for this integration under the Credentials menu.		
Trust Invalid SSL Certificates	Select this	Select this if web server's certificate is self-signed or is not recognized by browsers.		
Require Approval From	Select user(s) from list to ask the approval before executing actions on this integration.			
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.			

- 6. Click **Save** to save the integration definition.
- 7. Navigate to Configuration>Customization Library and edit ServiceNow Advanced Action Script Default Template.
- 8. Select the integration that you have added to **Integrations** menu.

Configuring SOAR Page 510 of 594

- 9. Click **Save** to complete the integration.
- 10. Click **Test**. **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. Create Incident

Action capability for creating incident on ServiceNow.

• Rollback: No

• Duplicate Check: Yes

The following table presents the **Create Incident** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Category and SubCategory	Category and Subcategory information of created incident	Enum	No	Yes
Description	Servicenow Incident Description	Text	No	Yes
Impact	ServiceNow incident impact	Enum	No	Yes
Urgency	Servicenow Incident Urgency	Enum	No	Yes
Comment	Servicenow Incident Comment	Text	No	Yes
Assignment Group	Servicenow Incident Assignee	Text	No	Yes

2. Close Incident

Action capability for closing incident on ServiceNow.

• Rollback: No

• Duplicate Check: No

The following table presents the **Close Incident** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
State	Closing State of Servicenow incident.	Enum	No	Yes
Resolution Code	Resolution Code for ServiceNow incident.	Enum	No	Yes

Capabilities Page 511 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Resolution Note	Resolution Notefor ServiceNow incident.	Enum	No	Yes

3. Update Incident

Action capability for updating incident on ServiceNow.

The following table presents the **Update Incident** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Description	Servicenow Incident Description	Text	No	No
Impact	ServiceNow incident impact	Enum	No	No
Urgency	Servicenow Incident Urgency	Enum	No	No
Comment	Servicenow Incident Comment	Text	No	No
Assignment Group	Servicenow Incident Assignee	Text	No	No
State	ServiceNow incident status	Enum	No	No

Output:

Case Scope: N/A

Human Readable Output: Yes

Integration Guide for Slack

Integration Overview

Slack is a messaging app for business that connects people to the information that they need. By bringing people together to work as one unified team, Slack transforms the way that organizations communicate. Slack supports asynchronous work. When work is organized in channels, the users can access the information as per their own time, regardless of the location, time zone or function. It can be used for asking questions, catching up with new developments and share updates without having to coordinate schedules.

Integration Capabilities

- List Channels
- · Get Channel Info
- Create Channel
- Send Message to Channel
- Archive Channel
- Invite User to Channel

Prerequisites

 You must have access to HTTPS as the ArcSight SOAR connects to Slack API through this service.

Configuring Slack

- 1. Log in to you Slack account and create your application using https://api.slack.com/apps.
- 2. Click **Create New App** to create new Slack application from scratch. Also, mention application name and pick your workspace to create the application.
- 3. Enter into your application and navigate to **Oauth and Permissions**.
- 4. Click **Scopes** > **User Token Scopes** provide the below scope permissions:

Capability	Scope Permissions Required
List Channels	channels:read, groups:read, im:read, mpim:read, identify:basic
Get Channel Information	channels:read, groups:read, im:read, mpim:read, identify:basic
Create Channel	channels:write, groups:write, im:write, mpim:write
Send Message to channel	chat:write
Archive Channel	channels:write, groups:write, im:write, mpim:write
Invite User to Channel	channels:write, groups:write, im:write, mpim:write

- 5. After all the scopes are added then install your application.
- 6. Navigate to **OAuth and permissions** > **OAuth tokens for Workspace** to find your User Oauth token. This User OAuth token is used to access the slack api.

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the Credential Editor:

Туре	Name	Username	Password	Private Key
Internal Credential	Display name of credential set (for example, Slack Credentials).	N/A	N/A	Bearer {Token}

- 3. Click **Save** to complete the integration
- 4. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. List Channels

Enrichment capability for retrieving channels list.

The following table provides the List Channels enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted(Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes

Output:

Case Scope

Action	Туре	Category/Value
None	N/A	N/A

Human Readable Output:

Configuring SOAR Page 514 of 594

Channel Name	Channel Id	Channel Type	Торіс	Purpose	Total Members	Created By	Create Time
random	C049XFVNJ1L	Private	N/A	This channel is for well, everything else. It's a place for team jokes, spur- of-the-moment ideas, and funny GIFs. Go wild!	4	chethan.p	2022-11- 09T06:18:00.0Z
create_private_c hannel	C049Y56N62J	Private	N/A	N/A	1	chethan.p	2022-11- 09T09:00:37.0Z
microfoucsconne ctor	C04A44DRVV0	Private	N/A	This channel is for everything #microfoucsconn ector. Hold meetings, share docs, and make decisions together with your team.	0	chethan.p	2022-11- 09T06:21:03.0Z
microfocusconne ctor	C04A6HRD85S	Private	N/A	This channel is for everything #microfocusconn ector. Hold meetings, share docs, and make decisions	3	chethan.p	2022-11- 09T06:19:36.0Z

2. Get Channel Info

Enrichment capability for retrieving channel information.

The following table provides the **Get Channel Info** enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integrtaion	Name of the third party integration	Integration	N/A	Yes
Channel Name	Name of the channel	Username Keyword Unknown	Yes	Yes

Output

Case Scope

Action	Туре	Category/Value
None	N/A	N/A

Human Readable Output:

Capabilities Page 515 of 594

Key	Value
Channel Name	create_private_channel
Channel ID	C049Y56N62J
Topic	N/A
Purpose	N/A
Total Members	1
Created By	chethan.p
Creation Time	2022-11-09T09:00:37.0Z
Is Archived	true

3. Create Channel

Action capability for creating a new channel.

Rollback: No

• Duplicate Control: Yes

The following table provides the **Create Channel** enrichment capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Channel Name	Name of the channel	N/A	N/A	Yes

Output:

Case Scope

N/A

Human Readable Output

4. Send Message to Channel

Action capability to send text messages to channel.

Rollback: No

• Duplicate Control: No

The following table provides the channel Information action capability details

Capabilities Page 516 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Channel Name	Name of the channel	Username Keyword Unknown	Yes	Yes
Message	Text message to send to channel	String	No	Yes

Output:

Case Scope

N/A

Human Readable Output

5. Archive Channel

Action capability to archive the channel.

• Rollback: No

• Duplicate Control: No

The following table provides the **Archive Channel** action capability details

Input Parameter	Description	Туре	Scope Restricted(Yes/No)	Required (Yes/No)
Integration	Query string for the search	Integration	Yes	Yes
Channel Name	Name of the channel	Username Keyword Unknown	Yes	Yes

Output:

Case Scope

N/A

Human Readable Output

6. Invite User to Channel

Action capability to invite user to a channel.

Rollback: No

• Duplicate Control: No

The following table provides the Invite User to Channel action capability details:

Capabilities Page 517 of 594

Input Parameter	Description	Туре	Scope Rectricted (Yes/No)	Required (Yes/No)
Integration	Name of the third party integration	Integration	N/A	Yes
Channel Name	Name of the channel	Username Keyword Unknown	Yes	Yes
User Name	Name of the Slack user	Username Keyword Unknown	Yes	Yes

Output:

Case Scope

N/A

Human Readable Output

N/A

Capabilities Page 518 of 594

Integration Guide for SMTP Mail Server

Integration Overview

ArcSight SOAR uses the SMTP Server to send emails and notification messages. ATAR can also use the same integration to access inboxes to read emails, such as device action approvals if it is configured as an IMAP server.

Integration Capabilities

- Action
- · Send email

Prerequisites

- SOAR connects to SMTP Mail Server integration via Simple Mail Transfer Protocol.Therefore SOAR must be able to connect this service.
- A user's credential is required for SMTP AUTH. The same credential will be used if IMAP is configured.

Configuration

Configuring SOAR Email Notification

- 1. Click Configuration > Parameters.
- Search for NotificationEMailFrom> Edit and set Email address.
- 3. Search for **ApprovalEMailFrom**> **Edit** and set Email address.
- 4. Search for ApprovalEMailEnabled> Edit and set it as True.
- Search for OutgoingMailIntegration > Edit and add SMTP Integration ID.
- 6. Search for IncomingMailIntegration > Edit and add SMTP Integration ID.

Configuring SOAR

- 1. Click Configuration > Integrations > Create Integration.
- 2. Specify the following parameter values in the **Configuration** form:

Param eter	Value
Name	Display name of the SMTP Mail Server integration
Туре	SMTP Mail Server
Addre ss	Address of the integration (the format should be 1.1.1.1 or abc.example.com).
Config	Specify the following configuration parameters:
uratio n	<pre>mail.default-encoding is the encoding format of emails. mail.transport.protocol is the default message transport protocol. mail.smtp.auth specifies whether SMTP Authentication will be enabled or not. It can be "true" or "false". mail.smtp.port is the port for the SMTP service. mail.smtp.starttls.enable specifies whether TLS for SMTP will be enabled or not. It can be "true" or "false". mail.store.protocol is the protocol to access inboxes (for email reading). Default value is "imaps". mail.imaps.host is the address of the IMAPS server. mail.imaps.port is the port for IMAPS service. # Server type should be default for standard SMTP connections, the type should be exchange-online to enable token authentication for Exchange Online SMTP devices.e. smtp.server.type=exchange-online # Imap mail account for token authentication connections imap.mail.account=imap.account@somehost.com # Imap message polling period in millis, the default value is 10000 ms #imap.polling.period=10000</pre> Specify the following to enable OAuth2 in SMTP:
	<pre>smtp.server.type=exchange-online imap.mail.account=imap.account@somehost.com</pre>
Crede ntial	Select newly created OAuth2 credential as credential.

Configuring SOAR Page 520 of 594

Param eter	Value
Trust Invalid SSL Certifi cates	Select this if Engine's certificate certificate is self-signed or is not recognized by browsers
Requir e Appro val From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.

- 3. Click **Test** to test the integration.
- 4. Click **Save** to complete the integration.

Additional Notes

- If a SMTP integration is used without credentials then it can't be used as incoming e-mail processor and for approvals.
- The global configuration parameter EMailDevice, under the Parameters tab of
 Configuration menu, configures the default mail server to be used in sending notifications
 and emails. Therefore, you must set the value of this parameter to the ID value for the
 SMTP Mail.

Additional Notes Page 521 of 594

Integration Guide for Sophos XG Firewall

Integration Overview

Sophos XG Firewall is an integrated security platform featuring next gen firewall capabilities.

Integration Capabilities

ArcSight SOAR has the following integration capability with Sophos XG Firewall:

- Block IP
- Block FQDN
- Block URL
- Block Email Sender

Use Case: Blocking bad actors on firewalls

With this integration, SOAR can block malicious IP addresses, hosts and URL addresses on firewall devices while responding cyber-attacks. This can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to Sophos XG Firewall API via management port. So access permission
- to this port is required.
- A user account for SOAR to connect to Sophos XG Firewall.

Configuration on Sophos XG Firewall

- 1. Click Configure > Authentication > Users menu and add an administrator user account.
- 2. Create a new profile or select a suitable one from the Profile list. Profile should have the following permissions:

- Read-write for Objects
- · Web & content filter
- Email protection
- None for the rest of the permissions
- Navigate to Backup & Firmware > API to enable API Configuration and add SOAR IP
 Address to the Allowed IP Address list.
- 4. Click Administration > Device Access to ensure that SOAR's assigned zone can access the HTTPS service of Sophos. You can prefer to create a Local Service ACL Exception Rule as well. For more information consult the Sophos How to use API documentation for further information.
- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor**:
 - a. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, Sophos XG Credentials)
Username	Username you have created on firewall.
Password	Password you have created on firewall.
Private Key	Empty

b. Credential Store:

Parameter	Value
Туре	External Credential
Name	Name of the credential with pull path of the safe on store

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of Sophos XG integration on SOAR.
Туре	Sophos XG Firewall.
Address	Address of the firewall (the format should be https://192.168.10.1:4444)

Parameter	Value
Configuration	Specify the following configuration parameters:
	<pre># IP host group name for adding ip hosts to block iphost.group.name=ATAR_IP_BLOCK # FQDN host group name for adding fqdns to block fqdnhost.group.name=ATAR_HOST_BLOCK # Web filter url group name for adding urls to block webfilterurl.group.name=ATAR_URL_BLOCK</pre>
Credential	Name of the credential set created on step 2 (For example, Sophos XG Credentials)
Trust Invalid SSL Certificates	Select this if Management UI's certificate certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration. Since SOAR only executes enrichments on Symantec DLP, leave it empty

- 5. Click **Test** to test the integration.
- 6. Click **Save** to complete the integration.

Additional Notes

- IP, FQDN and URL filter groups are automatically created by SOAR if they don't exist.1. IP, Host and URL filter groups are automatically created by SOAR if they don't exist.
- Sophos XG Firewall URL Filtering only accepts URLS with the following format http://www.example.com. URI paths are not accepted through API. Therefore SOAR transparently trim the URI part while submitting to Sophos XG Firewall.
- SOAR stores blocked email addresses in a list to keep track. Sophos currently does not
 provide a method to get the current list and any update will overwrite the list with the new
 address so administrator should only update the MTA Blocked Sender List through SOAR.
 Also this list is kept for each different Sophos integration but creating a second integration
 for the same device can lead to data inconsistency.

Integration Guide for SORBS Query

Integration Overview

SORBS Query provides free access to its DNS-based Block List to effectively block mail from more than 12 million host servers known to disseminate spam, phishing, attacks and other forms of malicious emails.

Integration Capabilities

- Action
- Check IP

Configuration

Configuration on SORBS Query

 ATAR connects to SORBS integrations's API via HTTPS. Therefore ATAR should be able to connect this service.

Configuring SOAR

Configuring SOAR

- 1. Click Configuration > Integrations > Create Integration.
- 2. Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of SORBS Query integration on SOAR.
Туре	SORBS Query.
Address	Address of the integration (the address should be http[s]://dnsbl.sorbs.net).

Parameter	Value
Trust Invalid SSL Certificates	Select this if Engine's certificate certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Not Applicable

- ${\it 3. \ \, Click \, Test \, to \, test \, the \, integration.}$
- 4. Click **Save** to complete the integration.

Configuring SOAR Page 526 of 594

folntegration Guide for Symantec Advanced Threat Protection

Integration Overview

Symantec Advanced Threat Protection is Symantec's endpoint protection platform closely works with SEP Manager.

Integration Capabilities

- Action Capabilities
- Quarantine Endpoint (isolate_endpoint and rejoin_endpoint)
- Delete File From Endpoint (delete_endpoint_file)
- Enrichment Capabilities
- Get Events (/events)

Configuration

Configuring Symantec Advanced Threat Protection

Symantec ATP uses https (tcp/443) for API access by default.

- Click Settings > Data Sharing > OAuth Clients > Add application with custo role to add the API application.
- The image in the Privileges section represents how the custom role must be configured.
 After creating user, Symantec displays the client secret and client id, which is used in SOAR configuration modal.

Configuring SOAR

- 1. Navgate to Configuration > Integrations.
- 2. Specify the following parameter values in the Integrations Editor:

Parameter	Value
Name	Display name of Symantec Advanced Threat Protection integration on SOAR
Туре	Symantec Advanced Threat Protection.
Address	Address of the integration (in the following format: https://1.1.1.1)
Configuration	Specify the following configuration parameters.
	#EVENT_RESULT_LIMIT
Credential	Name of the credential set created under the Credentials menu. You must use client id as username and client secret as password.
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an action on this integration

- 3. Click **Save** to save the integration.
- 4. Navigate to Configuration>Customization Library and edit Symantec Advanced Threat Protection Advanced Action Script Default Script Template.
- 5. Select the integration that you have added to Integrations menu.
- 6. Click **Save** to complete the integration.
- 7. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Configuring SOAR Page 528 of 594

Integration Guide for Symantec Bluecoat Malware Analysis Appliance (MAA)

Integration Overview

Symantec Bluecoat MAA is a malware analyzer sand-box solution. SOAR uses Symantec Bluecoat Malware Analysis Appliance to analyze files and URLs.

Integration Capabilities

- Action
- File Analysis
- Hash Analysis
- URL Analysis

Prerequisites

- SOAR connects to Symantec Bluecoat MAA's Remote API (RAPI) via HTTPS. Therefore, SOAR should be able to connect this service.
- A user account is required for SOAR to connect to Symantec Bluecoat MAA.

Configuration

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the Credential Editor:

Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, BlueCoat Malware Analysis Appliance Credentials)

Parameter	Value
Username	Username of the administrator
Password	Password of the admin user
Private Key	Empty

3. Credential Store:

Parameter	Value
Туре	External Credential
Name	Name of the credential with pull path of the safe on store

- 4. Navigate to Configuration > Integrations.
- 5. Specify the following parameter values in the **Integrations Editor**:

Parameter	Value
Name	Display name of Symantec Bluecoat MAA integration on SOAR.
Туре	Symantec Bluecoat MAA .
Address	Address of the integration (in the following format: http[s]://1.1.1:1234
Credential	Name of the credential set created under the Credentials menu.
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an action on this integration

- 6. Click **Test** to test the integration.
- 7. Click **Save** to save the integration.

Configuring SOAR Page 530 of 594

Integration Guide for Symantec Bluecoat Site Review

Integration Overview

Bluecoat Site Review is a site to report uncategorized URLs to Symantec/Bluecoat.

Integration Capabilities

- Action
- Report Uncategorized URL (should get URL from scope)

Configuration

Configuration on Bluecoat Site Review

No requirements

Configuring SOAR

 In SOAR Configuration, specify Name, Address and submissionEmailAddress to check submission result from returning mail.



Note: Add a dummy credential that can be removed in future releases.

Integration Guide for Symantec Data Loss Prevention (DLP)

Integration Overview

Symantec DLP is a solution to ensure that sensitive data is not lost, misused, or accessed by unauthorized users. This integration has been tested with Symantec DLP 14.6.0200 version.

Integration Capabilities

SOAR has the following integration capabilities with Symantec DLP:

Retrieve incidents

Use Case: Investigating Suspicious Behaviour

During investigation of a suspicious behaviour of an employee or an endpoint, SOAR integrated with Symantec DLP, can get access the related DLP incidents for better understanding of the case. Investigation can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to Symantec DLP API via HTTPS. Access to 443/tcp port is required.
- A user account is required for SOAR to connect to Symantec DLP.

Configuring Symantec DLP

- Login to Symantec DLP Enforce Server and navigate to System > Login Management >
 Roles to create a web service role. The web service role should have the following
 permissions:
 - Incidents: View
 - Perform Attribute Lookup
 - Incident Reporting and Update API: Incident Reporting

Display Attributes: All,

Custom Attributes: View all

- 2. Click **System > Login Management > DLP Users** and add a DLP user account with the role that is created on previous step.
- 3. Login to Symantec DLP Enforce server administration console with the DLP user account created in previous step.
- 4. Click Incidents > Incident Reports and select a system defined incident list, such as Incidents All.
- 5. Edit report filters to narrow down the results to be returned if needed. In the **Summarize** by menu verify that and are both selected.
- 6. Save the report as a new private report and note the new report's ID.

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor**:
 - a. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, Symantec DLP Credentials)
Username	User you have created for SOAR on Symantec DLP.
Password	Password of the user you have created for SOAR on Symantec DLP
Private Key	Empty

b. Credential Store:

Parameter	Value
Туре	External Credential
Name	Name of the credential with pull path of the safe on store

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of Symantec DLP integration on SOAR.
Туре	Symantec Data Loss Prevention.

Configuring SOAR Page 533 of 594

Parameter	Value
Address	Address of the integration (in the following format: https://192.168.2.15)
Configuration	Specify the following configuration parameters:
	<pre># Report id report.id=221</pre>
Credential	Name of the credential set created on step 2 (For example, Symantec DLP Credentials)
Trust Invalid SSL Certificates	Select this if Web UI's certificate certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration. Since SOAR only executes enrichments on Symantec DLP, leave it empty

- 5. Click **Test** to test the integration.
- 6. Click **Save** to complete the integration.

Additional Notes

For the details of web service role and report creation please refer to Symantec™ Data Loss Prevention Incident Reporting and Update API Developers Guide.

Configuring SOAR Page 534 of 594

Integration Guide for Symantec DeepSight Intelligence

Integration Overview

Symantec DeepSight Intelligence is a commercial threat intelligence service which provides actionable intelligence with context and technical details surrounding a threat so teams can quickly assess cyber risk and implement proactive controls.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Symantec DeepSight Intelligence Service:

- Ingest intelligence data as alert
- Domain Query
- File Query
- IP Query

Use Case: Investigating Phishing Campaigns

SOAR is integrated with Symantec DeepSight Intelligence, to help investigation and mitigation of phishing campaigns. When a phishing report email comes from user, SOAR extracts the indicators such as IP address, domains and attachments in message and a new incident is created on SOAR's own Incident Management Service Desk. SOAR then asks these indicators to Symantec DeepSight Intelligence if this is a known attack and previously analyzed. This can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to Symantec DeepSight API via HTTPS. Access to https://deepsightapi.symantec.com/v1/ (443/tcp port) and https://datafeeds.symantec.com/ (443/tcp port) is required.
- A user account and a certificate-password pair are required for SOAR to connect to Symantec DeepSight. These will be supplied by Symantec through DeepSight portal.

Configuring Symantec DeepSight Intelligence

SOAR requires a username and password to be created on Symantec DeepSight for authentication purposes for Alert Source. If enrichment capabilities are to be used an API key must be enabled and created. Use an administrator account to enable API Access for the account you wish to use in SOAR.

- Select user's detail tab. The tab includes a section for DeepSight API Token. Select Enable Access
- 2. Login with the SOAR account to the DeepSight portal.
- 3. Click Settings > My Profile and locate the DeepSight API Token tab.
- 4. Copy the API key.

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor**:

a. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, Symantec DeepSight Credentials).
Username	Empty
Password	API Key you've get from Symantec DeepSight Intelligence platform.
Private Key	Empty

b. Credential Store:

Parameter	Value
Туре	External Credential
Name	Name of the credential with pull path of the safe on store

Configuring Symantec DeepSight Intelligence as Alert Source

- 1. Click Configuration > Alert Source > Create Alert Source Configuration.
- 2. Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of Symantec DeepSight Intelligence Alert Source on SOAR.
Туре	Symantec DeepSight Intelligence Datafeeds
Address	Address of the Symantec DeepSight Intelligence DataFeeds (https://datafeeds.symantec.com/v1/).
Configuration	Specify the following configuration parameters:
	<pre># Number of item to ingest per data feed type on first integration alertCountPerFeedType=1000 # Minimum item reputation value to turn into Alert on SOAR minReputationToAlert=10 #usable behaviour names : attack,attacks,bot,cnc,fraud,malware,phish,spam,phish_host #behaviourNames=attack,bot,CnC,fraud,malware,spam # Integration ID of the proxy integration to use when connecting to current source. # If not provided, SOAR will try to use a direct connection. #proxy.id=5422 # configure how far (in minutes) into the past this enrichment will look. #cache.reusing.duration=20</pre>
Credential	Name of the credential set created on step 2 (For example, Symantec DeepSight Credentials)
Trust Invalid SSL Certificates	Select this if Web UI's certificate certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration. Since SOAR only executes enrichment on Symantec DeepSight, leave it empty.
Visible Alert Fields	You may define which alarm fields will be displayed on Incident Management Service Desk.

Configuring Symentec DeepSight Intelligence as Integration

- 1. Click Configuration > Alert Source > Create Alert Source Configuration.
- 2. Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of Symantec DeepSight Cyber Intelligence integration on SOAR.
Туре	Symantec DeepSight Cyber Intelligence
Address	Address of Symantec DeepSight Cyber Intelligence (https://deepsightapi.symantec.com/v1)
Configuratio	Specify the following configuration parameters:
n	<pre># Integration ID of the proxy integration to use when connecting to current integration. # If not provided, SOAR will try to use a direct connection. #proxy.id=123 # configure how far (in minutes) into the past this enrichment will look. #cache.reusing.duration=20</pre>
Credential	Name of the credential set created on step 2 (For example, Symantec DeepSight Credentials)
Trust Invalid SSL Certificates	Select this if Web UI's certificate certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration. Since SOAR only executes enrichment on Symantec DeepSight, leave it empty.
Notify	Select users from the list to notify when SOAR performs an action on this integration. Since SOAR only executes enrichment on Symantec DeepSight, leave it empty.

- ${\it 3. \ \, Click \, Test \, to \, test \, the \, integration.}$
- 4. Click **Save** to complete the integration

Integration Guide for Symantec Endpoint Protection Manager

Integration Overview

Symantec Endpoint Protection Manager (SEP Manager) is a management platform for security software suite, which consists of anti-malware, intrusion prevention and firewall features for server and desktop computers. This integration has been tested with Symantec Endpoint Protection Manager 14.2.760 version.

Integration Capabilities

SOAR has the following integration capabilities with Symantec Endpoint Protection Manager:

- Start Scan on Client
- Block File Hash
- Get Client Info

Use Case: Starting scan jobs on suspicious endpoints.

During the course of and investigation or responding a ongoing cyber-attack, it is required to run scan jobs on suspicious endpoints to validate the threat. SOAR can start scan jobs on Symantec Endpoint Protection Manager to help on deciding the next course of action.

This can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR needs to connect Symantec Endpoint Protection Manager API and Database.
- Access to 8443/tcp, 8446/tcp port for API acceess and 1433/tcp, 1434/udp port for database access is required.
- User accounts for API access and database access are required for SOAR to connect to Symantec Endpoint Protection Manager.

Configuring Symantec Endpoint Protection Manager

- 1. Login to SEP Management Server on https://SEPManager:8443/console/apps/sepm and create an administrator account on **Admin** tab.
- 2. Click Policy > Policy Components > File Fingerprint Lists and add a File Fingerprint List.
- 3. You might create a file containing MD5 value of eicar.com test signature 44d88612fea8a8f36de82e1278abb02f: to upload a file to create the list.
- 4. Login to SEP Manager Web Service Application Registration on https://SEPManager:8446/sepm with the admin account you've created on previous step and register a webservice application to be used by SOAR.



Note the Client ID and Client Secret values are generated.

5. Create a database user that has selected permissions and ensure that the SQL Browser service is configured and running on MSSQL Server.

Configuring SOAR

- Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor**:
 - a. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, SEP Manager Credentials).
Username	Username you have created for SOAR on Symantec Endpoint Protection Manager
Password	Password of the user you have created for ATAR on Symantec Endpoint Protection Manager.
Private Key	Empty

b. Credential Store:

Parameter	Value
Туре	External Credential
Name	Name of the credential with pull path of the safe on store

3. To create credentials to be used for database connection:

a. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, SEP Manager DB Credentials).
Username	Database username you have created for SOAR on SEP Manager Database.
Password	Password of the user you have created for SOAR on SEP Manager Database.
Private Key	Empty

b. Credential Store:

Parameter	Value
Туре	External Credential
Name	Name of the credential with pull path of the safe on store

- 4. Click Configuration > Integrations > Create Integration.
- 5. Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of Symantec Endpoint Protection Manager integration on SOAR
Туре	Symantec Endpoint Protection Manager
Address	Address of the integration (in the following format: https://192.168.2.140)
Configuration	Specify the following configuration parameters:
	<pre>client.id=xxxxxxxx-xxxx-xxxx-xxxx-xxxx-xxxxxxxxx</pre>
Credential	Name of the credential set created on step 2 (For example, SEP Manager Credentials).
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select user(s) from the list to notify when ATAR performs an action on this integration.

6. Click **Test** to test the integration.

Configuring SOAR Page 541 of 594

7. Click **Save** to complete the integration.

Additional Notes

Symantec Endpoint Protection Manager Webservice registration works on 8446/tcp port by default. If it is different than this value, you might configure it using **DefaultSEPMRestApiPort** paramater under **Configuration** > **Parameters**.

Configuring SOAR Page 542 of 594

Integration Guide for Symantec Managed Security Services (MSS)

Integration Overview

Symantec Managed Security Services (MSS) provides its customers security monitoring and real-time security analytics services including strategic insights needed to prioritize and respond to incidents and build strategies to protect the assets, reputations and viability of their organizations.

Integration Capabilities

SOAR has the following integration capabilities with Symantec MSS:

- Ingest Incident Records as Alert
- Update MSS incident record
- · Close MSS incident

Use Case #1: Investigating and Mitigating Cyber-attacks

Integrated with Symantec MSS, ATAR periodically collects new incidents and update the statuses of the open incidents as they change in Smyantec MSS system. When an incident record is created on Symantec MSS, ATAR automatically collects Incident Details such as Analyst Comment, Signatures that are triggering this alert, Comments that are added to the incident and possible Attachments inside this alert anc creates a new incident on its own Incident Management Service Desk.

Configuration

Prerequisites

- SOAR connects to Symantec MSS API via HTTPS. So access permission to https://api. managedsecurity.com is required.
 - A user account and a certificate-password pair are required for ATAR to connect to Symantec MSS API.

Configuring Symantec MSS

The Symantec MSS service uses client-side certificates for authentication.

- 1. Click Profile > Certificates > Create a certificate.
- 2. Select the **type of service** for the certificate.
- 3. Set the expiration date for the certificate. The available values are 6 months, 1 year, and 2 years.
- 4. [Optional] Specify the name for the certificate.
- 5. Click Register.



The certificates are enabled by default upon creation, but must be downloaded and installed before they can be used.

Configuring SOAR

To use the client-side certificate created on Symantec MSS, you must convert it with **openssl** command line tool as following:

openssl pkcs12 -in <certificate_created_in_MSS_Portal>.p12 -clcerts -nodes out <output_file>

Configuring Credentials

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor**:
- 3. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, Symantec MSS Credentials)).
Username	Empty
Password	Empty.
Private Key	Paste the content of the <output_file>.pem file into the Private Key area.</output_file>



The external credential stores can not be used with this integration type.

Configuring Symantec MSS as Alert Source

- To add a new incident severity configuration, click Configuration > Incidents > Severities .
 Symantec MSS integration requires the following incident severity definitions:
 - Informational
 - Warning
 - Critical
 - Emergency
- To add a new incident statues configuration, click Configuration > Incidents > Statuses.
 Symantec MSS integration requires the following incident status definitions:
 - New
 - In Progress as Open statuses
 - False Positive
 - Resolved
 - Deferred
 - No Action as closed statuses.
- 3. Click Configuration > Alert Source > Create Alert Source Configuration.
- 4. Specify the following parameter values in the **Configuration** form:

Para meter	Value
Name	Display name of Symantec MSS Alert Source on SOAR
Туре	Symantec MSS
Addre ss	Address of Symantec MSS service (in the following format: https://api.monitoredsecurity.com).
Alert Severi ties	Mapping of alert severity values to SOAR incident severities.

Para meter	Value
Confi gurati on	Specify the following configuration parameters: # Enables incident sync # Default: false #incident.autoSync=true # Request timeout in minutes # If not provided, ATAR will use 10 by default ##request.timeout=10 # Enable auto closing ATAR incidents when the related Symantec MSS incident is closed, # Default: false #incident.autoClose=true # Enable auto reopening ATAR incidents when the related Symantec MSS incident is reopened, # Default: false #incident.autoReopen=true # Scope fields to be extracted from base events and/or correlated events (field1:CATEGORY:ROLE, # CATEGORY is any of: EMAIL_ADDRESS, HASH, HOST, MAC_ ADDRESS, NETWORK_ADDRESS, # COMPUTER_NAME, UNKNOWN, URL, USERNAME, PROCESS # ROLE is any of: OFFENDER, IMPACT, RELATED # # Note: The fields in the baseevent.scope example below are always extracted by default. # Note: Extraction with same field name overrides the default one. # Note: Extraction with different field name does not override the default behaviour and extracted # Note: Field names must start with / character # Example: baseevent.scope=/sourceIPString:NETWORK_ADDRESS:OFFENDER # baseevent.scope= # Example: correlated.scope=/sourceV6:NETWORK_ADDRESS:OFFENDER # baseevent.scope= # Example: correlated.scope=/sourceV6:NETWORK_ADDRESS:OFFENDER # correlated.scope= # How far (in days) into the past ATAR will look for remote incidents at the initial sync task # If not provided, ATAR will use 14 days by default #days.to.look.back.at.initial.sync=14
Crede ntial	Name of the credential set you have created (For example, Symantec MSS Credentials).
Trust Invali d SSL Certifi cates	Select this if Engine's certificate is self-signed or is not recognized by browsers
Viisibl e Alert Fields	Select alarm fields that has to be displayed on Incident Management Service Desk.
Notify	Select user(s) from the list to notify when ATAR performs an action on this integration.

- 5. Click **Test** to test the integration.
- 6. Click Save to complete the integration.

Configuring Symantec MSS as an Integration

- 1. Click Configuration > Integrations > Create Integration.
- 2. Specify the following parameter values in the **Configuration** form:

Parameter	Value
Name	Display name of Symantec MSS integration on SOAR
Туре	Symantec MSS
Address	Address of Symantec MSS service (in the following format: https://api.monitoredsecurity.com).
Configuration	Specify the following configuration parameters:
	#proxy.id=5422
Credential	Name of the credential set you have created (For example, ArcSight ESM Credentials).
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or is not recognized by browsers
Require Approval From	Select user(s) from list to ask her/his approval before executing actions on this integration.
Notify	Select user(s) from the list to notify when ATAR performs an action on this integration.

- 3. Click **Test** to test the integration.
- 4. Click **Save** to complete the integration.

Additional Notes

The following configuration parameters can be used for fine tuning the integration.



Consult SOAR field engineering team before editing them:

Parameter Name Description Default Value

SymantecMssListenerMaxRetrySeconds Symantec MSS listener queue max message retry in seconds 1800

SymantecMssListenerQueueConcurrency Upper limit of Symantec MSS Listener consumer thread count 3

SymantecMssSyncLookBehindMinutes Minutes to look behind to incident in

```
Symantec MSS SyncTask 20
SymantecMssSyncPeriod Period in seconds to sync Symantec MSS incidents 60
Below Automation Bit sample could be used to automatically close incidents
via Trigger.
atar.require("underscore");
var remoteStatusList = [
'False Positive',
'Resolved',
'Deferred',
'No Action'
];
var remoteStatus = 'Resolved';
var statusName = atar.getTicket().getTicketStatus().getName();
if (_.contains(remoteStatusList, statusName)) {
remoteStatus = statusName;
var params = {'INCIDENT_CLOSING_STATUS': remoteStatus};
atar.action(ActionPluginCapability.CLOSE_INCIDENT, atar.getAlert(),
atar.device("Symantec MSS Integration"), params);
```

Additional Notes Page 548 of 594

Integration Guide for Symantec Messaging Gateway

Integration Overview

Symantec Messaging Gateway (Brightmail) is an email gateway which is used to filter incoming and outgoing emails. This integration has been tested with Symantec Messaging Gateway 10.6.5-1 version.

Integration Capabilities

SOAR has the following integration capabilities with Symantec Messaging Gateway:

- Block Sender
- Block in Dictionary

Use Case: Blocking phishing attacks

SOAR can follow the email inboxes for user's phishing reports and automatically creates an incident record on its service desk. To stop the phishing campaigns, SOAR can extract the sender address, IP, e-mail subject and block them on Symantec Messaging Gateway.

This can be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- SOAR connects to Symantec Messaging Gateway via HTTPS. Access to 443/tcp port is required.
- A user account for SOAR to connect Symantec Messaging Gateway.

Configuring Symantec Messaging Gateway

- 1. Click Administration > Users and select Create a new administration policy to create an administrator account. Select Manage Policies right.
 - Disable all other rights since they are unnecessary.
- Click Content > Dictionaries to create a dictionary.

3. To block hosts and IP addresses, SOAR uses Local Bad Sender IPs and Local Bad Sender Domains.

Configuring SOAR

- 1. Navigate to Configuration > Credentials and click Create Credential.
- 2. Fill the **Credential Editor** form with following parameter values:
 - a. Internal Credential:

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, Symantec Messaging Gateway Credential)
Username	Username you have created of SOAR on Symantec Messaging Gateway
Password	Password of the user you have created of SOAR on Symantec Messaging Gateway.
Private Key	Empty

b. Credential Store

Parameter	Value
Туре	External Credential
Name	Name of the credential with full path of the safe on store

- 3. Click Configuration > Integrations > Create Integration.
- 4. Fill the configuration form with the following parameter values:

Parameter	Value
Name	Display name of Symantec Messaging Gateway integration on SOAR.
Туре	Symantec Messaging Gateway.
Address	Address of the integration (the format must be192.168.2.212).)
Configuration	You need to specify the following configuration parameters. You can define multiple dictionaries by seperating " ", for example, dictionary.name=SOAR Dictionary 1 SOAR Dictionary 2
Credential	Name of the credential set you've just created on step 2 (for example, Symantec Messaging Credential.

Configuring SOAR Page 550 of 594

Parameter	Value
Trust Invalid SSL Certificates	Select this if Symantec Messaging Gateway's certificate is self-signed or not recognized by browserss.
Require Approval From	Select user(s) from list to ask her/his approval before executing actions on this integration.
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.

- $5. \ \ \, \text{Click Test to test the integration.}$
- 6. Click **Save** to complete integration.

Configuring SOAR Page 551 of 594

Integration Guide for Tenable Nessus

Integration Overview

Tenable Nessus is a vulnerability scanner used to detect vulnerabilities on the network. SOAR uses Tenable Nessus to gather vulnerability information to enrich incidents' context.

Integration Capabilities

- Action
- · Get Scan List
- Get All Vulnerabilities on a Scan

Configuration

Configuring Tenable Nessus

- SOAR connects to Tenable Nessus' API via HTTPS. Therefore SOAR must be able to connect this service.
- A user credential is required.

Configuration on SOAR

Configuring SOAR

- 1. Navigate to Configuration > Integrations.
- 2. In the Integrations Editor, specify the following parameter values:

Parameter	Value
Name	Display name of Tenable Nessus integration on SOAR
Туре	Tenable Nessus.
Address	Address of the integration (in the following format: http[s]://1.1.1.1:1234 or http [s]://abc.example.com:1234
Credential	Credential defined for the integration under the Credentials menu

Parameter	Value
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an action on this integration

- 3. Click **Test** to test the integration.
- 4. Click **Save** to complete the integration.

Configuring SOAR Page 553 of 594

Integration Guide for Tenable Security Center

Integration Overview

Tenable Security Center (Tenable SC) is a vulnerability management solution that provides visibility into network by identifying all vulnerabilities, misconfigurations and malware attack on assets and gives ability to manage and measure your cyber risk.

SOAR has the following integration capabilities with Tenable Security Center:

- Get Assets
- Get Vulnerabilities (System-wide)
- · Get Vulnerabilities on IP

.Use Case: Getting vulnerability details of assets

SOAR can integrate with Tenable Security Center to gather additional information about an asset during incident investigation. Knowing existing vulnerabilities on a system can help SOC analysts to understand possible root cause of an incident more precisely.

Configuration

Prerequisites

- SOAR connects to Tenable Security Center's API using HTTPS. Typically an access permission to 443/tcp port is required.
- A user account for SOAR to connect to Tenable Security Center.

Configuring Tenable Security Center

1. Login to Tenable Security Center with Security Manager User.



Note: This user account is different from admin account.

- 2. Navigate to **Users> Groups** and add a group to define the objects that SOAR can access. You must at select atleast one item from **Viewable Hosts and Repositories lists**.
 - There is no need to share any object under **Share to Group** tab.
- To add user for SOAR access, navigate to Users > Users. Select No Role and SOAR Access Group in Membership.

Configuring SOAR

- 1. Navigate to Configuration > Credentials and click Create Credential.
- 2. Fill the Credential Editor form with following parameter values:
 - a. Internal Credential:

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, Tenable SC Credential
Username	User you have created of SOAR on Tenable Security Center.
Password	Password of the user you have created of SOAR on Tenable Security Center.
Private Key	Empty

- 3. Click Configuration > Integrations > Create Integration.
- 4. Fill the configuration form with the following parameter values:

Parameter	Value
Name	Display name of Tenable Security Center integration on SOAR.
Туре	Tenable Security Center.
Address	Address of the integration (the format must be https://1.1.1.1:1234 or https://abc.example.com:1234)
Credential	Name of the credential set you've just created on step 2 (for example, Tenable SC Credential.
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or not recognized by browserss.
Require Approval From	Select user(s) from list to ask her/his approval before executing actions on this integration.
Notify	elect user(s) from the list to notify when SOAR performs an action on this integration.

- 5. Click **Test** to test the integration.
- 6. Click **Save** to complete integration.

Configuring SOAR Page 555 of 594

Integration Guide for Trend Micro Apex Central

Integration Overview

Trend Micro Apex Central is a web-based console that provides centralized management for Trend Micro products and services at the gateway, mail server, file server and corporate desktop levels.

Integration Capabilities


Quarantine

Prerequisites

 Access to the HTTPS is needed as ArcSight SOAR connects to Trend Micro Apex Central API through this service.

Configuring Trend Micro Apex Central

- 1. Login to Trend Micro Apex Central and navigate to Administration tab.
- Click Settings < Automation API Access Settings and add a new application as follows:



3. Note down the Application ID and API Key (for your reference later) after saving the

application as follows:



Configuring SOAR

- 1. Click Configuration > Credentials > Create Credentials.
- 2. Specify the following parameter values in the **Credential Editor**:

Internal Credential:

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, Trend Micro Apex Central Credentials)
Username	Empty
Password	Application ID that you've noted from created application.
Private Key	API Key that you have noted before from the created application.

3. Click Configuration > Integrations > Create Integration.

Specify the following parameter values in the **Configuration** form.:

Parameter	Value
Name	Display name of Trend Micro Apex Central integration on SOAR
Туре	Trend Micro Apex Central
Address	Address of the integration (the format must be (https://czbxlz.manage.trendmicro.com)
Credential	Name of the credential set that you created on step 2. (For example, Trend Micro Apex Central Credentials).

Configuring SOAR Page 557 of 594

Parameter	Value
Trust Invalid SSL Certificates	Select this if Trend Micro Apex Centrals certificate is self signed or it is not recognized by browsers.
Require Approval Form	Select user(s) from list who can provide approval before executing actions on this integration.
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.

- 4. Click **Save** to save the integration definition.
- Navigate to Configuration>Customization Library and edit Trend Micro Apex Central Advanced Action Script Default Script Template.
- 6. Select the integration that you have added to Integrations menu.
- 7. Click **Save** to complete the integration.
- 8. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid

Capablities

Quarantine

Action capability for quarantine a Hostname, IP address and MAC addresss.

• Rollback: Yes

• Duplicate Control: No

Input Parameter	Description	Туре	Scope Restricted Yes/No	Required Yes/No
Rollback Mode	Time to rollback this action. Default is no-rollback.	N/A	N/A	No
MAC Address / Network Address / Hostname	MAC Address/Network Address/Hostname to quarantine	MAC Address Network Address Hostname	Yes	Yes

Output:

Case Scope: N/A

Human Readable Output: N/A

Capablities Page 558 of 594

Integration Guide for Trend Micro Vision One

Integration Overview

Trend Micro Vision One is a purpose-built threat defense platform that provides added value and new benefits beyond XDR solutions, allowing you to see more and respond faster.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Trend Micro Vision One:

- Get Observed Attack Techniques
- Query Operating Systems
- Get Exception List
- Get Suspicious Object List
- Add Objects to Suspicious Object List
- Add Objects to Exception List
- Delete Objects from Suspicious Object List
- Delete Objects from Except List
- Prerequisites

You must have access to HTTPS as the ArcSight SOAR connects to Trend Micro Vision One to API through this service.

Configuration

Configuring Trend Micro Vision One

- 1. Login to the Vision Platform and create a user with the Master Administrator role and Trend Micro Vision One™ console and APIs access level.
- 2. Get access token of the created user that is used as a credential on ArcSight SOAR.

Configuring SOAR

- 1. Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the Credential Editor form.

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, Trend Micro Vision One Credential).			Bearer <space><access-token></access-token></space>

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration** form.

Parameter	Value				
Name	Display name of the integration.				
Туре	Trend Micro Vision One.				
Address	URL of API (for example,	API trend micro).			
Configuration	Specify the following configuration parameters:				
	cache.reusing.duration	Configure how far (in minutes) into the past this enrichment will look. For example: cache.reusing.duration=20 .			
	proxy.id	ID of the proxy integration when you access Trend Micro Vision One through a web proxy device. For example, proxy.id = 12345.			
Credential	Credential that has been	Credential that has been defined for this integration under the Credentials menu.			
Trust Invalid SSL Certificates	Select this if web server's certificate is self-signed or is not recognized by browsers.				
Require Approval From	Select user(s) from list to ask the approval before executing actions on this integration.				
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.				

- 5. Click **Save** to save the integration definition.
- 6. Navigate to Configuration>Customization Library and edit Trend Micro Vision One Advanced Action Script Default Template.
- 7. Select the integration that you have added to Integrations menu.
- 8. Click **Save** to complete the integration.
- 9. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Configuring SOAR Page 560 of 594

Capabilities

1. Get Observed Attack Techniques

Enrichment capability for getting observed attack techniques.

The following table presents the **Get Observed Attack Techniques** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	No	Yes
Risk Levels	Single or comma seperated risk values (high, critical, low, info, undefined, medium).	Text	No	No
Tactic IDs	Single or comma seperated tactid id values .	Text	No	No
Technique IDs	Single or comma seperated technique id values.	Text	No	No
Name Filter	Detection Filter name .	Text	No	No
Endpoint Name	Name of the endpoint.	Computer Name, Hosy, Keyword, Unknown	Yes	No
Time Range	Time range for attack times.	Time Range	No	Yes

Output:

Case Scope:

Action	Туре	Category/ Value
Add	Scope Item	Keyword (Related)

Human Readable Output:



2. Query Operating Systems

Enrichment capability for operating system information for all agents active in the last seven days.

The following table presents the Query Operating Systems action capability details:

Capabilities Page 561 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	No	Yes

Case Scope:

Action	Туре	Category/ Value
Add	Scope Item	Keyword (Related)

Human Readable Output:



3. Get Exception List

Enrichment capability for information about domains, file SHA-1 values, IP addresses, or URLs that are in the Exception List.

The following table presents the **Get Exception List** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	No	Yes
Туре	Single or comma seperated types ("domain", "ip", "sha1", "url").	Text	No	No

Output:

Case Scope:

Action	Туре	Category/ Value
Add	Scope Item	Keyword (Related)

Human Readable Output:



4. Get Suspicious Object Lists

Enrichment capability for information about domains, file SHA-1 values, IP addresses, or URLs that are in the Suspicious Object List

The following table presents the **Get Suspicious Object** action capability details:

Capabilities Page 562 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	No	Yes
Туре	Single or comma seperated types ("domain", "ip", "sha1", "url").	Text	No	No
Content Filter	Filters the list to suspicious objects that exactly match the specified string.	Text	No	No

Case Scope:

Action	Туре	Category/ Value
Add	Scope Item	Keyword (Related)

Human Readable Output:



5. Add Objects to Suspicious Object List

Action capability for Adding domains, file SHA-1 values, IP addresses, or URLs to the Suspicious Object List.

• Rollback: Yes

• Duplicate Check: No

The following table presents the **Add Objects to Suspicious Object List** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Rollback Mode	Time to rollback this action. Default is no-rollback.	Relative Time	No	No
Value	The value of the suspicious object which will be added.	Host, Network Address, Hash, URL	Yes	Yes
Description	Record description info.	Text	No	No

Capabilities Page 563 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/No)	Required (Yes/No)
Scan Action	Suspicious object record scan action, when not set, use system default settings. Risk Level. Type's scan action.	Enum	No	No
Risk Level	Suspicious object risk level when not set, use default value - high.	Enum	No	No
Expired Day	Suspicious object record expired day, when not set, use system default settings. Expired Day.	Text	No	No

Case Scope:

Action	Туре	Category/ Value
Add	Scope Item	Keyword (Related)

Human Readable Output: N/A

6. Add Objects to Exception List

Action capability for Adding domains, file SHA-1 values, IP addresses, or URLs to the Exception List and prevents these objects from being added to the Suspicious Object List.

• Rollback: Yes

• Duplicate Check: No

The following table presents the Add Objects to Exception List action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Rollback Mode	Time to rollback this action. Default is no-rollback.	Integration	No	Yes
Value	Suspicious object record value, it support full match or partial match, DOMAIN partial match: (with a wildcard before 1st, example, example.com) IP partial match: (ip range example, 200.102.35.1-200.102.35.254, cidr example: 200.102.35.1/24) URL Partial match: (support wildcard 'http://.", 'https://." at beginning, or "' at the end, or both two wildcards, example, https://.example.com/path1/) SHA1 (only full match).	Text	No	No
Description	Exception description info.	Text	No	No

Output:

Capabilities Page 564 of 594

Case Scope:

Action	Туре	Category/ Value
Add	Scope Item	Keyword (Related)

Human Readable Output: N/A

7. Delete Objects from Exception List

Action capability for Deleting domains, file SHA-1 values, IP addresses, or URLs from the Exception List.

• Rollback: Yes

• Duplicate Check: No

The following table presents the **Delete Objects from Exception List** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Rollback Mode	Time to rollback this action. Default is no-rollback.	Relative Time	No	No
Value	Suspicious object record exception value.	Host, Network Address, Hash, URL	Yes	Yes

Output:

Case Scope:

Action	Туре	Category/ Value
Add	Scope Item	Keyword (Related)

Human Readable Output: N/A

8. Delete Objects from Suspicious Object List

Action capability for Deleting domains, file SHA-1 values, IP addresses, or URLs from the Suspicious Object List:

• Rollback: Yes

• Duplicate Check: No

The following table presents the **Delete Objects from Suspicious Object List** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Rollback Mode	Time to rollback this action. Default is no-rollback.	Relative Time	No	No
Value	Suspicious object record exception value.	Host, Network Address, Hash, URL	Yes	Yes

Capabilities Page 565 of 594

Case Scope:

Action	Туре	Category/ Value
Add	Scope Item	Keyword (Related)

Human Readable Output: N/A

Capabilities Page 566 of 594

Integration Guide for Turkcell Threat Intelligence

Integration Overview

Turkcell Threat Intelligence is a service which lets users to query reputation of Indicators of Compromise such as data leakage, brand protection, and vulnerability modules.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Turkcell Threat Intelligence:

- Domain Query
- Email Query
- Hash Query
- IP Query

Use Case: Investigating Phishing Campaigns

SOAR integrates with Turkcell Threat Intelligence or Bozok to investigate and mitigate phishing campaigns. SOAR extracts the indicators such as sender address, IP address, and URLs from a phishing report email of the user and creates a new incident on the Incident Management Service Desk. SOAR then checks with Turkcell Threat Intelligence or Bozok if this is a known attack and previously analyzed. This investigation can either be performed automatically within a playbook or manually by an analyst.

Configuration

Prerequisites

- Access to https://bozok.turkcell.com.tr (443/tcp port) as SOAR connects to Turkcell Threat Intelligence/Bozok API through HTTPS
- An API key for SOAR to connect to Turkcell Threat Intelligence/Bozok service

Configuration on Turkcell Threat Intelligence or Bozok

No specific configuration is needed on Turkcell Threat Intelligence or Bozok.

Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the Credential Editor form:

a. Internal Credential:

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, Turkcell Threat Intelligence Credentials)
Username	Empty
Password	Empty
Private Key	API key obtained from the service provider

b. Credential Store:


Parameter	Value
Туре	External credential
Name	Name of the credential with full path of the safe on store

- 3. Click Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration form**:

Parameter	Value
Name	Display name of Turkcell Threat Intelligence integration on SOAR
Туре	Turkcell Threat Intelligence
Address	Address of Turkcell Threat Intelligence service(in the following format: (https://bozok.turkcell.com.tr)
Credential	Name of the credential set created (For example, Turkcell Threat Intelligence Credentials)
Trust Invalid SSL Certificates	Unselect

Configuring SOAR Page 568 of 594

Parameter	Value
Configuration	Specify the following configuration parameters:
	<pre># Integration ID of the proxy integration to use when connecting to current integration. # If not provided, SOAR will try to use a direct connection. proxy.id=5434 # configure how far (in minutes) into the past this enrichment will look. cache.reusing.duration=60</pre>
Require Approval From	Not applicable as SOAR executes enrichment on Turkcell Threat Intelligence
Notify	Not applicable as SOAR executes enrichment on Turkcell Threat Intelligence



- 5. Click **Test** to test the integration.
- 6. Click **Save** to save the integration.

Configuring SOAR Page 569 of 594

Integration Guide for Udger

Integration Overview

Udger is a query detection repository service that works for both cloud-based and local executions. Udger also provides Data Center name of given IP and many more.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with Udger:

Parse

Prerequisites

- You must have access to HTTPS as the ArcSight SOAR connects to Udger API through this service.
- API Token is needed to access Udger REST API.

Configuration

Configuring Udger

- 1. Login to udger and navigate to Products > Cloud Parser.
 - Click Subscribe Now.
 - Select Subscription Package > Activate.



Note: You can activate free package for the trial usage

• The access key is displayed in My Account > General



Note: Copy the access key as this is required during creating credential.

Configuring SOAR

- 1. Click Configuration > Integration > Create Integration.
- 2. In Configuration Editor, select Udger in List of Type.
- 3. Navigate to **Credential** and click **Create** to create new credential. Specify following values in the **Credential Editor**:

Туре	Username	Password	Private Key	Check
Internal Credential			Access Key that is copied from Udger web site (navigate to My Account > General tab on Udger UI).	Clear Text Access checkbox.

- 4. Click **Save** to save the integration definition.
- 5. Navigate to Configuration>Customization Library and edit Udger Advanced Action Script Default Template.
- 6. Select the integration that you have added to Integrations menu.
- 7. Click **Save** to complete the integration.
- 8. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. Parser

Parsing given IP and return JSON detail including Datacenter Name

The following table presents the **Parser** capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
IP	A valid IP Address to retrieve data.	Network Address Host	Yes	Yes
User Agent	User Agent information to query on IP.	Unknown Keyword	Yes	No

Output:

Case Scope:


Scope Item Property **Cloud Name** is added to the related scope item. When you click the related scope item to view its properties, a cloud name result is displayed.

The following table presents the case scope details:

Configuring SOAR Page 571 of 594

Action	Туре	Category/ Value
Set	Scope Item Property	Cloud Name

Human Readable Output:



Capabilities Page 572 of 594

Integration Guide for Urlscan

Integration Overview

The **URLscan** API allows you to submit URLs to scan, retrieve scan results, download Document Object Model (DOM) snapshots and page screenshots and search existing scans for different types of indicators.

Integration Capabilities

ArcSight SOAR has the following integration capabilities with urlscan:

- Search Domain
- Search Hash
- Search IP
- Search URL
- Submit URL

Configuration

Prerequisites

- You must have access to HTTPS as the ArcSight SOAR connects to urlscan io API through this service.
- URLScan requires an API key for access.

Configuring SOAR

- Click Configuration > Credential > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor** form:

Туре	Name	Username	Password	Private Key
Internal credential	Display name of credential set (for example, URL Scan API Credential).	Empty	Empty	Access Token

3. Click Configuration > Integrations > Create Integration.

4. Specify the following parameter values in the **Configuration** form.

Parameter	Value		
Name	Display name of the integration.		
Туре	Urlscan.io		
Address	Address of the integration (the format must be https://urlscan.io).		
Configuration	Specify the following configuration parameters:		
	proxy.id ID of the proxy integration if you access Urlscan.io through a web proxy device. For example: proxy.id = 12345.		
Credential	Credential that has been defined for this integration in the Credentials menu.		
Trust Invalid SSL Certificates	Select this if web server's certificate is self-signed or is not recognized by browsers.		
Require Approval From	Select user(s) from list to ask the approval before executing actions on this integration.		
Notify	Select user(s) from the list to notify when SOAR performs an action on this integration.		

- 5. Click **Save** to save the integration definition.
- 6. Navigate to Configuration>Customization Library and edit Urlscan Advanced Action Script Default Template.
- 7. Select the integration that you have added in the Integrations menu.
- 8. Click **Save** to complete the integration.
- 9. Click **Test**, an **Integration Successful** message is displayed if the credential and address are valid.

Capabilities

1. Search Domain

Enrichment capability for retrieving domain information for a relative time range.

The following table presents the **Search Domain** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Bucket Name	Name of the third party integration.	Integration	N/A	Yes
Domain	Domain to be queried from Urlscan.	Hash	Yes	Yes

Capabilities Page 574 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Relative Time Range	Specific relative time period that will be checked.	Time unit Hour (s) Day(s) Week(s) Month(s)	N/A	Yes

Case Scope:

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output:



2. Search Hash

Enrichment capability for retrieving hash information for a relative time range.

The following table presents the **Search Hash** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
SHA-256	SHA-256 hash value to be queried from Urlscan.	Hash	Yes	Yes
Relative Time Range	Specific relative time period that will be checked.	Time unit Hour (s) Day(s) Week(s) Month(s)	N/A	Yes

Output:

Case Scope:

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output:

Capabilities Page 575 of 594



3. Search IP

Enrichment capability for retrieving IP information for a relative time range.

The following table presents the **Search IP** action capability details:


Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
IP	Network address to be queried from Urlscan.	Network Address	Yes	Yes
Relative Time Range	Specific relative time period that will be checked.	Time unit Hour (s) Day(s) Week(s) Month(s)	N/A	Yes

Output:

Case Scope:

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output:



4. Search URL

Enrichment capability for retrieving URL information for a relative time range..

The following table presents the **Search URL** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
URL	URL to be queried from Urlscan.	URL	Yes	Yes

Capabilities Page 576 of 594

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Relative Time Range	Specific relative time period that will be checked.	Time unit Hour (s) Day(s) Week(s) Month(s)	N/A	Yes

Output:

Case Scope:

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output:

Server	Url	Screenshot	lp	Domain	Tags	Indexedat	Country
ATS/9.1.10.2 5	https://13.25 0.173.68/	https://urlsca n.io/screens hots/2fd9b71 6-4619-43f7- a7b5- 436b3e7377 58.png	13.250.173. 68	13.250.173. 68	["nonprod"]		SG

5. Submit URL

Enrichment capability for submitting a URL for investigation.

The following table presents the **Submit URL** action capability details:

Input Parameter	Description	Туре	Scope Restricted (Yes/ No)	Required (Yes/ No)
Integration	Name of the third party integration.	Integration	N/A	Yes
URL	URL to be queried from Urlscan.	URL	Yes	Yes
Tag	User-defined tags to annotate this scan, for example, phishing or malicious. Limited to 10 tags.	String	N/A	No
Visibility	Submitting visibility option which could either be Public, Private or Unlisted	String Public Unlisted Private	N/A	Yes
Do not Use Cache	If this option is checked, SOAR does not use cached results.	Boolean	N/A	No

Output:

Case Scope:

Capabilities Page 577 of 594

Enrichment	Туре	Category Value
None	N/A	N/A

Human Readable Output:



Capabilities Page 578 of 594

Integration Guide for VirusTotal

Integration Overview

VirusTotal inspects suspicious files and URLs to detect types of malware with over seventy antivirus scanners and URLs or domain blacklisting services, in addition to a myriad of tools to extract signals from the studied content.

Integration Capabilities

SOAR has the following integration capability with VirusTotal:

- Domain Query
- Domain/Downloaded Files Query
- Domain/Subdomains Query
- Domain/URLs Query
- File Query
- Hash Query
- IP Query
- IP/Downloaded Files Query
- IP/Passive DNS Query
- IP/URLs Query
- URL Query

Use Case: Blocking access to malicious URL

During the investigation of an attack, SOAR checks for suspicious IP addresses, URLs, files, and hash values to VirusTotal if these indicators are known and previously analyzed. According to returned confidence score, SOAR decides on the next course of action. This investigation can either be performed automatically within a playbook or manually by an analyst.

Configuration


Prerequisites

VirusTotal API version 3

- Access to tcp port 443 as SOAR connects to VirusTotal API http://www.virustotal.com
- An API key for SOAR to connect to VirusTotal

Configuring VirusTotal

- No specific configuration is needed on VirusTotal.
- Login to https://www.virustotal.com with your username and make a note of the API key under Settings> API Key.



Configuring SOAR

- 1. Click Configuration > Credentials > Create Credential.
- 2. Specify the following parameter values in the **Credential Editor**:
 - a. Internal Credential

Parameter	Value
Туре	Internal Credential
Name	Display name of credential set (For example, VirusTotal Credentials)
Username	Empty
Password	Empty
Private Key	API Key you have on VirusTotal

b. Credential Store:


Parameter	Value
Туре	External Credential
Name	Name of the credential with pull path of the safe on store

- 3. Navigate to Configuration > Integrations > Create Integration.
- 4. Specify the following parameter values in the **Configuration form**:

Parameter	Value
Name	Display name of VirusTotal integration on SOAR
Туре	VirusTotal
Address	Address of the integration (in the following format https://www.virustotal.com)
Configuration	Specify the following configuration parameters:
	# Retry HTTP requests when API limit has been exceeded (TRUE / FALSE) apilimit.tryagain.enabled=true # Seconds for wait before trying again after each API limit exceeded error apilimit.tryagain.waittime=5 apilimit.tryagain.waittime=5 # How many times to wait after API limit exceeded error has been received # Increasing this parameter should increase the success rate of parallel VirusTotal workflow apilimit.tryagain.waitlimit=3 # Integration ID of the proxy integration to use when connecting to current integration. # If not provided, ATAR will try to use a direct connection. #proxy.id=123 # configure how far (in minutes) into the past this enrichment will look. #cache.reusing.duration=20 # Enrichment timeout duration after start time (in seconds) scan.query.timeout=3600 # Expiration period of hash scans # If not provided, ATAR will use 30 days by default #scan.result.expiration.period.in.days=30 # VirusTotal APIV3 parameter # Limits page count for relation queries. SOAR will use 1 page by default #scan.result.page.count.max=1

Configuring SOAR Page 581 of 594





- 5. Click **Test** to test the integration.
- 6. Click **Save** to complete the integration.

Additional Notes

- Domain and IP-related queries retrieve results in 40-item batches. For some IOCs, this may result in too many consecutive queries and long query-times.
- The file queries are limited to 32MB due to limits with VirusTotal API.

Additional Notes Page 582 of 594

• Domain or URLs, Domain or Downloaded Files, IPor URLs, and IP or Downloaded Files only return the scope items with confidence score greater than 0.

Additional Notes Page 583 of 594

Integration Guide for VMware ESXi

Integration Overview

SOAR uses VMware ESXi(Elastic Sky X integration) to perform some actions on the virtual machines (VMs).

Integration Capabilities

Action

- Create Snapshot of a VM
- Export VM
- · Get Information of All VMs
- Power On VM
- Power Off VM
- Reset VM
- Reboot VM
- Standby VM
- Suspend VM

Configuration


Configuring VMware ESXi

- Access to HTTPs for SOAR to connect to VMware ESXi Server's SDK
- SOAR account with admin role

Configuring SOAR

- 1. Navigate to Configuration > Integrations.
- 2. In the Integrations Editor, specify the following parameter values:

Parameter	Value
Name	Display name of VMware ESXi integration on SOAR
Туре	VMware ESXi
Address	Address of the integration (in the following format: http[s]://1.1.1.1:1234[/sdk] or http[s]://abc.example.com:1234[/sdk])
Credential	Credential defined for the integration under the Credentials menu
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an action on this integration



- 3. Click **Test** to test the integration.
- 4. Click **Save** to complete the integration.

Configuring SOAR Page 585 of 594

Integration Guide for VxStream Sandbox

Integration Overview

VxStream Sandbox is an automated malware analysis system that includes the unique Hybrid Analysis technology. It is available as a standalone software package that is automatically deployed within your local infrastructure and operates without an external dependency or callback mechanism. It is possible to execute files on any Windows guest image (For example, a copy of your local workstation) and has a variety of integration and interface capabilities.

The feature set of VxStream Sandbox is extensive, with hundreds of generic indicators at its core. It detects unknown threats independent of Anti-Virus signatures. Empowered by Hybrid Analysis, the entire process memory gets analyzed using multiple timed snapshots, including the runtime sample. This feature allows the extraction of more indicators (Strings/API calls) regardless of execution. This approach enables the analysis of dormant code, evasive conditions, and extracts more valuable IOCs.

Integration Capabilities

Action

· Hash analysis

Configuration

Configuration on VxStream Sandbox


Access to HTTPs for SOAR to connect to VxStream Sandbox

Configuring SOAR

- Navigate to Configuration > Integrations.
- 2. In the Integrations Editor window, specify the following parameter values:

Parameter	Value
Name	Display name of VxStream Sandbox integration on SOAR
Туре	VxStream Sandbox

Parameter	Value
Address	Address of the integration (in the following format: https://www.hybrid-analysis.com)
Configuration	Specify the following configuration parameters:
	<pre># Integration ID of the proxy integration to use when connecting to # current integration. # If not provided, ATAR will try to use a direct connection. #proxy.id=123 # configure how far (in minutes) into the past this enrichment will look. #cache.reusing.duration=20</pre>
Credential	Credential defined for the integration under the Credentials menu
Trust Invalid SSL Certificates	Select this if Engine's certificate is self-signed or is not recognized by browsers
Require Approval From	Select users from the list who can provide approval before executing actions on this integration
Notify	Select users from the list to notify when SOAR performs an action on this integration



3. Click **Test** to test the integration.

Configuring SOAR Page 587 of 594

4. Click **Save** to complete the integration.

Configuring SOAR Page 588 of 594

Integration Guide for WinRM

Integration Overview

This appendix provides a detailed, step-by-step configuration procedure to enable SOAR to properly work with WinRM.

Configuration On Domain-Controller

- To create a Group Policy object for your domain:
- 1. Navigate to Start > Control Panel.
- 2. In the Control Panel, select Administrative Tools > Group Policy Management.
- From the menu tree, click Domains > [your domain's name].
- 4. Right-click and select Create a GPO in this domain, and Link it here.
- 5. Input WinRM-SOAR.
- 6. Execute the following command:

reg add HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Policies\System /v

LocalAccountTokenFilterPolicy /t REG_DWORD /d 1 /f

- 7. Click OK.
- To edit the new Group Policy object you created:
- 1. Right-click on the new WinRM-SOAR Group Policy Object and select Edit.
- From the menu tree, click Computer Configuration > Policies.
- 3. In the Policies, click Administrative Templates: Policy definitions > Windows Components > Windows Remote Management (WinRM).
- 4. Navigate to WinRM Service.



 $\textbf{Note:} \ \textbf{After editing the Group Policy Object, three WinRM service settings are enabled.}$

- a. To Allow remote server management through WinRM
 - Right-click either Allow automatic configuration of listeners (Windows Server 2010) or Allow remote server management through WinRM (Windows Server 2012)

- ii. Click Edit.
- iii. To allow remote server management through WinRM, select Enabled.
- iv. Enter an asterisk (*) in each field.
- v. Click OK.
- b. To Allow unencrypted traffic through WinRM
 - i. Right-click Allow unecrypted traffic and click Edit.
 - ii. Select Enabled and click OK.

Now the Windows Remote Management is enabled on the Group Policy.

- c. To Enable the Service that goes with it
 - In the Group Policy Management Editor window, click Preferences > Control Panel Settings > Services.
 - ii. Right-click Services and select New > Service.
 - iii. Select Automatic as the startup.
 - iv. Enter WinRM as the service name.
 - v. Select Start service as the service action.
 - vi. Select This account to log in as.
 - vii. Enter NT AUTHORITY\NetworkService as the user and use a space character as the password.
 - viii. Click OK.
- To allow inbound remote administration by updating the firewall rules:

The steps enable the following firewall rules:

- Windows Firewall: Allow inbound remote administration exception
- Windows Firewall: Allow ICMP exception
- In the Group Policy Management Editor, click Computer Configuration > Policies.
- Click Administrative Templates: Policy definitions > Network > Network Connections > Windows Firewall > Domain Profile.
- 3. Right-click Windows Firewall: Allow inbound remote administration exception and click Edit.
- 4. Select Enabled.
- 5. Enter an asterisk (*) into each field and click Ok.

- 6. Right-click Windows Firewall: Allow ICMP exception and click Edit.
- 7. Select Enabled.
- 8. Select Allow inbound echo request and click Ok.
- To create a new inbound firewall rule and update the network list manager for unidentified networks:
- Click Computer Configuration > Windows Settings > Security Settings > Windows Firewall with Advanced Security > Inbound Rules.
- 2. Right-click Inbound Rules and click New Rule.
- 3. Select Predefined.
- 4. Select Windows Remote Management from the list of services.
- 5. Click Next.
- 6. Unselect the entry profile Public and click Next.
- 7. Click Finish.
- 8. Right-click the new rule and click **Properties**.
- 9. Click the Advanced tab and unselect all and select Private.
- 10. Click the Scope tab.
- 11. Check these IP addresses on Remote IP Address and specify IP address of the SOAR machine and click **OK**.
- 12. From the menu tree, click Computer Configuration > Windows Settings > Security Settings > Network List Manager Policies.
- 13. Right-click Unidentified Networks and click Properties.
- 14. Select the Location type to Private and click Ok.

Configuring SOAR

Use the format *username* | Computer name as WinRM credentials. For example, localadmin | DEV-EXCHANGE18.

Configuring Domain-Controller for WinRM HTTPS Transport

- 1. Open the Certificate Authority management console.
- Right-click Certificate Templates and select Manage.
- In the template management console, scroll down and select Web Server template.
- 4. Right-click Web Server Template, select Duplicate Template.

Configuring SOAR Page 591 of 594

- 5. In the Certificate Property Window for the new template, navigate to the General Tab.
- 6. Set Display Name and Template Name to SOARWINRMHTTPS.
 - **Note:** Use the same name without spaces. If there is a space that leads to a bug where the process to enroll a new certificate repeats.
- 7. In the Subject Name tab, select Build from this Active Directory information.
- 8. In the Subject name format select Common Name and select DNS name.
- 9. Click **Security** > specify the **Domain Computers** group for the domain. Allow Read, Enroll and Autoenroll and click **OK**.
- In the Certificate Authority management console, right-click Certificate Templates and select New Template.
- 11. Double-click **SOARWINRMHTTPS** and close the window.
- 12. Navigate to Start > Control Panel.
- 13. Select Administrative Tools and Group Policy Management.
- 14. In the Menu tree, click **Domains** > [your domain's name].
- 15. Create a batch script for starting WinRM HTTPS Listener named **SoarWinRMSSLStartupScript.ps1**.
- 16. Copy and paste the following code into AtarWinRMSSLStartupScript.ps1:

```
Start-Transcript C:\Scripts\transaction.log
$sysinfo = Get-WmiObject -Class Win32_ComputerSystem
$server = "{0}.{1}" -f $sysinfo.Name, $sysinfo.Domain
$LatestThumb = Invoke-Command -ScriptBlock {
Get-ChildItem -Path Cert:\LocalMachine\My |
where {$_.subject -match "CN=$server"}
Sort-Object -Property NotAfter -Descending |
Select-Object -Last 1 -ExpandProperty Thumbprint
} -ErrorAction Stop
#If HTTPS Listener does not exist create Listener with quick config.Else
evaluate
# available certificates ,sort them by expire date , select first
thumbprint
$result=(((Get-ChildItem -Path WSMan:\localhost\Listener).keys) -match
'HTTPS')
if($result.Count -eq 0) {
Set-WSManQuickConfig -UseSSL -Force
} else {
Set-WSManInstance -ResourceURI winrm/config/Listener \
-SelectorSet @{Address="*";Transport="HTTPS"} \
-ValueSet @{CertificateThumbprint=$LatestThumb.Thumbprint[1]}
Restart-Service -Force -Name WinRM
```

```
}
Stop-Transcript
```

- 17. Navigate to Start > Control Panel.
- 18. Select Administrative Tools > Group Policy Management.
- 19. Right-click WinRM-SOAR and click Edit.
- 20. Click Computer Configuration > Policies > Windows Settings > Security Settings > Public Key Policies.
- 21. Double-click Certificate Services Client Auto-Enrollment.
- 22. Set the Configuration Model to Enable.
- 23. Select Renew expired certificates, update pending certificates, and remove revokedcertificates.and Update certificates that use certificate templates.
- 24. Click Ok.
- 25. Click Computer Configuration > Policies > Windows Settings > Scripts.
- 26. Double-click Startup.
- 27. In the PowerShell Scripts, click Add> Browse the file named AtarWinRMSSLStartupScript.ps1. and click OK.

Force Group Policy Update

Use the following PowerShell commands to force a Policy Update as described in the command block:

```
$computers = Get-ADComputer -Filter *
$computers | ForEach-Object -Process {Invoke-GPUpdate -Computer $_.name \
-RandomDelayInMinutes 0 -Force}
```

Additional Notes

The following patch must be applied to the target computer for WinRM to work without an error:

https://support.microsoft.com/en-us/kb/2842230

Support

Contact Information

Phone	A list of phone numbers is available on the Technical Support Page: https://softwaresupport.softwaregrp.com/support-contact-information
Support Web Site	https://softwaresupport.softwaregrp.com/
ArcSight Product Documentation	https://www.microfocus.com/documentation/arcsight/

Send Documentation Feedback

If you have comments about this document, you can <u>contact the documentation team</u> by email. If an email client is configured on this computer, click the link above and an email window opens with the following information in the subject line:

Feedback on Integration Guides (SOAR 3.9 3.9)

Just add your feedback to the email and click send.

If no email client is available, copy the information above to a new message in a web mail client, and send your feedback to MFI-Documentation-Feedback@opentext.com.

We appreciate your feedback!