

QA Center Performance Edition

Installation and Configuration Guide

Release 05.06



Technical support is available from our Customer Support Hotline or via our FrontLine Support Web site.

Customer Support Hotline: 1-800-538-7822

FrontLine Support Web Site: http://frontline.compuware.com

This document and the product referenced in it are subject to the following legends:

Access is limited to authorized users. Use of this product is subject to the terms and conditions of the user's License Agreement with Compuware Corporation.

© 1998-2007 Compuware Corporation. All rights reserved. Unpublished - rights reserved under the Copyright Laws of the United States.

U.S. GOVERNMENT RIGHTS

Use, duplication, or disclosure by the U.S. Government is subject to restrictions as set forth in Compuware Corporation license agreement and as provided in DFARS 227.7202-1(a) and 227.7202-3(a) (1995), DFARS 252.227-7013(c)(1)(ii)(OCT 1988), FAR 12.212(a) (1995), FAR 52.227-19, or FAR 52.227-14 (ALT III), as applicable. Compuware Corporation.

This product contains confidential information and trade secrets of Compuware Corporation. Use, disclosure, or reproduction is prohibited without the prior express written permission of Compuware Corporation.

Compuware, ActiveAnalysis, ActiveData, Interval, QACenter, QADirector, QALoad, QARun, Reconcile, TestPartner, TrackRecord, and WebCheck are trademarks or registered trademarks of Compuware Corporation.

Acrobat[®] Reader copyright © 1987-2007 Adobe Systems Incorporated. All rights reserved. Adobe, Acrobat, and Acrobat Reader are trademarks of Adobe Systems Incorporated.

ICU License - ICU 1.8.1 and later COPYRIGHT AND PERMISSION NOTICE Copyright (c) 1995-2003 International Business Machines Corporation and others All rights reserved. Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, provided that the above copyright notice(s) and this permission notice appear in all copies of the Software and that both the above copyright notice(s) and this permission notice appear in supporting documentation. THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABÍLITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF THIRD PARTY RIGHTS. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR HOLDERS INCLUDED IN THIS NOTICE BE LIABLE FOR ANY CLAIM, OR ANY SPECIAL INDIRECT OR CONSEQUENTIAL DAMAGES, OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE. Except as contained in this notice, the name of a copyright holder shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization of the copyright holder.

All trademarks and registered trademarks mentioned herein are the property of their respective owners.

All other company or product names are trademarks of their respective owners.

US Patent Nos.: Not Applicable.

Doc. CWQLIX560 September 12, 2007

Table of Contents



Introdu	ıctıon

Who Should Read This Guide	5
Related Publications	5
World Wide Web Information	6
Getting Help	7

Chapter 1

Getting Started


Overview of QACenter Performance Edition	9
Installation Types	10
Before Installation	10

Chapter 2

Installing QALoad

Installing Via Tar File	
Chapter 3	
Maintaining the Installation	
Accessing Maintenance Mode	39
Modifying an Installation	40
Repairing an Installation	40
Removing a Product	41

Introduction



The *QAC*enter Performance Edition Installation and Configuration Guide provides information and procedures to install and maintain *QAL*oad.

When installing File-AID/CS, refer to the *File-AID/CS Installation Guide* for installation instructions.

Who Should Read This Guide

This guide is intended for administrators who are installing and configuring *QAC*enter products; it does not contain reference or usage information. You can find that information in your product's online help facility and documentation set.

Compuware assumes that you are familiar with basic Microsoft Windows navigation. If this is not the case, familiarize yourself with the documentation for Microsoft Windows before reading this guide.

Related Publications

The QACenter Performance Edition installation documentation set is comprised of the following:

- ◆ The *QAC*enter Performance Edition Installation and Configuration Guide, which includes system requirements and instructions for installing *QAL*oad.
- The *Distributed License Management License Installation Guide*, which includes instructions for licensing your QACenter product.
- ◆ The *File-AID/CS Installation Guide*, which includes system requirements and instructions for installing File-AID/CS.

All of these books are provided in PDF format only. You can access the online versions of the *QAC*enter Performance Edition Installation and Configuration Guide and the *Distributed License Management License*

Installation Guide from the CD browser (see the instructions that follow) or from Compuware's FrontLine customer support Web site at http://frontline.compuware.com.

Viewing and Printing Online Books

To access these online books:

- 1 Insert the *QAC*enter CD into the CD-ROM drive. If the CD browser does not automatically start, navigate to the CD's root directory and run setup.exe.
- **2** Click Browse QACenter Documentation.
- 3 Select the installation guide that you wish to view. The document opens in Acrobat Reader. (If necessary, Acrobat Reader can be installed from the *QAC*enter CD by clicking **Install 3rd Party Software**, then clicking **Install Adobe Acrobat Reader**.)

Because PDF is based on PostScript, a PostScript printer is the most reliable way to print online books. In most cases, you can also print PDF files to PCL printers. If you cannot print the PDF files to your printer, refer to Adobe's Web site at http://www.adobe.com for troubleshooting information.

World Wide Web Information

To access Compuware Corporation's site on the World Wide Web, point your browser to http://www.compuware.com. The Compuware site provides a variety of product and support information.

FrontLine Support Web Site: You can access online technical support for Compuware products via the FrontLine support Web site. FrontLine provides fast access to critical information about your *QACenter* product. You can read or download documentation, frequently asked questions, and product fixes, or e-mail your questions or comments. To access FrontLine, follow these steps:

- 1 Open a web browser and go to: http://frontline.compuware.com The Welcome to FrontLine page appears.
- 2 On the right side of the page, enter your login ID and password and click **Login**.

Note: If you are a first-time visitor, click **Register** to receive your free password to access FrontLine. After you complete the registration form, your login ID and password will be e-mailed to you and your account will be activated.

3 From the drop-down list in the center of the page, select a product and click Go. You will see the product's FrontLine home page, where you can access documentation, technical information, fixes, and other support items.

Getting Help

At Compuware, we strive to make our products and documentation the best in the industry. Feedback from our customers helps us maintain our quality standards. If you need support services, please obtain the following information before calling Compuware's 24-hour product support hotline:

- The name, release (version), and build number of the *QAC*enter product. This information is displayed when you select the About command from your product's Help menu. The name and release are also on the covers of the product documentation.
- Installation information, including installed options, whether the product uses local or network databases, whether it is installed in the default directories, whether it is a standalone or network installation, and whether it is a client or server installation.
- Environment information, such as the operating system and release on which the product is installed, memory, hardware/network specifications, and the names and releases of other applications that were running.
- The location of the problem in the *QAC*enter product software, and the actions taken before the problem occurred.
- The exact product error message, if any.
- The exact application, licensing, or operating system error messages, if any.
- Your Compuware client, office, or site number, if available

Customer Support



Compuware Corporation One Campus Martius Detroit, MI 48226-5099 1-800-538-7822

http://frontline.compuware.com

Chapter 1

Getting Started



- ◆ Overview of QACenter Performance Edition
- ◆ Installation Types
- Before Installation

Overview of QACenter Performance Edition

QACenter Performance Edition helps organizations conduct realistic, indepth, and repeatable performance testing on applications throughout the enterprise. With a powerful combination of load testing, infrastructure monitoring, and results analysis tools, QACenter Performance Edition helps organizations find and resolve performance problems quickly.

The QACenter Performance Edition suite of automated testing and test management tools includes:

QALoad: Load tests enterprise client/server systems and associated networks. QALoad can stress your system by simulating thousands of users simultaneously performing different operations. It creates and runs test scripts that can simulate application transactions on the system without involving end users or their equipment.

File-AID/CS: A data management tool that saves time and reduces the level of complexity required in preparing and managing data for testing. It provides facilities for easily copying, transforming, creating, comparing, and modifying data; validating test results; and restoring test data to its baseline state. File-AID/CS is an excellent tool for any testing project where ensuring data and application reliability is critical.

In addition to the *QAC*enter Performance Edition suite of products, the *QAC*enter Performance Edition CD includes Adobe Acrobat Reader, Microsoft Internet Explorer, Microsoft Virtual Machine, and Java 2 SDK versions 1.4 and 1.5 installation programs. To install one or more of these products from the *QAC*enter Performance Edition CD, click **Install 3rd**

Party Software, then click on the product installation you would like to perform.

Installation Types

Before you begin, determine the type of installation you need to perform:

Initial Installation: An initial installation is the first-time installation of a product on your computer. See the installation chapter for each product for instructions.

Modify: A modification of the product installation occurs when you add or remove one or more of a product's components, but not all of them. See the maintenance chapter for instructions.

Repair: A repair installation may be necessary due to a corruption of a program or the inadvertent deletion of the product. See the maintenance chapter for instructions.

Remove: A remove or uninstallation removes all the components of a product. See the maintenance chapter for instructions.

Upgrade: Normally, an upgrade to a new release of a product does not require that you uninstall the current release first. If there are special concerns with regard to upgrading a *QAC*enter product, they are explained in the product's installation chapter.

Before Installation

Before installing any QACenter product, you should carefully review the following information.

System Requirements

Review the system requirements to ensure that you meet the prerequisites for the successful installation and operation of the product. System requirements are listed in the Release Notes as well as in each product's installation chapter in this book.

Release Notes

Review the Release Notes for information about new features, technical notes, and known issues that may enhance or impact your product's performance. Release Notes contain recent changes that may not be included in your *QAC*enter product documentation.

Release Notes can be viewed from the *QAC*enter CD or on FrontLine, Compuware's product support web site. The Release Notes on FrontLine are periodically updated as new information becomes available.

To access the Release Notes from the QACenter CD, follow these steps:

- Insert the *QAC*enter CD into the CD-ROM drive. If the CD browser does not start automatically, navigate to the CD's root directory and run setup.exe.
- 2 Click **View QA**Center **Release Notes**. The Release Notes open in your default web browser.
- Read the Release Notes online, or print the document.
- 4 After reading and/or printing the Release Notes, close the document to return to the CD browser.

To access the Release Notes on FrontLine, follow these steps:

- Open a web browser and go to: http://frontline.compuware.com.
 The Welcome to FrontLine page appears.
- 2 On the right side of the page, enter your login ID and password and click Login.

Note: If you are a first-time visitor, click **Register** to receive your free password to access FrontLine. After you complete the registration form, your login ID and password will be e-mailed to you and your account will be activated.

- From the drop-down list in the center of the page, select a product and click **Go**. You will see the product's FrontLine home page.
- 4 On the left side of the product's homepage, select the **Documentation** link. You will see the product's documentation page, which includes links to Release Notes and other documentation types.
- 5 Click the HTML or PDF icons to view documents.

Chapter 2

Installing QALoad



- Planning Your Installation
- System Requirements
- Installing QALoad
- Installing QALoad
- ◆ UNIX Player Installation

Planning Your Installation

QALoad consists of separate, installable components for script recording and editing, load testing and test execution management, virtual user generation, results analysis, server monitoring, and network traffic generation. (In addition, there are components related to specific middleware types.) Not all components are required in every testing situation. The following table describes what each component does, and why and where it should be installed. Please refer to this table to determine which components are appropriate for your load testing requirements. For supported operating systems and minimum system requirements for each component, see "System Requirements" on page 18.

13

After reviewing this table, carefully follow the instructions in "Installing QALoad" on page 25 to ensure that you install only those components that are appropriate for your testing needs.

Table 2-1. QALoad Component Descriptions

Component	Purpose	Where to Install
QALoad Script Development Workbench	Contains the elements necessary for recording, converting, compiling, and modifying test scripts.	Typically installed on the same workstation (Windows) as the QALoad Conductor and QALoad Analyze components and on the workstation that has the appropriate application you're recording transactions from.
QALoad Conductor	Controls the <i>QA</i> Load Players and manages tests. It is the center for application playback.	Must be installed on the same workstation as <i>QA</i> Load Analyze for reporting purposes.
	In addition, the QALoad Conductor is where you check out licenses for virtual users for your load tests. For further information, see "QALoad Concurrent Conductor Licensing" on page 18.	Most users will install QALoad Conductor on the same workstation as the QALoad Script Development Workbench.

Table 2-1. QALoad Component Descriptions

Component	Purpose	Where to Install
QALoad Player	Emulates users by running test scripts that mimic user transactions. QALoad Players are available for a number of operating environments. The QALoad Player is the most performance-sensitive component of QALoad, as it is responsible for creating hundreds or thousands of concurrent virtual users from the same workstation.	If you intend to run large volume load tests, Compuware recommends that you install QALoad Player on powerful and dedicated workstations. No other resource-intensive processes should be installed or running at the same time the QALoad Player is in use for load testing. In addition, although the Server Analysis Agent installs with the Windows QALoad Player, Compuware rec-
		ommends that to make load test management easier, you do not run both the Server Analysis Agent and QALoad Player simultaneously on the same workstation.
<i>QA</i> Load Analyze	The key component for the analysis of statistics measured during the load test. Lets you correlate and report on load testing performance and server utilization statistics gathered during the test.	Typically installed on the same Windows workstation as the <i>QA</i> Load Script Development Workbench.

Table 2-1. QALoad Component Descriptions

Component	Purpose	Where to Install
Server Analysis Agent	Monitors the servers and applications that a load test impacts, for example, web server, application server, database server, and database.	Must be installed with the Windows version of the QALoad Player (for automatic discovery and control). Although the Server Analysis Agent installs with the Windows QALoad Player, Compuware recommends that you do not run virtual users from the same workstations that you are trying to monitor in order to ensure test result accuracy.
NetLoad Server	The NetLoad UDP and TCP servers are required only when using the TCP and UDP options within NetLoad. They are not required for any other middleware options and need only be installed if using NetLoad.	There are no special considerations for where to install the NetLoad servers.

Integration and Monitoring Requirements

Once you install QALoad, you can configure the monitoring function. For information on requirements for integration and remote monitoring, refer to the QALoad *Conductor Online Help* for the *Integration and Monitoring Requirements* topic.

Integrated Compuware Product Support

Vantage Integration Support

The following table shows the Compuware Vantage products supported by *QA*Load. For release support information, refer to the Release Notes for *QA*Load. To identify the release of a product, select **Help>About** from the product's menu bar.

Table 2-2. Compuware Vantage Product Integration

	3 3	
Compuware Vantage Product/ Release	Purpose	Where to Install
ApplicationVantage Agent 10.0 Service Pack 2	Captures network traffic information from a remote machine. The captured data can be used to profile the effect of the network on an application's performance.	Must be installed on the same Windows machine as the QALoad Player. Note: If ApplicationVantage is installed on the QALoad Conductor machine, or if the machine's operating system is Microsoft Windows XP, you must install the Application-Vantage Remote Agent. The ApplicationVantage Agent version must match the version of the Vantage Console installed.
 ServerVantage Agent SVI Monitoring, 9.9 and 10.0. Remote Monitoring, 10.0 only 	Used for Performance Monitoring of servers and applications for SAP, WebLogic, WebSphere, WebSphere MQ, and WMI environments.	Must be installed on the same machine as the QALoad Conductor. The agent should be installed on a non-production machine that does not currently have a ServerVantage agent installed. For specific requirements for each environment, see "Installing QALoad" on page 25.
ClientVantage Agent	Manages end-user application performance and availability. Problems can be diagnosed by powerful fault detection and analysis capabilities as well as resource monitoring.	ClientVantage is not supported in this release.

QALoad Concurrent Conductor Licensing

Required: To use this feature, you must install the License Manager for Windows or UNIX on a license server. Refer to the *Distributed License Management License Installation Guide* guide for instructions on installing the License Manager. For information on checking out virtual user licenses in general, refer to the *QALoad Conductor Online Help Checking out virtual user licenses* topic.

QALoad's concurrent Conductor licensing, also referred to as Bulk Checkout, allows a number of Conductors to share a pool of virtual users. The number of concurrent Conductors is dependent on the license purchased. To determine how many Conductors and virtual users you are licensed for, view your license using the *Compuware License Administration Utility* (LAU). From the **Start** menu, choose

Programs>Compuware>License Administration>License Administration Utility - LAU4. The number of licensed Conductors is the value associated with the <code>QALoad_Conductor</code> string located in the Feature area in the Version column. The number of licensed virtual users is the value associated with the <code>QALoad</code> string.

Tip: You can also view the number of licensed virtual users by choosing Tools>Licensing from the QALoad Conductor menu. On the License Information dialog box, in the Current License Information area, you will see the Total number of Virtual User licenses.

If your license allows a single Conductor only, then the Bulk Checkout feature of QALoad does not apply to you. For more information on how to use the LAU, see the help in the *License Administration Utility*.

System Requirements

This section describes the general requirements for running a complete installation of *QA*Load, as well as requirements for each individual *QA*Load component that may be installed separately, and requirements for the individual middlewares. Review each section to determine which requirements apply to your configuration.

General Windows Installation Requirements

QALoad has the following minimum system requirements:

- Mid-level Pentium 4 PC with 1GB of RAM. RAM requirements may vary by middleware.
- ◆ 500 MB available disk space.
- Microsoft Windows 2000 Service Pack 4, Windows XP Professional Service Pack 2, Windows Vista*, or Windows Server 2003.

Note: Chinese, Japanese, and Korean operating systems only support the WWW middleware.

- Microsoft Internet Explorer 6 Service Pack 1 (SP1) or 7.0*. (See "WWW Requirements" on page 23 for information about support for other browsers.)
- ◆ Adobe Acrobat or Acrobat Reader (provided on the QACenter CD) to view the online books in PDF format.

Administrative Rights

Installing QALoad requires full administrative rights.

Additional Requirements by Component

Tip: *Refer to the

Technical Notes section of

the OALoad Release Notes

for more information

about using WIndows

Vista and IE 7.0.

The following sections detail the system requirements that differ by QALoad component. Requirements also vary by middleware; see "Middleware-Specific Requirements" on page 20.

QALoad Script Development Workbench

 Microsoft Visual Studio 6.0 Service Pack 4 or higher, Visual Studio 2002 .NET (7.0), Visual Studio .NET 2003 (7.1), or Visual Studio .NET 2005 (8.0) for script compilation and script validation.

Note: Refer to the Technical Notes section of the *QA*Load Release Notes for compiler information for the SAP and Citrix middlewares.

Microsoft .NET Framework version 2.0.

QALoad Conductor Requirements

- ◆ TCP/IP communications.
- Microsoft .NET Framework version 2.0.

QALoad Analyze Requirements

 MAPI32-compliant mail program such as Microsoft Outlook (required for use of timing file mailing utility). The dynamic link library cdo.dll must be installed on the machine to use the send utility. CDO is an optional messaging component of Microsoft Outlook. When you view the options for Office or Outlook setup, CDO is listed under the options for Outlook.

QALoad Windows Player Requirements

- ◆ Java 2 Runtime Environment 1.4 or 1.5 (provided on the *QAC*enter CD) for running Java scripts.
- TCP/IP communications.

Middleware-Specific Requirements

In addition, your Windows system may need to meet specific requirements to support the middleware you are testing. For middleware-specific requirements, see the following sections:

- ◆ "Oracle Net8/Net9 Requirements" on page 20
- "ODBC Requirements" on page 20
- ◆ "Uniface Requirements" on page 21
- ◆ "Citrix Requirements" on page 21
- ◆ "SAP Requirements" on page 22
- ◆ "ADO Requirements" on page 22
- "Oracle Forms Server Requirements" on page 22
- ◆ "Java Requirements" on page 22
- "WWW Requirements" on page 23
- "Streaming Media Requirements" on page 23

Note: The Winsock and NetLoad middlewares do not have any additional *QA*Load Windows Player.

Oracle Net8/Net9 Requirements

QALoad supports load testing of Oracle Net8/Net 9 environments when the following requirements are met:

QALoad Script Development Workbench

- Oracle Net8/Net9 client installation for recording.
- ◆ Oracle Call Interface (OCI) development environment for Windows. This is distributed with the Oracle Development Kit as part of the Oracle 8*i* or Oracle 9*i* client installation.

QALoad Player

Oracle Net8/Net9 client installation for playback.

ODBC Requirements

QALoad supports load testing of ODBC environments when the following requirements are met:

QALoad Script Development Workbench

• ODBC 2.0, 2.5, 3.0, or 3.5 client installation.

 Visual C++ or ODBC SDK. Libraries from Visual C++, if installed, are used by default unless ODBC SDK libraries are specified.

QALoad Player

• ODBC 2.0, 2.5, 3.0, or 3.5 client installation.

Supports QALoad Windows Player only.

Uniface Requirements

QALoad supports load testing under Uniface when the following requirements are met:

QALoad Script Development Workbench

- ♦ Microsoft Visual Studio C++ 6.0 Service Pack 4 Compiler
- Development environment of Uniface V8.2.xx, V8.3.xx, or V8.4.01, complete with the 3GL interface.
- Valid Uniface Software Enable Key (SEK).
- On the Windows XP operating system, QALoad EasyScript for Uniface requires Service Pack s603 or later. On Windows 2000, Uniface Service Pack s601 or later is required.

QALoad Player

- Development environment of Uniface V8.2.xx, V8.3.xx, or V8.4.01, complete with the 3GL interface.
- Valid Uniface Software Enable Key (SEK).
- Supports *QA*Load Windows Player only.

Citrix Requirements

QALoad supports load testing under Citrix when the following requirements are met:

QALoad Script Development Workbench

- Citrix ICA client installation version 9.x or 10.
- MetaFrame Presentation Server.
- NET 2.0 Framework.

QALoad Player

- Citrix ICA client installation version 9.x or 10.
- Supports QALoad Windows Player only.
- Mid-level Pentium 4 PC with 1GB of RAM.

Web Interface

- Citrix ICA client installation version 9.x or 10.
- Citrix Web Interface 4.2, 4.5.1*, or 4.6*
- JavaScript set to Limited or None when using Citrix Web Interface 4.6

Note: When running Citrix ICA client 10 against the Web Interface 4.5.1 or 4.6, the server should be set to have a preference for embedded ICA files. It may be necessary to change WebInterface.conf on the server from "LaunchClients=ICA-Local,ICA-Embedded" to LaunchClients=ICA-Embedded,ICA-Local".

SAP Requirements

QALoad supports load testing under SAP when the following requirements are met:

QALoad Script Development Workbench

- ◆ Appropriate SAP client installation version 6.20, 6.40, or 7.10.
- Appropriate SAP server patches installed:
 - ♦ SAP 4.6C server: patch level 32 or later
 - ♦ SAP 4.6D server: patch level 21 or later
 - ♦ SAP 6.10 server: patch level 17 or later

QALoad Player

- Appropriate SAP client installation version 6.20, 6.40, or 7.10 for playback.
- Supports QALoad Windows Player only.
- Mid-level Pentium 4 PC with 1GB of RAM.

ADO Requirements

QALoad supports load testing under ADO when the following requirements are met:

QALoad Script Development Workbench

◆ ADO 2.6, 2.7, or 2.8 for recording or script compilation.

QALoad Player

- ADO 2.6, 2.7, or 2.8 required for script playback.
- Supports QALoad Windows Player only.

Oracle Forms Server Requirements

QALoad supports load testing under Oracle Forms Server when the following requirements are met:

QALoad Script Development Workbench

- ◆ Oracle Forms versions 6*i*, 9*i*, and 10*g*, and Oracle E-Business Suite 12 and 11i running in servlet mode for both SSL and non-SSL.
- Oracle Forms versions *6i* and Oracle E-Business Suite 12 and 11i running in socket mode.

QALoad Player

 Java 2 Runtime Environment 1.5 (provided on the QACenter CD) for SSL scripts or non-SSL scripts.

Note: Compuware recommends you use the Java Client VM.

• Supports QALoad Windows Player only.

Java Requirements

QALoad supports load testing of J2EE components when the following requirements are met:

QALoad Script Development Workbench

◆ Java Development Kit 1.4 or 1.5 required for developing Java scripts.

QALoad Player

◆ Java 2 Runtime Environment 1.4 or 1.5 (provided on the *QAC*enter CD) to run Java scripts.

WWW Requirements

QALoad supports load testing of WWW environments when the following requirements are met:

QALoad Script Development Workbench

- For "Automatically Configure and Start Browser" recording: Internet Explorer 6 SP1 or 7.0.
- For "User Configured and Started Browser or Web Application" recording: Any HTTP application for which a proxy can be set can be used. Use this option to record a non-Internet Explorer browser such as Netscape, Mozilla, Firefox, or Opera.
- Visual Navigator requires Internet Explorer 6 SP1 or 7.0.

QALoad Player

NTLM playback is not supported on UNIX.

Streaming Media Requirements

QALoad supports Streaming Media under WWW when the following requirements are met:

QALoad Script Development Workbench

- For "Automatically Configure and Start Browser" recording: Internet Explorer 6 SP1 or 7.0.
- For "User Configured and Started Browser or Web Application" recording: Any HTTP application for which a proxy can be set can be used. Use this option to record a non-Internet Explorer browser such as Netscape, Mozilla, Firefox, or Opera.

QALoad Player

 RealOne Player Version 2.0 Build 6.0.x or later, or Windows Media Player 9.00.xx.

Note: Streaming Media playback does not work with player versions other than those stated above.

QALoad UNIX Player Requirements

The *QA*Load Player and associated utilities are supported on AIX, Linux and Solaris. Compilers that are 32-bit compatible are required. The following sections contain the requirements for each operating system.

Required: Compuware recommends that you have a user ID set up on the Player system specifically to run the Player software. For example,

set up a user ID (qaload) with a home directory of /usr/qaload or / home/gaload.

UNIX Player Requirements for AIX

- ◆ AIX 5L Version 5.2 or 5.3.
- ◆ 100 MB minimum available disk space.
- ◆ ANSI C compiler for compiling scripts. Compuware requires IBM's VisualAge C and C++ compilers, version 6.0 (patched to level 6.0.0.14). Compuware also supports the GNU GCC & G++ compilers version 3.4.4.
- ◆ Java Runtime Environment 1.4 or 1.5 for running Java scripts.
- ◆ TCP/IP communications.
- ◆ Appropriate client application environment (see "UNIX Player Middleware Requirements" on page 24).

UNIX Player Requirements for Linux

- Red Hat Enterprise Linux AS, Release 3 or 4.
- ◆ 100 MB minimum available disk space.
- ◆ Compuware requires the Linux system-provided GNU GCC & G++ compilers version 3.4.5.
- ♦ Java Runtime Environment 1.4 or 1.5 for running Java scripts.
- ◆ TCP/IP communications.
- ◆ Appropriate client application environment (see "UNIX Player Middleware Requirements" on page 24).

Required: For Release 3 only, the system should be updated to the packages indicated in the Red Hat Advisory: RHBA-2005:661-11. Additional packages required to resolve dependencies also should be applied.

UNIX Player Requirements for Solaris

- Solaris 8, 9, or 10.
- 100 MB minimum available disk space.
- ◆ ANSI C compiler for compiling scripts and Sun Studio 11. Compuware also supports GNU GCC & G++ compilers version 3.4.4.
- Java Runtime Environment 1.4 or 1.5 for running Java scripts.
- ◆ TCP/IP communications.
- ◆ Appropriate client application environment (see "UNIX Player Middleware Requirements" on page 24).

UNIX Player Middleware Requirements

The UNIX system running the QALoad UNIX Player may need to meet specific requirements based upon which middleware you are testing. See the following middleware-specific requirements:

UNIX Player Requirements for Oracle 8

- Oracle OCI development kit for UNIX installed on one of the QALoad Player systems to compile the scripts. The OCI development kit is distributed with Oracle Enterprise Server development libraries and client.
- The WWW and Winsock middlewares do not have any additional *QALoad UNIX Player requirements*.

Installing QALoad

This section explains the installation process for *QALoad*. Please review "System Requirements" on page 18 to ensure that *QALoad* installs and operates properly on your workstation.

Before proceeding with the *QA*Load installation, Compuware recommends that you review the *QA*Load Release Notes, which includes information about new features, technical notes, and known issues. In addition, it documents recent changes that may not be included in your *QA*Load documentation. Please review this information carefully; the Release Notes document is updated as new product information becomes available. To review the Release Notes prior to installation, see "Before Installation" in the "Getting Started" chapter.

Required: Compuware recommends that you exit all non-essential Windows programs before running this setup program. Some Windows programs may interfere with the installation process.

If a previous version of *QA*Load is installed on your computer, or if you have any Beta version installed, Compuware recommends that you back up your data and uninstall *QA*Load before installing the new version. Failure to do so may cause problems.

To perform the installation of QALoad, follow these steps:

- 1 Log on as a user with administrative permissions.
- 2 Insert the *QAC*enter installation CD in the CD-ROM drive. The *QAC*enter CD browser should automatically appear. If it does not, navigate to the root directory and run the setup.exe file.
- 3 Click **Install QA**Center **Products**.
- 4 Click **Install QA**Load. The Welcome dialog box appears.
- 5 Read the welcome screen and click **Next**. The License Agreement dialog box appears.

- 6 Read the license agreement and select I accept the terms in the **license agreement** to accept the terms of the agreement. Click **Next**. The Customer Information dialog box appears.
- Type your name and company in the User Name and Organization fields. Click Next. The Choose Destination Location dialog box appears.
- Select a location for the *QA*Load installation.
 - ♦ By default, *QA*Load installs in the folder x:\Program Files\Compuware\QALoad, where x is the drive where Windows resides on your computer.
 - ♦ To specify a different path, click **Browse** and select an existing folder or type the path name in the **Path** field. Click **OK**.
- 9 Click Next. The Select Features dialog box appears.
- 10 Highlight a component to view a brief description. Select the components you want to install. See Table 2-1 on page 14 for details on each component.
 - ♦ **Script Development Workbench:** Contains all of the elements necessary for recording, converting, compiling, and modifying test scripts. Select the EasyScript component(s) for which you are licensed. Compuware recommends that you do not select components for which you are not licensed because you cannot create test scripts with those components.
 - ♦ **Conductor:** Controls the *QALoad Players* and manages tests. The QALoad Conductor and Analyze must be installed on the same workstation for reporting purposes. QALoad Analyze is automatically selected for you, as well.
 - ♦ **Players:** Emulates users by running test scripts that mimic user transactions. Each supported platform's Player type can be selected separately for installation. The QALoad Player for running Java scripts is automatically installed with the Windows and UNIX Players.
 - ♦ **Analyze:** Allows you to view timing information from the test in table or graph format.
 - ♦ **Server Analysis Agent:** Monitors server, application, or database use during a load test. QALoad Windows Player is automatically selected for you, as well. The QALoad Server Analysis Agent requires that the QALoad Windows Player be installed on the same workstation.

- ApplicationVantage Agent: This option is not available if the ApplicationVantage Agent is already installed, or if the machine's operating system is Microsoft Windows XP. Allows you to capture trace data on Player machines. ApplicationVantage uses this captured data to analyze application performance problems. Note: The ApplicationVantage Agent version must match the version of the Vantage Console Installed.
- NetLoad Server: The NetLoad UDP and TCP server files are application files that enable NetLoad to perform UDP and TCP testing.
- ServerVantage Agent: Must be installed on the same machine as the QALoad Conductor. Used for Performance Monitoring of servers and applications for SAP, WebLogic, WebSphere, Web-Sphere MQ, and WMI.

Make your selection(s) and click **Next**. The Select Program Folder dialog box appears.

- 11 Specify a location for the *QA*Load program shortcuts. You may type a new folder name or select one from the existing folders list. Click **Next**. The Start Copying Files dialog box appears.
- 12 Review the summary of the settings that you specified and click Next to begin copying the program files. The Setup Status dialog box displays the progress of the installation.
- 13 After the installation completes, the Setup Complete dialog box appears. Depending on the circumstances, you may have the following options:
 - ♦ **Display Release Notes:** Choose to review the information in the ReleaseNotes.htm file. This file contains information about new features, technical notes, and known issues that may enhance or have an impact on *QALoad's* performance. Release Notes contain recent changes that may not be included in your *QALoad* product documentation.
 - Register for FrontLine: Choose to review the information on FrontLine technical support site. FrontLine provides fast access to critical information, such as documentation, frequently asked questions, and product fixes. The first time you access FrontLine, you are required to register and obtain a password.
 - Restart Your Computer: You may be prompted to restart your computer. If you are prompted to restart your computer, you may choose to restart it now (recommended) or to restart it later. If

you are migrating from a previous version of QALoad, you must restart before using QALoad.

- **14** Click **Finish** to complete the installation of *QALoad*.
- 15 If you purchased the EasyScript for Secure WWW module to test SSL (Secure Sockets Layer) or HTTPS calls that your browser/server may make, the encryption module is included on the QACenter Installation CD. To install the module:
 - Insert the CD into the CD-ROM drive.
 - **b** Click **Install QACenter Products.**
 - c Click Install SSL.

Required: You must install the SSL License before installing SSL.

Installing QALoad Windows Player

This section explains the installation process for *QAL*oad Windows Player. Please review "System Requirements" on page 18 to ensure that *QAL*oad Windows Player installs and operates properly on your workstation.

Before proceeding with the *QA*Load Windows Player installation, Compuware recommends that you review the *QA*Load Release Notes, which includes information about new features, technical notes, and known issues. In addition, it documents recent changes that may not be included in your *QA*Load documentation. Please review this information carefully; the Release Notes document is updated as new product information becomes available. To review the Release Notes prior to installation, see "Before Installation" in the "Getting Started" chapter.

To perform the installation of *QA*Load Windows Player, follow these steps:

- 1 Log on as a user with administrative permissions.
- 2 Insert the *QAC*enter installation CD in the CD-ROM drive. The *QAC*enter CD browser should automatically appear. If it does not, navigate to the root directory and run the setup.exe file.
- 3 Click **Install QA**Center **Products**.
- 4 Click **Install QA**Load **Windows Player**. The Welcome dialog box appears. Click **Next**.
- Read the welcome screen and click **Next**. The License Agreement dialog box appears.

- 6 Read the license agreement and select I accept the terms in the license agreement to accept the terms of the agreement. Click Next. The Customer Information dialog box appears.
- 7 Type your name and company in the User Name and Organization fields. Click Next. The Destination Folder dialog box appears.
- 8 Select a location for the *QALoad Windows Player installation*.
 - ♦ By default, *QAL*oad Windows Player installs in the folder x:\Program Files\Compuware\QALoad, where x is the drive where Windows resides on your computer.
 - To specify a different path, click Change and select an existing folder, create a new folder, or type the path name in the Folder name field. Click OK.
- 9 Click Next. The Custom Setup dialog box appears. The Server Analysis Agent component is unselected by default.
 - **Server Analysis Agent:** Monitors server, application, or database use during a load test. The *QA*Load Server Analysis Agent requires that the *QA*Load Windows Player be installed on the same workstation. See Table 2-1 on page 14 for more details on the component.
- 10 To install the component, select the drop-down menu to specify the installation of the feature.
 - ♦ Install the Server Analysis Agent on your local hard drive.
 - ♦ Install the Server Analysis Agent and all subfeatures on your local hard drive.

Make your selection and click **Next**. The Select Program Folder dialog box appears.

- 11 Click Install to install QALoad Windows Player.
- **12** Click **Finish** to complete the installation of *QA*Load Windows Player.

Where To Go Next

- The trial license that is supplied with your *QAC*enter product enables you to install the product and run it for a specific time period without first installing a license. During this trial period, you are informed of how much evaluation time remains.
 - At any time during the evaluation period, you can obtain and install a permanent license. When the evaluation period expires, you **must** obtain a license and install it before you can successfully run this product. See the *Distributed License Management License Installation Guide* for instructions on installing a license. To access this online book:

- a Insert the QACenter CD into the CD-ROM drive. If the CD browser does not automatically start, navigate to the CD's root directory and run setup.exe.
- **b** Click Browse QACenter Documentation.
- **c** Select the *Distributed License Management License Installation Guide.*
- If Adobe Acrobat or Acrobat Reader is not installed on your computer, click Install 3rd Party Software, then click Install Adobe Acrobat Reader from QACenter's CD browser. Adobe Acrobat or Acrobat Reader is required to view online books in PDF format.
- To install a QALoad Windows Player on an additional workstation, follow the instructions on the previous pages. However, on the Select Components dialog box, select to install *only* the QALoad Windows Player and deselect all other components.
- ◆ To install a UNIX Player, see "UNIX Player Installation" on page 30.
- If you are migrating from a previous release of QALoad, you must recompile your existing scripts in the Script Development Workbench to use them in this release.
- If you are ready to begin using QALoad, the Getting Started section of the QALoad online help.
- For information about modifying, repairing, or removing your QALoad installation, see Chapter 3, "Maintaining the Installation" on page 39.

UNIX Player Installation

This section explains the procedure for installing a Player on a UNIX system. The necessary UNIX Player software is distributed with your *QA*Load Windows installation. You can choose to install using a tar file or using the vendor-specific package installation mechanism.

Installing Via Tar File

Load the Player Files

To load the appropriate files for QALoad runtime playback onto UNIX, you must FTP the files to the UNIX system and run the installation script. The files are located in the \UNIX\<platform>\directory of your QALoad installation (for example,

c:\Program Files\Compuware\QALoad\UNIX\Solaris).

- 1 FTP, in binary mode, the tar file and installation script file to the desired installation directory, < installation >, on the UNIX system. The installation directory must not contain a previous version of QALoad.
- 2 Log on to the UNIX system.
- 3 On the UNIX system, change directories to *<installDir>*.
- 4 Type chmod 755 QALoadInstall
- 5 Run the installation file by typing ./QALoadInstall and follow the prompts.

Add the QALoad library directory, $\langle installDir \rangle / lib$, to the library path environment variable on your UNIX system. The name of this variable is specific to the operating system. The following table identifies the name of the library path environment variable for the UNIX operating systems that are supported by QALoad:

Table 2-3. Library Path Environment Variables

Operating System	Library Path Name
AIX	LIBPATH
Linux	LD_LIBRARY_PATH
Solaris	LD_LIBRARY_PATH

- 6 If you are replaying EasyScript for Java scripts, make the following changes to the environment on the UNIX system:
 - ♦ AIX: Add the path of libjvm.a to the LIBPATH environment variable.
 - ♦ Linux: Add the paths of libjvm.so and libhpi.so to the LD_LIBRARY_PATH environment variable. You must also add the fully-qualified path of libhpi.so to the LD_PRELOAD environment variable; this entry must end with libhpi.so.
 - ♦ **Solaris**: Add the path of libjvm.so to the **LD_LIBRARY_PATH** environment variable.
- 7 If you are using the Oracle middleware on any platform, add the following path to the appropriate library path environment variable: \$(ORACLE HOME)/lib
- If you purchased the *EasyScript for Secure WWW* module to test SSL (Secure Sockets Layer) or HTTPS calls that your browser/server may

make, the required files are available only from a Windows system where the QALoad SSL module is installed. For more information about installing this module, see step 15 on page 28.

After installing the SSL module on a Windows system, follow these steps:

- a Copy the 'InstallSSL' and 'SSL-<osName>.tar.Z' files from the <windowsInstallDir>\Unix\<platform>\SSL directory on the Windows system to the <installDir> directory on the Unix system.
- **b** In the <installDir> directory on the Unix system, make the installation script executable by typing: chmod +x InstallSSL.
- c In the <installDir> directory on the Unix system, execute the installation script by typing: InstallSSL.
- 9 If you are using the GNU compiler on Solaris or AIX, add the following line to the end of the <installdir>/qalplayer.conf file: CompilerType GNU
- 10 Start the Player Agent by typing ./PlayerAgent.

Required: If you restart the UNIX system, you must start the Player Agent manually by typing ./PlayerAgent in the installation directory.

Installing Via Package

Installing a UNIX Player on AIX

Load the Player Files

To load the appropriate package file for QALoad runtime playback onto AIX, you must either mount the installation CD onto the AIX system or FTP the package files from the installation CD to the UNIX system. Once the package is available on the AIX system, use "smit" to install the software. The package is located in the <CD drive>/cpwr/qaload/aix directory of your QALoad installation CD.

Command Line Installation

To install the UNIX Player on AIX, perform the following steps:

- 1 If using FTP:
 - Use binary mode to copy the package file QACPE.bff.Z to the AIX system.
 - Log on as root.

If using the CD:

- Log on as root.
- Mount the CD onto the AIX system.

- Copy the QACPE.bff.Z package file onto the system.
- 2 Change the directory (cd) to where the package file was placed. Note that "root" must have write permission in this directory.
- 3 Uncompress the package file by running the following command: uncompress QACPE.bff.Z This will expand the compressed package file and create the installable package QACPE.bff.
- 4 From the command prompt, type the following command: smit
- From the System Management screen, select **Software Installation** and **Maintenance** and press **Enter** on the keyboard.
- 6 Select **Install and Update Software** and press **Enter** on the keyboard.
- 7 Select **Install Software** and press **Enter** on the keyboard.
- **8** Type or select the directory where the QACPE.bff file can be found and press **Enter** on the keyboard.
- 9 Press Enter twice. When the installation is complete, the COM-MAND STATUS screen appears.
- 10 Locate the **Result** column and verify that the package installation was successful.
- 11 Add /opt/QALoad/lib to the LIBPATH environment variable.
- **12** If you are replaying *EasyScript for Java* scripts, add the path of lib-jvm.a to the **LIBPATH** environment variable.
- 13 If you are using the Oracle middleware, add the following path to the LIBPATH environment variable:

```
$(ORACLE HOME)/lib
```

- 14 If you purchased the *EasyScript for Secure WWW* module, to test SSL (Secure Sockets Layer) or HTTPS calls that your browser/server may make, the required file is available only from a Windows system where the QALoad SSL module is installed. For more information about installing this module, see step 15 on page 28.
- 15 After installing the SSL module on a Windows system, follow these steps:
 - a Copy the 'QACPE-SSL.bff.Z' file from the <windowsinstallDir/Unix/AIX/SSL directory on the Windows system to the <installDir> directory on the AIX system.
 - **b** In the <installDir> directory on the AIX system, uncompress the package file by running the following command:

uncompress QACPE-SSL.bff.Z

This expands the compressed package file and creates the installable package <code>QACPE-SSL.bff</code>.

- **c** From the command prompt, type the following command: smit
- d From the System Management screen, select **Software Installation and Maintenance** and press **Enter** on the keyboard.
- e Select Install and Update Software and press Enter on the keyboard.
- **f** Select **Install Software** and press **Enter** on the keyboard.
- **g** Type or select the directory where the QACPE-SSL.bff file can be found and press **Enter** on the keyboard.
- h Press Enter twice. When the installation is complete, the COM-MAND STATUS screen appears.
- i Locate the **Result** column and verify that the package installation was successful.
- 16 If you are using the GNU compiler, add the following line to the end of the <installdir>/qalplayer.conf file:

```
CompilerType GNU
```

- 17 Change directory (cd) to /opt/QALoad.
- **18** Start the Player Agent by typing ./PlayerAgent.

Installing a UNIX Player on Linux

Load the Player Files

To load the appropriate files for QALoad runtime playback onto Linux, you must either mount the installation CD onto the Linux system or FTP the package file(s) from the installation CD to the UNIX system. Once the package is available on the Linux system, use "rpm" to install the software. The package is located in the $\langle CD|drive\rangle/cpwr/qaload/linux$ directory of the QALoad installation CD.

Command Line Installation

To install the UNIX Player on Linux, perform the following steps:

- 1 If using FTP:
 - Use binary mode to copy the package file QACPE.rpm to the Linux system.
 - Log on as root.

If using the CD:

- Log on as root.
- Mount the CD onto the Linux system.
- Copy the QACPE.rpm package file onto the system.

- 2 Change directory (cd) to where you copied the package file. Note that "root" must have write permissions in this directory.
- 3 To install the *QA*Load Player to the default directory of /opt/QALoad, execute the following command:

```
rpm -Uvh QACPE.rpm
```

- 4 Add /opt/QALoad/lib to your LD_LIBRARY_PATH environment variable.
- 5 If you are replaying EasyScript for Java scripts, add the paths of <code>libjvm.so</code> and <code>libhpi.so</code> to the LD_LIBRARY_PATH environment variable. You must also add the fully-qualified path of <code>libhpi.so</code> to the LD_PRELOAD environment variable; this entry must end with <code>libhpi.so</code>.
- 6 If you are using the Oracle middleware, add the following path to the LD_LIBRARY_PATH environment variable:

```
$(ORACLE HOME)/lib
```

7 If you purchased the EasyScript for Secure WWW module to test SSL (Secure Sockets Layer) or HTTPS calls that your browser/server may make, the required file is available only from a Windows system where the QALoad SSL module is installed.For more information about installing this module, see step 15 on page 28.

After installing the module on a Windows system, follow these steps:

- a Copy the 'QACPE-SSL.rpm' file from the <windowsInstallDir>/ Unix/Linux/SSL directory on the Windows system to the <installDir> directory on the Linux system.
- **b** To install the QALoad Player to the default directory of /opt/QALoad, execute the following command:

```
rpm -Uvh QACPE-SSL.rpm
```

Required: The encryption package must be installed on the same directory as the QACPE package.

- **8** Change directory (cd) to the directory where QALoad is installed.
- **9** Start the Player Agent by typing ./PlayerAgent.

Installing a UNIX Player on Solaris

Load the Player Files

To load the appropriate package file for *QALoad* runtime playback onto Solaris, you must either mount the installation CD onto the Solaris system or FTP the package file(s) from the installation CD to the UNIX system. Once available on the Solaris system, you can use "pkgadd" to

install the software. The package is located in the *<CD drive*>/cpwr/ gaload/solaris directory of your QALoad installation CD.

Note: To install the vendor-specific package using the graphical installation, refer to the Solaris System Administrator's Guide 3rd Edition.

Command Line Installation

To install the UNIX Player on Solaris, perform the following steps:

- If using FTP:
 - Use binary mode to copy the package file QACPE.tar.Z to the Solaris system.
 - Log on as root.

If using the CD:

- Log on as root.
- Mount the CD onto the Solaris system.
- Copy the QACPE.tar.Z package file onto the system.
- 2 Change directory (cd) to the directory where you copied the package file. Note that "root" must have write permissions in this directory.
- 3 Uncompress the package file by running the following command: uncompress QACPE.tar.Z

This expands the compressed package file and creates the package tar file OACPE.tar.

4 Extract the contents of the tar file by running the following command:

```
tar -xvf OACPE.tar
```

This creates the directory structure required for installation.

5 Execute the following command:

```
pkgadd -d.
```

This displays the package to install and prompts you to select the package.

- Select the QACenter Performance Edition package and press Enter on your keyboard. You are prompted to Enter path to package base **directory**. This is the path where the package is installed. For example, typing /opt installs the package to /opt/QALoad.
- Type the base directory to begin installation.
- 8 When the installation is complete, the package to install selection displays again. Select q to quit.
- Add /<base directory>/QALoad/ to your LD LIBRARY PATH environment variable.

- 10 If you are replaying EasyScript for Java scripts, add the path of libjvm.so to the LD_LIBRARY_PATH environment variable.
- 11 If you are using the Oracle middleware, add the following path to the LD_LIBRARY_PATH environment variable:

```
$(ORACLE_HOME)/lib
```

12 If you purchased the EasyScript for Secure WWW module to test SSL (Secure Sockets Layer) or HTTPS calls that your browser/server may make, the required file is available only from a Windows system where the QALoad SSL module is installed.For more information about installing this module, see step 15 on page 28.

After installing the module on a Windows system, follow these steps:

- a Copy the 'QACPE-SSL.tar.Z' file from the <windowsInstallDir>/Unix/Solaris/SSL directory on the Windows system to the Solaris system.
- **b** Change directory (cd) to the directory where you copied the encryption package file. Note that "root" must have write permissions in this directory.
- **c** Extract the contents of the tar file by running the following command:

```
tar -xvf QACPE-SSL.tar
```

This creates the directory structure required for installation.

d Execute the following command:

```
pkgadd -d .
```

This displays the QACPE-SSL package to be installed and prompts you to select the package.

- e Select the QACenter Performance Edition SSL Libraries package and press Enter on your keyboard. You are prompted to Enter path to package base directory. This is the path where the package is installed. For example, typing /opt installs the package to /opt/QALoad.
- f To begin installation, type the name of the base directory where the main OACenter Performance Edition is installed.
- **g** When the installation is complete, the package to install selection displays again. Select q to quit.
- 13 Change directory (cd) to the installation directory, which is either /opt/QALoad or the

 /opt/QALoad or the

- 14 If you are using the GNU compiler, add the following line to the end of the <installdir>/qalplayer.conf file:

```
CompilerType GNU
```


15 Start the Player Agent by typing ./PlayerAgent

Where to Go Next

To begin using QALoad, refer to the Getting Started section of the QALoad online help.

Chapter 3

Maintaining the Installation



- Accessing Maintenance Mode
- Modifying an Installation
- Repairing an Installation
- Removing a Product

Accessing Maintenance Mode

There are two methods for accessing a *QAC*enter product's maintenance mode: from the *QAC*enter CD or from the Windows Control Panel.

Required: Compuware recommends that you exit all non-essential Windows programs before running this setup program. Some Windows programs may interfere with the installation process.

Accessing Maintenance Mode from the Windows Control Panel

- 1 Click the Windows **Start** button and choose **Settings>Control Panel**. The Control Panel window appears.
- 2 Choose the Add/Remove Programs icon. The Add/Remove Programs dialog box appears. Select the QACenter product to maintain and click Change/Remove.

You are presented with the three maintenance mode options: modify, repair, and remove. For more information about these options, see the appropriate section in this chapter.

Accessing Maintenance Mode from the QACenter CD

1 In the CD-ROM drive, insert the QACenter CD containing the same version of the product that you have installed. The QACenter CD

browser should automatically appear. If it does not, navigate to the root directory and run the setup.exe file.

- 2 Click Install QACenter Products.
- 3 Click **Install** product name (where product name is the name of the product that you want to maintain).

You are presented with three maintenance mode options: modify, repair, and remove.

Modifying an Installation

For products with optional components, you may want to add or remove a component.

Rather than uninstall and re-install the product, you can modify your installation.

Modifying Products With Optional Components

- Access maintenance mode using one of the two methods described at the beginning of this chapter.
- Select the **Modify** option. Click **Next**. The Select Components dialog box appears allowing you to add or remove components.
- 3 Click Next. Setup will add or remove the appropriate components.
- 4 After modifying, you may be prompted to restart your computer. If you are prompted to restart your computer, you may choose to restart it now (recommended) or to restart it later.
- 5 Click **Finish** to complete the maintenance.

Repairing an Installation

There may be times when you will need to repair a damaged QACenter product installation. This could be due to an inadvertent deletion or corruption of the program. To repair your QACenter product, follow these steps:

- Access maintenance mode using one of the two methods described in "Accessing Maintenance Mode" at the beginning of this chapter.
- Select the **Repair** option. Click **Next**. Setup will repair the specified QACenter product.


- 3 After repairing, you may be prompted to restart your computer. If you are prompted to restart your computer, you may choose to restart it now (recommended) or to restart it later.
- 4 Click **Finish** to complete the maintenance.

Removing a Product

If you want to remove a QACenter product from a PC, follow these steps:

- 1 Access maintenance mode using one of two methods described at the beginning of this chapter.
- 2 Select the **Remove** option. Click **Next**. The Confirm File Deletion dialog box appears.
- 3 Click **OK**. Setup will remove the specified *QAC*enter product from your PC. If your product uses a database repository, it will not be deleted.
- 4 After uninstalling, you may be prompted to restart your computer. If you are prompted to restart your computer, you may choose to restart it now (recommended) or to restart it later.
- 5 Click **Finish** to complete the maintenance.

Index



A access methods maintenance 39 ADO requirements 22 AIX 31, 32, 33 UNIX Player Requirements 24 Analyze system requirements 20	requirements 19 components QALoad 14 Compuware technical support FrontLine Web site 6 Compuware World Wide Web sites 6 concurrent Conductor licensing 18 customer support 7
Application Expert 17	
Application Vantage Remote Agent 17	descriptions QACenter products 9
В	
before installing 10 new version 25 QALoad 13 beta version uninstalling (QALoad) 25	FrontLine technical support Web site 6
	G
C	getting started 9
Citrix requirements 21 ClientVantage agent 17, 18 component	н
component	help 7

FrontLine Web site 6	maintenance access methods 39 modify 40 remove 41 repair 40
installation	middleware
planning 13	UNIX Player requirements 24
installation pre-requisites 10	modify
installation types 10	maintenance 40
installing	
modify product components 40	
package (UNIX) 32	
process (QALoad) 25	N
QACenter products prerequisites 9	new version
QALoad 25, 30	before installing 25
repairing a product installation 40	
tar file (UNIX) 30	
types of installations 10	
UNIX Player 30	0
introduction 5	ODBC
	requirements 21
	operating requirements
The second secon	QALoad 18
	Oracle Forms Server
Java	requirements 22
requirements 22	
	P
L	package (UNIX)
licensing	installing 32
QALoad 18	planning
Linux	installation 13
UNIX Player requirements 24	QALoad installation 13
load testing	planning your installation
requirements 13	QALoad 13
	pre-installation 10
	prerequisites for QACenter product installa-
M	tion 9
M	process
Maintaining the Installation 39	installing QALoad 25

Q	load testing 13
QACenter	ODBC 21
FrontLine Web site 6	Oracle Forms Server 22
help 6	SAP 21
technical support 6	Uniface 21
QACenter products	UNIX Player 23
descriptions 9	WWW 23
QALoad	
Analyze, requirements 20	
before installing 13	S
components 14	
concurrent Conductor licensing 18	SAP
Conductor	requirements 21
licensing 18	ServerVantage Agent 17
requirements 19	Solaris
installing 25, 30	UNIX Player requirements 24
operating requirements 18	Streaming Media 23
planning your installation 13	RealOne Player 23
Script Development Workbench, require-	Windows Media Player 23
ments 19	support
system requirements 18	FrontLine Web site 6
upgrading 25	system requirements
Windows Player	AIX on UNIX 24
installing 28	complete Windows 19
requirements 20	Linux on UNIX 24
	QALoad 18
	QALoad Analyze 20
R	QALoad Conductor 19
	Script Development Workbench 19
RealOne Player 23	Solaris on UNIX 24
Remote Agent	
Application Vantage 17	
remove	_
maintenance 41	
repair	tar file (UNIX)
maintenance 40	installing 30
requirements	technical support 7
ADO 22	FrontLine Web site 6
by component 19	types of installation 10
Citrix 21	
Java 22	

```
U
```

```
Uniface
requirements 21
uninstalling
beta version (QALoad) 25
UNIX Player
installing 30
middleware requirements 24
requirements 23
UNIX Player requirements
AIX 24
Linux 24
Solaris 24
upgrading
QALoad 25
```



Vantage 16 Vantage Agent 17



Windows
system requirements 19
Windows Media Player 23
World Wide Web, Compuware sites 6
WWW
requirements 23