



QALoad

Installation and Configuration Guide

Release 5.8

Technical support is available from our Technical Support Hotline or via our FrontLine Support Web site.

Technical Support Hotline:
1-800-538-7822

FrontLine Support Web Site:
<http://frontline.compuware.com>

This document and the product referenced in it are subject to the following legends:

Access is limited to authorized users. Use of this product is subject to the terms and conditions of the user's License Agreement with Compuware Corporation.

© 1998-2008 Compuware Corporation. All rights reserved. Unpublished - rights reserved under the Copyright Laws of the United States.

U.S. GOVERNMENT RIGHTS

Use, duplication, or disclosure by the U.S. Government is subject to restrictions as set forth in Compuware Corporation license agreement and as provided in DFARS 227.7202-1(a) and 227.7202-3(a) (1995), DFARS 252.227-7013(c)(1)(ii)(OCT 1988), FAR 12.212(a) (1995), FAR 52.227-19, or FAR 52.227-14 (ALT III), as applicable. Compuware Corporation.

This product contains confidential information and trade secrets of Compuware Corporation. Use, disclosure, or reproduction is prohibited without the prior express written permission of Compuware Corporation.

Compuware, ActiveAnalysis, ActiveData, Interval, QACenter, QADirector, QALoad, QARun, Reconcile, TestPartner, TrackRecord, and WebCheck are trademarks or registered trademarks of Compuware Corporation.

Acrobat[®] Reader copyright © 1987-2002 Adobe Systems Incorporated. All rights reserved. Adobe, Acrobat, and Acrobat Reader are trademarks of Adobe Systems Incorporated.

This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>)

This product includes software developed by Teodor Danciu (<http://jasperreports.sourceforge.net>)

This product includes software developed by the University of California, Berkeley and its contributors.

All other company or product names are trademarks of their respective owners.

US Patent Nos.: Not Applicable.

Doc. *CWQLIX570*
May 1, 2009

Contents

Introduction	5
Who Should Read This Guide	5
Related Publications	5
World Wide Web Information	6
Getting Help	6
Chapter 1 • Getting Started	9
Overview of QALoad	9
Installation Types	9
Before Installation	9
Chapter 1 • Installing QALoad	11
Planning Your Installation	11
Integration and Monitoring Requirements	12
Integrated Compuware Product Support	13
Vantage Integration Support	13
QALoad Concurrent Conductor Licensing	14
System Requirements	15
General Windows Installation Requirements	15
Additional Requirements by Component	15
Middleware-Specific Requirements	16
QALoad UNIX Player Requirements	19
Installing QALoad	20
UNIX Player Installation	23
Installing Via Tar File	23
Installing Via Package	24
Chapter 1 • Maintaining the Installation	27
Accessing Maintenance Mode	27
Modifying an Installation	27
Repairing an Installation	28
Removing a Product	28
Index	29

Introduction

The *QALoad Installation and Configuration Guide* provides information and procedures to install and maintain QALoad.

Who Should Read This Guide

This guide is intended for administrators who are installing and configuring Quality Solutions products; it does not contain reference or usage information. You can find that information in your product's online help facility and documentation set.

Compuware assumes that you are familiar with basic Microsoft Windows navigation. If this is not the case, familiarize yourself with the documentation for Microsoft Windows before reading this guide.

Related Publications

The QALoad installation documentation set is comprised of the following:

- ◆ The *QALoad Installation and Configuration Guide*, which includes system requirements and instructions for installing QALoad.
- ◆ The *Distributed License Management Licensing Guide*, which includes instructions for licensing your Quality Solutions product.

All of these books are provided in PDF format only. You can access the online versions of the *QALoad Installation and Configuration Guide* and the *Distributed License Management Licensing Guide* from the media browser (see the instructions that follow) or from Compuware's FrontLine customer support Web site at <http://frontline.compuware.com>.

Viewing and Printing Online Books

To access these online books:

- 1 Insert the installation media into the CD-ROM drive. If the CD browser does not automatically start, navigate to the CD's root directory and run **setup.exe**.
- 2 Click **Read the Installation Guide**.
- 3 The document opens in Acrobat Reader. (If necessary, Acrobat Reader can be installed from the installation media by clicking **Install Adobe Reader**.)

Because PDF is based on PostScript, a PostScript printer is the most reliable way to print online books. In most cases, you can also print PDF files to PCL printers. If you cannot print

the PDF files to your printer, refer to Adobe's Web site at <http://www.adobe.com> for troubleshooting information.

World Wide Web Information

To access Compuware Corporation's site on the World Wide Web, point your browser to <http://www.compuware.com>. The Compuware site provides a variety of product and support information.

FrontLine Support Web Site: You can access online technical support for Compuware products via the FrontLine support Web site. FrontLine provides fast access to critical information about your Quality Solutions product. You can read or download documentation, frequently asked questions, and product fixes, or e-mail your questions or comments. To access FrontLine, follow these steps:

- 1 Open a web browser and go to: <http://frontline.compuware.com>. The Welcome to FrontLine page appears.
 - 2 On the right side of the page, enter your login ID and password and click **Login**.
- Note:** If you are a first-time visitor, click **Register** to receive your free password to access FrontLine. After you complete the registration form, your login ID and password will be e-mailed to you and your account will be activated.
- 3 From the drop-down list, select a product. You will see the product's FrontLine home page, where you can access documentation, technical information, fixes, and other support items.

Getting Help

At Compuware, we strive to make our products and documentation the best in the industry. Feedback from our customers helps us maintain our quality standards. If you need support services, please obtain the following information before calling Compuware's 24-hour product support hotline:

- ◆ The name, release (version), and build number of the Quality Solutions product. This information is displayed when you select the About command from your product's Help menu. The name and release are also on the covers of the product documentation.
- ◆ Installation information, including installed options, whether the product uses local or network databases, whether it is installed in the default directories, whether it is a standalone or network installation, and whether it is a client or server installation.
- ◆ Environment information, such as the operating system and release on which the product is installed, memory, hardware/network specifications, and the names and releases of other applications that were running.
- ◆ The location of the problem in the Quality Solutions product software, and the actions taken before the problem occurred.
- ◆ The exact product error message, if any.
- ◆ The exact application, licensing, or operating system error messages, if any.

- ◆ Your Compuware client, office, or site number, if available



Customer Support

Compuware Corporation
One Campus Martius
Detroit, MI 48226-5099
1-800-538-7822

<http://frontline.compuware.com>

Chapter 1

Getting Started

- ◆ [Overview of QALoad](#)
- ◆ [Installation Types](#)
- ◆ [Before Installation](#)

Overview of QALoad

QALoad helps organizations conduct realistic, in-depth, and repeatable performance testing on applications throughout the enterprise. With a powerful combination of load testing, infrastructure monitoring, and results analysis tools, QALoad helps organizations find and resolve performance problems quickly.

QALoad can stress your system by simulating thousands of users simultaneously performing different operations. It creates and runs test scripts that can simulate application transactions on the system without involving end users or their equipment.

Installation Types

Before you begin, determine the type of installation you need to perform:

Initial Installation: An initial installation is the first-time installation of a product on your computer. See the installation chapter for each product for instructions.

Modify: A modification of the product installation occurs when you add or remove one or more of a product's components, but not all of them. See the maintenance chapter for instructions.

Repair: A repair installation may be necessary due to a corruption of a program or the inadvertent deletion of the product. See the maintenance chapter for instructions.

Remove: A remove or uninstallation removes all the components of a product. See the maintenance chapter for instructions.

Upgrade: Normally, an upgrade to a new release of a product does not require that you uninstall the current release first. If there are special concerns with regard to upgrading a Quality Solutions product, they are explained in the product's installation chapter.

Before Installation

Before installing Quality Solutions, you should carefully review the following information.

System Requirements

Review the system requirements to ensure that you meet the prerequisites for the successful installation and operation of the product. System requirements are listed in the Release Notes as well as in each product's installation chapter in this book.

Release Notes

Review the Release Notes for information about new features, technical notes, and known issues that may enhance or impact your product's performance. Release Notes contain recent changes that may not be included in your Quality Solutions product documentation.

Release Notes can be viewed from the installation media or on FrontLine, Compuware's product support web site. The Release Notes on FrontLine are periodically updated as new information becomes available.

To access the Release Notes from the installation media, follow these steps:

- 1 Insert the installation media into the CD-ROM drive. If the CD browser does not start automatically, navigate to the CD's root directory and run **setup.exe**.
- 2 Click **Read the Release Notes**. The Release Notes open in your default web browser.
- 3 Read the Release Notes online, or print the document.
- 4 After reading and/or printing the Release Notes, close the document to return to the CD browser.

To access the Release Notes on FrontLine, follow these steps:

- 1 Open a web browser and go to: <http://frontline.compuware.com>. The Welcome to FrontLine page appears.
 - 2 On the right side of the page, enter your login ID and password and click **Login**.
- Note:** If you are a first-time visitor, click **Register** to receive your free password to access FrontLine. After you complete the registration form, your login ID and password will be e-mailed to you and your account will be activated.
- 3 From the drop-down list, select a product. You will see the product's FrontLine home page.
 - 4 Delect the **Documentation** link. You will see the product's documentation page, which lists all documentation releases.
 - 5 Click the current release number to go to the product's documentation page for that release. This includes links to Release Notes and other documentation types.
 - 6 Click the **HTML** or **PDF** icons to view documents.

Chapter 1

Installing QALoad

- ◆ [Planning Your Installation](#)
- ◆ [Integration and Monitoring Requirements](#)
- ◆ [Integrated Compuware Product Support](#)
- ◆ [System Requirements](#)
- ◆ [Installing QALoad](#)
- ◆ [UNIX Player Installation](#)

Planning Your Installation

QALoad consists of separate, installable components for script recording and editing, load testing and test execution management, virtual user generation, results analysis, server monitoring, and network traffic generation. In addition, there are components related to specific middleware types. Not all components are required in every testing situation. The following table describes what each component does, and why and where it should be installed. Please refer to this table to determine which components are appropriate for your load testing requirements. For supported operating systems and minimum system requirements for each component, see “[System Requirements](#)” on page 15.

After reviewing this table, carefully follow the instructions in “[Installing QALoad](#)” on page 20 to ensure that you install only those components that are appropriate for your testing needs.

Table 1-1. QALoad Component Descriptions

Component	Purpose	Where to Install
QALoad Script Development Workbench	Contains the elements necessary for recording, converting, compiling, and modifying test scripts.	Typically installed on the same workstation (Windows) as the QALoad Conductor and QALoad Analyze components and on the workstation that has the appropriate application you're recording transactions from.

Table 1-1. QALoad Component Descriptions

Component	Purpose	Where to Install
QALoad Conductor	<p>Controls the QALoad Players and manages tests. It is the center for application playback.</p> <p>In addition, the QALoad Conductor is where you check out licenses for virtual users for your load tests. For further information, see “QALoad Concurrent Conductor Licensing” on page 14.</p>	<p>Must be installed on the same workstation as QALoad Analyze for reporting purposes.</p> <p>Most users will install QALoad Conductor on the same workstation as the QALoad Script Development Workbench.</p>
QALoad Player	<p>Emulates users by running test scripts that mimic user transactions. QALoad Players are available for a number of operating environments. The QALoad Player is the most performance-sensitive component of QALoad, as it is responsible for creating hundreds or thousands of concurrent virtual users from the same workstation.</p>	<p>If you intend to run large volume load tests, Compuware recommends that you install QALoad Player on powerful and dedicated workstations. No other resource-intensive processes should be installed or running at the same time the QALoad Player is in use for load testing.</p>
QALoad Analyze	<p>The key component for the analysis of statistics measured during the load test. Lets you correlate and report on load testing performance and server utilization statistics gathered during the test.</p>	<p>Typically installed on the same Windows workstation as the QALoad Script Development Workbench.</p>
ApplicationVantage Agent	<p>See “Vantage Integration Support” on page 13.</p>	
ServerVantage Agent	<p>See “Vantage Integration Support” on page 13.</p>	

Integration and Monitoring Requirements

Once you install QALoad, you can configure the monitoring function. For information on requirements for integration and remote monitoring, refer to the *QALoad Conductor Online Help* for the ***Integration and Monitoring Requirements*** topic.

Integrated Compuware Product Support

Vantage Integration Support

The following table shows the Compuware Vantage products supported by QALoad. For release support information, refer to the Release Notes for QALoad. To identify the release of a product, select **Help>About** from the product's menu bar.

Table 1-2. Compuware Vantage Product Integration

Compuware Vantage Product/Release	Purpose	Where to Install
ApplicationVantage Agent 10.1, 10.2, and 11.0	Captures network traffic information from a remote machine. The captured data can be used to profile the effect of the network on an application's performance.	Must be installed on the same Windows machine as the QALoad Player. Note: If ApplicationVantage is installed on the QALoad Conductor machine, or if the machine's operating system is Microsoft Windows XP, you must install the ApplicationVantage Remote Agent. The ApplicationVantage Agent version must match the version of the Vantage Console installed. For requirements for installing on Microsoft Windows Vista, see "Installing QALoad" on page 20.
ServerVantage Agent <ul style="list-style-type: none"> SVI Monitoring 10.1, 10.2, and 11.0. Remote Monitoring, 10.1 SP1.5 	Used for Performance Monitoring of servers and applications for JVM, OAS, SAP, WebLogic, WebSphere, WebSphere MQ, and WMI environments.	Must be installed on the same machine as the QALoad Conductor. The agent should be installed on a non-production machine that does not currently have a ServerVantage agent installed. For specific requirements for each environment, see "Installing QALoad" on page 20.

Table 1-2. Compuware Vantage Product Integration

Compuware Vantage Product/Release	Purpose	Where to Install
ClientVantage Agent (QALoad is packaged with the current version of ClientVantage at time of release.)	Manages end-user application performance and availability. Problems can be diagnosed by powerful fault detection and analysis capabilities as well as resource monitoring.	For more information on installing ClientVantage, refer to the documentation for ClientVantage.
Vantage Analyzer 10.1 SP1	Used to drill into specific problem transactions to determine bottlenecks in production applications and determine what activities are most time consuming on the server machine.	Must be installed on the same machine as QALoad Analyze.

QALoad Concurrent Conductor Licensing

Required: To use this feature, you must install the License Manager for Windows or UNIX on a license server. Refer to the *Distributed License Management License Installation Guide* guide for instructions on installing the License Manager. For information on checking out virtual user licenses in general, refer to the *QALoad Conductor Online Help* **Checking out virtual user licenses** topic.

QALoad's concurrent Conductor licensing, also referred to as Bulk Checkout, allows a number of Conductors to share a pool of virtual users. The number of concurrent Conductors is dependent on the license purchased. To determine how many Conductors and virtual users you are licensed for, view your license using the *Compuware License Administration Utility* (LAU). From the **Start** menu, choose **All Programs>Compuware>Distributed License Management**. The number of licensed Conductors is the value associated with the `QALoad_Conductor` string located in the **Feature** area in the **Version** column. The number of licensed virtual users is the value associated with the `QALoad` string.

Tip: You can also view the number of licensed virtual users by choosing **Tools>Licensing** from the **QALoad Conductor** menu. On the License Information dialog box, in the **Current License Information** area, you will see the **Total number of Virtual User licenses**.

If your license allows a single Conductor only, then the Bulk Checkout feature of QALoad does not apply to you. For more information on how to use the LAU, see the help in the *License Administration Utility*.

System Requirements

This section describes the general requirements for running a complete installation of QALoad, as well as requirements for each individual QALoad component that may be installed separately, and requirements for the individual middlewares. Review each section to determine which requirements apply to your configuration.

General Windows Installation Requirements

QALoad has the following minimum system requirements:

- ◆ Mid-level Pentium 4 PC with 1GB of RAM. RAM requirements may vary by middleware.
- ◆ 500 MB available disk space.
- ◆ QALoad can be installed on Microsoft Windows XP Professional SP2 and SP3 (32-bit) editions, Windows Server 2003 Standard and Enterprise SP1 and SP2 (32-bit) editions, Windows Vista Business, Enterprise, and Ultimate SP1 and SP2* (32-bit) editions, or Windows Server 2008 Standard and Enterprise SP1 (32-bit) editions

Tip: *Refer to the Technical Notes section of the QALoad Release Notes for more information about using Windows Vista and IE 7.0.

Note:

- ◇ Chinese, Japanese, and Korean operating systems only support the WWW middleware.
- ◇ User Locale affects how some programs format and display numbers, currencies, dates, and time. QALoad only supports native operating systems locales. Switching User Locale to something other than that of the native OS may result in improper functioning of QALoad components.
- ◆ Microsoft Internet Explorer 6 Service Pack 1 (SP1), 7.0*, or 8.0. (See [“WWW Requirements”](#) on page 19 for information about support for other browsers.)
- ◆ Adobe Acrobat or Acrobat Reader (provided on the installation media) to view the online books in PDF format.

Administrative Rights

Installing QALoad requires full administrative rights.

Additional Requirements by Component

The following sections detail the system requirements that differ by QALoad component. Requirements also vary by middleware; see [“Middleware-Specific Requirements”](#) on page 16.

QALoad Script Development Workbench

- ◆ Microsoft Visual Studio .NET 2003 (7.1), Visual Studio .NET 2005 (8.0), or Visual Studio .NET 2008 (9.0) for script compilation and script validation, or
- ◆ Microsoft Visual Studio Express 2008 for WWW script compilation and script validation

Note: Visual Studio Express supports WWW middleware only. In Universal sessions, select WWW only. If you plan to test middleware other than WWW, you must install one of the supported Visual Studio .NET versions.

Note: Refer to the Technical Notes section of the QALoad Release Notes for compiler information for the SAP and Citrix middlewares.

- ◆ Microsoft .NET Framework version 2.0 Service Pack 1.

QALoad Conductor Requirements

- ◆ TCP/IP communications.
- ◆ Microsoft .NET Framework version 2.0 Service Pack 1.

QALoad Analyze Requirements

- ◆ MAPI32-compliant mail program such as Microsoft Outlook (required for use of timing file mailing utility).
- ◆ The dynamic link library **cdo.dll** must be installed on the machine to use the send utility. CDO is an optional messaging component of Microsoft Outlook. When you view the options for Office or Outlook setup, CDO is listed under the options for Outlook.

Note: If you are using Microsoft Office 2007, you must download cdo.dll from the Microsoft website.

- ◆ In order to use the Automated Reports utility, one version of Microsoft Word 97 through 2007 must be installed on the machine.

QALoad Windows Player Requirements

- ◆ Java 2 Runtime Environment 1.5 or 1.6 for running Java scripts.
- ◆ Mid-level Pentium 4 PC with 1GB of RAM.
- ◆ TCP/IP communications.

Middleware-Specific Requirements

In addition, your Windows system may need to meet specific requirements to support the middleware you are testing. For middleware-specific requirements, see the following sections:

- ◆ [“ODBC Requirements”](#) on page 17
- ◆ [“Citrix Requirements”](#) on page 17
- ◆ [“.NET Requirements”](#) on page 17
- ◆ [“TestPartner Requirements”](#) on page 18
- ◆ [“SAP Requirements”](#) on page 18
- ◆ [“Oracle Forms Server Requirements”](#) on page 18
- ◆ [“Java Requirements”](#) on page 18
- ◆ [“WWW Requirements”](#) on page 19
- ◆ [“Streaming Media Requirements”](#) on page 19

QALoad Script Development Workbench

ODBC Requirements

QALoad supports load testing of ODBC environments when the following requirements are met:

QALoad Script Development Workbench

- ◆ ODBC 2.0, 2.5, 3.0, or 3.5 client installation.
- ◆ Visual C++ or ODBC SDK. Libraries from Visual C++, if installed, are used by default unless ODBC SDK libraries are specified.

QALoad Player

- ◆ ODBC 2.0, 2.5, 3.0, or 3.5 client installation.
- ◆ Supports QALoad Windows Player only.

Citrix Requirements

QALoad supports load testing under Citrix when the following requirements are met:

QALoad Script Development Workbench

- ◆ Citrix ICA client installation version 9.x, 10.x, or 11.x.
- ◆ MetaFrame Presentation Server 4.x or XenApp 5.0

QALoad Player

- ◆ Citrix ICA client installation version 9.x, 10.x, or 11.x.
- ◆ Supports QALoad Windows Player only.

Web Interface

- ◆ Citrix ICA client installation version 9.x, 10.x, or 11.x.
- ◆ Citrix Web Interface 4.2, 4.5.1, or 4.6, or 5.0
- ◆ JavaScript set to Limited or None when using Citrix Web Interface 4.6 or 5.0

Note: When running Citrix ICA client 10.x or 11.0 against the Web Interface 4.5.1 or later, the Web Interface site should not be set as a Trusted Site in Internet Explorer security settings, or the server should be set to have a preference for embedded ICA files. It may be necessary to change WebInterface.conf on the server from "LaunchClients=ICA-Local,ICA-Embedded" to LaunchClients=ICA-Embedded,ICA-Local". Also, when performing a QALoad recording in this configuration, an error message may appear on the Web Interface page indicating "An error occurred while making the requested connection." The error should have no effect on the recording and can be ignored.

.NET Requirements

QALoad supports load testing under .NET when the following requirements are met:

QALoad Script Development Workbench

- ◆ Visual Studio 2005 with Microsoft .NET Framework version 2.0 Service Pack 1 or Visual Studio 2008.

QALoad Player

- ◆ Microsoft .NET Framework version 2.0 Service Pack 1.
- ◆ Supports QALoad Windows Player only.

TestPartner Requirements

QALoad Script Development Workbench

- ◆ QALoad supports load testing under TestPartner 6.1 and 6.2.

QALoad Player

- ◆ Supports QALoad Windows Player only.

SAP Requirements

QALoad supports load testing under SAP when the following requirements are met:

QALoad Script Development Workbench

- ◆ Appropriate SAP client installation version 6.20, 6.40, or 7.10.
- ◆ Appropriate SAP server patches installed:
 - ◇ SAP 4.6C server: patch level 32 or later
 - ◇ SAP 4.6D server: patch level 21 or later
 - ◇ SAP 6.10 server: patch level 17 or later

QALoad Player

- ◆ Appropriate SAP client installation version 6.20, 6.40, or 7.10 for playback.
- ◆ Supports QALoad Windows Player only.

Oracle Forms Server Requirements

QALoad supports load testing under Oracle Forms Server when the following requirements are met:

QALoad Script Development Workbench

- ◆ Oracle Forms versions *6i, 9i, and 10g*, and *Oracle E-Business Suite 11i and 12* running in *servlet mode for both SSL and non-SSL*.
- ◆ Oracle Forms versions *6.0, 6i, and Oracle E-Business Suite 11i and 12* running in socket mode.

QALoad Player

- ◆ Java 2 Runtime Environment 1.5 or 1.6.

Note: Compuware recommends you use the Java HotSpot Client VM.

- ◆ Supports QALoad Windows Player only.

Java Requirements

QALoad supports load testing of J2EE components when the following requirements are met:

QALoad Script Development Workbench

- ◆ Java Development Kit 1.5 or 1.6 required for developing Java scripts.

QALoad Player

- ◆ Java 2 Runtime Environment 1.5, or 1.6 to run Java scripts.

WWW Requirements

QALoad supports load testing of WWW environments when the following requirements are met:

QALoad Script Development Workbench

- ◆ For "Automatically Configure and Start Browser" recording: Internet Explorer 6 SP1 or later, 7.0, or 8.0.
- ◆ For "User Configured and Started Browser or Web Application" recording: You can use any HTTP 1.0 or 1.1 application for which a proxy can be set. Use this option to record a non-Internet Explorer browser such as Mozilla, Firefox, or Opera.

QALoad Player

- ◆ NTLM playback is not supported on UNIX.

Streaming Media Requirements

QALoad supports Streaming Media under WWW when the following requirements are met:

QALoad Player

- ◆ RealOne Player Version 10.x or Windows Media Player 9.00.xx.

Note: Windows Media Player is not currently supported on Windows Vista.

QALoad UNIX Player Requirements

The QALoad Player and associated utilities are supported on Linux and Solaris. Compilers that are 32-bit compatible are required. The following sections contain the requirements for each operating system.

Required: Compuware recommends that you have a user ID set up on the Player system specifically to run the Player software. For example, set up a user ID (qaload) with a home directory of /usr/qaload or /home/qaload.

UNIX Player Requirements for Linux

- ◆ Red Hat Enterprise Linux AS Release 4 or RedHat Enterprise Linux Release 5.
- ◆ 100 MB minimum available disk space.
- ◆ Compuware requires the Linux system-provided GNU GCC & G++ version 3.4.5 compiler for RedHat Enterprise Linux AS Version 4 and GNU GCC & G++ version 4.1.1 compiler for RedHat Enterprise Linux Version 5
- ◆ Java 2 Runtime Environment 1.5 or 1.6 for running Java scripts.
- ◆ TCP/IP communications.
- ◆ Appropriate client application environment (see [“UNIX Player Middleware Requirements”](#) on page 20).

UNIX Player Requirements for Solaris

- ◆ Solaris 9 or 10.

- ◆ 100 MB minimum available disk space.
- ◆ ANSI C compiler for compiling scripts and Sun Studio 11. Compuware also supports GNU GCC & G++ compilers version 4.2.1.
- ◆ Java 2 Runtime Environment 1.5 or 1.6 for running Java scripts.
- ◆ TCP/IP communications.
- ◆ Appropriate client application environment (see [“UNIX Player Middleware Requirements”](#) on page 20).

UNIX Player Middleware Requirements

The UNIX system running the QALoad UNIX Player may need to meet specific requirements based upon which middleware you are testing.

Installing QALoad

This section explains the installation process for QALoad. Please review [“System Requirements”](#) on page 15 to ensure that QALoad installs and operates properly on your workstation.

Before proceeding with the QALoad installation, Compuware recommends that you review the QALoad Release Notes, which includes information about new features, technical notes, and known issues. In addition, it documents recent changes that may not be included in your QALoad documentation. Please review this information carefully; the Release Notes document is updated as new product information becomes available. To review the Release Notes prior to installation, see [“Before Installation”](#) in the [“Getting Started”](#) chapter.

Required: Compuware recommends that you exit all non-essential Windows programs before running this setup program. Some Windows programs may interfere with the installation process.

If a previous version of QALoad is installed on your computer, or if you have any Beta version installed, Compuware recommends that you back up your data and uninstall QALoad before installing the new version. Failure to do so may cause problems.

To perform the installation of QALoad, follow these steps:

- 1 Log on as a user with administrative permissions.
- 2 Insert the installation media in the CD-ROM drive. The installation media browser should automatically appear. If it does not, navigate to the root directory and run the `setup.exe` file.
- 3 Click the **Products** tab.
- 4 Click **Install QALoad**. The Welcome dialog box appears.
- 5 Read the welcome screen and click **Next**. The License Agreement dialog box appears.
- 6 Read the license agreement and click **Yes**. The Customer Information dialog box appears.
- 7 Type your name and company in the **User Name** and **Company Name** fields. Click **Next**. The Choose Destination Folder dialog box appears.

- 8 Select a location for the QALoad installation.
 - ◇ By default, QALoad installs in the folder `x:\ProgramFiles\Compuware\QALoad`, where `x` is the drive where Windows resides on your computer.
 - ◇ To specify a different path, click **Browse** and select an existing folder or type the path name in the **Path** field. Click **OK**.
- 9 Click **Next**. The Custom Setup dialog box appears.
- 10 Highlight a component to view a brief description. Select the components you want to install. See [Table 1-1](#) on page 11 for details on each component.
 - ◇ **Script Development Workbench:** Contains all of the elements necessary for recording, converting, compiling, and modifying test scripts. Select the EasyScript component(s) for which you are licensed. Compuware recommends that you do not select components for which you are not licensed because you cannot create test scripts with those components.
 - ◇ **Conductor:** Controls the QALoad Players and manages tests. The QALoad Conductor and Analyze must be installed on the same workstation for reporting purposes. QALoad Analyze is automatically selected for you, as well.
 - ◇ **Players:** Emulates users by running test scripts that mimic user transactions. Each supported platform's Player type can be selected separately for installation. The QALoad Player for running Java scripts is automatically installed with the Windows and UNIX Players.
 - ◇ **Analyze:** Allows you to view timing information from the test in table or graph format.
 - ◇ **ApplicationVantage Agent:** This option is not available if the ApplicationVantage Agent is already installed. Allows you to capture trace data on Player machines. ApplicationVantage uses this captured data to analyze application performance problems. **Note:** The ApplicationVantage Agent version must match the version of the Vantage Console installed.
 - ◇ **ServerVantage Agent:** Must be installed on the same machine as the QALoad Conductor. Used for Performance Monitoring of servers and applications for JVM, OAS, SAP, WebLogic, WebSphere, WebSphere MQ, and WMI.

Make your selection(s) and click **Next** to display the Start Copying Files dialog box with the current settings you selected.

- 11 Review the summary of the settings that you specified.
- 12 Click **Next** to begin copying the program files. The Setup Status dialog box displays the progress of the installation.

Note: If you selected ApplicationVantage Agent and your operating system is Windows Vista, a Windows security dialog box appears during file transfer: "Would you like to install this device software?" Click **Install**.

- 13 After the installation completes, the Setup Complete dialog box appears. Depending on the circumstances, you may have the following options:

- ◇ **Display Release Notes:** Choose to review the information in the ReleaseNotesQL.htm file. This file contains information about new features, technical notes, and known issues that may enhance or have an impact on QALoad's performance. Release Notes contain recent changes that may not be included in your QALoad product documentation.
- ◇ **Register for FrontLine:** Choose to review the information on FrontLine technical support site. FrontLine provides fast access to critical information, such as documentation, frequently asked questions, and product fixes. The first time you access FrontLine, you are required to register and obtain a password.
- ◇ **Restart Your Computer:** You may be prompted to restart your computer. If you are prompted to restart your computer, you may choose to restart it now (recommended) or to restart it later. If you are migrating from a previous version of QALoad, you must restart before using QALoad.

14 Click **Finish** to complete the installation of QALoad.

Where To Go Next

- ◆ The trial license that is supplied with your Quality Solutions product enables you to install the product and run it for a specific time period without first installing a license. During this trial period, you are informed of how much evaluation time remains.

At any time during the evaluation period, you can obtain and install a permanent license. When the evaluation period expires, you **must** obtain a license and install it before you can successfully run this product. See the *Distributed License Management License Installation Guide* for instructions on installing a license. To access this online book:

- a Insert the installation media into the CD-ROM drive. If the CD browser does not automatically start, navigate to the CD's root directory and run `setup.exe`.
- b Select the **License** tab, then click **Read the installation guide**.
- ◆ If Adobe Acrobat or Acrobat Reader is not installed on your computer, click **Install Adobe Reader** from the installation media. Adobe Acrobat or Acrobat Reader is required to view online books in PDF format.
- ◆ To install a QALoad Windows Player on an additional workstation, follow the instructions on the previous pages. However, on the Select Components dialog box, select to install **only** the QALoad Windows Player and deselect all other components.
- ◆ To install a UNIX Player, see "[UNIX Player Installation](#)" on page 23.
- ◆ If you are migrating from a previous release of QALoad, you must re-compile your existing scripts in the Script Development Workbench to use them in this release.
- ◆ If you are ready to begin using QALoad, go to the Getting Started section of the QALoad online help.
- ◆ For information about modifying, repairing, or removing your QALoad installation, see [Chapter 1, "Maintaining the Installation"](#) on page 27.

UNIX Player Installation

This section explains the procedure for installing a Player on a UNIX system. The necessary UNIX Player software is distributed with your QALoad Windows installation. You can choose to install using a tar file or using the vendor-specific package installation mechanism.

Installing Via Tar File

Load the Player Files

To load the appropriate files for QALoad runtime playback onto UNIX, you must FTP the files to the UNIX system and run the installation script. The files are located in the `\Unix\<platform>` directory of your QALoad installation (for example,

```
c:\Program Files\Compuware\QALoad\Unix\Solaris).
```

- 1 FTP, in binary mode, the tar file and installation script file to the desired installation directory, **<installDir>**, on the UNIX system. The installation directory must not contain a previous version of QALoad.
- 2 Log on to the UNIX system.
- 3 On the UNIX system, change directories to **<installDir>**.
- 4 Type `chmod 755 QALoadInstall`
- 5 Run the installation file by typing `./QALoadInstall` and follow the prompts.

Add the QALoad library directory, **<installDir>/lib**, to the library path environment variable on your UNIX system. The name of this variable is specific to the operating system. The following table identifies the name of the library path environment variable for the UNIX operating systems that are supported by QALoad:

Table 1-3. Library Path Environment Variables

Operating System	Library Path Name
Linux	LD_LIBRARY_PATH
Solaris	LD_LIBRARY_PATH

- 6 If you are replaying EasyScript for Java scripts, make the following changes to the environment on the UNIX system:
 - ◇ **Linux:** Add the paths of `libjvm.so` and `libhpi.so` to the **LD_LIBRARY_PATH** environment variable. You must also add the fully-qualified path of `libhpi.so` to the **LD_PRELOAD** environment variable; this entry must end with `libhpi.so`.
 - ◇ **Solaris:** Add the path of `libjvm.so` to the **LD_LIBRARY_PATH** environment variable.

- 7 If you are using the GNU compiler on Solaris, add the following line to the end of the `<installdir>/qalplayer.conf` file:
`CompilerType GNU`
- 8 Start the Player Agent by typing `./PlayerAgent`.

Required: If you restart the UNIX system, you must start the Player Agent manually by typing `./PlayerAgent` in the installation directory.

Installing Via Package

Installing a UNIX Player on Linux

Load the Player Files

To load the appropriate files for QALoad runtime playback onto Linux, you must either mount the installation media onto the Linux system or FTP the package file(s) from the installation media to the UNIX system. Once the package is available on the Linux system, use “rpm” to install the software. The package is located in the `<CDdrive>/qalloadsetup/qalload/linux` directory of the QALoad installation media.

Command Line Installation

To install the UNIX Player on Linux, perform the following steps:

- 1 If using FTP:
 - Use binary mode to copy the package file `QACPE.rpm` to the Linux system.
 - Log on as `root`.

If using the installation media:

 - Log on as `root`.
 - Mount the installation media onto the Linux system.
 - Copy the `QACPE.rpm` package file onto the system.
- 2 Change directory (`cd`) to where you copied the package file. Note that “root” must have write permissions in this directory.
- 3 To install the QALoad Player to the default directory of `/opt/QALoad`, execute the following command:


```
rpm -Uvh QACPE.rpm
```
- 4 Add `/opt/QALoad/lib` to your **LD_LIBRARY_PATH** environment variable.
- 5 If you are replaying EasyScript for Java scripts, add the paths of `libjvm.so` and `libhpi.so` to the **LD_LIBRARY_PATH** environment variable. You must also add the fully-qualified path of `libhpi.so` to the **LD_PRELOAD** environment variable; this entry must end with `libhpi.so`.

- 6 Change directory (cd) to the directory where QALoad is installed.
- 7 Start the Player Agent by typing `./PlayerAgent`.

Installing a UNIX Player on Solaris

Load the Player Files

To load the appropriate package file for QALoad runtime playback onto Solaris, you must either mount the installation media onto the Solaris system or FTP the package file(s) from the installation media to the UNIX system. Once available on the Solaris system, you can use “`pkgadd`” to install the software. The package is located in the `<CD drive>/qaload/setup/qaload/solaris` directory of your QALoad installation media.

Note: To install the vendor-specific package using the graphical installation, refer to the *Solaris System Administrator's Guide 3rd Edition*.

Command Line Installation

To install the UNIX Player on Solaris, perform the following steps:

1 If using FTP:

- Use binary mode to copy the package file `QACPE.tar.Z` to the Solaris system.
- Log on as `root`.

If using the installation media:

- Log on as `root`.
- Mount the installation media onto the Solaris system.
- Copy the `QACPE.tar.Z` package file onto the system.

2 Change directory (cd) to the directory where you copied the package file. Note that “`root`” must have write permissions in this directory.

3 Uncompress the package file by running the following command:

```
uncompress QACPE.tar.Z
```

This expands the compressed package file and creates the package tar file `QACPE.tar`.

4 Extract the contents of the tar file by running the following command:

```
tar -xvf QACPE.tar
```

This creates the directory structure required for installation.

5 Execute the following command:

```
pkgadd -d
```

This displays the package to install and prompts you to select the package.

- 6 Select the package and press **Enter** on your keyboard. You are prompted to **Enter path to package base directory**. This is the path where the package is installed. For example, typing `/opt` installs the package to `/opt/QALoad`.
- 7 Type the base directory to begin installation.
- 8 When the installation is complete, the package to install selection displays again. Select **q** to quit.
- 9 Add `<base directory>/QALoad/` to your `LD_LIBRARY_PATH` environment variable.
- 10 If you are replaying EasyScript for Java scripts, add the path of `libjvm.so` to the `LD_LIBRARY_PATH` environment variable.
- 11 Change directory (`cd`) to the installation directory, which is either `/opt/QALoad` or the `<base directory>` you selected.
- 12 If you are using the GNU compiler, add the following line to the end of the `<installdir>/qalplayer.conf` file:
`CompilerType GNU`
- 13 Start the Player Agent by typing `./PlayerAgent`

Where to Go Next

To begin using QALoad, refer to the Getting Started section of the QALoad online help.

Chapter 1

Maintaining the Installation

- ◆ [Accessing Maintenance Mode](#)
- ◆ [Modifying an Installation](#)
- ◆ [Repairing an Installation](#)
- ◆ [Removing a Product](#)

Accessing Maintenance Mode

There are two methods for accessing a Quality Solutions product's maintenance mode: from the installation media or from the Windows Control Panel.

Required: Compuware recommends that you exit all non-essential Windows programs before running this setup program. Some Windows programs may interfere with the installation process.

Accessing Maintenance Mode from the Windows Control Panel

- 1 Click the Windows **Start** button and choose **Settings>Control Panel**. The Control Panel window appears.
- 2 Choose the **Add/Remove Programs** icon. The Add/Remove Programs dialog box appears. Select the Quality Solutions product to maintain and click **Change/Remove**.

You are presented with the three maintenance mode options: modify, repair, and remove. For more information about these options, see the appropriate section in this chapter.

Accessing Maintenance Mode from the Installation Media

- 1 In the CD-ROM drive, insert the installation media containing the same version of the product that you have installed. The installation media browser should automatically appear. If it does not, navigate to the root directory and run the **setup.exe** file.
- 2 Click the **Products** tab, then click **Install QALoad**.

You are presented with three maintenance mode options: modify, repair, and remove.

Modifying an Installation

For products with optional components, you may want to add or remove a component.

Rather than uninstall and re-install the product, you can modify your installation.

Modifying Products With Optional Components

- 1 Access maintenance mode using one of the two methods described at the beginning of this chapter.
- 2 Select the **Modify** option. Click **Next**. The Select Components dialog box appears allowing you to add or remove components.
- 3 Click **Next**. Setup will add or remove the appropriate components.
- 4 After modifying, you may be prompted to restart your computer. If you are prompted to restart your computer, you may choose to restart it now (recommended) or to restart it later.
- 5 Click **Finish** to complete the maintenance.

Repairing an Installation

There may be times when you will need to repair a damaged Quality Solutions product installation. This could be due to an inadvertent deletion or corruption of the program. To repair your Quality Solutions product, follow these steps:

- 1 Access maintenance mode using one of the two methods described in “Accessing Maintenance Mode” at the beginning of this chapter.
- 2 Select the **Repair** option. Click **Next**. Setup will repair the specified Quality Solutions product.
- 3 After repairing, you may be prompted to restart your computer. If you are prompted to restart your computer, you may choose to restart it now (recommended) or to restart it later.
- 4 Click **Finish** to complete the maintenance.

Removing a Product

If you want to remove a Quality Solutions product from a PC, follow these steps:

- 1 Access maintenance mode using one of two methods described at the beginning of this chapter.
- 2 Select the **Remove** option. Click **Next**. The Confirm File Deletion dialog box appears.
- 3 Click **OK**. Setup will remove the specified Quality Solutions product from your PC. If your product uses a database repository, it will not be deleted.
- 4 After uninstalling, you may be prompted to restart your computer. If you are prompted to restart your computer, you may choose to restart it now (recommended) or to restart it later.
- 5 Click **Finish** to complete the maintenance.

Index

Symbols

.NET [17](#)

A

access methods

 maintenance [27](#)

Analyze

 system requirements [16](#)

Application Vantage

 Remote Agent [13](#)

B

before installing [9](#)

 new version [20](#)

 QALoad [11](#)

beta version

 uninstalling (QALoad) [20](#)

C

Citrix

 requirements [17](#)

ClientVantage agent [14](#)

component

 requirements [15](#)

components

 QALoad [11](#)

Compuware technical support

 FrontLine Web site [6](#)

Compuware World Wide Web sites [6](#)

concurrent Conductor licensing [14](#)

customer support [6](#)

D

description

 QALoad [9](#)

F

FrontLine technical support

 Web site [6](#)

G

getting started [9](#)

H

help [6](#)

 FrontLine Web site [6](#)

I

installation

 planning [11](#)

installation pre-requisites [9](#)

installation types [9](#)

installing

 modify product components [27](#)

 package (UNIX) [24](#)

 process (QALoad) [20](#)

 QACenter products prerequisites [9](#)

 QALoad [20](#), [23](#)

 repairing a product installation [28](#)

 tar file (UNIX) [23](#)

 types of installations [9](#)

 UNIX Player [23](#)

introduction [5](#)

J

Java
 requirements 18

L

licensing
 QALoad 14
 Linux
 UNIX Player requirements 19
 load testing
 requirements 11

M

Maintaining the Installation 27
 maintenance
 access methods 27
 modify 27
 remove 28
 repair 28
 middleware
 UNIX Player requirements 20
 modify
 maintenance 27

N

new version
 before installing 20

O

ODBC
 requirements 17
 operating requirements
 QALoad 15
 Oracle Forms Server
 requirements 18

P

package (UNIX)
 installing 24
 planning

installation 11
 QALoad installation 11
 planning your installation
 QALoad 11
 pre-installation 9
 prerequisites for QACenter product
 installation 9
 process
 installing QALoad 20

Q

QALoad
 Analyze, requirements 16
 before installing 11
 components 11
 concurrent Conductor licensing 14
 Conductor
 licensing 14
 requirements 16
 FrontLine Web site 6
 help 6
 installing 20, 23
 operating requirements 15
 planning your installation 11
 Script Development Workbench,
 requirements 15
 system requirements 15
 technical support 6
 upgrading 20
 Windows Player
 requirements 16
 QALoad product
 description 9

R

RealOne Player 19
 Remote Agent
 Application Vantage 13
 remove
 maintenance 28
 repair
 maintenance 28
 requirements
 by component 15
 Citrix 17
 Java 18
 load testing 11

ODBC [17](#)
 Oracle Forms Server [18](#)
 SAP [18](#)
 UNIX Player [19](#)
 WWW [19](#)

S

SAP
 requirements [18](#)
 ServerVantage Agent [13](#)
 Solaris
 UNIX Player requirements [19](#)
 SSL [18](#)
 Streaming Media [19](#)
 RealOne Player [19](#)
 Windows Media Player [19](#)
 support
 FrontLine Web site [6](#)
 system requirements
 complete Windows [15](#)
 Linux on UNIX [19](#)
 QALoad [15](#)
 QALoad Analyze [16](#)
 QALoad Conductor [16](#)
 Script Development Workbench [15](#)
 Solaris on UNIX [19](#)

T

tar file (UNIX)
 installing [23](#)
 technical support [6](#)
 FrontLine Web site [6](#)
 TestPartner [18](#)
 types of installation [9](#)

U

uninstalling
 beta version (QALoad) [20](#)
 UNIX Player
 installing [23](#)
 middleware requirements [20](#)
 requirements [19](#)
 UNIX Player requirements
 Linux [19](#)
 Solaris [19](#)

upgrading
 QALoad [20](#)

V

Vantage [13](#)
 Vantage Agent [13](#)

W

Windows
 system requirements [15](#)
 Windows Media Player [19](#)
 World Wide Web, Compuware sites [6](#)
 WWW
 requirements [19](#)

