



SERENA[®] **DIMENSIONS[®] RM 12.4.1**

RM Browser User's Guide

Serena Proprietary and Confidential Information

Copyright © 2001–2016 Serena Software, Inc. All rights reserved.

This document, as well as the software described in it, is furnished under license and may be used or copied only in accordance with the terms of such license. Except as permitted by such license, no part of this publication may be reproduced, photocopied, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, recording, or otherwise, without the prior written permission of Serena. Any reproduction of such software product user documentation, regardless of whether the documentation is reproduced in whole or in part, must be accompanied by this copyright statement in its entirety, without modification.

This document contains proprietary and confidential information, and no reproduction or dissemination of any information contained herein is allowed without the express permission of Serena Software.

The content of this document is furnished for informational use only, is subject to change without notice, and should not be construed as a commitment by Serena. Serena assumes no responsibility or liability for any errors or inaccuracies that may appear in this document.

Trademarks

Serena, TeamTrack, StarTool, PVCS, Comparex, Dimensions, Prototype Composer, Mariner and ChangeMan are registered trademarks of Serena Software, Inc. The Serena logo, Version Manager and Mover are trademarks of Serena Software, Inc. All other products or company names are used for identification purposes only, and may be trademarks of their respective owners.

U.S. Government Rights

Any Software product acquired by Licensee under this Agreement for or on behalf of the U.S. Government, its agencies and instrumentalities is "commercial software" as defined by the FAR. Use, duplication, and disclosure by the U.S. Government is subject to the restrictions set forth in the license under which the Software was acquired. The manufacturer is Serena Software, Inc., 1850 Gateway Drive, 4th Floor, San Mateo California, 94404-4061.

Publication date: September 2016

Table of Contents

	Preface	11
	Contacting Technical Support	11
<i>Chapter 1</i>	RM Browser Basics	13
	Main Pages of the RM Browser Interface	14
	General Navigation and Controls in RM Browser	15
	Welcome Menu	15
	Menu Bar	16
	Project Bread Crumb	16
	Categories Pane	17
	Actions Pane	18
	Attribute Types	19
	Editable Grid, Grid, and Form Views	20
	Editable Grid View	21
	Grid View	22
	Form View	23
	Selecting Multiple Requirements	23
	Common Dialog Controls	24
	Category Drop-Down List	24
	Attributes to Display List	25
	Sorting Order List	25
	HTML Text Formatting Toolbar	26
	Attribute Constraints Tab	28
	Relationship Constraints Tab	31
	Display Options Tab	34
	What Can RM Browser Do?	37
	Logging In	38
	Switching to Another Project	39
	Changing Your Password	40
	Logging Out	40
	Getting Help	41
	Enabling and Disabling E-Mail Notifications	41
	Viewing Version, System, and Contact Information	42
	Demonstration Projects	42
	The QLARIUS_RM Project	42
	The RMDEMO Project	43
	Using Spell Check in RM Browser	43
	Configuring Internet Explorer	44
	Configuring Firefox	44
	Configuring Chrome	45
	Limitations of the RM Browser Interface	46

Chapter 2

Configuring User Settings and Project Settings 49

User Settings Versus Project Settings. 50

Configuring User Settings and Project Settings 50

 General Settings 50

 Quick Search Settings 53

 Document Settings 54

 Report Settings 55

 Link Browser Settings 56

 Split View Settings 56

Customizing My Work Page 57

Chapter 3

Working with the Home View 59

About the Home View. 60

Dashboard Tab 60

 Using Dashboards 61

 Using Dashboard Widgets. 62

 Creating a Dashboard 62

 Adding a Standard Report to the Dashboard. 64

 Adding a Graphical Report to the Dashboard 64

 Using Reports with Runtime Parameters. 65

 Adding a Website to the Dashboard. 65

 Copying a Dashboard. 66

 Renaming a Dashboard 66

 Deleting a Dashboard 66

Documents Tab 67

Reports tab. 67

Collections Tab 68

Baselines Tab 69

Chapter 4

Working with Requirements 71

Requirement Basics 72

 Finding Requirements with Quick Search 72

 Printing Requirements 76

 Explaining Update and Delete Functions. 80

 Viewing Information about a Class 81

 About Requirement Versions. 81

 About Requirement Locks 81

 Workflows 82

 Copying the URL of a Requirement to the Clipboard. 84

Working with Requirements and Change Requests. 85

 Creating a New Requirement 85

 Proposing a New Requirement 87

 Editing a Requirement 88

 Copying a Requirement 90

 Expanding a Requirement 90

 Deleting a Requirement 90

 Undeleting a Requirement 91

 Removing a Requirement Version 91

Printing a Requirement	91
Viewing the Requirements in a Category, Document, Report, Collection, or Baseline	91
Submitting a Change Request	92
Reviewing a Change Request/Proposed Requirement	93
Viewing Requirement History	94
Viewing History Differences	95
Changing the Attributes in the History Section	97
Changing Requirement Versions in Documents	97
Using Pedigree View	98
Merging Requirement Changes	100
Merge Status	102
Viewing Prior Versions of the Requirement	102
Merging Changes	103
Working with Containers	103
Inherited Containers	105
Container Properties	105
Adding Requirements to an Existing Collection	106
Working with Links	106
Link Properties	112
Suspect Links	112
Inherited Links	114
Using Link Browser	115
Working with Group Attributes	118
Working with File Attachments	120
Polling	121
Creating a Poll	121
Modifying a Poll	123
Closing a Poll	123
Casting a Vote	124
Viewing Polling Results	124
Adding Built-In Queries to Your My Work Page	125
Participating in Discussions	125
Adding a Comment from the Menu Bar	125
Adding a Comment from a Discussion	125
Changing the Discussion View	126
Chapter 5 Working with Documents	127
About Documents	128
Navigation and Controls of the Document Work Page	128
Navigation Pane	129
Detail Pane	130
Printing from the Detail Pane	133
Formatting Documents	133
Formatting Chapters	136
Creating a New Document	137
Opening a Document to the Document Work Page	139
Save a Copy of a Document Under a New Name	139

Editing Document Attributes	140
Change which Requirement Version Is Included in a Document	141
Deleting a Document	141
Deleting a Requirement from a Document	142
Creating a Snapshot of a Document	142
Working with Snapshots of an Open Document	143
Working with Snapshots of a Closed Document	143
Comparing Documents and Snapshots	144
Publish as a Microsoft Word Document	146
Publish as an Adobe PDF Document	148
Specifying Document Properties	149
Restricting Requirement Classes in a Document	151
Document Dependencies	151
Creating a Chapter	151
Editing a Chapter	153
Deleting a Chapter	154
Moving Chapters and Requirements	154
Adding Requirements to a Document	155
Assigning an ECP to a Document	156
Finding and Replacing Character Strings	157
Working with Limited Permissions	159
Merging Document Changes	160
Merge Status	161
Viewing Prior Versions of the Document	161
Merging Changes	162
Merging Chapter Changes	162
Merge Status	164
Viewing Prior Versions of the Chapter	164
Merging Changes	164
Copying the URL of a Document to the Clipboard	165
Moving a Document or Snapshot to a different Category	166

Chapter 6

Working with Reports	167
Running Reports	168
Editing a Report	168
Creating a Class Report	170
Creating a Relationship Report	172
Creating a Traceability Report	173
Working in the Traceability Work Page	175
Understanding the Traceability Tree	176
Customizing the Traceability Tree	177
Creating a Graphical Report	177
Moving and Copying Reports to a Different Category	180
Renaming Reports	181
Deleting Reports	181
Copying the URL of a Report to the Clipboard	182

<i>Chapter 7</i>	Managing Containers and Collections	185
	About Containers	186
	Types of Containers	186
	Deleting a Container	186
	Updating Container Properties	186
	Moving Containers to a Different Category	187
	Comparing Containers	188
	Refreshing the Contents of a Container	188
	Copying the URL of a Container to the Clipboard	188
	About Collections	189
	Opening a Collection to the Collection Work Page	190
	Managing Requirements in a Collection	190
	Creating a New Collection	191
	Baselining a Collection	192
<i>Chapter 8</i>	Importing Requirements	195
	Importing Requirements from Microsoft Word Documents	196
	Should I Use RM Browser or RM Import?	196
	Formatting Requirements for Import	196
	Formatting an Entire Word Document for Import	198
	Importing a Word File	199
	Category Import Formats	200
	Date Import Formats	200
	Importing Requirements from an XML File	200
	Category Import Formats	202
	Date Import Formats	202
	Importing Requirements from a CSV File	202
	Category Import Formats	206
	Date Import Formats	207
	Importing Test Case and Test Run Requirements	207
	Importing Requirements from a ReqIF File	208
	Importing Requirements from IBM Rational DOORS	208
	Importing Baselines from IBM Rational DOORS	211
	Importing Previously Exported Requirements	211
<i>Chapter 9</i>	Test Case Management	213
	Overview	214
	Creating a Test Case	214
	Creating a Test Run	214
	Test Step Functions	215
<i>Chapter 10</i>	Agile	217
	Before you start	218
	Agile Basics	218
	About Agile	218
	Comparing Requirements Management and Agile Approaches	219
	Accessing Agile	219
	About Products	220

About Releases	220
About Stories	220
About Sprints	220
About Features	220
About Epics	220
About Badges	221
About Capacity	221
Tool Tips	221
Display Options	222
Agile Tabs	222
Overview Tab	222
Product Backlog Tab	223
Product Storyboard Tab	225
Sprint Planning Tab	225
Sprint Storyboard Tab	226
Using Agile	227
Using Products	227
Using Releases	228
Using Epics	229
Using Features	230
Using Stories	231
Using Sprints	232

Chapter 11

Administration	233
Managing Users	234
Creating a New User	234
Copying an Existing User	234
Editing a User	235
Assigning a User to one or several Groups	236
Un-Assigning a User from one or several Groups	236
Deleting a User	236
Managing Groups	237
Assigning Users to a Group	237
Un-Assigning Users from a Group	237
Managing Categories	238
Moving Requirements Between Categories	241
Managing Document Locks	242
Managing Requirement Locks	243
Configuring Project Settings	243
Configuring Agile	243
Products	243
Releases	244
Sprints	244
Epics	245
Features	245
Stories	245
Clearing Agile Mappings	246

Chapter 12

Script Syntax	247
Overview	248
SELECT Statement	248
DTPtag	249
DTP_TEXT Display Item	250
RTM_KEYWORD Display Item	250
WHERE Clause	250
ORDER BY Clause	259
CALCULATE Statement	260
XREF Statement	261
PLUS Statement	263
COMMENT Statement	263
Adding Rich Format Text to Query Prompts	265
Glossary	267
Index	277

Preface

This document describes how to use the RM Browser client for Serena® Dimensions® RM, a comprehensive requirements management package that allows development teams to capture, engineer, and manage requirements throughout the entire product lifecycle.

Objective

The purpose of this document is to describe how to use Dimensions RM after the product is installed.

Audience

This document is intended for members of project teams who use Dimensions RM to create, manage, and track requirements during the lifecycle of a project.

Contacting Technical Support

Serena provides technical support for all registered users of this product, including limited installation support for the first 30 days. If you need support after that time, contact Serena Support at the following URL and follow the instructions:

<http://support.serena.com>

Language-specific technical support is available during local business hours. For all other hours, technical support is provided in English.

The Serena Support web page can also be used to:

- Report problems and ask questions.
- Obtain up-to-date technical support information, including that shared by our customers via the Web, automatic e-mail notification, newsgroups, and regional user groups.
- Access a knowledge base, which contains how-to information and allows you to search on keywords for technical bulletins.
- Download fix releases for your Serena products.

License and Copyright Information for Third-Party Software

License and copyright information for third-party software included in this release can be found as part of the software download available at:

<http://support.serena.com/Download/Default.aspx>


Chapter 1

RM Browser Basics

Main Pages of the RM Browser Interface	14
General Navigation and Controls in RM Browser	15
Editable Grid, Grid, and Form Views	20
Common Dialog Controls	24
What Can RM Browser Do?	37
Logging In	38
Switching to Another Project	39
Changing Your Password	40
Logging Out	40
Getting Help	41
Viewing Version, System, and Contact Information	42
Demonstration Projects	42
Using Spell Check in RM Browser	43
Limitations of the RM Browser Interface	46

Main Pages of the RM Browser Interface

RM Browser includes the following main pages:

- **Home:** Is where you select the Category, Document, Report, Collection, or Baseline that you wish to work in. Once the desired item is selected, select an operation from the Actions pane to open the item in the relevant dialog or work page. To display the Home View, click .
- **My Work:** By default, this page displays items that you have recently worked on. You can customize this page to determine which items are displayed, and define queries to populate more sections. Click the **My Work** button to display this page.
- **Work Pages:** Are where you view and work on groups of requirements. Each page includes the features specific to the type of group that you selected on the Home View. There are the following types of work pages:
 - **Category:** Displays the requirements included in the category or categories that you selected on the Home View. You can view the requirements in Editable Grid, Grid, or Form view. This page includes Quick Search, so you can quickly find a specific requirement or group of requirements within the category.
 - **Document:** Displays a document-like presentation of requirements, with a table of contents, chapters, and subchapters. Requirements and subrequirements are contained within the chapters and subchapters. Microsoft® Word documents that you have imported into RM are displayed on this page. You can add, delete, move, and edit chapters and requirements. The left pane is the navigation tree that represents the table of contents. The right pane is the detail pane, and displays information based on what you selected in the navigation tree. You can view requirements in a grid format that displays multiple requirements in a tabular style, and a paragraph format that displays multiple requirements in a paragraph style.
 - **Class Report:** Displays the results of queries within a single class. You can view the requirements in Editable Grid, Grid, or Form view.
 - **Relationship Report:** Relationships define interactions between classes of requirements, and these are defined by the administrator in the project schema. This page displays the results of queries built around those relationships. You can view the requirements in Editable Grid, Grid, or Form view.
 - **Traceability Report:** Traceability is a way to analyze the linkages between requirements. The left pane is the traceability tree with a top-level class from which related classes and requirements flow in a hierarchical format. The right pane displays information based on what you selected in the traceability tree.
 - **Collection:** Displays the requirements included in the collection that you selected on the Home View. You can view the requirements in Editable Grid, Grid, or Form view.
 - **Baseline:** Displays the requirements included in the baseline that you selected on the Home View. You can view the requirements in Editable Grid, Grid, or Form view.

General Navigation and Controls in RM Browser

See the following subsections for an overview of the main navigational and control elements of the RM Browser interface:

- ["Welcome Menu" on page 15](#)
- ["Menu Bar" on page 16](#)
- ["Project Bread Crumb" on page 16](#)
- ["Categories Pane" on page 17](#)
- ["Actions Pane" on page 18](#)
- ["Attribute Types" on page 19](#)

Welcome Menu

 [Welcome, joe](#) ▾

Change Password

Help

User Settings

Notifications


About

Log Out

The Welcome menu appears at the upper right of all RM Browser's main window. Clicking it opens a sub-menu which includes the following entries:

- **Change Password:** This opens the **Change Password** page. See ["Changing Your Password" on page 40](#).
- **Help:** This opens the RM Browser help. See ["Getting Help" on page 41](#).
- **User Settings:** This opens the **User Settings** dialog, where you can override the project settings, e.g. which attributes are displayed in the **Quick Search** results. See ["RM Browser Basics" on page 13](#).
- **Notifications:** This opens the **Notifications** dialog, where you can enable and disable e-mail notification settings for your user account. See ["Enabling and Disabling E-Mail Notifications" on page 41](#).
- **About:** This opens the **About Dimensions RM** dialog. It displays information such as the version of Dimensions RM and the operating system of the server. See ["Viewing Version, System, and Contact Information" on page 42](#).
- **Log Out:** This ends your RM Browser session and displays the **Log In** page. See ["Logging Out" on page 40](#).

Menu Bar



This appears at the upper left of all RM Browser pages. It includes the following menus and buttons:

- **New:** This menu opens the dialogs that create new items, such as requirements, reports, documents, collections, and baselines.
- **My Work:** This button opens the My Work page, which displays items you have recently worked on, and/or the results of various queries you have defined for this purpose. To configure the My Work page, see ["Customizing My Work Page" on page 57](#).
- **Requirements:** This button opens the Requirements view which allows easy searching, editing, deleting and exporting of requirements. For further information on the Requirements view, see [Chapter 4, "Exporting Requirements" on page 76](#).
- **Import:** This menu opens the dialogs that import external content, such as CSV, Microsoft Word, and XML files into RM requirements. See [Chapter 8, "Importing Requirements" on page 195](#).
- **Containers:** This menu opens dialogs that manage, move, and compare containers. See [Chapter 7, "Managing Containers and Collections" on page 185](#).
- **Administration:** This menu opens dialogs for administrative functions, such as managing and organizing categories, breaking user locks on documents and requirements, and configuring project-level settings for RM Browser behavior (which is the behavior all users see unless they override it with their own local user settings). See [Chapter 11, "Administration" on page 233](#).


Project Bread Crumb

ORCL : [RMDemo](#) ▼ > [RMDemo](#) > [Relationship](#) > [All Current Product Rqmts](#) ▼

This appears at the upper left of all RM Browser pages, just below the Menu Bar. It includes the following elements:

- The left-most element displays the database name followed by the RM project name. Clicking the project name opens the Home View. By clicking on the arrow you can switch to another project. For further information about switching projects see ["Switching to Another Project" on page 39](#).
- The second element is the name of the category that was selected on the Home View. If the selection includes subcategories, the name of the top-most selected category is displayed. If the root category was selected, then the second element will be the same as the first element: the name of the RM project.
- The third element identifies the type of item that is currently open in the work page. For example, it would say **Relationship** if a relationship report is open.
- The fourth element is the name of the item that is currently open in the work page. It includes a drop-down list from which you can open other items of this type., if any others exist in the currently selected category.





Categories Pane



Standard View

Favorites View

This appears on left side of the Home View. It is where you select the category or sub-categories that you wish to work in. It includes the following elements:

-  **Expand/Collapse:** This button expands or collapses the Categories pane.
- **Search:** This field limits the display in the category tree to those categories that match the search string. The search is dynamic, and increasingly narrows the displayed results as you enter more characters. Potential matches are shown in bold. To return to displaying the full category tree, delete the string from the Search field or click the **X** button in the Search field.
-  **Switch Favorites View:** This button switches between Standard View and Favorite View.
-  **Include sub categories:** When colored, this toggle button indicates that sub categories below the selected category will be included. When grayed out, it indicates that only the selected category will be included.
-  **Collapse all sub categories:** This button collapses any open branches in the category tree, so only the first level of categories below the root are displayed.


To view the requirements in a category and/or sub-categories, do the following:

- 1 Select the desired categories in the Category pane.
- 2 Click **View Requirements** from the Category group of the Actions pane.

To change the category for a document, snapshot, collection, or baseline:

- 1 Select the object to move in the Home View.
- 2 Drag and drop the object to the desired category in the tree.


To add a category to the Favorites View:

- 1 Move the mouse pointer over the desired category.
- 2 Click .

To remove a category from the Favorites View:

- 1 Move the mouse pointer over the desired category.
- 2 Click ★.





Actions Pane



This appears on the right side of all RM Browser pages. It lists the Actions that are possible in the current context. These actions are arranged in expandable/collapsible groups. If an action is grayed out, either you do not have permission to perform this action, or an item of the relevant type is not currently selected. Like the Categories pane, it includes an Expand/Collapse button to show or hide the pane.

Attribute Types



Dimensions RM allows to enter data which are represented by different attribute types. The following table lists these attribute types and the controls through which you can access them.

Attribute Type	Description
Alphanumeric	A single line of text up to 1000 characters.
Text	<p>A block of text up to 65.000 characters. Note that characters which need more than one byte (e.g. Chinese or Japanese characters) decrease the maximum number of characters.</p> <p>If the text attribute has HTML functionality enabled, you can format the contained text, e.g. text color or font style. For further information about HTML formatting see chapter "HTML Text Formatting Toolbar" on page 26.</p>
Date	Allows to select either date or date and time. The date format is defined by the administrator.
List	<p>A list of values configured by the administrator.</p> <p>If selection of multiple values is allowed, use these modifier keys:</p> <p>Click: Makes a list value as selected value. All other selected values will be unselected.</p> <p>Ctrl+Click: Add or remove a list value from the selected values.</p> <p>Shift+Click: Adds all values between the previous selected value and the clicked value to the selected values.</p>
Group	<p>Like a list attribute, but composed of a series of sub attributes. Each drop down list box depends on its left neighbor.</p> <p>Example: Assume, you have a group of 3 drop down boxes. The middle drop down box shows only those values which are related to the selected value of the left drop down box. The right drop down box shows only those values which are related to the selected value of the middle drop down box.</p> <p>A group list box can have several rows. To add a new (empty) row, click  . To add a new row with the values of the selected row, click  . To remove a row, click  .</p> <p> TIP To have all values added, choose (Select all) from the drop down list.</p>

Attribute Type	Description
User	<p>A list of user names, which can be configured by group or individual user names. Note that the user list does not necessarily show all users. The list may be limited by the administrator's choice of users, or groups, or by category.</p> <p>Examples:</p> <ul style="list-style-type: none"> ■ The Administrator configured the user list to show only users of the Administrators group. ■ User access rights have been configured by category. If the requirement is in category A, the user list shows only users who have access rights for category A. All other users are not in the list.
Numeric	Accepts only numeric values.
File Attachment	<p>The file attachment attribute holds one file. File attachments are added, viewed, replaced, or deleted by clicking links.</p> <p>To add a file attachment, click Attach.</p> <p>To replace a file attachment, click Replace.</p> <p>To delete a file attachment, click Delete.</p> <p>To view a file attachment, click the file name.</p> <p>By default, file attachment attributes reside in the File Attachments section of a requirement.</p>

Editable Grid, Grid, and Form Views

The work pages, except for Documents and Traceability, include the ability to toggle between the following views of the requirements they contain: Editable Grid, Grid, and Form. Use the view buttons to select the desired view:

- **Editable Grid:**  "Editable Grid View" on page 21
- **Grid:**  "Grid View" on page 22
- **Form:**  "Form View" on page 23




NOTE If the query includes more than one class, the Form view is not available.

Editable Grid View


Category	Rqmt ID	Title	Text
RMDEMO	MRKT_000003	Runs on "standard" home PC	The ePhoto system shall be accessible to the user from a regi
RMDEMO	MRKT_000004	Annotate photos with text	The user shall be able to annotate their photos with textual des
RMDEMO	MRKT_000020	Provide photo special effects	The ePhoto system shall allow users to apply various special
RMDEMO	MRKT_000021	Border layouts provided	The ePhoto system shall allow users to display photos in vari

This is a tabular view of requirements with which you can directly edit requirement attributes. It includes the following controls:

- **Refresh:** This button repopulates the view with fresh data from the database.
- **Apply changes:** This button saves the changes you have made. Unsaved changes have a red triangle in the upper left.
- **Undo changes:** This button restores the original contents of the view, removing any unsaved changes you have made.
- **Create new requirement:** This button adds a blank row to the view, into which you enter the attributes the new requirement that you wish to create. System attributes, such as the requirement ID number, will be populated once you click the **Apply changes** button.
- **Page Controls:** If the view contains multiple pages of content, you can select or enter a specific page to view in the **Page** field. Or you can browse through the pages in sequence with the **First Page**, **Previous Page**, **Next Page**, and **Last Page** controls.
- **Formatting Tool Bar:** If the attribute can accept text formatting, this tool bar appears in the cell when you double-click the cell for editing. It has two modes. To toggle between them, click the **Source Edit** () button.
 - **Format:** In this mode you can apply formatting to the text, but you cannot edit the text.



- **Source Edit:** In this mode you can edit the text, but you cannot apply formatting to the text.



Click a column header to sort the requirements by that attribute. To edit an attribute, double-click it; the attribute's cell will then become editable.

Simple Text Attributes: A simple text attribute does not allow text formatting and does not allow line breaks.

Multiline Text Attributes: A multiline text attribute does not allow text formatting, but allows the contained text to be on multiple lines. To start a new line, press **Enter**.

HTML Text Attributes: An HTML text attribute allows text formatting and line breaks. For text formatting, use the **Formatting Tool Bar** as described above.

List Attributes: If the attribute is a selection from a predefined list, you will be presented with a drop-down list to select from. Note that the cell will still show a deleted list value, but the drop-down list will not.

Text Attributes: If the attribute is a text value, a cursor will appear in the cell so you can edit the text as needed. If the attribute can accept text formatting, the Formatting Tool Bar appears in the cell.






TIPS

- To set an attribute to the same value across multiple requirements, select the desired requirements, double-click one instance of the attribute, set it to the desired value, and press the Enter key.
- Except for HTML text attributes, editable cells allow these shortcuts:
 - **Shift+Enter:** Apply changes to cell and navigate to the same cell in the row above.
 - **Ctrl+Enter:** Apply changes to cell and navigate to the same cell in the row below.

To perform other actions on the currently selected requirement or requirements, select the desired action from the Requirements group of the Actions pane. To perform an action on the entire grouping of requirements, select an action from the Actions pane group that corresponds to the group type you are working on, for example: Category, Report, Collection, etc.

Grid View

<u>Marketing Requirements</u>				
 Category▲	Rqmt ID	Title	Text	
 RMDemo	MRKT_000003	Runs on "standard" home PC	The ePhoto system shall be acce	
 RMDemo	MRKT_000004	Annotate photos with text	The user shall be able to annotat	
RMDemo	MRKT_000020	Provide photo special effects	The ePhoto system shall allow us	
RMDemo	MRKT_000021	Border layouts provided	The ePhoto system shall allow us	

This is a tabular view of requirements. Click a column header to sort the requirements by that attribute. To open a requirement for editing, double-click it; the requirement opens in the Edit Attributes dialog (see ["Editing a Requirement" on page 88](#)).

To perform other actions on the currently selected requirement or requirements, select the desired action from the Requirements group of the Actions pane. To perform an action on the entire grouping of requirements, select an action from the Actions pane group that corresponds to the group type you are working on, for example: Category, Report, Collection, etc.

Form View

The screenshot shows a software interface for viewing a requirement. At the top, there is a 'Quick Search' field and a toolbar with icons for search, grid, and list views. Below this is a navigation bar with left and right arrow buttons and an 'Edit' button next to the text '12 of 28 objects'. The main content area has a blue header bar with the text 'Marketing_Requirements: MRKT_000004'. To the right of the header, it says 'Category: RMDEMO'. Below the header is a list of expandable sections: 'Standard Attributes', 'Custom Attributes', 'System Attributes', 'File Attachments', 'Comments', 'Links', 'History', 'Polls', and 'Container'. The 'Standard Attributes' section is expanded, showing 'Rqmt ID: MRKT_000004' and 'Title: Annotate photos with text'. Below the title, there is a text field containing the description: 'Text: The user shall be able to annotate all their photos with textual descriptions.'

This view displays the attributes of one requirement at a time. Attributes are grouped into expandable/collapsible sections by type. You can browse through the requirements in sequence with the **First**, **Previous**, **Next**, and **Last** controls. To edit the current requirement, click the **Edit** button; the requirement opens in the Edit Attributes dialog (see ["Editing a Requirement" on page 88](#)).

To perform other actions on the currently selected requirement, select the desired action from the Requirements group of the Actions pane. To perform an action on the entire grouping of requirements, select an action from the Actions pane group that corresponds to the group type you are working on, for example: Category, Report, Collection, etc.

Selecting Multiple Requirements

In requirement lists you can usually select more than one requirement. The following selection methods are supported:

- **Ctrl+click** to multi-select
- **Shift+click** to select a block of requirements
- **Ctrl+A** to select all requirements



NOTE


- If the requirements are shown in sections (e.g. in Quick Search when searching over several/all classes), **Ctrl+A** only selects the requirements in the active section.
- When using Quick Search in Split View mode, multi-selection is only allowed for the referenced class.

Common Dialog Controls

See the following subsections for an overview of the control elements common to many RM Browser dialogs:

- "Category Drop-Down List" on page 24
- "Attributes to Display List" on page 25
- "Sorting Order List" on page 25
- "HTML Text Formatting Toolbar" on page 26
- "Attribute Constraints Tab" on page 28
- "Relationship Constraints Tab" on page 31
- "Display Options Tab" on page 34

Category Drop-Down List




Click the collapsed list to expand it and access the following features:

- **Find:** Enter a search string to dynamically find categories that match it.
- To select multiple categories, press the CTRL key when selecting the categories. Selected categories are highlighted with blue. Multi-select is available only for some operations, such as creating reports.
- To select all sub-categories under a parent category:
 - a Click the desired parent category.
 - b Shift-click the parent category.

Attributes to Display List

The **Attributes to Display** list defines which attributes of a requirement should be shown in a table or list. Different requirement classes can show different attributes.




To specify the attributes to display:

- 1 Select the attribute or attributes in the **Attributes to Display** list.
- 2 Click the right arrow button. The attribute or attributes are moved to the display list on the right. If you change your mind, select the attribute or attributes and click the left arrow button to move them back to the **Attributes to Display** list. (Alternatively, you can double-click an attribute to add it to the display list on the right.)
- 3 Use the up and down arrow buttons to the right of the display list to change the display order of the columns.



For a list of special attributes see chapter ["Special Attributes"](#) on page 36.

Sorting Order List

The **Sorting Order** list defines in which order requirements should be sorted. You can specify several attributes for sorting. If you want to order by title, you might want to sort by requirement ID as to ensure an identical order on different executions.



To specify the sort type:



- 1 Select one or more attributes in the **Sorting Order** list.
- 2 Click one of the following buttons:
 - Alphabetic button  for a simple alphabetic sort.
 - Numeric button  for a numeric sort. This type of sort can be used for alphanumeric attributes such as paragraph numbers in outlines. For example, with

a numeric sort, the numbers (10, 20, 1, and 2) are sorted as (1, 2, 10, 20) instead of (1, 10, 2, 20).



NOTE Alternatively, you can double-click an attribute to add it as an alphabetic sort to the sort list on the right.

To specify the sort order:



- 1 Select an entry in the sort list.
- 2 To change the sort order, click one of the following buttons:
 - Button  to have the data sorted before other data.
 - Button  to have the data sorted after other data.

For example, select **Paragraph ID** if you want the query results to be sorted in the order presented in the original document, and click the **Numeric** button to sort by paragraph number. Then select **Priority** and click the **Alphabetic** button if you want the requirements with the same paragraph ID sorted by the priority assigned to them.




NOTE If you choose an attribute with the *Date* data type, the results are sorted in date order regardless of whether you chose **Alphabetic** or **Numeric**.

To specify the sort direction:

- 1 Select an entry in the sort list.
- 2 To change the sort direction, click one of the following buttons:
 - Button  to sort ascending (A-Z, 0-9).
 - Button  to sort descending (Z-A, 9-0).



HTML Text Formatting Toolbar








HTML formatted text content

A table	with two columns
and	two rows



If a text attribute can accept HTML formatting (an option set by the administrator for each attribute), this toolbar appears when you click in the attribute's field. It includes the following controls grouped into two rows:

- **First Row of Controls:**
 -   Undo and Redo
 - Select text formats


- **B** **I** Apply bold and italic formatting.
 - **A** **A** Select text color and background color.
 - Select the font family and size.
 -  Align the text.
- **Second Row of Controls:**
-  Apply list formatting.
 -  Apply indentation formatting.
 -  **Insert/edit link:** To create a link or edit an existing link, select the text and click the **Insert/edit link** button. The **Insert link** dialog appears. Complete the fields as needed, and click **OK**.




TIP If you want to upload a file or attachment, use the **Insert/edit link** function.

-  **Remove link:** To remove an existing link, select the link and click the **Remove link** button.
-  **Insert/edit image:** To insert a graphic into the attribute, place the cursor where you want to insert the image. To edit the HTML parameters of an existing

image, select the image element. Then click the **Insert/edit image** button. The **Insert/edit image** dialog opens. Complete the fields as needed and click **OK**.

-  **Toggle fullscreen mode:** Click to toggle between a dialog view and a full screen view of the text attribute you are editing.

Attribute Constraints Tab

This tab uses relationship criteria to determine which requirements are included.

To complete the Attribute Constraints tab:

- 1 Click the **Attribute Constraints** tab.
- 2 If you want to change the category or categories that are searched, select them in the **Category** list.
- 3 With Traceability reports, select an entry from the **Choose attribute constraints for class** box. You can choose the top class or any sub-class you selected on the **Related Classes to Display** tab.
- 4 For each attribute in one of the following sections, specify a value.

Note the following:

- If you leave a field blank, any value for that attribute is retrieved in the query.
 - If you select multiple values for attributes that are displayed in a list, any of the selected values are matched.
 - You can use wildcards in the attributes constraints sections to query for a keyword. For example, if you want to find the requirements that have the word "system" in the title, type ***system*** in the **Title** field in the **Standard Attributes** section.
- 5 To enter values into the attribute boxes of more than one class, repeat steps 3 and 4.
 - 6 Select the **Case sensitive search** check box if you want the search results to exactly match the capitalization of the attribute values.

Attribute Constraints Tab Controls

This section describes the controls associated with attributes on the **Attributes Constraints** tab.

Categories

Category constraints describe categories to use when retrieving requirements. You can choose whether the user is to enter the category or categories at runtime (that is, at script execution time) or whether the category or categories are stored as part of the query. The category and runtime choices apply to all the classes in the traceability report.

Perform one of the following steps:

- Click the down arrow ▾ to the right of the **Categories** list, and select **Enter now**. Select one or more categories from the **Categories** list, click the down arrow to the left of the **Categories** list, and select **in** or **not in** to specify whether the categories should be included in the query.
- Click the down arrow to the right of the **Categories** list, and select **Enter at runtime**.
- Click the down arrow to the left of the **Categories** list, and select **in** or **not in** to specify whether the category or categories should be included in the query.



NOTES

- The **null** and **not null** options are not used for categories.
- To select all categories between two categories, select the top category, follow these steps:
 - Press SHIFT and keep it pressed.
 - Click the selected category
 - Click the last category
 - Release SHIFT.
- To select more than one category, press CTRL and click the categories.
- To select a category and its subcategories, hold down SHIFT and click a category. Pressing CTRL+SHIFT and clicking a category adds the category and its subcategories without changing the current selection.
- To deselect a category, press CTRL and click the selected category. Because the CTRL key toggles the selection of the clicked category, the other categories are not affected. Clicking a category without pressing CTRL removes all other selections.
- To search for a category, type one or more letters from the category name in the **Find** box.
- If no categories are selected, **Choose categories** is displayed in the list box, and all categories are included in the query.
- If more than one category is selected, **(n selected)** is displayed in the list box.
- If only one category is selected, **Category Name** is displayed in the list box.



TIP To return the category list to an empty selection, hold down CTRL and then click each selected category until no categories are selected. Then, the categories list displays **Choose Categories** again. Alternatively, you can click any category, hold down CTRL, and click the same category again.

Group Attributes:

When querying a group attribute, all values of a group attribute must match for a requirement to show up in the report result. If a group attribute has several rows, a requirement must match all rows of the group attribute to show up in the report result. For further information about group attributes see chapters ["Finding Requirements with Group Attributes" on page 73](#) and ["Working with Group Attributes" on page 118](#).

Operators

If you hover over the down arrow ▼ to the left of the attribute label, a list of operators opens. The list includes only the operators that are appropriate for the attribute type. The following table describes each operator.

Operator	Description
=	The attribute equals the value you specify. The * and % wildcards are supported.
not =	The attribute does not equal the value you specify. The * and % wildcards are supported.
<	The attribute is less than the value you specify.
>	The attribute is greater than the value you specify.
<=	The attribute is less than or equal to the value you specify.
>=	The attribute is greater than or equal to the value you specify.
between	The attribute is between the two values you specify. When you select the "between" operator, another field appears that allows you to type the second value.
not between	The attribute is not between the two values you specify. When you select the "not between" operator, another field appears that allows you to type the second value.
null	The attribute has not been set (not initialized).
not null	The value has been set (initialized).
in	The attribute equals one of the values you specify.
not in	The attribute does not equal one of the values you specify.

Runtime Choice

If you hover over the down arrow ▼ to the right of the attribute label, a list opens that lets you choose whether the attribute value is to be entered at runtime (that is, at script


execution time) or stored as part of the query. The following table describes the choices in the list.

Choice	Description
Enter now	The attribute value is stored as part of the query.
Enter at runtime	The user is prompted to enter the attribute value when the query runs.

Date and Time Control

The date and time shown in the date and time control matches the date format specified in the attribute definition.

To use the date and time control:

- 1 Click the calendar icon . The date and time control opens.



- 2 Do one of the following:
 - Select a month, year, day, and time, and then click **close**.



NOTE To change a unit of time (that is, an hour, minute, or second), select the unit of time, and then click the up or down arrow button.

- Click **now** to specify the current date and time.

The date attribute field is populated with the date and time you specified.

- 3 To clear the date attribute field, click the calendar icon, and click **clear**.

Relationship Constraints Tab

This tab uses relationship criteria to determine which requirements are included.



NOTE The constraints you select on the **Constraints** tab are combined using an AND operation. That is, the requirement must meet all the constraints that are specified before it is included in the report.

To complete the Relationship Constraints tab:

- 1 Click the **Relationship Constraints** tab.

Collection restraints describe collection memberships to use when retrieving requirements. Select collections from the **Collections** list, and select from the constraint options to specify whether they should be included in the query. To select multiple collections in the list, hold down the Control key while you select the collections. To select a range of collections, select the first collection, press the Shift key, and then select the last collection. You can find collections by scrolling in the list, or by typing a substring of the collection name in the **Find collection** box.

The constraint options include:

- **In any selected collection(s)** to include requirements in any of the collections you have selected
 - **Not in any selected collection(s)** to exclude requirements from any of the collections you selected
 - **In all selected collection(s)** to include requirements that are in each of the collections you selected
 - **Not in all selected collection(s)** to exclude requirements that are not in each of the collections you selected
 - **In any collection(s)** to include requirements in any - even just one - of the collections you selected
 - **Not in any collection(s)** to exclude requirements that are in any - even just one - of the collections you selected
- 2 Baseline constraints describe baselined collection memberships to use when retrieving requirements. Select baselines from the **Baselines** list, and select **In** or **Not In** to specify whether they should be included in the query. You can include more than one baseline constraint in the query. You can find baselines by scrolling in the list, or by typing a substring of the baseline name in the **Find baseline** box.

To select multiple baselines in the list, hold down the Control key while you select the baselines. To select a range of baselines, select the first baseline, press the Shift key, and then select the last baseline.

The constraint options include:

- **In any selected baseline(s)** to include requirements in any of the baselines you have selected
 - **Not in any selected baseline(s)** to exclude requirements from any of the baselines you selected
 - **In any baseline(s)** to include requirements in any - even just one - of the baselines you selected
 - **Not in any baseline(s)** to exclude requirements that are in any - even just one - of the baselines you selected
- 3 Document constraints describe documents to use when retrieving requirements. Select documents from the **Documents** list, and select **In** or **Not In** to specify whether they should be included in the query.

You can find documents by scrolling in the list, or by typing a substring of the document name in the **Find document** box.

To select multiple documents in the list, hold down the Control key while you select the documents. To select a range of documents, select the first document, press the Shift key, and then select the last document.

The constraint options include:

- **In any selected document(s)** to include requirements in any of the documents you have selected
 - **Not in any selected document(s)** to exclude requirements from any of the documents you selected
 - **In any document(s)** to include requirements in any - even just one - of the documents you selected
 - **Not in any document(s)** to exclude requirements that are in any - even just one - of the documents you selected
- 4 A snapshot is a version of a document at a specific point in time. Snapshot constraints describe snapshots to use when retrieving requirements. Select snapshots from the **Snapshots** list, and select **In** or **Not In** to specify whether they should be included in the query. You can include more than one snapshot constraint in the query. You can find snapshots by scrolling in the list, or by typing a substring of the snapshot name in the **Find snapshot** box.

To select multiple snapshots in the list, hold down the Control key while you select the snapshots. To select a range of snapshots, select the first snapshot, press the Shift key, and then select the last snapshot.

The constraint options include:

- **In any selected snapshot(s)** to include requirements in any of the snapshots you have selected
 - **Not in any selected snapshot(s)** to exclude requirements from any of the snapshots you selected
 - **In any snapshot(s)** to include requirements in any - even just one - of the snapshots you selected
 - **Not in any snapshot(s)** to exclude requirements that are in any - even just one - of the snapshots you selected
- 5 *Class, Graphical and Traceability Report only:* Relationships connect a primary and a secondary class. Select relationships from the **Relationships** list, and select **In** or **Not In** to specify whether they should be included in the query. You can include only one relationship constraint in a query.

You can find relationships by scrolling in the list, or by typing a substring of the relationship name in the **Find relationship** box.



NOTE

- **<Source>** and **<Immediate>** are special relationships that are used to locate versions of requirements. The **<Source>** relationship refers to the original requirement in a chain of versions. The **<Immediate>** relationship refers to the immediate predecessor or successor of a requirement.
- Relationship constraints are not present on the **Relationship Constraints** tab on the **New Traceability Report** dialog box.
- If you select a relationship, and then type the first few letters of another relationship, the first relationship is no longer selected.

Display Options Tab

This tab determines what fields are displayed and in what order. Slightly different versions of this tab appear in a number of dialogs.





NOTE

- The attributes you select to display in the **Display Options** tab in the **New Traceability Report** dialog box are only shown in Requirements View after you run a traceability report.
- There are two meta attributes that can be displayed in a traceability report or Query by Class or Query by Relationship:
 - **<DEFAULT_TITLE>** is in a column named **Title**. It gets the data for the attribute marked as the Title attribute in Class Definition. For more information about the Title attribute, see the *Serena Dimensions RM Administrator's Guide*.
 - **CM Associations** is in a column named **CM Associations**. In the traceability report or query, if a requirement is in a collection that is linked to a Dimensions CM project, that collection name is displayed in the column.

To complete the Display Options tab:

- 1 Click the **Display Options** tab.



NOTE The tabs shown in the preceding illustrations are from the **Query by Class** and **New Traceability Report** dialog boxes. The appearance of **Display Options** tabs can differ.

- 2 *New Traceability Report* only: Select a class from the **Choose a class** list. All classes are displayed on this tab, but the only attributes that are saved are those that are in classes that are displayed in the traceability report. You can sort attributes for each class.

- 3 To specify the columns to display and their order, see chapter "[Sorting Order List](#)" on [page 25](#).
- 4 *Query by Class, Query by Relationship, and New Traceability Report only:* Select the **Add row count** check box to display the number of rows at the bottom of the query results.
- 5 To specify the sort type and order, see chapter "[Sorting Order List](#)" on [page 25](#).
- 6 Select the **Remember these options** check box to remember the settings on this tab the next time this dialog box is invoked. The settings are remembered if the same user invokes the dialog box from the same project and queries the same class or relationship. They are remembered in the **Query Class, Query Relationship, Link, Organize by Collections, and Add to Chapter** dialog boxes.



NOTE All of the dialog boxes cited above share the settings. For example, if you save the settings for the Marketing Requirements class in the **Query Class** dialog box, you will see the same settings for the Marketing Requirements class in the **Link** dialog box.

Special Attributes

The lists contain some special attribute names which are surrounded by <>. These attributes are not class attributes, but contain collected or calculated values. The following list shows these attributes:

Attribute Name	Script Name	Description
<Baselines>	RTM_BASELINES	The names of the baselines referencing the requirement.
<Collections>	RTM_COLLECTIONS	The names of the collections referencing the requirement.
<Containers>	RTM_KEYWORD	The names of the containers referencing the requirement.
<Documents>	RTM_DOCUMENTS	The names of the documents referencing the requirement.
<Links Out>	RTM_LINKS_FROM	The number of links from the requirement to other requirements. In in result lists (i.e. Quick Search, reports or documents in Grid/Editable Grid Requirement Layout mode), you can open a list of linked requirements by clicking the arrow or number in the Links Out column of a requirement in the result list. Clicking a requirement in the list opens that requirement for editing.

Attribute Name	Script Name	Description
<Links In>	RTM_LINKS_TO	The number of links from other requirements to the requirement. In in result lists (i.e. Quick Search, reports or documents in Grid/Editable Grid Requirement Layout mode), you can open a list of linked requirements by clicking the arrow or number in the Links In column of a requirement in the result list. Clicking a requirement in the list opens that requirement for editing.
<Snapshots>	RTM_SNAPSHOTS	The names of the document snapshots referencing the requirement.

Script names are used when writing or modifying report scripts or accessing Dimensions RM Web Services. For further information about scripts see chapter "[Script Syntax](#)" on page 247. For further information about Dimensions RM Web Services refer to the *Web Service and Rest Service Reference* guide.

What Can RM Browser Do?

RM Browser provides Web access to Serena® Dimensions® RM functions. In RM Browser, you can do the following:

- View query results generated in real time from existing filters and scripts
- Create new queries and optionally save them as filters or scripts
- Edit queries
- Print or save query results
- Print individual requirements
- Create, update, replace, delete, and remove requirements
- View file attachments and add file attachments to requirements
- Create new discussion threads and participate in existing ones
- Submit change requests and group them into Engineering Change Proposal (ECP) requirements
- Approve or reject change requests
- Create and traverse links between requirements
- Create and modify polls about specific requirements, vote in polls, and view current poll results
- Add requirements to or remove requirements from collections; and create, delete, and rename collections
- Associate collections to Dimensions CM projects, and associate Dimensions RM requirements to Serena® Dimensions® CM requests
- Create baselines from collections

- Organize requirements and scripts within categories. Categories are used to restrict the visibility of parts of the project based on user groups.
- View, create, and modify requirements and chapters in a hierarchical document-like structure, and optionally export those document-like structures as Microsoft® Word documents
- Create and edit traceability reports in which you can analyze linkages between requirements, edit requirements, and print traceability reports
- View and clear links that are considered "suspect"
- View the history of a requirement
- Merge changes to documents, chapters, and requirements that were made by users making changes at the same time
- Unlock chapters and requirements that were locked by another user so that you can edit them

Logging In

The login process that you experience will depend upon which login source has been implemented by your administrator:

- RM or LDAP
- Single Sign On (SSO)
- Single Sign On with SmartCard (CAC)



NOTE

- Cookies must be enabled to log in to RM Browser.
- After a period of inactivity, an RM Browser session times out, and you are logged out of RM Browser. A login dialog opens so you can log in again. By default, the session timeout is 30 minutes. Your administrator can modify this value. It is recommended that you log out of RM Browser when you finish your work in it.

RM or LDAP Login

To log in to RM Browser:

- 1 Navigate to the URL provided by your project administrator. The User Log in page opens.
- 2 Enter your user name and password.
- 3 Select the database in which you will be working. The first time you log in, the full list of databases is included in the list of databases. Afterward, the last database in which you worked is selected by default.
- 4 Select the project in which you will be working. Only the projects to which you have access are included in the list of projects. The last project in which you worked is selected by default.

- 5 Click the **Login** button or press the Enter key.

Single Sign On Login

To log in via SSO:

- 1 Navigate to the URL provided by your project administrator. The SSO sign in page opens.
- 2 Enter your user name and password.
- 3 Click the **Log In** button. The User Log in page opens.
- 4 Select the database in which you will be working. The first time you log in, the full list of databases is included in the list of databases. Afterward, the last database in which you worked is selected by default.
- 5 Select the project in which you will be working. Only the projects to which you have access are included in the list of projects. The last project in which you worked is selected by default.
- 6 Click the **Login** button or press the Enter key.

Single Sign On with SmartCard Login

To log in via SmartCard:

- 1 Navigate to the URL provided by your project administrator. The SSO sign in page opens.
- 2 Ensure that your SmartCard is inserted into a reader, and click the **SmartCard Login** button.
- 3 Select a valid certificate from your SmartCard (CAC) and enter the appropriate PIN.
- 4 Click the **OK** button. The User Log in page opens with the **Username** field populated and read-only.
- 5 Select the database in which you will be working. The first time you log in, the full list of databases is included in the list of databases. Afterward, the last database in which you worked is selected by default.
- 6 Select the project in which you will be working. Only the projects to which you have access are included in the list of projects. The last project in which you worked is selected by default.
- 7 Click the **Continue** button or press the Enter key.

Switching to Another Project

To switch to another project within the same database, click on the ▼ button next to the project name:

ORCL : [RMDEMO](#) ▼

For switching to another project in a different database, you must log out and then log into the desired database. See "[Logging In](#)" on page 38.

Changing Your Password

It is best security practice for users to change their passwords from time to time. The RM administrator can enforce this practice by setting the number of days a password lasts before it expires. Additionally, the RM administrator can enforce password quality requirements, such as the minimum length; minimum number of characters that must be different between the new and the old password; the minimum number of letters, numerals, and special characters; and the number of old passwords that are stored to ensure that a password is not reused too soon. Using the procedure below, you can view the password rules that are in effect for the RM database.



NOTE The RM password rules do not affect logins via LDAP, as these would be managed in LDAP.

Before your current password is due to expire, you receive a warning dialog box that gives you the opportunity to change your password.

To change your password:

- 1 Click the **Welcome, UserID** link in the upper right of the screen. The Change Password dialog box appears.
- 2 To view the password rules in effect for this RM database, click the **Password Rules** link.



NOTE

- The rules apply to all projects in the database.
- The RM administrator can exempt individual users from the rules. However, exempt users will still see the rules if they click the Password Rules link.

- 3 Type your existing password in the **Old Password** field.
- 4 Type the new password in the **New Password** field.
- 5 Type the new password again in the **Confirm Password** field.
- 6 Click **OK**.

Logging Out

To log out of RM Browser:

- Click the **Log Out** link in the upper right of RM Browser.



NOTE It is recommended that you log out of RM Browser when you finish working in it.

Getting Help

You can get help specific to the page or dialog box you are currently using, or use the TOC and Search features of the full help system to look up information.



To get help for the page or dialog box you are on:

- 1 Click the **Help** link at the top right of the page or dialog box. A Help topic specific to the RM Browser page or dialog box opens.
- 2 Optionally, to display the TOC, Search, and other navigation features of the help system, click the **Show** link at the top of the help topic



Enabling and Disabling E-Mail Notifications

You can enable or disable e-mail notifications for your user account or the group(s) you are a member of. Note that enabling or disabling e-mail notifications for a group only affect your user account — other user accounts are not affected.

To enable e-mail notifications, do the following:

- 1 Select **Notifications** from the **Welcome** menu. This opens the **Notifications** dialog.
- 2 In the **Inactive Notifications** list, expand the desired class by clicking  next to the class name.
- 3 Select the desired e-mail notification rule.
- 4 Click .
- 5 Click **Save**.
- 6 Click **Cancel** to close the dialog.

To disable e-mail notifications, do the following:

- 1 Select **Notifications** from the **Welcome** menu. This opens the **Notifications** dialog.
- 2 In the **Active Notifications** list, expand the desired class by clicking  next to the class name.
- 3 Select the desired e-mail notification rule.
- 4 Click .
- 5 Click **Save**.
- 6 Click **Cancel** to close the dialog.

Viewing Version, System, and Contact Information

To view version and system information:

- 1 Click the **About** link in the upper right of RM Browser. The **About Dimensions RM** dialog box opens.

The following information is displayed:

- **Version:** The version of Dimensions RM you are using.
 - **Web Server:** The type of Web server that is hosting RM.
For example, Apache/Tomcat 6.0.26(Win32).
 - **Web Server OS:** The operating system in use on the Web server.
 - **Database:** The Oracle version in use.
 - **Browser Name:** The name of browser software you are using.
 - **Browser Agent:** Version specific information about the browser software you are using and its features.
 - **Attributions:** Third-party tools utilized by RM Browser.
- 2 **E-mail config info to Serena:** Click this button if you are working with Serena Customer Support on an issue and have been asked to send the configuration information.
 - 3 For links to Serena's home page, Serena contact information, and other useful links, see the **Contact Information** tab.

Demonstration Projects

Two demonstration projects are included with Dimensions RM. If your administrator has installed them, you may find them to be a convenient way to get acquainted with the features of Dimensions RM.

The QLARIUS_RM Project

The QLARIUS_RM demonstration project lets business analysts and product managers quickly understand how the key functionality of Dimensions RM is beneficial in their own requirement lifecycles. QLARIUS_RM demonstrates how requirements are categorized and stored, and how the requirements lifecycle is automated and enforced. QLARIUS_RM provides predefined requirement classes, links between classes, and built-in reporting.

The default users and passwords for the QLARIUS_RM project are listed in the following table.

QLARIUS_RM	
User Name	Password
DMSYS	rtm
MARK	mark

QLARIUS_RM	
User Name	Password
PETA	peta
QLARIUSADMIN	rtm
QUIN	quin
SALLY	sally
TED	ted

The RMDEMO Project

RMDEMO is another demonstration project that provides a rich set of Dimensions RM features and functionality.

The default users and passwords for the RMDEMO project are listed in the following table.

RMDEMO	
User Name	Password
ADMINISTRATION	rtm
DEVELOPMENT	rtm
ENGINEERING	rtm
EPHOTO	rtm
EPHOTO_INFO	rtm
JOE	joe
MANAGEMENT	rtm
MARKETING	rtm
RMDEMOADMIN	rtm
RTMADMIN	rtm
SALES	rtm
SUPPORT	rtm
TECH_PUBS	rtm
TEST	rtm
TRAINING	rtm

Using Spell Check in RM Browser

Dimensions RM supports spell checking in these requirement input fields:

- Text boxes
- HTML Text boxes in Edit Attributes dialog or Editable Grid

Configuring Internet Explorer

Internet Explorer allows spell check for several languages. Note that only one language can be used at a time. The default language for spell check is either the language of your Windows installation or English.


To configure Spell Check in Internet Explorer 11, execute these steps:

- 1 Do one of the following
 - Click the cog, then select **Manage add-ons** from the shortcut menu.
 - Press the **Alt** key and release it, then select **Manage add-ons** from the **Tools** menu.
- 2 In the **Add-on Types** list, select **Spelling Correction**.
- 3 Ensure that the **Enable spelling correction** option is selected.
- 4 To change the spell check language, right-click the desired language and select **Set as default** in the shortcut menu.
- 5 Click **Close**.

Configuring Firefox

Firefox allows spell check for several languages. Note that only one language can be used at a time. The default language for spell check is either the language of your Firefox installation.

To configure Spell Check in Firefox 44, execute these steps:

- 1 Do one of the following
 - Click , then select **Options** from the menu.
 - Press the **Alt** key and release it, then select **Options** from the **Tools** menu.
- 2 Select **Advanced** in the left pane.
- 3 Select the **General** tab.
- 4 Ensure that the **Check my spelling as I type** option is selected.

Installing additional Dictionaries

To install dictionaries, execute these steps:



CAUTION! Dictionaries in Firefox are add-ons. Only install dictionaries if the policies of your organization allow installation of add-ons.

- 1 Open a website with a text field.
- 2 Right-click the text field. This opens the shortcut menu. If the shortcut menu does **not** show **Languages**, do the following:
 - a Click **Check Spelling** in the shortcut menu.

- b** Right-click the text field to open the shortcut menu again.
- 3** Select **Languages**, then **Add Dictionaries...**
- 4** Find the language you want to install and click **Install Dictionary**. This opens the **Add-ons** page for that dictionary.
- 5** Click **Add to Firefox**.
- 6** After download is complete, click **Install**.

Using Spell Check

Firefox allows spell checking for any language a dictionary has been installed. To install dictionaries, see chapter "[Installing additional Dictionaries](#)" on page 44.


To check the spelling of a text field, execute these steps:

- 1** Right-click the text field you want to check.
- 2** From the shortcut menu, select **Check Spelling**. This uses the language of your most recent spell check.
- 3** To repeat the spell check with a different language, execute these steps:
 - a** Right-click the text field you want to check.
 - b** In the **Languages** menu, select the language you want to use for your spell check.

Configuring Chrome

Chrome allows spell checking for any language a dictionary has been installed. To install dictionaries, see chapter "[Installing additional Dictionaries](#)" on page 45.

To configure Chrome 49, execute these steps:

- 1** Click , then select **Settings** from the menu.
- 2** Browse to the end of the page and click **Show advanced settings**.
- 3** Scroll down until you reach the **Languages** section.
- 4** Click **Languages and input settings...**
- 5** In the **Languages** list, select the language you want to use.
Note that not all languages can be used for spell checking.
- 6** Ensure that the **Use this language for spell checking** option is enabled.
If there are several languages installed, you can enable or disable the **Use this language for spell checking** option for those languages as well.
- 7** Click **Done**.

Installing additional Dictionaries

To add a dictionary to Chrome 49, execute these steps:

- 1** Click , then select **Settings** from the menu.

- 2 Browse to the end of the page and click **Show advanced settings**.
- 3 Scroll down until you reach the **Languages** section.
- 4 Click **Languages and input settings...**
- 5 In the **Languages** list, click **Add**. This opens the **Add language** dialog.
- 6 From the **Language** box, select the desire language.
- 7 Click **OK**.
- 8 If you want to use the language you added for spell checking, select it in the **Languages** list and ensure that the **Use this language for spell checking** option is enabled.
- 9 Click **Done**.

Limitations of the RM Browser Interface

RM Browser provides a powerful and flexible interface for working in Dimensions RM, including many convenient features not available in previous interfaces. However, RM Browser also lacks some features that where available in previous interfaces.

If you must on occasion utilize a feature that is not available in RM Browser, use an old interface for that purpose. However, we recommend that you use RM Browser for normal day-to-day operations.

The following sections list *some* of the features not available in RM Browser. The features below may, *or may not*, be added at some point in the future as priorities dictate.

Focusing Objects

RM Browser does not implement this feature. However, RM Browser does correctly display focus events in an object's history.

Internet Explorer's Compatibility View

Using Internet Explorer's Compatibility View is not recommended with RM Browser. To turn off Compatibility View, follow these steps:

- 1 Open Internet Explorer
- 2 Open Compatibility View Settings
 - **Internet Explorer 11**
 - Click on the cog in the top right corner
 - Unselect **Display intranet Sites in Compatibility View**
- 3 Select Compatibility View Settings
 - **Internet Explorer 8, 9 and 10**
 - Press the **Alt** key

- Open the **Tools** menu and click on **Compatibility View settings**
 - Unselect **Display intranet Sites in Compatibility View**
 - Unselect **Display all websites in Compatibility View**
- 4** If the server is listed in the list of websites, remove this server from the list.

Chapter 2

Configuring User Settings and Project Settings

User Settings Versus Project Settings	50
Configuring User Settings and Project Settings	50
Customizing My Work Page	57

User Settings Versus Project Settings

By default, RM Browser uses the project settings that are in effect for a given project. If the RM administrator changes the project settings, this affects all users who have not specified their own settings. Each user can override the project settings by specifying their own. The following sections describe user settings and project settings.



NOTE

- If this guide refers to a **Use Project settings** checkbox, this checkbox only exists in the **User Settings** dialog.
- Some settings are grayed out and cannot be edited in the **User Settings** dialog. These settings are administrative settings and can only be changed in the **Project Settings** dialog (thus affecting all users).

Configuring User Settings and Project Settings

The following sections describe how to specify user and project settings. Each sub-chapter refers to the settings you select in the pane on the left hand side.

To open the User Settings dialog:

Select **User Settings** from the **Welcome** menu at the top right corner of the screen.

To open the Project Settings dialog:

Select **Project Settings** from the **Administration** menu. You can select **Project Settings** only if your user account is in the Administrator group.

General Settings

Concurrent Editing

This setting can only be changed in the **Project Settings** dialog.

RM Browser can be configured to use locking or merging to handle the situation where multiple users edit a requirement, chapter, or document at the same time. If locking is in effect and another user has an item locked, you will see that the item is locked and by whom if you open it for editing.



NOTE Baseline Locked indicates that the item version is part of a baseline and thus cannot be modified. This is unrelated to concurrent editing mode.

To specify the concurrent editing mode:

- 1 If you want to lock a requirement while you edit it, which means that no other user can make changes without unlocking it, select **Lock requirements while editing**.

- 2 If you want to allow others to make changes to a requirement while you are editing it, which means that the changes must be merged later, click **Allow concurrent editing and merging**.
- 3 Click **OK**.

Client Session Idle Timeout

This setting can only be changed in the **Project Settings** dialog.

After a period of inactivity, an RM Browser session times out, and you are logged out of RM Browser. A login dialog opens so you can log in again. By default, the session timeout is 30 minutes.

To specify the RM Browser session time out value:

- 1 Type the number of minutes in the **Client session idle timeout (minutes)** box.
- 2 Click **OK**.

Change Reason

This setting can only be changed in the **Project Settings** dialog.

You can require users to specify change reasons for new and changed proposals. For further information about proposing requirements, see chapter "[Proposing a New Requirement](#)" on page 87.

The following rules apply to change reasons depending on whether they are set to mandatory:

- When replacing requirements, the change reason is mandatory in the edit page.
- When updating requirements, even if the change reason is mandatory, if you do not enter a new reason the previously entered reason will be carried forward.
- When rejecting requirements.

To require change reasons for change requests:

- 1 Select **Project Settings** from the Administration menu. This opens the **Project Settings** dialog.
- 2 Select **General**.
- 3 Select either of the following in the **Change Reason** section:
 - **Make Change Reason Mandatory for Propose New**
 - **Make Change Reason Mandatory for Propose Change**

Container: Automatic Refresh

You can choose whether all containers and collections based on queries and scripts should be refreshed by default when they are opened. This may affect performance. If collections based on queries significantly slow performance, you can manually refresh their content as needed as well. For further information, see chapter "[Refreshing the Contents of a Container](#)" on page 188.

To automatically refresh containers based on queries:

- 1 In the **Containers** section, select the **Automatic Refresh** checkbox.
- 2 Click **OK**.

Display Settings for User Attributes

This setting can only be changed in the **Project Settings** dialog.

By changing this setting you can define how user attributes will be displayed. This affects custom attributes as well as the system attributes **Created By**, **Initial Created By** and **Modified By**.

To change the display settings, execute these steps:

- 1 Select **Project Settings** from the **Administration** menu. This opens the **Project Settings** dialog.
- 2 Select **General**.
- 3 In the Display Settings for User Attributes section, select one of these options:
 - **Show User ID**: Shows only the user ID, e.g. JOE.
 - **Show User Full Name**: Shows only the user's full name, e.g. Joe Manager.
 - **Show User Full Name and User ID**: Shows the user's full name and ID, e.g. Joe Manager (JOE).
 - **Show User ID and User Full Name**: Shows the user ID and the full name, e.g. JOE (Joe Manager).



CAUTION! When importing user attributes, the setting must be **Show User ID**.

Agile

This setting can only be changed in the **Project Settings** dialog.



IMPORTANT! Before enabling Agile, ensure that all required classes and relationships have been created by your Administrator. For further information on creating classes and relationships see chapter "Agile" in *Dimensions RM Administrator's Guide*.

To enable Agile, execute these steps:

- 1 Select **Project Settings** from the **Administration** menu. This opens the **Project Settings** dialog.
- 2 Select **General**.
- 3 Select the **Agile** option.
- 4 Click **OK**.

Quick Search Settings

Displayed Columns and Sort Order

By default, project display properties determine the columns that are displayed in the Quick Search results for a specific class. You can personalize your Quick Search results, overriding the project settings.



NOTE The project defaults are set by the administrator in the **Project Settings** dialog.

To change the columns displayed in Quick Search results:

- 1 Select a class in the **Choose a class** list. The **Attributes To Display** and **Sorting Order** sections are displayed.
- 2 **Use project settings:** Deselect this checkbox to override the display and order settings set by your administrator at the project level for the selected class.



NOTE This first **Use project settings** checkbox appears in the upper portion of the dialog just below the Sorting Order controls. It applies only to the display and order settings of the selected class. You cannot edit these settings until you disable this checkbox.

- 3 To specify the columns to display, see chapter "[Attributes to Display List](#)" on page 25.
- 4 To specify the sort order, see chapter "[Sorting Order List](#)" on page 25.
- 5 Select another class, if necessary, and repeat the preceding steps.



NOTE You do not have to click **Apply** before you select another class. The changes you make are remembered as long as the dialog box is open.

Additional Settings

Automatically run default query: Select this checkbox to run the most recently used search criteria when you open the page. If this feature is not enabled, the Quick Search fields will be populated with the criteria of the most recent search, but no results will be displayed until you click the Search button.

Use Project settings: Select this checkbox to override your local pagination settings with those set by your administrator at the project level.



NOTE This second **Use Project settings** checkbox appears in the lower portion of the dialog and applies only to the pagination settings. You cannot edit these settings until you disable this checkbox.

Activate Pagination: Select this checkbox to break the results up into multiple pages if they exceed a certain quantity. Specify that quantity in the **Number Of Records Display Per Page** field.



NOTE By default, only current requirement versions are shown in the results even if a baseline or snapshot is selected. To see the actual versions used in a baseline or snapshot, select the **Automatically activate query across all requirement versions if baseline or snapshot is selected** checkbox.

Split View

For configuration of Quick Search's Split View, see chapter "[Split View Settings](#)" on page 56.

Document Settings

Title Numbering

In Documents View in RM Browser, requirements and chapters are numbered. By default, when you publish a Microsoft® Word document from Documents View, the Word document includes the numbers you see in the document in Documents View.

To prevent the numbers from appearing in the Word document:

- 1 Use Project settings:** Deselect this checkbox in order to use your own numbering settings rather than those in the project settings.
- 2 Publish Chapter Title numbering:** Clear this check box if you want to create your own styles in Word for chapters that include automatic numbering. In this case, the automatic numbering may not match the numbers that you see in the document in Document View.
- 3 Publish Requirement Title numbering:** Clear this check box if you want to create your own styles in Word for requirements that include automatic numbering. In this case, the automatic numbering may not match the numbers that you see in the document in Document View.
- 4 Click OK.**

Autoloading of Documents

You set the default for autoloading of documents, that is, the document that was last opened in the previous RM Browser session is opened in the next session.

To set autoloading of documents:

- 1** Select or clear the **Auto load document** check box.
- 2** Click **OK**.

Lock Document During Edit

This setting can only be changed in the **Project Settings** dialog.

If this option is enabled, only one person can edit a document at a time. Any concurrent user opens this document in read-only mode and receives a message that this document is locked.

If this option is enabled, several users can edit a document at a time. For the following examples we assume that 2 users, JOE and EPHOTO are editing the same document:

Example 1:

JOE adds a chapter. EPHOTO adds a chapter after JOE.

EPHOTO will find JOE's chapter in his document tree, but JOE will not find EPHOTO's chapter in his document tree.

Resolution: JOE would either have to click  or add another chapter (which refreshes the document tree).

Example 2:

Both, JOE and EPHOTO, open the same chapter for editing. JOE saves his modifications first.

EPHOTO receives a warning that JOE made changes and that his changes can only be saved after the conflict has been resolved. For further information about resolving conflicts, see chapter ["Merging Chapter Changes" on page 162](#).

Default Requirement Layout

The **Default Requirement Layout** option defines the default layout for requirements in a document. This default is only used when creating a document. After a document has been created, the default for that document can be changed in the **Format Document** or **Format Chapter** dialog as described in chapters ["Formatting Documents" on page 133](#) and ["Formatting Chapters" on page 136](#).

To change the default requirement layout:

- 1 In the **Document Settings** group, select one of these options from the **Default Requirement Layout** list box:
 - Editable Grid
 - Grid
 - Paragraph
- 2 Click **OK**.

Report Settings**Traceability Settings**

For traceability report, you can change between Gap View and Outline View. The default view is defined in the User Settings dialog.

To set the default view:

- 1 In the **Traceability Settings** group, select **Gap** or **Outline** from the **Default View** list box.
- 2 Click **OK**.

Link Browser Settings

For Link Browser, you can change the colors for each class and the node radius.

To change the class color:

- 3 Select a class name from the **Choose a class** list.
- 4 Select a color from the **Choose a color** list.
- 5 Click **OK**.

To change the node radius:

- 1 Ensure that the **Use Project Settings** box is cleared before changing.
- 2 Do one of the following:
 - a Enter a number (minimum 40) into the **Node radius (px)**.
 - b Select the **Fit to PUID** check box. This will adjust the node radius to fit the length of the requirement ID.
- 3 Click **OK**.

Split View Settings

For the Split View mode of Quick Search you can define separately which columns you want to display in Split View mode.

To change the columns displayed in Split View mode:

- 1 Select a class in the **Choose a class** list. The **Attributes To Display** and **Sorting Order** sections are displayed.
- 2 **Use project settings:** Deselect this checkbox to override the display and order settings set by your administrator at the project level for the selected class.
- 3 To specify the columns to display, see chapter "[Attributes to Display List](#)" on page 25.
- 4 To specify the sort order, see chapter "[Sorting Order List](#)" on page 25.
- 5 Select another class, if necessary, and repeat the preceding steps.



NOTE You do not have to click **Apply** before you select another class. The changes you make are remembered as long as the dialog box is open.

- 6 **Auto Run Query:** Select this checkbox to run the most recently used search criteria when you open the page. If this feature is not enabled, the Quick Search fields will be populated with the criteria of the most recent search, but no results will be displayed until you click the Search button.

- 7 **Limit Number Of Records Displayed In Grid:** Specify the number of records to be displayed.
- 8 Click **OK**.

Customizing My Work Page

You can specify up to seven expandable sections to appear on your My Work page. Each section displays the results of a query.



NOTE You must have "read" access to run the default scripts and filters that are provided on your My Work page. You must be granted "read" access to all scripts to access the default scripts and filters, because it is not possible to grant access to these scripts and filters specifically. You must also be in a group that has access to the categories where the scripts exist.

The following prebuilt sections are available.



NOTE The **Recent Comments**, **Recently Changed Requirements**, and **Recent Polls** sections are displayed by default.

- **Proposals** — If the **Filter By Me** option is clear (this is the default setting), this section shows proposals that were created or updated by **any user**, and shows pending proposals that were submitted as requests for new requirements by **any user**.
If the **Filter By Me** option is selected, this section shows proposals that were created or modified by the **logged-in user** or where the associated requirement was created or modified by the **logged-in user**.
- **Recent Comments** — Shows comments that were added to requirements that were created or updated by any user within the specified timeframe.
- **Recently Changed Requirements** — Shows requirements that have been modified or created by any user within the specified timeframe.
- **Recent Polls** — Shows polls that meet the specified conditions within the specified timeframe.

You can also create custom sections based on the scripts of your choice.

To customize the My Work page:

- 1 From the My Work page, click **Customize** in the **Actions** menu. The Customize dialog box opens.
- 2 Select the check box next to each predefined query that you want to include. Clear the check box next to each predefined query that you do not want to include.
- 3 Select a timeframe for each predefined query that you want to include. The default timeframe for these queries is **in the last 14 days**.
- 4 Select the category or categories from which requirements should be included in the query results.

In the **Categories** lists in the predefined queries, click a category to select it. To select all categories that belong to a parent category, select the parent category, press Shift and then click the parent category. To select more than one category, press CTRL and click each category. To deselect a category, press CTRL and click the selected category. If you click a category without pressing CTRL, all other selections are removed.

To search for a category, type one or more letters from the category name in the **Find** box.

If no categories are selected, **Choose categories** is displayed in the list box, and all categories are included in the query.

If you select more than one category, **(n selected)** is displayed in the list box. If you select only one category, **Category Name** is displayed in the list box.


- 5 For the **Recent Polls** predefined query, select whether the poll state should be active polls, closed polls, or any poll; whether the participants should be you or anyone; and whether the poll was started by you or anyone.
- 6 For each custom section you want to include, do the following:
 - a Type the section title that you want to appear on your My Work page.
 - b Select the category from which you want to select scripts. The number of scripts that exist in each category is displayed in parentheses after the category name in the **Category** list.
 - c Select the script you want to associate with the section.
- 7 For each custom section that you want to remove, select **Choose script** or **Choose category, then script**.
- 8 Click **Save**.

Chapter 3

Working with the Home View

About the Home View	60
Dashboard Tab	60
Documents Tab	67
Reports tab	67
Collections Tab	68
Baselines Tab	69

About the Home View




The Home View allows you selecting the document, report, collection, or baseline that you wish to work in. It includes the following elements:

- The top left element is the name of the category that was selected on the Home View. If the selection includes subcategories, the name of the top-most selected category is displayed.
- **Search:** This field limits the display in the active tab to those items that match the search string. The search is dynamic, and increasingly narrows the displayed results as you enter more characters. To return to displaying all items, delete the string from the Search field or click the **X** button in the Search field.
- **Tabs:** A number in the title of each tab indicates how many of each item type exist in the selected category. Double-click an item to open it in the relevant work page, or select the item and then click an action in the Actions pane. See the following subsections for a description of each tab.

Dashboard Tab

The dashboard allows you to add graphical and text reports. You can add an unlimited number of dashboards and each dashboard can have an unlimited number of reports. However, for a better overview, a maximum of 9 reports is recommended. To access your dashboard, select the **Home View** and click on the **Dashboards** tab.



Using Dashboards

To switch to another dashboard, select it from the list next to the **Add Widget** button. The dashboard reports use the requirements of the category selected in the Category Tree on the left hand side of the screen. This also means that if a dashboard was created for a category it is only available within this category or in the subcategories of that category if this was defined on creation of the dashboard.

Class reports and relationship reports allow multi-selection of requirements. For further information about multi-selection, see chapter ["Selecting Multiple Requirements"](#) on page 23.

Limiting Report Data

- Filter by Categories:** If selected, the dashboard only shows data matching the category in the **Categories** tree. If unselected, the dashboard shows all data.



NOTE If a report has constraints on one or more categories, it will override the category selected in the Categories tree. As a result, the report will show all requirements which match its category constraint.





- Include Subcategories:** If selected, the dashboard shows data from the selected category and its subcategories.



NOTE You can the **Include Subcategories** check box only, if **Filter by Categories** is selected.

Using Dashboard Widgets

When moving the cursor over the title bar of a report, these functions become available:


-  **Settings:** Opens the dialog *Edit Widget* dialog. This dialog offers the same functionality as the *Add Widget* dialog. For further information refer to chapter "Adding a Standard Report to the Dashboard" on page 64, "Adding a Graphical Report to the Dashboard" on page 64, or "Adding a Website to the Dashboard" on page 65.
-  **Fullscreen:** Magnifies the report that it fills the whole screen.
-  **Refresh:** Refreshes the data of the report. To refresh the data of all reports, click on **Refresh View** in the **Dashboard** group of the **Action** pane.
-  **Delete:** Removes the report from the dashboard.

Moving Widgets

You can move reports freely within the selected dashboard by following these steps:

- 1 Move the mouse pointer to the report you want to move.
- 2 Click on the title bar and keep holding the mouse button.
- 3 Move the report to the new position. The new position is marked by dashed lines. If a report is already at the new position, it is moved away.
- 4 Release the mouse button.

Resizing Widgets

Apart from resizing a report to full screen by clicking the Fullscreen icon  in the report's title bar, you can also resize it to fill one or several tiles by following these steps:

- 1 Move the mouse pointer to the bottom right corner of the report you want to resize. The mouse pointer changes to a double-arrow pointer.
- 2 Click on the corner and keep holding the mouse button.
- 3 Move the mouse pointer to the position to which you want to extend the report. If a report is already at the new position, it is moved away.
- 4 Release the mouse button.

Creating a Dashboard

To create a dashboard:

- 1 Go to the **Home View** and click on the **Dashboards** tab.

- Click the **+ New** button under the Dashboards tab or click **New** from the **Dashboard** group of the **Action** pane. This opens the *New Dashboard* dialog.



NOTE The dashboard will be available in the category selected in the Category tree and optionally also in the subcategories.

- Enter the **Title** of the dashboard.
- Select the **Visibility**. If your user account has the **Create Public** right, you can choose between **Public** and **Private**:
 - Public** means that other users can access the dashboard.
 - Private** means that only the user who created the dashboard can access it.
- If **Show in Subcategories** is checked it means that you can access the dashboard also in subcategories of the category it was created in.
- Select one of these layouts:



Freestyle: Allows to add reports anywhere on the dashboard.



Tile 9: Creates a matrix of 3x3 tiles.



Horizontal 3: Creates 3 rows of identical size.



Horizontal 2/3: Creates 2 rows with the first to use about 2/3 of the dashboard.



Horizontal 1/3: Creates 2 rows with the first to use about 1/3 of the dashboard.



Vertical 3: Creates 3 columns of identical size.



Vertical 2/3: Creates 2 columns with the first to use about 2/3 of the dashboard.



Vertical 1/3: Creates 2 columns with the first to use about 1/3 of the dashboard.

- Click on **Save**.

Adding a Standard Report to the Dashboard

Standard reports show their data in a table. To create your own reports, see chapter ["Working with Reports" on page 167](#).

To add a standard report to the dashboard:

- 1 Go to the **Home View** and click on the **Dashboards** tab.
- 2 Select a dashboard from the Dashboard list or create a dashboard as described in chapter ["Creating a Dashboard" on page 62](#).
- 3 Click on the **Add Widget** button under the Dashboards tab or click **Add Widget** from the **Dashboard** group of the **Action** pane. This opens the *Add Widget* dialog.
- 4 Ensure that the **Widget Type** box shows **Show a report**.
- 5 In the **Category** box, select the category in which the report is located.
- 6 Select a report.



TIP You can get a better overview by selecting an entry from the **Report Type** list and/or entering part of the report name into the **Title Filter** text box.

- 7 If you like, change the title of the report by changing the text in the **Widget Title** text box.
- 8 If the selected report uses runtime parameters, see chapter ["Using Reports with Runtime Parameters" on page 65](#).
- 9 Click **Save**.

Adding a Graphical Report to the Dashboard

Graphical reports show their data in with diagrams. To create your own graphical reports, see chapter ["Creating a Graphical Report" on page 177](#).

To add a graphical report to the dashboard:

- 1 Go to the **Home View** and click on the **Dashboards** tab.
- 2 Select a dashboard from the Dashboard list or create a dashboard as described in chapter ["Creating a Dashboard" on page 62](#).
- 3 Click on the **Add Widget** button under the Dashboards tab or click **Add Widget** from the **Dashboard** group of the **Action** pane. This opens the *Add Widget* dialog.
- 4 Ensure that the **Widget Type** box shows **Show a report**.
- 5 Select **Graphical** from the **Report Type** list.
- 6 In the **Category** box, select the category in which the report is located.
- 7 Select a report.



TIP You can get a better overview by entering part of the report name into the **Title Filter** text box.

- 8 If you like, change the title of the report by changing the text in the **Widget Title** text box.
- 9 If the selected report uses runtime parameters, see chapter ["Using Reports with Runtime Parameters"](#) on page 65.
- 10 Select the **Report Style** tab to select the style for the report.
- 11 Click **Save**.

Using Reports with Runtime Parameters

Some reports may require that you enter or select data when running the report. These runtime parameters must be defined when adding the report to the dashboard. If a report has runtime parameters, a tab named **Parameters** appears next to the **Report** tab.

To enter or select Runtime Parameters:

- 1 Select the **Parameters** tab.
- 2 Enter a value or select from the list of each parameter.



TIPS

- **Using Lists Parameters:**

To select or deselect all entries in a list, click **Select all** or **Deselect all**.

- **Using Category Parameters:**

To open or close all categories, click **Open all** or **Close all**.

To select or clear all categories, click **Check all** or **Uncheck all**.

Adding a Website to the Dashboard

Instead of reports, you can also add websites to the dashboard. The websites must use the http or https protocol. Other protocols, e.g. ftp or gopher are not supported.

To add a website to the dashboard:

- 1 Go to the **Home View** and click on the **Dashboards** tab.
- 2 Select a dashboard from the Dashboard list or create a dashboard as described in chapter ["Creating a Dashboard"](#) on page 62.
- 3 Click on the **Add Widget** button under the Dashboards tab or click **Add Widget** from the **Dashboard** group of the **Action** pane. This opens the *Add Widget* dialog.
- 4 Select **Show a website** from the **Widget Type** box.
- 5 Enter the URL to the website.



IMPORTANT! You must enter the protocol (http:// or https://) as a prefix to the URL, for example `http://www.serena.com`.

If you do not enter the protocol, the dashboard will show an error message instead of the website.

- 6 Enter a title for the website into the **Widget Title** text box.
- 7 Click **Save**.

Copying a Dashboard

When copying a dashboard you can set these properties:

- **Title:** The title of the dashboard.
- **Visibility:** If you are an administrator, you can choose between **Public** and **Private**:
 - **Public** means that other users can access the dashboard.
 - **Private** means that only the user who created the dashboard can access it.
- **Show in Subcategories:** If this checkbox is checked it means that you can access the dashboard also in subcategories of the category it was created in. To copy a dashboard:
 - 1 Go to the **Home View** and click on the **Dashboards** tab.
 - 2 Select a dashboard from the Dashboard list.
 - 3 Click **Save As** of the **Dashboard** group in the **Action** pane.
 - 4 Enter a new **Title**.
 - 5 Select **Visibility** and **Show in Subcategories** if required.
 - 6 Click **Save**.

Renaming a Dashboard

To rename a dashboard:

- 1 Go to the **Home View** and click on the **Dashboards** tab.
- 2 Select a dashboard you want to rename from the Dashboard list.
- 3 Click **Rename** of the **Dashboard** group in the **Action** pane.
- 4 Enter a new name in the *Rename Dashboard* dialog.
- 5 Click **Save**.

Deleting a Dashboard

Please note that deleting a dashboard is irreversible.

To delete a dashboard:

- 1 Go to the **Home View** and click on the **Dashboards** tab.
- 2 Select a dashboard you want to delete from the Dashboard list.
- 3 Click **Delete** of the **Dashboard** group in the **Action** pane.
- 4 Confirm the *Delete Dashboard* dialog.

Documents Tab

RMDEMO

[Dashboards \(2\)](#)
[Documents \(1\)](#)
[Reports \(91\)](#)
[Collections \(10\)](#)
[Baselines \(2\)](#)

Search [Show Dependent Documents](#)
[Hide Snapshots](#)

E		
ePhoto Requirements	ePhoto Requirements 1.0	26-AUG-2016
	ePhoto Requirements 2.0	26-AUG-2016

This is an alphabetical listing of the RM documents in the currently selected category or categories, as filtered by the Search field.

Show Dependent Documents/Hide Dependent Documents: This toggles the display of the child documents column, which displays any child documents of the currently selected master document. Showing dependent documents hides the snapshot display.

Show Snapshots/Hide Snapshots: This toggles the display of the snapshots column, which displays any snapshots of the currently selected document. Showing snapshots hides the dependent documents display.

Double-click an item to open it in the Document work page, or select the item and then click an action in the Actions pane. See [Chapter 5, "Working with Documents" on page 127](#).

Reports tab

RMDEMO

[Dashboards \(2\)](#)
[Documents \(1\)](#)
[Reports \(91\)](#)
[Collections \(10\)](#)
[Baselines \(2\)](#)

Search

CLASS	RELATIONSHIP	TRACEABILITY
Component_Requiremen	A	C
Defects	All Current Component R	Component Requirement
Marketing_Requirements	All Current Data Comp R	Component Requirement
Product_Requirements	All Current Defects	Component Requirement
Tests		

This is an alphabetical listing of the reports in the currently selected category or categories, as filtered by the Search field. It contains separate columns for each type of

report: Class, Relationship, and Traceability. The Class list includes a folder for each class that has reports. The other two lists are simple alphabetical lists.

Double-click an item to open it in the relevant report work page, or select the item and then click an action in the Actions pane. See [Chapter 6, "Working with Reports" on page 167](#).

Collections Tab

RMDEMO

Dashboards (2) Documents (1) Reports (91) **Collections (10)** Baselines (2)

Search

E

- Engineering Hot List
- ePhoto - Release 1.0
- ePhoto - Release 1.1
- Ephoto Hot List

H

- Hot Lists

This is an alphabetical listing of the collections in the currently selected category or categories, as filtered by the Search field.

Double-click an item to open it in the Collections work page, or select the item and then click an action in the Actions pane.

After opening a collection, you select multiple requirements. For further information about multi-selection, see chapter ["Selecting Multiple Requirements" on page 23](#).


Baselines Tab

RMDEMO


Dashboards (2) Documents (1) Reports (91) Collections (10) Baselines (2)

Search

B

 Baseline of Engineering Hot List

S

 Specification Baseline - Release 1.0

This is an alphabetical listing of the baselines in the currently selected category or categories, as filtered by the Search field.

Double-click an item to open it in the Baselines work page, or select the item and then click an action in the Actions pane.

After opening a baseline, you select multiple requirements. For further information about multi-selection, see chapter "[Selecting Multiple Requirements](#)" on page 23.

Chapter 4

Working with Requirements

Requirement Basics	72
Working with Requirements and Change Requests	85
Viewing Requirement History	94
Merging Requirement Changes	100
Working with Containers	103
Working with Links	106
Working with Group Attributes	118
Working with File Attachments	120
Polling	121
Participating in Discussions	125

Requirement Basics

Finding Requirements with Quick Search

The Quick Search pane in Requirements View allows you to easily find requirements. You can filter the content by category, class, attribute and container. By default, the Quick Search pane is displayed when you navigate to Requirements View.

To run a query using the Quick Search pane:

- 1 Enter a word or string to narrow the query results to requirements that contain that text in one of their attributes.
 - If you enclose a string in quotation marks, the search returns requirements containing the whole string, even if there are spaces between words in the string.
 - If you do not enclose a string in quotation marks, the search returns requirements containing each of the individual words in the string.
- 2 Select the **PUID, Title, & Description only** check box if you want to search only the title and description attributes (displayed in the *Title* and *Text* columns). If you clear this check box, text and alphanumeric attributes that are visible are searched as well. System attributes are not searched.



NOTE This check box determines what is searched, but not what is displayed. The displayed columns are always the same. To change the displayed columns see chapter "[Quick Search Settings](#)" on page 53.

- 3 By setting a checkmark into the **Subcategories** checkbox you query results from the current category and child categories. If not checkmark is set, you query results only in the current category.
- 4 You can restrict your search by choosing any of these groups:
 - **Classes and Attributes**
 - To add more than one class click on the rightmost plus icon
 - To add attributes, click on the plus icon next to the class list
 - **System Attributes**

- **Containers**

- 5 If you chose to search by attribute, select the attribute and chose **Is** or **Is Not** to compare an attribute having a value. Choose **Null** to include requirements with an empty attribute. Choosing **Not Null** includes requirements where the selected attribute is not empty.
- 6 Click the plus icon to add a new search criteria or click the minus icon to remove search criteria.
- 7 If you choose **Container** or **Versions**, select **In** or **Not In** and choose to include or exclude the following from the search:
 - a A specific container
 - b A version at a specific state such as *Current*
- 8 To change the **Category**, there are two options:
 - a Change the category for the whole search by choosing from the list which is above the **Classes and Attributes** group
 - b Change the category for a single container by clicking on the link following the folder icon next to the container list
- 9 Click **Search** to execute the search.

**TIP**

- To reset the Quick Search configuration, click on **Default Filter** in the **Actions** pane.
- For multi-selection of requirements, see chapter "[Selecting Multiple Requirements](#)" on page 23.



NOTE Previous versions of RM Browser included empty sections if a search was made over all classes. With Dimensions RM 12.4.1, RM Browser only includes sections which contain requirements.

Finding Requirements with Group Attributes

Normally, all attributes have to match for making a query. As group attributes behave like a table with one or several values per row, Quick Search allows to define how the values in should be considered for the search. You can select one of the following:

- Is (AND)
- Is (OR)
- Is not (AND)
- Is not (OR)
- Null

- Not Null



NOTE When specifying only a single row in your query:



- **Is (AND)** and **Is (OR)** return the same results.
- **Is not (AND)** and **Is not (OR)** return the same results.

The following examples uses the **Tests** class of the **RMDEMO** project.

Is (AND)

When choosing the **Is (AND)** operator, a requirement is added to the result list if all values of the group attribute match all queried values.

Example:

- 1 Select the class **Tests**.
- 2 Add the attribute **Operating System**.
- 3 In the group attribute boxes, select **Desktop, Windows, XP**.
- 4 Click  .
- 5 In the group attribute boxes, select **Desktop, Windows, Vista**.
- 6 Click  .
- 7 In the group attribute boxes, select **Desktop, Windows, 7**.
- 8 Ensure that the box shows **Is (AND)**.
- 9 Click **Search**.

The result list contains one requirement: TEST_000003, which contains these values in the **Operating System** attribute:

- Desktop-Windows-7
- Desktop-Windows-XP
- Desktop-Windows-Vista





NOTE Quick Search would still find the requirement if it had extra values.

Is (OR)

When choosing the **Is (OR)** operator, a requirement is added to the result list if any of the values of the group attribute matches at least one of the queried values.

Example:

- 1 Select the class **Tests**.
- 2 Add the attribute **Operating System**.
- 3 In the group attribute boxes, select **Desktop, Windows, XP**.



- 4 Click  .
- 5 In the group attribute boxes, select **Desktop, Windows, Vista**.
- 6 Click  .
- 7 In the group attribute boxes, select **Desktop, Windows, 7**.
- 8 Ensure that the box shows **Is (OR)**.
- 9 Click **Search**.

The result list contains 34 requirements, which contain either **Desktop-Windows-XP**, **Desktop-Windows-Vista** or **Desktop-Windows-7** (among other values) in its **Operating System** attribute.

Is not (AND)

When choosing the **Is not (AND)** operator, a requirement is added to the result list if the values of the group attribute do not match all of the queried values.

Example:


- 1 Select the class **Tests**.
- 2 Add the attribute **Operating System**.
- 3 In the group attribute boxes, select **Desktop, Windows, XP**.
- 4 Click  .
- 5 In the group attribute boxes, select **Desktop, Windows, Vista**.
- 6 Click  .
- 7 In the group attribute boxes, select **Desktop, Windows, 7**.
- 8 Ensure that the box shows **Is not (AND)**.
- 9 Click **Search**.


The result list contains 49 requirements with the **Operating System** attribute does not have all of the following values: **Desktop-Windows-XP**, **Desktop-Windows-Vista** or **Desktop-Windows-7**.

Is not (OR)

When choosing the **Is not (OR)** operator, a requirement is added to the result list if the values of the group attribute do not match any of the queried values.

Example:

- 1 Select the class **Tests**.
- 2 Add the attribute **Operating System**.
- 3 In the group attribute boxes, select **Desktop, Windows, XP**.
- 4 Click  .

- 5 In the group attribute boxes, select **Desktop, Windows, Vista**.
- 6 Click  .
- 7 In the group attribute boxes, select **Desktop, Windows, 7**.
- 8 Ensure that the box shows **Is (OR)**.
- 9 Click **Search**.

The result list contains 16 requirements, which contain neither **Desktop-Windows-XP**, **Desktop-Windows-Vista** or **Desktop-Windows-7** in its **Operating System** attribute.

Null

When choosing the **Null** operator, a requirement is added to the result list if no group attribute value has been specified.

Not Null

When choosing the **Not Null** operator, a requirement is added to the result list if any group attribute value has been specified.

Refreshing Data

To refresh the current work page, select **Refresh View** from the first group in the Actions pane.



NOTE Pressing the F5 key in RM Browser does not refresh the displayed data. This action instead brings the RM Browser page to its initial state.

Printing Requirements

You can print the contents of the Editable Grid or Grid views.



NOTE To print the From view of a single requirement, see ["Printing a Requirement" on page 91](#).

To print a work page:

- 1 Select **Print to fit** from the top group of the Actions pane. A window opens with the content formatted for printing.
- 2 Your systems's Print dialog opens. Click **Print**. The content is sent to your printer.
- 3 After the content has printed, close the window of formatted content.

Exporting Requirements

To export the requirements, follow these steps:

- 1 Click **Export As** in the **Category** group of the **Action** pane
- 2 Select the desired file format. These formats are available:

- Excel Spreadsheet (*.xls)
- Word Document (*.docx)
- PDF Document (*.pdf)
- XML Document (*.xml)
- Web Page (*.html)
- CSV (Comma delimited) (*.csv)
- Plain Text (*.txt)
- Plain Text Table (*.txt)

3 Click on one of these buttons:

- **All Pages:** Exports all requirements
- **Selected Page:** Exports the requirements of the currently selected page. If there are no pages, the result is identical with **All Pages**.



NOTE

- On the server, Microsoft Word is required to generate DOCX and PDF files. If Microsoft Word is not installed on the server, Microsoft Word documents are created with file extension .doc instead of a DOCX or PDF file. When opening a .doc file, you might receive a message that informs you that this file is in a different format than .doc. You can safely click **Yes** in this dialog box and the file will open in Word.
- If a .doc file is created, all links in the Table of Contents point to page number one. To correctly number the entries in the Table of Contents, right-click the Table of Contents and select **Update** in the context menu.
- When exporting *Test Case* or *Test Run* requirements (as defined for "[Test Case Management](#)" on page 213) to CSV format:
 - The Test Step columns will be split into these individual columns:
 - Test Steps - Description
 - Test Steps - Expected Result
 - Test Steps - Actual Result (only for *Test Run* requirements)
 - The Test Step number will not be exported.



CAUTION! When exporting *Test Case* or *Test Run* requirements (as defined for "[Test Case Management](#)" on page 213) to CSV format, you **must** include an ID column (PUID or object ID) if you want to re-import the CSV file. For further information about importing *Test Case* or *Test Run* requirements, see chapter "[Importing Test Case and Test Run Requirements](#)" on page 207.

Understanding a Saved XML Document

This section includes excerpts from an example XML document that is produced from the Save As XML command, and a table that describes the elements in the excerpts.

```

1 - <?xml version="1.0" encoding="iso-8859-1" ?>
2 - <REPORT name="Baseline Check" project="SPRINT5" user="EPHOTO"
3 -   xmlns="http://schemas.serena.com/rm/2005">
4 - <SUBREPORT>
5 - <LAYOUT>
6 -   <COLUMN name="PUID" attrId="26" classId="1">PUID</COLUMN>
7 -   <COLUMN name="TEXT" attrId="31" classId="1">Baseline 1</COLUMN>
8 -   <COLUMN name="PUID" attrId="26" classId="1">PUID</COLUMN>
9 -   <COLUMN name="TEXT" attrId="31" classId="1">Baseline 2
10 -     Modifications</COLUMN>
11 - </LAYOUT>
12 - <SCHEMA>
13 -   <CLASS name="MARKETING_REQUIREMENTS" id="1">
14 -     <ATTRIBUTE name="PUID" id="26" type="puid" mandatory="false" editable="false"
15 -       unique="false" visible="true">
16 -       <FORMAT>MRKT_<#></FORMAT>
17 -       <DISPLAYNAME>Rqmt ID</DISPLAYNAME>
18 -     </ATTRIBUTE>
19 -     <ATTRIBUTE name="TEXT" id="31" type="text" mandatory="true" editable="true"
20 -       unique="false" visible="true">
21 -       <DEFAULTVALUE>Dummy Text</DEFAULTVALUE>
22 -       <DISPLAYNAME>Text</DISPLAYNAME>
23 -     </ATTRIBUTE>
24 -   </CLASS>
25 - </SCHEMA>
26 - <requirement class="MARKETING_REQUIREMENTS" id="1" version="1"
27 -   puid="MRKT_000001">
28 -   <attribute id="PUID">MRKT_000001</attribute>
29 -   <attribute id="TEXT">
30 -     This system shall enable the user to browse an on-line photo album. It
31 -     shall look and feel just like an electronic photo album.
32 -   </attribute>
33 - </requirement>
34 - <LINK name="Marketing_Requirements_CHANGE">
35 - <requirement class="MARKETING_REQUIREMENTS" id="8" version="1"
36 -   puid="MRKT_000001">
37 -   <attribute id="PUID">MRKT_000001</attribute>
38 -   <attribute id="TEXT">
39 -     shall look and feel just like an electronic photo album.
40 -   </attribute>
41 - </requirement>
42 - <LINK name="Marketing_Requirements_CHANGE">
43 - <requirement class="MARKETING_REQUIREMENTS" id="8" version="1"
44 -   puid="MRKT_000001">
45 -   <attribute id="PUID">MRKT_000001</attribute>
46 -   <attribute id="TEXT">
47 -     The ePhoto system shall enable the user to browse an on-line photo
48 -     album. It shall look and feel just like an electronic photo album, just
49 -     like the one on the coffee table.
50 -   </attribute>
51 - </requirement>
52 - <requirement class="MARKETING_REQUIREMENTS" id="42" version="1"
53 -   puid="MRKT_000001">
54 -   <attribute id="PUID">MRKT_000001</attribute>
55 -   <attribute id="TEXT">
56 -     The ePhoto system shall enable the user to browse an on-line photo
57 -     album. It shall look and feel just like an electronic photo album, just
58 -     like the one on the coffee table.
59 -   </attribute>
60 - </requirement>
61 - </LINK>
62 - </requirement>
63 - <requirement class="MARKETING_REQUIREMENTS" id="2" version="1"
64 -   puid="MRKT_000002">
65 -   <attribute id="PUID">MRKT_000002</attribute>

```

⑩

```

</attribute>
</requirement>
</SUBREPORT>
<SCRIPT>
- <![CDATA[
select <PUID>PUID <Baseline 1>TEXT from Marketing_Requirements where
group in ('Baseline 1') and STATUS != 'Deleted'

xref source secondary_history

select <PUID>PUID <Baseline 2 Modifications>TEXT from
Marketing_Requirements where group in ('Baseline 2')

plus

select <PUID>PUID <Baseline 2 Additions>TEXT from
Marketing_Requirements where group in ('Baseline 2') and group not
in ('Baseline 1') and NOT_SECONDARY_IN immediate

plus

select <PUID>PUID <Baseline 1 Deletions>TEXT from
Marketing_Requirements where group in ('Baseline 1') and
STATUS='Deleted'
]]>
</SCRIPT>
</REPORT>

```

The following table describes the elements in the preceding excerpts. Note the following terms:

- **Tags** are enclosed by < > brackets.
- **Attributes** are anything of type name=value within a tag.
- **Content** is any plain text between opening and closing tags.

Key	Description
①	<REPORT> is the root tag in the XML document. It has attributes for the query name, the project name, and the user who performed the query.
②	A PLUS statement in a query can be used to join multiple scripts into one script. The outcome of the resulting script is multiple reports produced in one data extraction run. If a PLUS report is run, there are additional <SUBREPORT> tags for each subreport.
③	Each <REPORT> or <SUBREPORT> tag contains a <LAYOUT> tag that describes the mapping from the Dimensions RM attribute names and the display names to be used in a report.
④	The <SCHEMA> tag contains the classes used in the query and more details about the attributes involved. NOTE: The <LAYOUT> tag may define the same attribute more than once, but the <SCHEMA> tag displays the attribute only once.
⑤	The <CLASS> tag is created for each requirement that is returned from the query. The content of the tag is the class name and the class ID.

Key	Description
6	Each <ATTRIBUTE> tag has attributes for name, ID, and type; and mandatory, editable, unique, and visible flags. For each RM attribute of type "puid," "alphanumeric," or "date," a <FORMAT> tag is created. The attribute type determines the attributes of the <FORMAT> tag. For each Dimensions RM attribute of type "list," a <LISTVALUES> tag is created that lists the valid values for the attribute.
7	For each Dimensions RM requirement returned from the query, a tag is created that matches the Dimensions RM class name (for example, <requirement class>) and that contains the requirement ID. Each requirement tag then contains the attributes requested in the query (see element number 8).
8	For each Dimensions RM attribute requested in the query for a particular requirement, a tag is created that matches the Dimensions RM attribute name (for example, <TEXT>). The content of the tag is the value of the Dimensions RM attribute.
9	The XREF statement in a query allows you to show the linkage or traceability between requirements. If an XREF report is run, the relationships are shown as nested <LINK> tags. The "name" attribute is the name of a Dimensions RM relationship. The <LINK> tag contains tags for the related requirements. There may be more than one <LINK> tag at the same level to indicate multiple links to the same requirement. The same requirement may appear more than once in the XML output because of different relationships to the same requirement.
10	The last tag in the report is the <SCRIPT> tag. The content of the tag is the query string used for the query. Because it may contain incompatible XML text, it is wrapped in a [!CDATA] block to preserve all text.

Explaining Update and Delete Functions

Dimensions RM allows you to modify requirements in several fundamentally different ways. It is critical to understand the difference between these options:

- **Replace** creates a new version while maintaining a history of changes. This allows you to trace change to a requirement over time. This is the recommended method for changing requirements to ensure auditability.
- **Update** overwrites the content of the requirement version without maintaining a record of what was changed. This option is not recommended if you need to maintain a history, or audit trail, of changes to requirements over time. A Trend report for example requires the history information to calculate the trend. All other attributes, including Current Status, remain intact.
- **Delete** marks the requirement as deleted and makes it unavailable for modification. However, it remains in the database and can be undeleted later on. By default, deleted requirements are not visible; however, you can query for them.
- **Remove** removes the current version of a requirement from the database and makes the previous version current. Unlike Delete, a removed requirement cannot be restored.
- **Undelete** restores a requirement which has been deleted with the Delete function.

Viewing Information about a Class

When entering data into the form or dealing with a workflow, there might be situations where the information provided by the form may not describe the required action clearly enough.

To view the class information, follow these steps:

- 1 Open a requirement or create a new requirement of the desired class.
- 2 At the top of the window, click **Get Help for this Class**.
This opens the **Information about class: Class Name** dialog.

The **Information about class** dialog provides these informations:

- Class description
- Workflow diagram (if class uses a workflow)
- State descriptions
- Transition descriptions
- Custom attribute descriptions
- System attribute descriptions

About Requirement Versions

When replacing a requirement, a new version of the requirement is created. These versions allow to follow the requirement history as you can open a previous version of a requirement and compare it with any other requirement version. For further information about a requirement's history, see chapter ["Viewing Requirement History" on page 94](#).

To inform you that the requirement you opened is not the current version, a warning message is shown in the **Edit Attributes** dialog. This warning message disappears after 5 seconds. Then, you can click the **Edit Current Version** link which loads the current version of the requirement.

About Requirement Locks



NOTE RM Browser can be configured to use locking or merging to handle the situation when multiple users want to edit a requirement or chapter at the same time. This section describes the locking mechanism. See ["Merging Requirement Changes" on page 100](#).

This configuration is set through the Project Settings dialog, which is available only to administrators. For further information, see chapter ["Concurrent Editing" on page 50](#).

Requirements and chapters (including the "root chapter" of a document, which is the document itself) are locked persistently when you open the respective "edit" dialog box. When a requirement or chapter is locked, a lock icon is displayed in the dialog box banner, and other users cannot edit the requirement or chapter.

The lock icon is displayed in the following scenarios:

- The current user locked the requirement.
- Another user locked the requirement.

- The requirement is CM locked.
- The requirement is baselined.

In the last three scenarios, the user receives a warning message about the lock. A tooltip, which is displayed when you hover over the icon, indicates the reason the requirement is locked.

Locks are removed when one of the following occurs:

- You close the dialog.
- You save changes.
- You use the Administer Locks dialog to remove locks (see "[Managing Requirement Locks](#)" on page 243). Users can unlock the requirements or chapters they locked; users with *Unlock* permission can unlock requirements or chapters that others locked.
- An administrator uses RM Manage to grant the Unlock permission to users. For information about granting permissions, see the *Serena Dimensions RM Administrator's Guide*.

Workflows

For a requirement class, the administrator can define a workflow. A workflow ensures the proper flow of requirements using a defined process that consists of attributes, states and transitions. Requirements must follow this workflow from the time they are submitted.

Workflow Elements

A workflow consists of two elements: states and transitions.

State: A state is a position in a workflow where a requirement resides. While a requirement resides in a given state, it has an owner who is responsible for performing a specific task with the requirement before it can be transitioned to the next state. You can review all previous states of a requirement in the **State Change History** section.




Figure 4-1. State Change History

Transition: A transition activates the movement of a requirement from one state to another in the workflow. A user who has ownership of a requirement transitions the item to the next state in the workflow when the corresponding task is finished. To execute a transition, click the button with the desired transition name. You find these buttons on top of the **Edit Attributes** dialog for a requirement.




Figure 4-2. Transitions Return, Approve and Reject

Details: Clicking **Details** (at the bottom of the transition info), opens the transition details dialog.



Attribute	Prior Value	New Value
Text	This system shall make use of multiple Monitors.	This system shall make use of multiple Monitors. This system shall save the monitor dimensions and locations and recognize them when started.
Priority	Medium	High
Workflow State	In Analysis	In Review
Owner	EPHOTO	PRODUCT_MANAGER
File Attachment		Diagram.jpg
Manager	DEV_MANAGER	PRODUCT_MANAGER
Team		DEV

Figure 4-3. Transition Details Dialog

You can open the **History Differences** dialog by clicking  which is located in the title bar of the transition details dialog.

Transitioning Requirements to a different Workflow State

Each transition allows to show a dialog which must be completed for completion of the transition. If this is not required, the administrator can configure the transition that no dialog is shown. In this case, the transition completes immediately.

Transitioning a Single Requirement to a different Workflow State

To transition a single requirement, do the following:

- 1 Open the **Edit Attributes** dialog for the requirement. For further information on how to edit a requirement, see chapter ["Editing a Requirement" on page 88](#).
- 2 Click the desired transition button which us at the top of the dialog.

Transitioning Several Requirements to a different Workflow State

To transition several requirements, do the following:

- 1 Perform a search in Quick Search to find the requirements you want to transition. For further information on how to find requirements, see chapter ["Finding Requirements with Quick Search" on page 72](#).
- 2 Select the requirements you want to transition.
- 3 Click **Execute Transition** in the Requirements group of the Actions pane. This opens the Execute Transition for **Multiple Requirements** dialog.
- 4 Select the desired transition from the **Transition** box.
- 5 Click **OK**.
If the transition is a regular transition, this opens a dialog for editing the attribute

values of the requirement(s). Continue with step [Step 6](#).


If the transition is a quick transition (which shows no form) this starts execution of the transition: Continue with [Step 8](#).

- 6 Fill out the fields of that dialog.



NOTE

- If multiple requirements are transitioned, the values specified will be used for all requirements..
- Empty attribute values (or lists without a selected value) do not reset the values, but does not change the attribute values of the requirement(s).

- 7 Click **OK** to start execution of the transition.
- 8 When the process has completed, the **Transition Result** dialog opens. To view the IDs of the transitioned requirements, expand the result list by clicking .

Copying the URL of a Requirement to the Clipboard

You can copy the URL of a requirement and paste it into a file for future use and reference. When that URL is later invoked, it will open RM Browser to that requirement.

You can copy a URL that will always lead to the most current version of the requirement, or you can copy a URL to a specific version of the requirement. See the appropriate section below.

Copying the URL of the Latest Version of a Requirement

To copy the URL of the latest version of a requirement:

- 1 Open the requirement for editing. See ["Editing a Requirement" on page 88](#).
- 2 Expand the **System Attributes** section of the Edit Attributes dialog.
- 3 Right-click on the URL labeled as the **Requirement Link**.
- 4 Select **Copy Shortcut** (or a similar menu item, depending upon the browser you are using).

The URL is now on the Windows clipboard. You can now paste it into the file in which you wish to keep it.

Copying the URL of a Specific Version of a Requirement

To copy the URL of a specific version of a requirement:

- 1 Open the requirement for editing. See ["Editing a Requirement" on page 88](#).

- Expand the **History** section of the Edit Attributes dialog.

TIME MODIFIED	OBJECT ID	MODIFIED BY	CURRENT STATUS
18-MAY-2006@08:59:35	21	EPHOTO	Replaced (Baselined)
09-DEC-2014@16:29:53	80	JOE	Current

- Right-click the link icon next to the version that you want.
- Select **Copy Shortcut** (or a similar menu item, depending upon the browser you are using).

The URL is now on the Windows clipboard. You can now paste it into the file in which you wish to keep it.

Working with Requirements and Change Requests

Creating a New Requirement

You can create a new requirement if you have **Create** permission for the class to which the requirement belongs. If you do not have **Create** permission, but you do have **CreateCR** permission, you can submit a change request for the new requirement. See "[Proposing a New Requirement](#)" on page 87.



TIP If you are using Firefox, you can enable the Firefox spell-check feature. Consult Firefox online help for more information.

To create a new requirement:


- Select **Requirement** from the **New** menu. The **New** dialog opens.
- Class:** Select the class to which the new requirement will belong. This list includes all of the classes for which you have "create" or "submit" permission.



NOTE



- If a requirement was selected or open when you invoked the dialog, the dialog opens with a class already selected.
- If you invoked the New dialog by clicking the **Create New and Link** button in the **Links** section of the Edit Attributes dialog, you cannot change the class selection.

- Category:** Select the category to which the new requirement will belong.
- Attributes:** Complete the fields in the attributes sections, as needed. Attributes that are incomplete or incorrect are flagged with a red exclamation mark (❗). A green

check mark () indicates that the value is acceptable. To view a tip as to what values are acceptable, hover over the attribute's exclamation mark or check mark.

**NOTE**

- **Group Attributes:** If this section appears, the requirement class has been defined to include one or more group attributes. See ["Working with Group Attributes" on page 118](#).
- **Applying HTML Formatting:** If a text attribute can accept HTML formatting, a text formatting tool bar appears when you click in the attribute's field. See ["HTML Text Formatting Toolbar" on page 26](#).

- 5 **File Attachments:** To attach a file to the requirement, expand this section and click **Attach**. The Add Attachment dialog opens. Enter the full path to the file or click **Browse** to locate the file, and then click the **OK** button.
- 6 **Container:** To add the new requirement to a collection, expand this section and click one of the following buttons:
 -  **Create New Container & Add** to create a new Collection and add the new requirement to it. The Add to Containers - New Collection dialog opens. See ["Creating a New Collection" on page 191](#), but ignore the **Based on** section as that does not apply to this invocation of the dialog.
 -  **Add to Containers** to add the new requirement to an existing collection. The Add to Containers dialog opens. Select the desired collection or collections and click the **OK** button.
- 7 **Add as subrequirement:** (only appears if the New dialog was invoked from a document) If you invoked the dialog while a requirement was selected in a document, select this checkbox to add the new requirement as a subrequirement of the selected requirement; or deselect this checkbox to add the new requirement to the parent chapter of the selected requirement. If a requirement was not selected when you invoked the dialog, this checkbox does not appear, and the new requirement is added to whatever element was selected in the document tree.
- 8 **Close requirement after save:** Select this check-box to close the requirement after saving it. Otherwise, the requirement opens for editing after you save it.
- 9 Click one of the following buttons:
 - **Save** to create the new requirement and close the New dialog. The requirement opens for editing if the **Close requirement after save** checkbox is not selected. See ["Editing a Requirement" on page 88](#).
 - **Save & Copy** to create the new requirement and retain the attribute values for creating another new requirement.



NOTE An attribute is copied into the next requirement only if the administrator selected the **Populate On Copy** option when defining the attribute. See the *Administrator's Guide*.

- **Save & New** to create the new requirement and clear the attribute values for creating another new requirement.

Proposing a New Requirement

If you have permission to submit change requests (CreateCR), you can propose a new requirement. This is true even if you do not have permission to create new requirements. In doing so, you can specify the desired attributes for the new requirement.

To propose a new requirement:

- 1 Select **Propose New** from the Requirements group of the Actions pane. The *Propose New Requirement* dialog opens.
- 2 **Class:** Select the class to which the new requirement will belong. This list includes all of the classes for which you have **create** or **submit** permission.



NOTE If a requirement was selected or open when you invoked the dialog, the dialog opens with a class already selected.

- 3 **Category:** Select the category to which the new requirement will belong.
- 4 **Attributes:** Complete the fields in the attributes sections, as needed. Attributes that are incomplete or incorrect are flagged with a red exclamation mark (❗). A green check mark (✅) indicates that the value is acceptable. To view a tip as to what values are acceptable, hover over the attribute's exclamation mark or check mark.



NOTE

- **Group Attributes:** If this section appears, the requirement class has been defined to include one or more group attributes. See ["Working with Group Attributes" on page 118](#).
- **Applying HTML Formatting:** If a text attribute can accept HTML formatting, a text formatting tool bar appears when you click in the attribute's field. See ["HTML Text Formatting Toolbar" on page 26](#).

- 5 **File Attachments:** To attach a file to the requirement, expand this section and click **Attach**. The Add Attachment dialog opens. Enter the full path to the file or click **Browse** to locate the file, and then click the **OK** button.
- 6 **Reason for change:** Enter the reason you want to create a new requirement.
- 7 **ECP:** If you want to link the new requirement to an ECP class object, select the desired ECP from the list. If no ECPs have been defined, the list does not appear.



NOTE ECPs are a high-level change management class type (Engineering Change Proposal) that can be used to collect multiple change requests into a single package.

- 8 **Add change request to the document:** If you invoked the dialog from a Document work page, you have the option of adding the change request to that document.
- 9 Click one of the following buttons:
 - **Submit** to submit the change request and close the dialog.
 - **Submit & Next** to submit the change request and keep the dialog open for submitting another change request.



NOTE When creating a new proposal, links and collections are inherited from the original requirement. For further information, see chapters ["Inherited Links" on page 114](#) and ["Inherited Containers" on page 105](#).

Editing a Requirement

This section describes using the Edit Attributes dialog to edit an existing requirement.



TIP Some attributes can be directly edited in the Editable Grid view. In this view, it is possible to edit an attribute across multiple requirements at once. See ["Editable Grid, Grid, and Form Views" on page 20](#).

To edit a requirement:

- 1 After selecting the desired requirement in a work pane, select **Edit** from the Requirements group of the Actions pane. The **Edit Attributes** dialog opens.
- 2 **Category:** Click the arrow next to the category to select a different category.
- 3 **Attributes:** Complete the fields in the attributes sections, as needed. Attributes that are incomplete or incorrect are flagged with a red exclamation mark (❗). A green check mark (✅) indicates that the value is acceptable. To view a tip as to what values are acceptable, hover over the attribute's exclamation mark or check mark.



NOTES

- **List Attributes:** If an entry in a list appears in a different color, this entry has been deleted and cannot be selected.
 - **Group Attributes:** If this section appears, the requirement class has been defined to include one or more group attributes. See ["Working with Group Attributes" on page 118](#).
 - **User Attributes:** If a user attribute shows a user name with a link, you can open a popup window with the user information (e.g. full name, e-mail address, phone number) by clicking that link. Note that only those data will be available which have been entered upon user creation. If the user attribute shows a group name, the popup shows the users of the group.
 - **Applying HTML Formatting:** If a text attribute can accept HTML formatting, a text formatting tool bar appears when you click in the attribute's field. See ["HTML Text Formatting Toolbar" on page 26](#).
- 4 **File Attachments:** To attach a file to, or remove a file from, the requirement, expand this section. See ["Working with File Attachments" on page 120](#).
 - 5 **Comments:** To view comments associated with the requirement or participate in or start a discussion, expand this section. See ["Participating in Discussions" on page 125](#).
 - 6 **Container:** To add/remove the requirement to/from a collection, expand the Container section. See chapter ["Working with Containers" on page 103](#).

- 7 **Links:** To add links to or remove links from the requirement, edit linked requirements, clear suspect links, and select which attributes to display in the section, expand this section. See ["Working with Links" on page 106](#).



NOTE Any linked objects displayed here are the current version of the object. See the Container section for object links specific to the version in a container.

- 8 **Dimensions CM:** This section displays Dimensions CM projects and requests that are associated with this requirement.
- 9 **History:** This section displays information such as the date and time the requirement was modified, who modified it, and its status.
- 10 **Polls:** To create a poll associated with the requirement, modify an existing poll, vote in a poll, or view poll results, expand this section. See ["Polling" on page 121](#).
- 11 **Show navigation bar / Hide navigation bar:** Click to show/hide the navigation bar at the bottom of the dialog. You can browse through the requirements in sequence with the **First**, **Previous**, **Next**, and **Last** controls.
- 12 Click one of the following buttons:
- **Copy** to copy the attribute values for use in creating a new requirement. If the user does not have the **Create** right but the **CreateCR** right for classes, a proposal will be created instead. The New *ClassName* dialog opens (see ["Creating a New Requirement" on page 85](#)).



NOTE An attribute is copied into the next requirement only if the administrator selected the **Populate On Copy** option when defining the attribute. See the *Administrator's Guide*.

- **Copy with Links** As above, but includes links to other requirements.
 - **Update** to close the dialog and save your changes without creating a new version of the requirement. (This option is not recommended if you need to maintain a history, or audit trail, of changes to requirements over time.)
- Update & Next:** As above, except the dialog remains open and the next requirement is loaded. This version of the button appears when the Navigation Bar is visible.
- **Replace** to close the dialog and save your changes as a new version of the requirement.
 - **Replace & Next:** As above, except the dialog remains open and the next requirement is loaded. This version of the button appears when the Navigation Bar is visible.



NOTE If the requirement is in an ECP-controlled document that you have not assigned an ECP to, and **Update to Current (Tip)** is in effect, the action will be halted and you will receive a message upon clicking the **Replace** or **Replace & Next** button. See ["Assigning an ECP to a Document" on page 156](#).

Copying a Requirement

If you want to create a new requirement which is mostly identical to an existing requirement, you can copy that existing requirement and modify it before you submit it. You can create a new requirement if you have **Create** permission for the class to which the requirement belongs. If you do not have **Create** permission, but you do have **CreateCR** permission, you can propose a new requirement with the Copy function.

You can use the Copy function at these locations:

- In the **Edit Attributes** dialog by using the **Copy** or **Copy with Links** buttons.
- In the **Actions** pane by selecting a requirement. You can select requirements in these views:
 - **Requirements** View
 - **Document** View
 - **My Work** View

Expanding a Requirement

Expanding allows you to break down a requirement into several requirements. The linkage between the original requirement and the new requirements can be viewed in **Pedigree View** (see chapter "Using Pedigree View" on page 98).

To expand a requirement:

- 1 In **Requirements View**, select a requirement with object status **Current** or **Expanded**.
- 2 Click **Expand** in the **Requirements** group of the **Actions** pane. This opens the **New Class Name** dialog.
- 3 Make your modifications as desired.
- 4 Click **Save**.



NOTE Expanding a requirement sets the object status of the original requirement to **Expanded**. The new requirement has the object status **Current**.

Deleting a Requirement

When you delete a requirement, it is marked as deleted, but the data is retained. You can delete requirements whose state is "Current" if you have "Delete" permission for its class. When you delete a requirement, a new version is created to ensure that a full audit trail of the requirement's deletion is maintained.

To delete a requirement:

- 1 After selecting the desired requirement in a work pane, select **Delete** from the Requirements group of the Actions pane.
- 2 You are prompted to confirm the operation. Click the **OK** button.

Undeleting a Requirement

When you delete a requirement, it is marked as deleted, but the data is retained. When you undelete a requirement, a new version replaces the previous version to ensure that a full audit trail of the requirement's deletion is maintained.

To undelete a requirement:

- 1 After selecting a deleted requirement in a work pane, select **Undelete** from the Requirements group of the Actions pane.
- 2 You are prompted to confirm the operation. Click the **OK** button.

Removing a Requirement Version

When you remove a requirement, the selected version is permanently removed from the project, and the previous version is made current. You can remove requirements whose state is "Current" if you have "Remove" permission for its class.



CAUTION! A remove operation cannot be undone.


To remove a requirement:

- 1 After selecting the desired requirement in a work pane, select **Remove** from the Requirements group of the Actions pane.
- 2 You are prompted to confirm the operation. Click the **OK** button.

Printing a Requirement

You can print a requirement from the **Edit Attributes** dialog box.

To print a requirement:

- 1 After selecting the desired requirement in a work pane, select **Edit** from the Requirements group of the Actions pane. The Edit Attributes dialog opens.
- 2 You must expand sections and sub-sections if you wish to print their contents.
- 3  Click the **Print** button at the top right of the dialog box. A window opens with content formatted for printing; the RM controls shown in this window are non-functional.
- 4 Your system's Print dialog opens. Click **Print**. The requirement is sent to your printer.
- 5 After the content has printed, close the window that displayed the formatted content.

Viewing the Requirements in a Category, Document, Report, Collection, or Baseline

To view the list of requirements in a specific item:

- 1 Open the Home View by clicking .

- 2 To view the requirements in a:
 - **Category or sub-category**, select the desired categories in the Category pane. Then click **View Requirements** from the Category group of the Action pane.
 - **Document or snapshot**, double-click the desired document or snapshot in the Documents tab of the selection pane.
 - **Report**, double-click the desired report in the Reports tab of the selection pane.
 - **Collection**, double-click the desired collection in the Collections tab of the selection pane.
 - **Baseline**, double-click the desired baseline in the Baselines tab of the selection pane.


Submitting a Change Request





To submit a change request, you must have "Create CR" permission for classes.



NOTE To submit a change request that proposes the creation of a new requirement, see ["Proposing a New Requirement" on page 87](#).

To submit a change request for a requirement:

- 1 After selecting the desired requirement in a work pane, select **Change Request** from the Requirements group of the Actions pane. The Submit a Change Request dialog opens.
- 2 Change the attributes in the attributes sections as desired. Changes are marked by a triangle icon .
- 3 In the **Reason for change** box, type the justification for the change request. There is no practical limit to the number of characters. The HTML editing control is not available in the **Reason for change** field.
- 4 If you want to link the change request to an Engineering Change Proposal (ECP) class object, select the object in the **ECP** list. The **ECP** list box does not appear if no ECPs have been defined.
- 5 **Exchange in:** If the request was submitted from a document, you can select this checkbox to replace the version in the document with the new version.
- 6 Do one of the following:
 - Click **Submit** to submit the change request.
 - Click **Submit & Next** to submit the change request and then load the next requirement in the query results.
 - Please note:
 - The labels on the buttons vary depending on whether the navigation bar is shown or hidden. If it is shown, **Submit & Next** appears. If it is hidden, **Submit** appears.
 - You can also submit a change request for a new requirement from the **New Change Request** dialog box. For more information, see ["Proposing a New Requirement" on page 87](#).

- 7 The navigation bar at the bottom of the dialog box allows you to navigate to other requirements from the query from which the displayed requirement was generated. To hide the navigation bar, click **Hide navigation** bar. To show the navigation bar, click **Show navigation bar**. The navigation bar is not visible if there only one requirement in the query results. The name of the entity from which the list of requirements was generated is displayed in the navigation bar. These entities include a filter name, a script name, **Quick Search**, and **Query Results**.
- 8 To navigate to the next or previous requirement in the query from which the requirement was generated, click the next  or previous  button. To navigate to the first requirement or last requirement, click the first  or last  button.



NOTE When submitting a change request, links and containers are inherited. For further information see chapters ["Inherited Links" on page 114](#) and ["Inherited Containers" on page 105](#).

Reviewing a Change Request/Proposed Requirement

When a change request is accepted, the changed requirement replaces the current version of the requirement. If there are multiple change requests against the requirement, any requests that have not been rejected are linked to the new requirement. Therefore, you should reject unacceptable requests. For traceability, the replaced requirement is still linked to any change request, whether the request was accepted or rejected.

Pending Change Requests is a prebuilt section that you can add to your My Work page. When a change request is submitted against a requirement you own or a change request for a new requirement is submitted, the change request is added to this section.

To review change requests submitted against a requirement:

- 1 After selecting the desired requirement in a work pane, select **Approve/Reject** from the Requirements group of the Actions pane. The Approve Changes dialog opens.
- 2 A list of all pending change requests against the requirement is displayed in the left pane. Select a change request to view its details.

The differences between the proposed changes and the current version are marked in the text.
- 3 Enter a reason for accepting or rejecting the change, if necessary.
- 4 Click **Accept** to accept the change request or **Reject** to reject it. In either case the reason for change entered when the request was submitted will be carried forward.



NOTE If the requirement is in an ECP-controlled document that you have not assigned an ECP to, and **Update to Current (Tip)** is in effect, the action will be halted and you will receive a message upon clicking the **Accept** button. See ["Assigning an ECP to a Document" on page 156](#).

- 5 To accept a previously rejected change request, do the following:
 - a Click the **Show previously rejected requests** link at the top left of the dialog box.
 - b Select the rejected change request.

- c If you have permission to approve the rejected change request, the **Accept** button is enabled. Click the **Accept** button. Once you accept a rejected change request, you cannot reject it again.

6 Click **Close**.


Viewing Requirement History

A requirement history lets you track changes to a requirement over time. A **History** section is displayed on a requirement form if the requirement is displayed in grid format. You can select the attributes that you see in the form and the order in which the attributes are displayed. You can also use the **History** section to see the differences between the requirement that is open and a selected version of the requirement or between two other versions of the requirement.

To view the history of a requirement:


- 1 After selecting the desired requirement in a work pane, select **Edit** from the Requirements group of the Actions pane. The Edit Attributes dialog opens.
- 2 Expand the **History** section.

TIME MODIFIED	OBJECT ID	MODIFIED BY
05-OCT-2015@13:15:52	229	EPHOTO
05-OCT-2015@13:16:04	230	EPHOTO
05-OCT-2015@13:20:01	231	EPHOTO

Clicking  (preceding a history entry), opens the history details dialog between the current and the selected item.

Attribute	Prior Value	New Value
Text	This system shall make use of multiple Monitors.	This system shall make use of multiple Monitors. This system shall save the monitor dimensions and locations and recognize them when started.
Priority	Medium	High
Workflow State	Proposed	In Review
Owner	DEV_MANAGER	PRODUCT_MANAGER
File Attachment		Diagram.jpg
Manager	DEV_MANAGER	PRODUCT_MANAGER
Team		DEV

Figure 4-4. History Details Dialog


You can open the **History Differences** dialog by clicking , which is located in the title bar of the history details dialog.



Viewing History Differences

You can view the differences between the open requirement and a selected version of the requirement, or between two versions of the requirement.

To view the differences:


- 1 Expand the **History** section, if it is not already expanded.



TIME MODIFIED	OBJECT ID	MODIFIED BY	CURRENT STATUS
 18-MAY-2006@08:59:35	21	EPHOTO	Replaced (Baselined)
 09-DEC-2014@16:29:53	80	JOE	Current

- 2 Click **Differences**.
- 3 Perform one of the following actions:
 - If you want to compare the open requirement with another version of the requirement, select the other version and then click **Differences**.
 - If you want to compare two versions of the requirement, select them and then click **Differences**.

The **History Differences** dialog box opens, and contains visual indications of what changed between the two versions.



Note the following points:

- If only one version is displayed in the **History** section, and you click **Differences**, an error message is displayed, because you cannot compare a requirement to itself.
- If you select more than two versions in the **History** section, the **Differences** link is disabled, because you can only compare two versions at the same time.
- The version with the greater Object ID is used as the newer item.
- A new requirement is not displayed in the **History** section.
- In the default.xml file, the **History** section is called "history." If this conflicts with the name of a user-customized section, the administrator must modify the customization. For more information about Web form customizations, see the *Serena Dimensions RM Administrator's Guide*.

Changing the Attributes in the History Section

You can change the attributes that you see in the **History** section, and specify the order of the attributes.



NOTE

- In the **History Properties** dialog box, if you move all attributes from the boxes on the right to the **Attributes to Display** and **Sorting Order** boxes, the default attributes and sorting are used in the **History** section.
- The attributes and their order are remembered for each class and are used when viewing the history for any requirement in that class.








To change the attributes:


- 1 Expand the **History** section, if it is not already expanded.
- 2 Click **Properties**. The **History Properties** dialog box opens.
- 3 To specify the attributes to display, see chapter "[Attributes to Display List](#)" on page 25.
- 4 To specify the sort order, see chapter "[Sorting Order List](#)" on page 25.

Changing Requirement Versions in Documents

In some cases, you need to change the requirement within a document to a different version as the one which is already in the document. To do this, execute these steps:

- 1 Open the document with the requirement you want to change the version for.
- 2 Select that requirement.
- 3 Expand the **History** section.

History			
Pedigree			Properties Differences
	TIME MODIFIED	MODIFIED BY	CURRENT STATUS
  	18-MAY-2006@09:17:06	EPHOTO	Replaced
  	25-NOV-2014@08:23:23	EPHOTO	Replaced
	30-SEP-2015@01:54:24	EPHOTO	Current
Polls			

- 4 Find the version you want to use and click  . This opens the **Exchange Requirement** dialog.

Exchange Requirement x

Are you sure you want to exchange requirement 'MRKT_000029' version 3 with version 1?

Also exchange requirement in these document(s):

<input type="checkbox"/>	Name	Time Created	Time Modified	Modified By
<input checked="" type="checkbox"/>	ePhoto Tablet Requirements	02-AUG-2016@12:47:32	02-AUG-2016@12:49:01	JOE

By selecting the documents in the list, the requirement version will be exchanged for these documents as well. To select a document, click into the box next to its name. To select all documents, click the box in the heading (next to the **Name:** heading).



NOTE The **Exchange Requirement** dialog only shows those documents which have the **Update To Current (Tip)** option disabled.

- 5 Click **Yes**.

Using Pedigree View

Pedigree View is a graphical representation of the history of a requirement.

To open Pedigree View, follow these steps:

- 1 Select the desired requirement in the Requirements View.
- 2 Click **Pedigree** in the Requirements group of the Actions Pane. This opens the **Pedigree View** dialog.

If you the requirement is shown in the **Edit Attributes** dialog, you can follow these steps:

- 1 Expand the **History** section.
- 2 Click **Pedigree**. This opens the **Pedigree View** dialog.




Figure 4-5. Pedigree View of a requirement

The elements in the figure above have the following meaning:

- 1 This is the original requirement.
- 2 This is a modified version of #1.
- 3 This is a modified version of #2.
- 4 This is a rejected proposal based on #3.
- 5 This is an accepted proposal based on #3.
- 6 This is the requirement which resulted on the accepted proposal (#5). This requirement has been expanded (split) into 2 requirements (#7 and #8).
- 7 This is a requirement which was created by expanding #6.
- 8 This is a requirement which was created by expanding #6.

The Pedigree View tool bar provides these functions:



Reload: Reloads the Pedigree View dialog.



Download: Creates an image of the current Pedigree View dialog which can be downloaded.



Print: Prints the Pedigree View dialog.

The shortcut menu (right-click a requirement element), provides these functions:

Open: Opens the selected version of the requirement.

Expand: Expands the requirement.

Note that you can only expand requirements with object status **Current** or **Expanded**. For further information about expanding requirements, see chapter ["Expanding a Requirement" on page 90](#).

Show Differences: Opens the **History Differences** dialog which shows the changes between the selected version and the current version. Note that this function is not available if the selected version is the current version.

Browse Links: Opens **Link Browser** on the selected version of the requirement.

Pedigree: Opens another **Pedigree View** dialog for the selected requirement.



NOTE Pedigree View uses the settings of Link Browser. If you change the settings for Link Browser, this also changes the settings for Pedigree View.

Merging Requirement Changes



NOTE RM Browser can be configured to use locking or merging to handle the situation when multiple users want to edit a requirement or chapter at the same time. This section describes requirement merging. For information about the locking mechanism, see ["About Requirement Locks" on page 81](#).

This configuration is set in the **Project Settings** dialog. See ["Configuring Project Settings" on page 243](#).

If RM Browser is configured to use merging, requirement changes must be merged when two users edit a requirement at the same time.

Changes can be *automatic* or *conflicting*, as described in the following table.


Change Type	Description
Automatic	When the change made by the first user is the same as the change made by the second user or when the change made by the first user is distinct from any change made by the second user, automatic merging can occur because a review of the change is not strictly necessary. However, it is recommended that the second user review the change made by the first user before accepting it.
Conflicting	When the change the second user makes conflicts with the change the first user made, the second user must review the changes and do one of the following: <ul style="list-style-type: none"> ■ Accept the change the second user made ■ Accept the change the first user made ■ Accept the original value ■ Combine the changes manually by editing the value directly in the main part of the dialog box


The following scenario summarizes the actions that lead to requirement merging.


- 1 Two users edit a requirement at the same time.
- 2 The first user clicks **Replace** on the **Edit Attributes** dialog box. The requirement is replaced and the **Edit Attributes** dialog box closes.
- 3 The second user clicks **Replace** on the **Edit Attributes** dialog box.
- 4 The second user is notified that the first user made one or more changes to the requirement. The notification either tells the second user that the merge can be done automatically (because the change the first user made does not conflict with the change the second user made) or that the changes conflict and must be resolved before the second user can replace the requirement.
- 5 The second user clicks **OK** on the notification message. The **Edit Attributes** dialog box becomes the **Merge Attributes** dialog box. The **Merge Attributes** dialog box differs from the **Edit Attributes** dialog box in that the **Merge Attributes** dialog box:
 - Has a section at the top that summarizes the changes and provides a user interface for merging the changes
 - Does not have an **Update** button
 - Has visual indications next to its attributes that identify the type of merge that the second user selected
- 6 The second user uses the merge section at the top of the **Merge Attributes** dialog box to resolve the changes as described in ["Viewing Prior Versions of the Requirement" on page 102](#) and ["Merging Changes" on page 103](#).

Merge Status

The merge status of the changes made by Mary and Joe are highlighted in the **Changed Attributes** section at the top of the **Merge Attributes** dialog box.




Joe made the first change when he added "Windows XP" to the *Text* attribute. In the **Merge Status** column, **Automatic** is selected in the list, because the change does not involve a conflict with a change that Mary made. The icon that represents an automatic merge is a diamond shape with a merge arrow in it  and is displayed to the left of the **Merge Status** list and to the left of the **Text** attribute box in the main part of the dialog box.


The second change and third change involve conflicts. In the second change, Joe changed the *Verification Level* attribute value to **Component**, but Mary changed this attribute value to **Module**. In the **Merge Status** column, **Conflict** is selected in the list. The icon that represents a conflict is a triangle with an exclamation point in it  and is displayed to the left of the **Merge Status** list and to the left of the *Verification Level* attribute in the main part of the dialog box.

The third change also involves a conflict because Mary changed the *Verification Method* attribute value to **Inspection** while Joe changed it to **Analysis**.

Viewing Prior Versions of the Requirement

It can be useful to view prior versions of the requirement before you resolve changes.



- The second user can view the original version of the requirement by clicking the **View original version of requirement** button  or by clicking **Original** in the appropriate **Merge Status** column list.

- The second user can view the requirement in the state it was in after the first user made changes but before the second user made changes by clicking the **New version of requirement prior to your changes** button .

Merging Changes

After the second user has decided how to resolve the changes, he or she can merge them.




To merge changes:

- 1 If **Automatic** is selected in the **Merge Status** column list box, perform one of the following steps:
 - Retain the **Automatic** selection to accept the change.
 - Select the name of the user who made the change to accept the change.
 - Select **Original** to restore the attribute to its original value.
- 2 If **Conflict** is selected in the **Merge Status** column list box, perform one of the following steps:
 - Select the name of the user whose change you want to accept.
 - Select **Original** to restore the attribute to its original value.
 - Edit the value manually in the main form so that it matches the value you want to accept.
- 3 If you want to accept all changes made by a particular user (for example, Mary or Joe), click the **Accept all changes by Mary** button  or the **Accept all changes by Joe** button .
- 4 Click **Replace**.

Working with Containers

Containers can hold requirements of any class. You can add requirements of different classes into the same container. For further information about containers, see chapter ["About Containers" on page 186](#).

The **Container** section offers these functions:

	Properties: Opens the <i>Container Properties</i> dialog. For details see chapter "Container Properties" on page 105 .
	Add to Containers: Opens the <i>Add to Containers</i> dialog which allows to add the current requirement to an existing container. Add to Containers is available if the user has the <i>Link</i> right for classes and the <i>Link</i> right for collections.
	Remove from Containers: Permanently removes the requirement from the select container(s). Remove from Container is available if the user has the <i>Link</i> right for classes and the <i>Link</i> right for collections.
	Open Container: Opens the desired container. If the container is a document or snapshot, it will open at the first location of the requirement in the document. If the container is a collection or baseline, it will select the requirement which opened it.

The data of all containers the requirement has been added to is shown in a table. You can sort the entries of that table by clicking a column header. Clicking a column header toggles between ascending and descending sort order. A little arrow next to the sorted column name shows the sort order.

▲	Ascending order: The entries are sorted by the values of the marked column in ascending order (0...9, A...Z).
▼	Descending order: The entries are sorted by the values of the marked column in descending order (9...0, Z...A).


To create, remove, or view links in the context of a specific container, expand the container's subsection. See ["Working with Links" on page 106](#).




NOTE The version of any linked objects displayed here corresponds to the version of the object that is in the container. That may, or may not, be the current version of the object (see the Current Status column).

See the Links section if you want to see only links to the current version of an object.


Adding a Requirement to an Existing Container

- 1 Open the *Edit Attributes* dialog for a requirement.
- 2 Expand the **Container** section.
- 3 Click . This opens the *Add to Containers* dialog.
- 4 Select the containers you want to contain the requirement.
- 5 Click **OK**.

Removing a Requirement from a Container

- 1 Open the *Edit Attributes* dialog for a requirement.
- 2 Expand the **Container** section.
- 3 Select the containers you want to delete or to remove.
- 4 Click .

Opening a Container


- 1 Open the *Edit Attributes* dialog for a requirement.
- 2 Expand the **Container** section.
- 3 Click  next to the container you want to open.

Inherited Containers

When making a proposal, any containers on the originating requirement are inherited.

To identify inherited containers:

- 1 After selecting the desired proposal in a work pane, select **Edit** from the Requirements group of the Actions pane. The Edit Attributes dialog opens.




- 2 Expand the **Container** section.
- 3 Inherited containers are marked by .



NOTE When making a proposal, also the links of the original requirement are inherited. For further information, see chapter "Inherited Links" on page 114.


Container Properties

In the *Container Properties* dialog you can define which data should be displayed in the **Container** section.





To add columns:


- 1 Select one or more columns in the **Columns to Display** list.

- 2 Click  to add the selected columns.

To specify column order:

- 1 Select one or more columns in the right-hand list.
- 2 Click  or  to specify in which order you want the columns to appear.

To remove columns:

- 1 Select one or more columns in the right-hand list.
- 2 Click  to remove the selected columns.

Adding Requirements to an Existing Collection

From the Requirements view, you can add requirements to an existing collection or collections simply by selecting them and clicking a button.



TIP To add a larger and/or more complex set of requirements to a collection, use Attribute Constraints and Relationship Constraints. See "[Managing Requirements in a Collection](#)" on page 190.

To add requirements to an existing collection:

- 1 After selecting the desired requirements in a work pane, select **Add to Collection** from the Requirements group of the Actions pane. The Add to Containers dialog opens.
- 2 Select the desired collection or collections.



TIP To filter the list of containers, enter a string in the **Find Container** field.

- 3 Click the **OK** button.









Working with Links

Links allow you to relate requirements to each other. For example, you can link requirements in the Software Requirements class to requirements in the Test Case class. You can then run a traceability report that shows how many software requirements are covered by test cases.


In RM Browser, you can add links to or remove links from a single requirement. If you select a requirement from a category in which you do not have *Link* permission for the class, all classes, or the project, the **Create Link** command is disabled.


Links between object versions are maintained even as objects are replaced with new versions. For example, if you link the current versions of two objects and then replace each object with new versions, the link between the previous versions remains intact.


The **Links** section offers these functions:

	Properties: Opens the <i>Link Properties</i> dialog. For details see chapter " Link Properties " on page 112.
	Link Existing: Opens the <i>Link Requirements</i> dialog which allows to link the current requirement to an existing requirement. Link Existing is available if the user has the <i>Link</i> right for classes and the <i>Create</i> right for relationships.
	Create New & Link: Opens the <i>New Class_Name</i> dialog and links the created requirement. Create New and Link is available if the user has the <i>Link</i> right for classes, the <i>Create</i> right for classes and the <i>Create</i> right for relationships.
	Propose New & Link: Opens the <i>Propose New Requirement</i> dialog and links the created proposal. Propose New & Link is available if the user has the <i>Link</i> right for classes, the <i>CreateCR</i> right for classes and the <i>Create</i> right for relationships.
	Delete Link: Deletes the selected link. Delete Link is available if the user has the <i>Link</i> right for classes and the <i>Delete</i> right for relationships.
 	Remove Link: Permanently removes a link. Remove Link is available if the user has the <i>Link</i> right for classes and the <i>Remove</i> right for relationships. CAUTION! You cannot restore a removed link.
	Undelete Link: Restores a deleted link. Undelete Link is available if the user has the <i>Link</i> right for classes and the <i>Undelete</i> right for relationships. For details on how to undelete a deleted link, see chapter " Link Properties " on page 112.
	Resolve Suspicion: Clears one or several suspect links. Resolve Suspicion is available if the user has the <i>Link</i> right for classes and the <i>Clear Suspect Links</i> and <i>Mass Clear Suspect Links</i> rights for relationships. For details about clearing suspect links see chapter " Suspect Links " on page 112.

Linking an Existing Requirement

- 1 Open the *Edit Attributes* dialog for a requirement.
- 2 Expand the **Links** section.
- 3 Expand the class which contains the requirement you want to link to.
- 4 Click  . This opens the *Link Requirements* dialog.
- 5 **Constraints:** As needed, specify criteria to locate the desired requirements. See "[Attribute Constraints Tab](#)" on page 28 and "[Relationship Constraints Tab](#)" on page 31.
- 6 **Display Options:** As needed, specify how to display the results. See "[Display Options Tab](#)" on page 34.
- 7 **Remember these options:** Select this checkbox to retain the current settings as the default for future invocations of the dialog.

- 8 Find Now:** Click this button to run the search. The results are displayed in the lower pane of the dialog. Each requirement that is linked to the original requirement has a chain icon  next to it.

Rqmt ID	Title
 COMP_000001	Utilize Tcl/Tk
COMP_000002	Application settings will be saved
COMP_000003	Default window size 140x100

- 9 New Search:** Click this button to clear the current search criteria and results.
- 10** Select the requirements you want to link to. For multi-selection of requirements, see chapter ["Selecting Multiple Requirements" on page 23](#).
- 11** Click on **Add Link**.

Linking Existing Requirements through Quick Search

A comfortable way of linking requirements with each other is the Split View function of Quick Search. The Split View allows to easily find linkable requirements and link them to each other. For further information about finding requirements, refer to chapter ["Exporting Requirements" on page 76](#).

To use Split View for linking, follow these steps:

- In the menu bar, click **Requirements** to open Quick Search.
- In the Actions pane, click **Split View**. This divides the Quick Search window into two Quick Search windows.
The left Quick Search window allows selection of the parent class.
The right Quick Search window allows selection of the child class. Note that the

Classes and Attributes box only shows classes which can be linked to the parent class.




Figure 4-6. Quick Search in Split View mode

The right Quick Search window provides these extra functions:



Create Link: Links one or more child class requirements to one parent class requirement. Create Link is available if the user has the *Link* right for classes and the *Create* right for relationships.



TIP You can also use drag & drop to link requirements.



Delete Link: Deletes the links between one or several child class requirements and one parent class requirement. Delete Link is available if the user has the *Link* right for classes and the *Delete* right for relationships.



Remove Link: Permanently removes the links between one or several child class requirements and one parent class requirement. Remove Link is available if the user has the *Link* right for classes and the *Remove* right for relationships.



CAUTION! You cannot restore a removed link.



Undelete Link: Restores previously deleted links between one or several child class requirement and one parent class requirement. Undelete Link is available if the user has the *Link* right for classes and the *Undelete* right for relationships.

Relationship: Shows all relationships between the parent class and the child class.

Show: Filters the requirements of the child class. You can select one of these values:

- **All:** Shows all requirements.
- **Linked:** Shows only requirements which are linked.
- **Not Linked:** Shows only requirements which are not linked.
- **Deleted Links:** Shows only requirements with deleted links.




Shows requirements in a table. This is the standard view for Quick Search.



Show requirements as separate cards. Each card shows the following information:

- Requirement ID
- Title
- Owner
- Last modification date
- Number of links




To return to the regular Quick Search window, click **Quick Search** in the Actions pane.



NOTE In order to create, delete, remove or undelete a link, you need to select one parent class requirement and one or several child class requirements.


Creating a new Requirement and linking to it

- 1 Open the *Edit Attributes* dialog for a requirement.
- 2 Expand the **Links** section.
- 3 Expand the class which contains the requirement you want to link to.
- 4 Click on . This opens the dialog to add a new requirement.
- 5 Fill out the attributes.
- 6 Click on **Save**.



NOTE If configured by the administrator, the attribute values of the parent requirement might be copied to the newly created requirement.



Proposing a new Requirement and linking to it

- 1 Open the *Edit Attributes* dialog for a requirement.
- 2 Expand the **Links** section.
- 3 Expand the class which contains the requirement you want to link to.
- 4 Click on  . This opens the dialog to add a new requirement.
- 5 Fill out the attributes.
- 6 Click on **Submit**.



NOTE If configured by the administrator, the attribute values of the parent requirement might be copied to the newly created requirement.

Deleting or Removing Links

- 1 Open the *Edit Attributes* dialog for a requirement.
- 2 Expand the **Links** section.
- 3 Expand the class which contains the requirement you want to delete or to remove.
- 4 Select the requirements you want to delete or to remove.
- 5 To delete, click on  . To remove, click on  .




CAUTION! You cannot restore a removed link.

- 6 Confirm the popup message.

Restoring a deleted Link



A deleted link is only shown in the list if you turned on the option Show deleted links for the class. For details on how to show deleted links, see chapter "[Link Properties](#)" on page [112](#).

To restore a deleted link:

- 1 Open the *Edit Attributes* dialog for a requirement.
- 2 Expand the **Links** section.
- 3 Expand the class which contains the requirement you want to restore.
- 4 Select the deleted links you want to restore. Deleted links use an italic font and red text color.
- 5 Click on  .
- 6 Confirm the popup message.

Clearing a Suspect Link

- 1 Open the *Edit Attributes* dialog for a requirement.

- 2 Expand the **Links** section.
- 3 Expand the class which contains the requirement you want to restore.
- 4 Select the suspect links you want to clear. Suspect links show an  icon in the leftmost column.
- 5 Click on  .
- 6 Confirm the popup message.

For further information about suspect links, see chapter "[Suspect Links](#)" on page 112.

Link Properties

In the *Link Properties* dialog you can define for each class which data should be displayed in the **Links** section. These settings are available:

- **Attributes To Display:** To specify the attributes to display, see chapter "[Attributes to Display List](#)" on page 25.
- **Sorting Order:** To specify the sort order, see chapter "[Sorting Order List](#)" on page 25.
- **Include all requirement versions:** If checked, shows all versions of the requirements. It is recommended to include the **Current Status** attribute in the **Attributes To Display** list.
- **Show link creation information:** If checked, the list shows date and time the link was created. Note that the link creation information is used for all classes, and not just for the class selected when the dialog was opened.
- **Show deleted links:** If checked, shows delete links including the user who deleted it and date and time it was deleted.

Suspect Links

After relationships exist between requirements, it is possible for changes in one requirement to affect other requirements. If you are working in a team, you need to know whether a change to a related requirement has possibly rendered other requirements questionable, or "suspect."


For example, suppose a marketing requirement dictates that all user interfaces adhere to the blue logo color. From this marketing requirement, there may be several linked product requirements that state that the desktop UI, the Web client, and a plugin adhere to the blue logo color. If the marketing manager changes her mind and decides that the red logo color should be used instead, all of the linked requirements become invalid.

Actions that trigger suspect links include updating, replacing, and accepting a change request. Actions that do not trigger suspect links include linking, and baselining.

The suspect links feature allows you to clearly see which requirements are under suspicion and which ones are not. After you find a link that is marked as suspect, you can either change the requirement or if you have permission, clear the suspect status.


Not all relationships require linked requirements to be marked as suspect. The administrator decides whether a relationship participates in the suspect links feature. The

following illustration shows how REQ_300 is not a suspect link, because class B does not participate in the suspect links feature.



Identifying Suspect Links

To identify suspect links:

- 1 After selecting the desired requirement in a work pane, select **Edit** from the Requirements group of the Actions pane. The Edit Attributes dialog opens.
- 2 A suspect link icon  is displayed in the top left corner of the dialog box if the requirement is suspect. The icon is not displayed once all of the links that caused this requirement to be marked as suspect are cleared.

The screenshot shows the 'Marketing_Requirements: MRKT_000001' dialog box. The 'Links' section is expanded, showing a table of links. The table has columns for 'RQMT ID', 'TITLE', and 'OBJECT VERSION ID'. The first row is highlighted and has a yellow warning icon in the 'RQMT ID' column.

RQMT ID	TITLE	OBJECT VERSION ID
PROD_000001	Try to use Tcl/Tk	6
PROD_000003	Default window size	5
PROD_000004	Expand image to full size	5

- 3 Expand the **Links** section.




- 4 Look at each suspect requirement and examine whether the change affects the requirement.
- 5 Change the requirement if the change affects it, or clear the suspect link if it does not affect the requirement.



NOTE The suspect link icon is displayed in other areas of RM Browser, such as in the Quick Search query results and the navigation tree of the Document and Traceability work pages.

Clearing Suspect Links

To clear suspect links:


- 1 Clear all links that caused this requirement to be marked as suspect by doing one of the following:
 - Click the **Clear all suspect links** button  in the title bar of the **Edit Attributes** dialog box to clear all suspect links associated with this requirement.
 - Click the **Clear all suspect links** link at the top right of the **Links** section.
- 2 Clear individual links that caused this requirement to be marked as suspect by selecting the requirement or requirements and then clicking the **Resolve Suspicion** icon  at the top right of the **Links** subsection. When the last suspect link is cleared, the  icon is no longer displayed in the title bar of the dialog box.
- 3 In Requirements View, select one or several requirements and click **Resolve Suspicions** in the **Requirements** group of the **Actions** pane.


Inherited Links

When making a proposal, any links on the originating requirement are inherited.

To identify inherited links:

- 1 After selecting the desired proposal in a work pane, select **Edit** from the Requirements group of the Actions pane. The Edit Attributes dialog opens.




- 2 Expand the **Links** section.
- 3 Open a class which has links.
- 4 Inherited links are marked by  .



NOTE When making a proposal, also the collections of the original requirement are inherited. For further information, see chapter "[Inherited Containers](#)" on page 105.

Using Link Browser

Link Browser displays the relationship of requirements and containers. To access Link Browser, select one or several requirements with links in the **Requirement View** and click on **Browse Links** in the **Requirements** group of the **Action** pane.



By clicking on a requirement, the child requirements and containers to which the requirement belongs to are shown. Double-clicking a requirement opens the *Edit Attributes* dialog. Link Browser allows zoom in or zoom out by turning the mouse-wheel.

Toolbar

The toolbar provides these general functions:



Scope: Clicking on this icon opens a sub-menu with these entries:

Classes and Relationships: Allows to select classes and/or links from one class to another class the linked requirements must belong to in order to be displayed. If you unselect all classes, Link Browser will only show the current class.

Category: Allows to select the category the linked requirements must belong to in order to be displayed.

Container: Allows to select which container the linked requirements must belong to in order to be displayed.

After making your changes, click on **Apply**.



Display: Clicking on this icon opens a sub-menu with these entries:

Containers

- **Containers:** If checked, Link Browser shows the containers the requirements belong to. A container is displayed as a light blue rectangle.
- **Only Current Objects:** If checked, Link Browser only shows current requirements and links. The status of a non-current requirement is shown at the bottom of the requirement.
- **Show Deleted Links:** If checked, Link Browser also shows deleted links. A deleted link is shown as a dashed line.
- **Highlight Suspect Links:** If checked, suspect links will be colored red.
- **Relation depth:** The specified value defines to which depth links should be followed when a requirement is loaded or clicked on. A value of 1 means that only children are displayed. Setting a value of 2 means that children and grandchildren are displayed.

After making your changes, click on **Apply**.



Design: Opens the *User Settings* dialog which allows to set the color for each class. This is identical to selecting **User Settings** in the **Login menu** and then selecting **Link Browser**.



Apply: Applies the option changes and loads the objects based on the current view.



Reload: Applies the option changes and loads the objects based on the original object.



Download: Creates an image of the current Link Browser dialog which can be downloaded.



Print: Prints the Link Browser dialog.



Return to default filter: Resets the scope to its default.

Context Menu

The context menu provides functions for requirements and links.

Context Menu for Requirements

This context menu is only available when selecting a requirement. Not all of these functions may be available for every requirement:

- **Edit:** Opens the dialog for editing the requirement's attributes.
- **Browse Links:** Opens a new Link Browser dialog with the selected requirement as parent.
- **Delete:** Deletes the selected requirement.
- **Remove:** Removes the selected requirement.
- **Undelete:** Undeletes the selected requirement.
- **Resolve Suspicions:** Clears all suspect links.
- **Create Link:** Opens the *Link Requirements* dialog. This allows linking a requirement to the selected requirement.
- **Create New & Link:** When selecting a class from the sub-menu, this opens the New requirement dialog for the selected class. When saving the requirement, the new requirement is linked to the selected requirement.
- **Add to Collection:** Opens the *Add to Containers* dialog. This allows adding the selected requirement to a collection.

Context Menu for Links

This context menu is only available when selecting a link. Not all of these functions may be available for every link:

The context menu provides these functions:

Delete: Deletes the link.

Remove: Removes the link.

Undelete: Undeletes a link.

Resolve Suspicion: Clears the suspected link.

Working with Group Attributes

A group attribute is like a list attribute in that it provides a predefined list of values for user selection. But unlike a simple list attribute, a group attribute is composed of a series of sub attributes. The choices available to the user depend upon the selections they made in the higher level, or parent, attributes within the group attribute.

For example, a group attribute named *Operating System* contains the sub (member) attributes: *Platform*, *Family*, and *Version*. *Platform* is the first (parent) attribute in the group and includes the following values for selection: *Mobile*, *Desktop*, and *Server*.

If Desktop is selected, desktop operating system names are available for selection in the Family sub attribute. If one of the other values is chosen in Platform, such as Mobile, The Family attribute would show mobile operating system names.

TEST_000001 - Edit Attributes - Dimensions RM - Internet Explorer

Tests: TEST_000001

Edit attributes Add a comment Propose a change

Standard Attributes

Custom Attributes

Attachment: Creation Date: 08/28/2001

Designer: Engineer 1 Estimated DevTime: 0

Execution Status: Passed

Operating System:

Platform	Family	Version
Desktop	Windows	XP
Desktop	Windows	7

Path: td_73\Applicat Steps: 0

In the example above, the Family sub attribute also has a child attribute, Version, whose available values depend upon the selection made for Family. The chain of dependencies flows from left to right through the sub attributes of the group attribute.



NOTE As shown in the example above, any given requirement may include multiple value-sets (rows) of a group attribute.

In the Grid View, the example looks like the selected row of the image below:

PUID▲	Test Name	Operating System
TEST_000001	Application CRUD Processing	Desktop-Windows-XP Desktop-Windows-7
TEST_000002	Application Image Viewing Size Settings	Mobile-Android-KitKat
TEST_000003	Application Opens Image on Windows	Desktop-Windows-7 Desktop-Windows-XP Desktop-Windows-Vista



NOTE Each value-set of the group attribute, Requester, appears on its own line within the requirement's row.

For display in the grid, the individual values of the group attribute are separated by a dash character (-). The first line (value-set) in our example is: Desktop-Windows-7, so Desktop is the value of Platform, Windows is the value of Family, and 7 is the value of Version.

The icons to the rightmost attribute box provide these functions:

- Adds a new (empty) row
- Adds a new row with the values of the selected row
- Removes the selected row



TIP To quickly create value-sets representing each possible value of a given member, select the **Select All** drop-down menu item for that member.

Working with File Attachments

You can add file attachments as attributes to an requirement. Each file attachment attribute for the requirement is represented by a single line in the **File Attachments** section on the **Edit Attributes** dialog box. Each file attachment attribute holds only one file attachment.




TIP To attach multiple files to a single file attachment attribute, store the files in a single zip file and attach the zip file to the attribute.



NOTE Before file attachment lines appear in the **File Attachments** section, an administrator must add one or more File Attachment attributes to each relevant class. For more information, see the *Serena Dimensions RM Administrator's Guide*.

To attach, replace, delete, or download a file:

- 1 After selecting the desired requirement in a work pane, select **Edit** from the Requirements group of the Actions pane. The Edit Attributes dialog opens.
- 2 If it is collapsed, expand the **File Attachments** section on the **Edit Attributes** dialog box.



- 3 Do any of the following:
 - **Attach:** Click this link to attach a file to the requirement. The Add Attachment dialog opens. Type the full path to the file or click **Browse** to locate the file, and then click **OK**.
 - **Replace:** Click this link to replace the existing file with a different file. The Replace Attachment dialog box opens. Type the full path to the file or click **Browse** to locate the file, and then click **OK**.
 - **Delete:** Click this link to detach the file from the requirement.
 - **FileName:** Click the filename link to download the file to your computer. You are prompted to either **Save** or **Open** the file.



CAUTION! File attachment changes are not saved until you click the **Update** or **Replace** button as described below.

- 4 **Show navigation bar / Hide navigation bar:** Click to show/hide the navigation bar at the bottom of the dialog. You can browse through the requirements in sequence with the **First**, **Previous**, **Next**, and **Last** controls.
- 5 Click one of the following buttons:

- **Copy** to close the dialog and copy the attribute values for use in creating a new requirement. The New *ClassName* dialog opens (see "Creating a New Requirement" on page 85).



NOTE An attribute is copied into the next requirement only if the administrator selected the **Populate On Copy** option when defining the attribute. See the *Administrator's Guide*.

- **Update** to close the dialog and save your changes without creating a new version of the requirement. (This option is not recommended if you need to maintain a history, or audit trail, of changes to requirements over time.)

Update & Next: As above, except the dialog remains open and the next requirement is loaded. This version of the button appears when the Navigation Bar is visible.

- **Replace** to close the dialog and save your changes as a new version of the requirement.

Replace & Next: As above, except the dialog remains open and the next requirement is loaded. This version of the button appears when the Navigation Bar is visible.

Polling

Polling allows you to solicit feedback about a requirement from selected users. Polls are typically used to decide whether a specific requirement should be accepted, or to reach consensus concerning the content of a requirement.

A poll consists of a question, at least two answers, and at least one participant. In RM Browser, if you have the appropriate permissions, you can create and modify polls. Poll participants use RM Browser to vote and view current poll results.


Creating a Poll






A user with the "Create" permission for the Poll class can create a poll. Before a poll can be created, the Poll class and a relationship to the required classes must be added to the database using the Class Definition tool. When you create relationships between other classes and the Poll class, the other classes must be primary and the Poll class must be secondary. For more information, see the *Serena Dimensions RM Administrator's Guide*.

To create a poll:

- 1 After selecting the desired requirement in a work pane, select **Setup Poll** from the Requirements group of the Actions pane. The Create Poll dialog opens.
- 2 Type the title of the poll. The poll title does not have to be unique; other polls can have the same title.
- 3 Type the question for which you need feedback.
- 4 Type at least two answers to the poll.


There is no practical limit to the number of answers that you can include. When you begin typing in the last answer field, a new answer field is automatically created below it.



- 5 To rearrange the answers:
 - Click the **insert** button  to add a new answer above the selected answer, instead of adding it to the end of the list.
 - Select an answer and click the **delete** button  to delete it. Blank answers do not have to be deleted because they are ignored.
 - Click the up arrow  and down arrow  buttons to move the selected answer up or down in the list.
 - Click the **sort** button  to sort the answers alphabetically.
- 6 In the **Response deadline** section, either select **No deadline** or select the date and time that the poll should close.

The poll closes when the selected date and time have passed, when the poll creator clicks the **Stop** button, or when all participants have voted.
- 7 Click the **Participants** tab.
- 8 Select the users you want to participate in the poll. A minimum of one participant is required.

If you select a group, its members are displayed below the lists on the **Create Poll** dialog box.



- 9 Click **Start** to start the poll.

Modifying a Poll

The user who created the poll or a user with the "Update" permission for the Poll class can modify an existing poll. If the poll is already active, you can stop the poll, change the deadline, or add users or groups to the list of participants. The user cannot change the poll title or question.

To modify a poll:

- 1 Click **Modify** under **Polls** on the **Edit Attributes** dialog box or on the Requirements View. The **Modify Poll** dialog box opens.
- 2 Change the polling information.
- 3 Click **Modify**.

Closing a Poll

To close a poll:

- Click **Modify** under **Polls** on the **Edit Attributes** dialog box. The **Modify Poll** dialog box opens.
- Click **Stop**.

The poll also closes if the specified deadline passes or if all participants have voted.

Casting a Vote

Users with the "Read" permission for the Poll class can vote in a poll. Poll participants cast votes from the **Cast Vote** dialog box. Participants typically receive an e-mail message when the poll has started that provides a link that takes them to the **Cast Vote** dialog box. The **Cast Vote** dialog can also be accessed from the **Polls** section of the **Edit Attributes** dialog box or from the List view of Requirements View.



NOTE Before polling e-mail notifications can be sent, an administrator needs to configure and enable the RM Mail service. For information, see the *Serena Dimensions RM Administrator's Guide*.

To cast a vote:

- 1 Do one of the following:
 - Click the link in an e-mail message you received, and then log in to Dimensions RM.
 - Click the **Vote** link from the **Polls** section of the **Edit Attributes** dialog box or List view of Requirements View.

The **Cast Vote** dialog box opens.

- 2 Select a single answer. Before you vote, you can view the details of the requirement for which the poll is being placed, and view the current results of the voting. To do so, click the link at the bottom left of the dialog box.
- 3 If you want, type a comment in the **Additional comment** section.
- 4 Click **Vote**.

Viewing Polling Results

You can view the details of a poll that is in progress or has already completed. The current polling status is displayed after you cast a vote. You can also view the polling status from the **Edit Attributes** dialog box or the List view of Requirements View.

To view polling results:

- 1 Do one of the following:
 - Cast a vote.
 - Click the **View details** link at the bottom of the **Cast Vote** dialog box before you cast your vote.
 - Edit a requirement and display the Edit Attributes dialog box.
 - Navigate to the List view of Requirements View.
- 2 If you used the first method in [Step 1](#), the **Poll Results** dialog box opens.
- 3 If you used the second, third, or fourth method in the preceding step, expand the **Polls** section on the dialog box that opens (if it's not already expanded), and then expand the poll you want to view.
- 4 To view who voted for each answer and their comments, click **Show details**. To hide this information, click **Hide details**.

- 5 To view a list of participants who have not voted yet, click **View users who haven't voted**.

Adding Built-In Queries to Your My Work Page

You can view polls from a pre-built section on your My Work page. This section appears by default.

Participating in Discussions

You can start a discussion by adding a comment to a requirement or you can reply to comments that are already part of a discussion. There are two ways you can view discussions: date view and subject view.



NOTE To add a comment or reply to a comment, you must have the following permissions:

- "Create" permission on the Comment class
- "Read" permission on the requirement class
- "Create" permission on the relationship between the Comment class and the requirement class.

Adding a Comment from the Menu Bar

To add a comment from the menu bar:

- 1 After selecting the desired requirement in a work pane, select **Add Comment** from the Requirements group of the Actions pane. The Add a Comment dialog opens.
- 2 Click **Add Comment** button. The Add a Comment dialog appears.
- 3 Type a title for the comment in the **Subject** box.
- 4 Type the comment in the **Comment** box. There is no practical limit to the number of characters.
- 5 Select your role from the **Role** list to indicate your perspective in creating the comment. An administrator can configure this dialog box to omit the **Role** menu.
- 6 Click **Add** or **Add & Close**.

Adding a Comment from a Discussion

To add a comment from within a discussion:

- 1 In the Add a Comment dialog box or in the Edit Attributes dialog box for a requirement, do one of the following:
- 2 Click **Start a new discussion** at the top of the **Comments** section.
 - Click **Reply** at the bottom of a comment.

The **Add a comment** action becomes active, and the dialog box expands to include a comments section.

- 3** If you are starting a new discussion, type the subject of the discussion in the **Subject** box. If you are replying to a comment, the title is already filled in and has *Re.* prepended to it. If you change the title, the comment is no longer part of the original discussion thread, but will start a new discussion.
- 4** Type the comment in the **Comment** box. There is no practical limit to the number of characters.
- 5** Select your role from the **Role** list to indicate your perspective in creating the comment. An administrator can configure this dialog box to omit the **Role** menu.
- 6** Click **Add** or **Add & Close**.

Changing the Discussion View

To change the discussion view:

Click **Group by Subject** or **Group by Date** at the top right portion of the **Comments** section.

Chapter 5

Working with Documents


About Documents	128
Navigation and Controls of the Document Work Page	128
Printing from the Detail Pane	133
Formatting Documents	133
Formatting Chapters	136
Creating a New Document	137
Opening a Document to the Document Work Page	139
Save a Copy of a Document Under a New Name	139
Editing Document Attributes	140
Change which Requirement Version Is Included in a Document	141
Deleting a Document	141
Deleting a Requirement from a Document	142
Creating a Snapshot of a Document	142
Working with Snapshots of an Open Document	143
Working with Snapshots of a Closed Document	143
Comparing Documents and Snapshots	144
Publish as a Microsoft Word Document	146
Publish as an Adobe PDF Document	148
Specifying Document Properties	149
Creating a Chapter	151
Editing a Chapter	153
Deleting a Chapter	154
Moving Chapters and Requirements	154
Adding Requirements to a Document	155
Assigning an ECP to a Document	156
Finding and Replacing Character Strings	157
Working with Limited Permissions	159
Merging Document Changes	160
Merging Chapter Changes	162
Copying the URL of a Document to the Clipboard	165
Moving a Document or Snapshot to a different Category	166

About Documents

A document is a structure in Dimensions RM which allows to add chapters and requirements. Chapters can contain text requirements. A regular document has all chapters and requirements defined in itself.

Master and Child Documents

A child document inherits its layout from a master document. Changes to the master document are propagated immediately to any related child document. In a child document, any parts inherited from the master document are read-only and thus cannot be modified. The following image shows a use case for master/child documents.




Navigation and Controls of the Document Work Page













This work page has the following unique controls and features:

- ["Navigation Pane" on page 129](#)
- ["Detail Pane" on page 130](#)

Navigation Pane



This appears on left side of the page and includes the following elements:

-  **Expand/Collapse:** This button expands or collapses the pane.
-  **Down/Up:** These buttons move the selected chapter or requirement down or up in the document's structure.
-  **New chapter:** This button invokes the New Chapter dialog. The new chapter will be placed at the same level as the currently selected chapter, unless the **Add as subchapter** checkbox is enabled or the root of the document is currently selected. See ["Creating a Chapter" on page 151](#).
-  **Format chapter:** This button invokes the Format Chapter dialog where you can configure how the chapter is displayed in the Details pane and when published. See ["Formatting Chapters" on page 136](#).
-  **Delete chapter:** This button deletes the currently selected chapter. To complete the operation, click **OK** on the resulting confirmation dialog. See ["Deleting a Chapter" on page 154](#).
-  **Expand all chapters:** This button expands all chapters in the document tree.
-  **Collapse all chapters:** This button collapses all sub-chapters, leaving only the root-chapters visible.
-  **Reload this document:** This button retrieves the currently open document from the server and reloads it into the work page.
-  **Root:** This is the root level of the document.
-  **Chapter:** This a chapter in the document.
-  **Requirement:** This is a requirement in the document.
-  **Suspect Link:** This is a requirement that has a suspect link.



NOTE The Foreword, if there is one, is located in the root of the document. It typically contains items such as the company logo, copyright information, and a history table. It does not include the Table of Contents.

When the document is published, the Foreword is displayed before the Table of Contents.

Note the following functional aspects of the Navigation pane:

- Chapters and requirements are automatically numbered using a hierarchical numbered outline format. This numbering updates whenever you change the structure or order of the document's contents.
- To make a requirement a sub-requirement of a requirement, select the requirement's name and drag it to the parent requirement.
- To make a chapter a subchapter of another chapter, select the chapter and drag it to the parent chapter.
- The classes that the document or a chapter can include are displayed as a tool tip when you hover your cursor over the name of the document or chapter.
- The PUID and object ID of each requirement is displayed as a tool tip when you hover your cursor over the requirement name.
- The contents of the element selected in the Navigation pane will be displayed in the Detail pane.

Detail Pane

The look of the Detail pane depends on what element is selected in the Navigation pane, what layout is selected in the Detail pane, as well as the format settings in effect at the document and chapter levels.

If the selected chapter or document root contains:



- **Only requirements**, it can be displayed with either the Grid or Paragraph layouts. The user can switch between the layouts as desired, as well as set the default layout used for a given chapter or the entire document.
- **Only chapters**, it is displayed with the Paragraph layout.
- **Both chapters and requirements**, the chapters are displayed with the Paragraph layout, but the requirements section can be switched between the Grid and Paragraph layouts as desired.



Chapters can be viewed in these modes:

- **Paragraph Layout**: Shows the chapter and requirements in book style.
- **Grid Layout**: Shows the requirements in table format.
- **Editable Grid Layout**: Shows the requirements in table format. In this mode you can edit the displayed attributes without opening the Edit dialog.
- **Form Layout**: This layout is used when you select an individual requirement.

You can switch between **Paragraph**, **Grid** and **Editable Grid** Layout by clicking the link of the desired layout in the **Layout** bar.

All layouts, except Form Layout, the following controls and features are available:

-  **Find and replace**: This button invokes the Find and Replace in Document dialog so you can search the document or the selected chapter for a string. See "[Finding and Replacing Character Strings](#)" on page 157.
-  **Print**: This button invokes your system's Print dialog to print the current contents of the Details pane. See "[Printing from the Detail Pane](#)" on page 133.

-  **Edit:** This button invokes the Edit Chapter dialog or the Edit Document dialog, depending on what is currently selected in the Navigation pane. See "Editing a Chapter" on page 153 and "Editing Document Attributes" on page 140.
-  **Refresh:** This button repopulates the Detail pane with fresh data from the database.

Paragraph Layout



3.2 Miscellaneous Requirements

Requirements Layout: [Editable Grid](#) | [Grid](#) | [Paragraph](#)

3.2.1 System response times

Rqmt ID: MRKT_000029

The system response time shall not be greater than 3 seconds for 80 percent of the transactions.

3.2.2 System weight

Rqmt ID: MRKT_000030

The system shall weigh less than 8 pounds.

3.2.3 System comes in different colors

Rqmt ID: MRKT_000031

The system shall be available in a variety of colors.

Paragraph Layout provides all functions from the list on [page 130](#).


To perform an action on a requirement listed in the Paragraph layout, select the requirement and then select the desired action from the **Requirements** group of the **Actions** pane.

Grid Layout



3.2 Miscellaneous Requirements

Requirements Layout: [Editable Grid](#) | [Grid](#) | [Paragraph](#)

	#▲	Rqmt ID	Title	Text
	3.2.1	MRKT_000029	System response times	The system response time shall not be greater than 3 seconds for 80 percent of the transactions.
	3.2.2	MRKT_000030	System weight	The system shall weigh less than 8 pounds.
	3.2.3	MRKT_000031	System comes in different colors	The system shall be available in a variety of colors.

Grid Layout provides all functions from the list on [page 130](#) and in addition:

- **Sorting:** Click a column heading to sort by that attribute.
- **Requirement Editing:** Double click a requirement to open the *Edit* dialog.

To perform an action on a requirement listed in the Grid layout, select the requirement and then click on the desired action from the **Requirements** group of the **Actions** pane.

Editable Grid Layout

The screenshot shows a web interface for '3.2 Miscellaneous Requirements'. At the top right, there are icons for search, print, edit, and refresh. Below the title, there are icons for grid, table, and paragraph, with 'Row count: 3' displayed. A table with three columns is shown: '#', 'Rq...', and 'Title'. The table contains three rows of requirements.

#	Rq...	Title	Text
3.2.1	MRKT_000029	System response times	The system response time shall not be greater than 3 seconds for 80 percent of the transactions.
3.2.2	MRKT_000030	System weight	The system shall weigh less than 8 pounds.
3.2.3	MRKT_000031	System comes in different colors	The system shall be available in a variety of colors.

Editable Grid Layout provides all functions from the list on [page 130](#) and in addition:

- **Sorting:** Click a column heading to sort by that attribute.
- **Attribute Editing:** Double click the table cell to edit the attribute of the requirement.
- **Requirement Editing:** Double click a requirement to open the *Edit* dialog.

To perform an action on a requirement listed in the Grid layout, select the requirement and then click on the desired action from the **Requirements** group of the **Actions** pane.

Form Layout

The screenshot shows a form layout for '3.2.2 System weight'. At the top right, there are buttons for 'Propose', 'Refresh', 'Edit', and 'Print'. Below the title, the category is 'RMDEMO\Functional\Design and Construction'. The form is divided into several sections: 'Standard Attributes', 'Custom Attributes', 'System Attributes', 'File Attachments', 'Comments', 'Links', 'History', 'Polls', and 'Container'. The 'Standard Attributes' section is expanded, showing 'Rqmt ID:MRKT_000030' and 'Title:System weight'. The 'Text' field contains 'The system shall weigh less than 8 pounds.'

This layout includes the following controls and features:

- **Propose:** This button invokes the Submit a Change Request dialog so you can propose a change to the currently selected requirement. See ["Submitting a Change Request" on page 92](#).
- **Refresh:** This button repopulates the Detail pane with fresh data from the database.
- **Edit:** This button invokes the Edit Requirements dialog. See ["Editing a Requirement" on page 88](#).

- **Print:** This button invokes your system's Print dialog to print the current contents of the Details pane. See "[Printing from the Detail Pane](#)" on page 133.



NOTE The contents of the sections in the Form layout are printed only if the sections are expanded.

- To perform an action on the currently selected requirement, select the desired action from the Requirements group of the Actions pane.

Printing from the Detail Pane

You can print the contents of the Detail pane when you select a requirement, chapter, or document in the Navigation pane.

To print the contents of the Detail pane:

- 1 Click **Print** in the Detail pane. A window opens with content formatted for printing; the RM controls shown in this window are non-functional.



NOTE The contents of the sections in the Form layout are printed only if the sections are expanded.

- 2 Your system's Print dialog opens. Click **Print**. The requirement is sent to your printer.
- 3 After the content has printed, close the window that displayed the formatted content.


Formatting Documents

You can specify whether the document uses the Grid or Paragraph layout. If the document uses the Paragraph layout, you can select a custom template from which to publish the document. You can also number requirements separately from chapters and specify the character string that delineates the two.

To specify document format:

- 1 Select the root of the document in the Navigation pane.

- 2 Select **Format Document** from the Documents group of the Actions pane. The Format Document dialog opens.



TIP If you selected a chapter, or a requirement within a chapter, when you opened the Format Document dialog, a **Format currently selected chapter instead** link is displayed. If you wish to format only that chapter, click the link to open the Format Chapter dialog.

- 3 To change the **Requirement Layout**, select the **Grid** or **Paragraph** layout option.



NOTE If there is no chapter in a document or if there are mixed requirements from different classes in the same chapter or sub-chapter, the Grid option is disabled.



TIP If you want to include requirements of different classes into the same chapter, put the requirements of each class into a separate sub-chapter.

- 4 To change which attribute labels are shown in the Detail pane and in the published document, select or deselect the check boxes for **<Default Title>** and **<Default Description>**.
- 5 **Reset all chapters:** This button reverts the *Requirement Layout* and *Show and Publish LABELS for* settings of all chapters in the document to the default of inheriting the settings from their parents.
- 6 To use a custom template to publish the document, select a template from the **Publish Requirement Templates** list. This list contains templates that your

administrator defined. If you select **None**, the standard grid or paragraph format is used.



NOTE To use a custom template, the requirement must be in a chapter that uses paragraph format. If it is in a chapter that uses grid format, the requirement is displayed in the standard grid format.

- 7 To change chapter numbering within the document, do the following:
 - a To **Separate chapters and requirements numbering**, select the check box. Else, any requirements located at the same level in the document as the top-level chapters will be counted as a chapter for numbering purposes. Adding or removing such a requirement would result in the renumbering of all chapters in the document.
 - b To define the **Format string** that will be used to display requirement numbers in the document, enter the desired format in this field. The string can be up to 10 characters long. The following characters have special meaning:
 - The number (#) character represents the position of the requirement number. (The number character is known by many names around the world, including: pound, hash, and octothorp.)
 - The caret (^) character serves as an escape symbol. You would use it in front of a # character if you wanted an # character to be displayed rather than representing the position of the requirement number.

The examples below assume two requirements located in a sub chapter numbered 2.1.1.

String	Example Results
.#	2.1.1.1 Mac Support 2.1.1.2 Deadline (This is the default.)
-#	2.1.1-1 Mac Support 2.1.1-2 Deadline
^##	2.1.1#1 Mac Support 2.1.1#2 Deadline
^^#	2.1.1^1 Mac Support 2.1.1^2 Deadline
RQ:#	2.1.1RQ:1 Mac Support 2.1.1RQ:2 Deadline
ReqNumber#	2.1.1ReqNumber1 Mac Support 2.1.1ReqNumber2 Deadline
	Mac Support Deadline NOTE There will be no requirement numbering displayed in the document, document tree, or the grid layout.



NOTE After changing the numbering settings and clicking **OK**, you will be prompted to make a snapshot of the document before the new settings are applied. If you do not wish to make a snapshot, just Cancel the snapshot dialog when it appears.

- 8 Click **OK**.




TIP Click the **Refresh** button to see changes to numbering take effect on the work page.

Formatting Chapters

To specify the layout you want for a chapter:

- 1 Click the **Format chapter** () button. The **Format Chapter** dialog opens.



- 2 **Inherit Layout from Parent:** Selecting this check box reverts the *Requirement Layout* and *Show and Publish LABELS for* settings of the chapter to the default of inheriting the settings from its parent.
- 3 To change the **Requirement Layout**, select the **Grid** or **Paragraph** layout option.



NOTE If there are mixed requirements from different classes in the same chapter or sub-chapter, the Grid option is disabled.



TIP If you want to include requirements of different classes into the same chapter, put the requirements of each class into a separate sub-chapter.

- 4 To change which attribute labels are shown in the Detail pane and in the published document, select or deselect the check boxes for **<Default Title>** and **<Default Description>**.
- 5 Click **OK**.

Creating a New Document

When you create a new document, you can use one of the following as a template:

- The blank template.
- The chapter structure of an existing document.
- The chapter structure and requirements of an existing document.



NOTE

- You must have the "Create" permission for both the chapter class and for collections.
- If you select **Chapters Only** or **Chapters and Requirements** for the Create Options, you must also have the following additional permissions:
 - Chapter class: "Read"
 - Collections: "Link" and "Create Based on Existing Collection"

To create a new document:

- 1 Select **Document** from the New menu. The **New Document** dialog opens.
- 2 **Name:** Enter a name for the document.



NOTE A document name can contain a maximum of 256 characters and cannot include single quotes (').

- 3 **Description:** Enter a description of the document. This description will be shown in the Open Document dialog. The text may be truncated in the Description column of this dialog; however, it is shown in its entirety in the tooltip that appears when you hover your mouse over the description.



NOTE

- The description is not copied if you are creating a document from an existing document.
- The administrator specifies the maximum length of the **Description** field in the Chapter class in Class Definition.

- 4 **Publish Title:** Select to use the string in the **Name** field as the document's title when publishing to Word.
- 5 **Update To Current (Tip):** Select to automatically update the document with the newest version of each requirement. When creating a document with option "Blank", "Update To Current (Tip)" will be set from the value specified on the form. If a document is created by using a template ("Chapters Only" or "Chapters and Requirements"), then "Update To Current (Tip)" will be set from the template document.



NOTE To manually change the version of a specific requirement that is included in the document, see ["Change which Requirement Version Is Included in a Document" on page 141](#).

- 6 **ECP Controlled:** Enable this checkbox if you want to require that users link the document to an ECP class object before editing it.



CAUTION! Once ECP Control is enabled on a document, **it cannot be disabled.**



NOTE

- ECPs are a high-level change management class type (Engineering Change Proposal) that can be used to collect multiple change requests into a single package.
- If ECP Control is in effect, but the current user has not assigned an ECP, the document will be Read-Only until he assigns an ECP to it. A notice to this effect will be displayed to the right of the Project Bread Crumb.
- To assign an ECP, see "[Assigning an ECP to a Document](#)" on page 156.

- 7 **Master Document:** Select this option to make the document a master document.
- 8 **Category:** Select the category to which to add the new document. A document can belong to any category to which you have access.
- 9 **Create Options:** Select one of the following:
- **Blank:** Creates the document from the blank template. When you select this option, the documents in the Template list are disabled. This is the default.
 - **Chapters Only:** Creates the document based upon the chapter structure of an existing document that you select from the Template list.
 - **Chapters and Requirements:** Creates the document based upon the chapter structure and requirements of an existing document that you select from the Template list.
 - **As Child:** Shows a list of master documents to which this newly created child document should relate to.
 - **Based on Sibling:** This option is only available when **As Child** is selected. If you select this option, the master document list contains child documents which you can select. The new child document will be a copy of the selected child document and also have the same master document.
- 10 **Template:** Select the document to use as the template. If needed, use the **Find template** field at the bottom of the dialog filter the documents shown in the list.



NOTE

- These controls are enabled only if you did **NOT** choose **Blank** from the Create Options.
- If you restrict classes in a document, these restrictions are inherited by the new document. For further information about restricting classes in a document see chapter "[Assigning an ECP to a Document](#)" on page 156.

- 11 **Foreword tab:** Click in the **Foreword** field. The HTML Toolbar appears. Enter any information that would precede the table of contents.




NOTE The **Foreword** tab is enabled only if you choose **Blank** from Create Options.

- 12 **System Attributes tab:** As needed, modify the system attributes for the document, such as the **Owner** and **Approval Status**.
- 13 Click **OK**.

Opening a Document to the Document Work Page

To open a document:

- 1 Open the Home View by clicking .
- 2 Double-click the desired document in the Documents tab of the Selection pane. The Document work page opens.

Opening a Document or Snapshot in a New Browser Window

To open the currently open document/snapshot in a new window:

- 1 Click **Open in New Window** from the Documents group in the Actions pane. The document or snapshot opens in a new browser window.

Save a Copy of a Document Under a New Name

This feature saves a copy of the currently open document under a new name.



PRIVILEGES Save As requires the following permissions:

- Chapter class: "Create" and "Read"
- Collections: "Create," "Link," "Create Based on Existing Collection"

To save a document under a new name:

- 1 Open the document to the Document work page, if it is not already open. See ["Opening a Document to the Document Work Page" on page 139](#).
- 2 Click **Save As** in the Documents group of the Actions pane. The Document Save As dialog opens.
- 3 **Name:** Enter a name for the new copy of the document.
- 4 **Description:** Enter a description of the document.

- 5 **Chapters Only:** Select this checkbox to copy only the chapters of the original document (no requirements).
- 6 Click the **OK** button.

Editing Document Attributes

These are the attributes from the General, Foreword, and System Attributes tabs of the New Document dialog.

To edit a document's attributes:

- 1 Open the document to the Document work page, if it is not already open. See ["Opening a Document to the Document Work Page" on page 139](#).
- 2 Click the **Edit** button at the top of the Detail pane. The Edit Document dialog opens.
- 3 Do any of the following as needed:
 - **Name:** Edit the name of the document.
 - **Description:** Edit the description of the document.
 - **Publish Title:** Select to use the string in the Name field as the document title when publishing to Word.
 - **Update To Current (Tip):** Select to automatically update the document with the newest version of each requirement.



NOTE To manually change the version of a specific requirement that is included in the document, see ["Change which Requirement Version Is Included in a Document" on page 141](#).

- **ECP Controlled:** Enable this checkbox if you want to require that users link the document to an ECP class object before editing it.



CAUTION! Once ECP Control is enabled on a document, **it cannot be disabled**.



NOTE

- ECPs are a high-level change management class type (Engineering Change Proposal) that can be used to collect multiple change requests into a single package.
 - If ECP Control is in effect, but the current user has not assigned an ECP, the document will be Read-Only until he assigns an ECP to it. A notice to this effect will be displayed to the right of the Project Bread Crumb.
 - To assign an ECP, see ["Assigning an ECP to a Document" on page 156](#).
- **Foreword:** Edit the foreword of the document.



TIP When you click in the field, formatting controls will appear.



- **Approval Status:** Select **approved** or **unapproved**.
- 4 Click **OK**.


Change which Requirement Version Is Included in a Document


You can swap the version of a requirement currently in use in a document for another version of the requirement.

To change which requirement version is included in a document:

- 1 In the Navigation pane of the Document work page, select the requirement you wish to change.
- 2 Expand the **History** section of the requirement in the Detail pane.

▶ Links				
▼ History		Properties Differences		
	TIME MODIFIED	OBJECT ID	MODIFIED BY	CURRENT STATUS
	18-MAY-2006@09:17:06	33	EPHOTO	Replaced
	25-NOV-2014@08:23:23	51	EPHOTO	Current (Baselined)
▶ Polls				

The version in use by the document will not have an Exchange () icon (nor will rejected versions).

- 3 Click the Exchange () icon of the version you want to use in the document. A dialog appears asking you to confirm this change.
- 4 Click **OK**.

Deleting a Document

To delete a document:

- 1 In the Navigation pane of the Document work page, select the root of the document.



NOTE The **Delete** command is only enabled if you have the "Remove" permission for both the Chapter class and for collections.

- 2 Click **Delete** in the Documents group of the Actions pane.
- 3 When prompted, confirm that you want to delete the document.



IMPORTANT! When you delete a document, the document and chapters are deleted, but the requirements are not deleted from the database.

Deleting a Requirement from a Document

To delete a requirement from a document:

- 1 In the Navigation pane of the Document work page, select the requirement you wish to remove from the document. To select more than one requirement, click additional requirements while holding the CTRL key.
- 2 Click **Delete** from Requirements group of the Actions pane. The **Delete from Document** dialog box opens.
- 3 If you also want to delete the requirement from the project, select the **Also delete from project** check box.
- 4 Click **Yes** to confirm that you want to delete the requirement.

Creating a Snapshot of a Document

A snapshot is a read-only copy of a document. It preserves the current state of the document for future reference. While creating a snapshot, you can also create a baseline of the requirement versions currently in the document.



NOTE

- When you create a snapshot of a document, the settings specified in the Properties dialog box are maintained.
- To create a snapshot, you must have the "Create Baseline" permission for collections.

To create a snapshot of a document:

- 1 Open the document to the Document work page, if it is not already open. See ["Opening a Document to the Document Work Page" on page 139](#).
- 2 Click **Create/View Snapshots** in the Documents group of the Actions pane. The Snapshots dialog opens.
- 3 Click the **New Snapshot** button. The New Snapshot dialog opens.
- 4 **Name:** Initially this field will contain the name of the original document. Modify it as needed.
- 5 **Description:** Initially this field will contain the description of the original document. Modify it as needed.
- 6 **Automatically create corresponding Baseline:** Enable this checkbox if you want to create a baseline of the requirement versions currently in the document.



NOTE The baseline creation process runs in the background and is likely still in progress after the snapshot creation process has completed. No notice will appear upon either completion or failure of the baseline creation process.

- 7 Click the **OK** button in the New Snapshot dialog.

- 8 Click the **Close** button in the Snapshots dialog.

Working with Snapshots of an Open Document

To access a snapshot follow these steps:

- 1 With the document open in the Document work page, click **Create/View Snapshots** in the Documents group of the Actions pane. The Snapshots dialog opens.
- 2 Select the desired snapshot from the list.
- 3 Click one of the following buttons:
 - **Open:** The snapshot opens in the Document work page.
 - **Modify:** The Modify Snapshot dialog opens. Modify the **Name** and **Description** fields as needed, and click the **OK** button.
 - **Save As:** Copies the current document into a new document.
 - **Delete:** Click **OK** on the resulting confirmation dialog. The snapshot is deleted.



TIP You can also directly open snapshots from the **Documents** tab of the Home View. See "[Working with Snapshots of a Closed Document](#)" on page 143.

Working with Snapshots of a Closed Document

access a snapshot follow these steps:

- 1 Select the document of the desired snapshot in the **Documents** tab of the Home page.
- 2 Click **Show Snapshots** if snapshots are not already visible.
- 3 Select the desired snapshot.
- 4 Click one of the following in the Actions pane:
 - **View/Edit:** The snapshot opens in the Document work page.
 - **Publish:** The Publish Document dialog prompts you to choose in which format you want to publish the document. Choose **Word Document (*.docx)** or **PDF document (*.pdf)** and click **Publish**. When prompted by your browser, click **Save** to save the file to your local system. See "[Publish as a Microsoft Word Document](#)" on page 146 for more information on publishing.
 - **Save As:** Saves the selected snapshot as a new document.
 - **Delete:** Click **OK** on the resulting confirmation dialog. The snapshot is deleted.

Comparing Documents and Snapshots

You can compare a document and one of its snapshots or compare two snapshots of the same document. The differences are flagged in the Navigation and Detail panes.

To compare documents and snapshots:

- 1 Open the document or snapshot to the Document work page, if it is not already open. See ["Opening a Document to the Document Work Page" on page 139](#).
- 2 Click **Compare Document** in the Documents group of the Actions pane. The Compare Snapshots dialog opens.
- 3 **Select document:** This field displays the name of the document, or the parent document of the snapshot, that was open when the dialog was invoked. If needed, click the Browse (...) button to select a different document.
- 4 **Select document versions to compare:** Do the following:
 - a Select the snapshot or document to use as the base of the comparison and click the **Set Base Document** arrow button to populate the **Base version** field.
 - b Select the snapshot or document that you want to compare to the base and click the **Set Changed Document** arrow button to populate the **Changed version** field.
- 5 Click the **Compare** button. The Compare Snapshots dialog closes.

The Navigation pane of the Document work page now contains the union of all of the chapters in the two documents, and the detail pane contains a **Requirement Difference Summary**. See ["Working with the Requirement Difference Summary" on page 144](#).

Working with the Requirement Difference Summary

The **Requirement Difference Summary** is a special chapter that is displayed before all other chapters in the Navigation pane. When this chapter is selected, the Detail pane contains five sections: **Added Requirements**, **Removed Requirements**, **Moved Requirements**, **Changed Requirements**, and **Unchanged Requirements**. Each section contains three columns: **Rqmt ID**, **Title**, and **Class**.

To work with the Requirement Difference Summary:

- 1 Click the **Requirement Difference Summary** node in the Navigation pane.
 - Icons in the Navigation pane indicates if a given chapter or requirement was added, removed, moved, changed, or unchanged.
 - At the chapter level, the change icons account only for the chapter description, not for the requirements in the chapter. Therefore, if a description of a chapter did not change, but subchapters or requirements in the chapter changed, the chapter icon indicates that the chapter is unchanged.
 - If the title of a chapter or requirement is different in the two documents, both titles are displayed in the Navigation pane.

- When a chapter is selected in the Navigation pane, the Detail pane shows requirements in the grid view.



NOTE The attributes shown are those defined for display in the document. See ["Specifying Document Properties" on page 149](#).

- Only those attributes that were selected in the **Properties** dialog box are shown.
- The icon that indicates whether the requirement was added, removed, moved, changed, or unchanged is also shown in the grid view.
- When you select a changed requirement in the Navigation pane:
 - The Detail pane shows the differences between the two versions.
 - For HTML-enabled text attributes, only the textual differences are shown in the Detail pane. The HTML tags are removed from the attribute and then the attributes are compared.
 - An icon is displayed next to the sections in the Detail pane that include changed attributes, and the sections that include changed attributes are expanded.
- The comparison is relative to the base version, especially for moved requirements (requirements that have been added and removed as a result of a drag-and-drop operation).

Publishing the Document Differences Report

The **Publish** command lets you publish a Microsoft Word document from the Document work page, as described in ["Publish as a Microsoft Word Document" on page 146](#). However, the Table of Contents will have **[ADDED]**, **[REMOVED]**, **[MOVED]**, **[CHANGED]**, or **[UNCHANGED]** appended to the end of each chapter title in the published document.



NOTE A Word document containing tables is created when you publish the document differences report. If you view this Word document in Print Layout, some of the tables are not visible. However, if you view this Word document in Normal layout, the entire document is visible.

Viewing a Snapshot or Document

You can view the individual snapshot or document from the "compare" version of the Document work page.

To view a snapshot or document from the "compare" version of Documents View:

- Click a document or snapshot link next to **Go to:** at the top of the Detail pane.

The normal Document work page of the document or snapshot is displayed. Because snapshots are read-only, their chapters, subchapters, and requirements are dimmed in the Navigation pane.

Publish as a Microsoft Word Document

You can publish an RM document or snapshot as a Microsoft Word file from the **Document View**.

- The RM document name becomes the name of the Word file.
- The RM document name becomes the title of the Word document, unless you cleared the **Publish Title** check box in either the *New Document* or *Edit Document* dialog.
- The Navigation pane becomes the table of contents for the Word document.
- The content and layout in the Detail pane define the body of the Word document.

You can download or open the Word document after it is published.



NOTE

- The published Word document is not stored in the Dimensions RM database.
- If Microsoft Word is not installed on the server, Microsoft Word documents are created with file extension `.doc` instead of `.docx`. When opening a `.doc` file, you might receive a message that informs you that this file is in a different format than `.doc`. You can safely click **Yes** in this dialog box and the file will open in Word.
- If a `.doc` file is created, all links in the Table of Contents point to page number one. To correctly number the entries in the Table of Contents, right-click the Table of Contents and select **Update** in the context menu.

To publish to a Microsoft Word file:

- 1 Open the document or snapshot to the Document work page, if it is not already open. See ["Opening a Document to the Document Work Page" on page 139](#).
- 2 Click **Publish** in the Documents group of the Actions pane.
- 3 The Publish Document dialog prompts in which format you want to publish the document. Select **Word Document (*.docx)** and click on **Publish**.
- 4 When prompted by your browser, click **Save** to save the file to your local system.



NOTE An administrator can configure the system to print headers and footers in the published document and use custom styles for the published document. An administrator can also create custom templates that you can select for the published document.

To select an existing custom template, see ["Formatting Documents" on page 133](#). To create a custom template, see chapter *"Creating Templates to Publish Requirements"* in *Dimensions RM Administrator's Guide*.

Viewing Attachments in the Published Document

If requirements in the document contain file attachment attributes, they can be included as links in the published Word document. To see the links, you must add the File Attachment attribute to the **Attributes to Display** list in the *Document Properties* dialog box. For information about this dialog box, see ["Specifying Document Properties" on page 149](#).

The links are displayed as icons. Double-click the icon in the published document to open the associated file.





NOTE

- Because the published document and the file attachments are stored in one document, the size of the document can be quite large. Its size depends on the number of requirements that have file attachments and the size of the file attachments.
- You can install Microsoft Word on your Dimensions RM Web server to publish attachments within your document, or you can choose to install it on other server. An administrator can configure the server if you do not want Word installed on the Web server. For more information, please see the *Serena Dimensions RM Administrator's Guide*.

The following illustration shows the file attachment links in the published document in grid layout.

3.1.3 Functional Requirements

#	Rqmt ID	Title	Text	File Attachment
3.1.3.1	MRKT_000001	EPhoto will be an online photo album	The ePhoto system shall enable the user to browse an on-line photo album. It shall look and feel like an electronic photo album, just like the one on the coffee table.	no file attached
3.1.3.1.1	MRKT_000024	Stored photo slideshows	The ePhoto system shall provide the capability to create a slide shows of stored photos.	 prototype.png
3.1.3.1.2	MRKT_000023	EPhoto will be an online photo album	The ePhoto system shall enable the user to browse an on-line photo album. It shall look and feel like an electronic photo album, just like the one on the coffee table.	 prototype.png

The following illustration shows the file attachment links in the published document in paragraph layout:

3.1.3 Functional Requirements

3.1.3.1 EPhoto will be an online photo album


Rqmt ID: MRKT_000001 **File Attachment:** no file attached

This ePhoto system shall enable the user to browse an on-line photo album in a manner similar to browsing the one on the coffee table.

3.1.3.1.1 Stored photo slideshows

Rqmt ID: MRKT_000024

File Attachment:




The ePhoto system shall provide the capability to create a slide shows of stored photos.

3.1.3.1.2 Displaying stored photo infos

Rqmt ID: MRKT_000023

File Attachment:



The ePhoto system shall allow users to display any of the information stored with the photo.

Publish as an Adobe PDF Document

You can publish an RM document or snapshot as an Adobe PDF file from the **Document View**.

- The RM document name becomes the name of the PDF file.
- The RM document name becomes the title of the PDF document, unless you cleared the **Publish Title** check box in either the *New Document* or *Edit Document* dialog.
- The Navigation pane becomes the table of contents for the PDF document.
- The content and layout in the Detail pane define the body of the PDF document.

You can download or open the PDF document after it is published.



NOTE

- The published PDF document is not stored in the Dimensions RM database.
- Attachments cannot be embedded into a PDF document.
- On the server, Microsoft Word is required to generate PDF files. If Microsoft Word is not installed on the server, Microsoft Word documents are created with file extension .doc instead of a PDF file. When opening a .doc file, you might receive a message that informs you that this file is in a different format than .doc. You can safely click **Yes** in this dialog box and the file will open in Word.

To publish to an Adobe PDF file:

- 1 Open the document or snapshot to the Document work page, if it is not already open. See ["Opening a Document to the Document Work Page" on page 139](#).
- 2 Click **Publish** in the Documents group of the Actions pane.
- 3 The Publish Document dialog prompts in which format you want to publish the document. Select **PDF Document (*.pdf)** and click on **Publish**.
- 4 When prompted by your browser, click **Save** to save the file to your local system.



NOTE An administrator can configure the system to print headers and footers in the published document and use custom styles for the published document. An administrator can also create custom templates that you can select for the published document.

To select an existing custom template, see ["Formatting Documents" on page 133](#). To create a custom template, see *"Creating Templates to Publish Requirements"* in *Dimensions RM Administrator's Guide*.

Specifying Document Properties

In the **Properties of Document** dialog box, you can specify which attributes are displayed for the requirements in a class.




NOTE These settings are specific to the current document. You must specify properties for each document individually.

To specify document properties:

- 1 Open the document to the Document work page, if it is not already open. See ["Opening a Document to the Document Work Page" on page 139](#).

- Click **Edit Properties** in the Documents group of the Actions pane. The **Properties of document** dialog opens.



- In the **Choose a class** list, select the class for which you want to specify properties.
- Attributes To Display:** To specify the attribute columns to display in the Details pane of the document, see chapter ["Attributes to Display List" on page 25](#).
- Attributes to Display in the Tree:** To specify the attributes to display in the Navigation pane of the document, see chapter ["Attributes to Display List" on page 25](#).
- Attributes to Display in the Tooltip:** To specify the attributes to display in the Navigation pane tooltips of the document, see chapter ["Attributes to Display List" on page 25](#).



NOTE Optionally, change the maximum **Display Length for Text attributes** for both the Navigation pane and tooltips. If the total length of the combined attribute string exceeds this limit, the string will be truncated and end in an ellipsis (...). The default is 50 characters.

- Click **OK**.

Restricting Requirement Classes in a Document

A document may be restricted to allow only certain classes in a document. This setting can be made at any time and has no effect on requirements which exist in the document already. To be able to restrict a document to certain requirement classes, your user account must have the **Create** and **Update Properties** rights for documents.

To restrict certain classes to a document, execute these steps:

- 1 Open the document you want to restrict.
- 2 In the **Actions** pane, click **Edit Properties** in the **Documents** group.
- 3 Select the **Restrict Classes** tab.
- 4 In the **Select Allowed Classes** table, clear the checkboxes of those classes you do not want to be added to the document. To toggle all checkboxes, click the checkbox next to **Name**.
- 5 Click **OK**.



NOTE


- The **Add to Chapter** dialog does not offer restricted classes.
- Documents created on a document with class restrictions inherit those restrictions.

Document Dependencies

A child document depends on a master document. This dependency can be viewed in the **Document Properties** dialog for both, master and child documents.

To review the dependencies between master and child documents:

- 1 Open the master or child document for which you want to show the dependencies.
- 2 In the **Actions** pane, click **Edit Properties** in the **Documents** group.
- 3 Select the **Dependencies** tab.

If the document is a child document, you can change the document to an independent document by clicking .

Creating a Chapter

You can create a chapter and then add individual requirements to it at a later time, or you can populate the chapter based on the requirements returned by a query. In the case of a query, it can be a one time operation or the chapter can be linked to the query and be updated along with it.

To create a chapter:

- 1 Open the document to the Document work page, if it is not already open. See ["Opening a Document to the Document Work Page" on page 139](#).

- Click the **New Chapter** button in the Navigation pane. The **New Chapter** dialog opens.

- In the **Title** field, type the name of the chapter.
- Click in the box under the title. The HTML edit control is displayed. Type the description in the box.
- To populate the content of the chapter based on a specific query, select the **Based on Query** option. You can then select the query to use as the basis of the chapter's content. This may be a class report, relationship report, or traceability report.



NOTE If the query returns multiple versions or non-current versions of a requirement, they will be included in the document. Prior to RM 11.2.2, only the Current version would be included.

- Optionally choose the **Update chapter when script is updated** checkbox to dynamically refresh the content in the chapter when the query is updated.



NOTE

- If the query specifies requirement version by status (Current, Replaced, etc.), the version(s) included in the document will be updated to reflect whichever version of the requirement is assigned to the specified status.
- If the query specifies a specific object version number, that version of the requirement will remain in the document regardless of changes to its status.

- If you selected a chapter when you clicked **Create**, the **Add as subchapter** checkbox is enabled. Select this check box if you want to add this chapter as a subchapter of the selected chapter.

- 8 Click **OK**.



NOTE Any chapter created in a master document, will become available in the related child documents immediately.

Editing a Chapter

You can change the name and description of a chapter, and change it to populate its content based on a query.

To change the name and description of a chapter:

- 1 Open the document to the Document work page, if it is not already open. See ["Opening a Document to the Document Work Page" on page 139](#).
- 2 Select the chapter in the Navigation pane.
- 3 Click the **Edit** button in the Detail pane. The **New Chapter** dialog opens.



NOTE If the document is a child document, you cannot edit a chapter from the master document.

- 4 Edit the title and description as desired.



TIP For information on formatting text, see ["HTML Text Formatting Toolbar" on page 26](#).

- 5 To populate the content of the chapter based on a specific query, select the **Based on Query** option. You can then select the query to use as the basis of the chapter's content. This may be a class report, relationship report, or traceability report.



NOTE If the query returns multiple versions or non-current versions of a requirement, they will be included in the document. Prior to RM 11.2.2, only the Current version would be included.

- 6 Optionally choose the **Update chapter when script is updated** checkbox to dynamically refresh the content in the chapter when the query is updated.



NOTE

- If the query specifies requirement version by status (Current, Replaced, etc.), the version(s) included in the document will be updated to reflect whichever version of the requirement is assigned to the specified status.
- If the query specifies a specific object version number, that version of the requirement will remain in the document regardless of changes to its status.

- 7 Click **OK**.

Deleting a Chapter

To remove a chapter:

- 1 Select the chapter in the navigation tree. To select more than one chapter, click additional chapters while holding the CTRL key.
- 2 Click the **Delete** button.



NOTE If the document is a child document, you cannot delete a chapter from the master document.

- 3 When prompted, confirm that you want to delete the selected chapters.



NOTE



- The selected chapters and any sub chapters are deleted from the document.
- Any requirements in the selected chapter are removed from the document, but not from the RM database.
- The **Delete** command is enabled only if you have the *Remove* permission for the Chapter class.

Moving Chapters and Requirements

You can move chapters or requirements in a document by using drag and drop. For all drag and drop operations, these rules apply:

- You cannot drop a chapter onto a requirement.
- When dropping chapters or requirements onto a chapter, they become children of that chapter. The new children are inserted before any existing children.
- When dropping requirements onto a requirement, they become children of that requirement. The new children are inserted before any existing children.
- Dropping chapters or requirements in-between chapters or requirements inserts them at that location.
- When dropping chapters or requirements, the original sequence of the selected chapters or requirements is maintained.
- If automatic numbering is enabled, moving chapters or requirements changes the numbering of the moved chapters or requirements and all subsequent chapters or requirements.

To move a single chapter or requirement:

- 1 Select a chapter or requirement.
- 2 Do one of the following:
 - Click  or .

- Drag the chapter or requirement and drop it at its new location.

To move several chapters:

- 1 Select a chapter.
- 2 Do one of the following:
 - Shift-click a chapter: This selects all chapters between the chapter selected in step 1 and the shift-clicked chapter (including it).
 - Ctrl-click one or several chapters: This adds the chapters you Ctrl-clicked to the selection.
- 3 Drag one selected chapter and drop it at its new location.

To move several requirements:

- 1 Select a requirement.
- 2 Do one of the following:
 - Shift-click a requirement: This selects all requirements between the requirement selected in step 1 and the shift-clicked requirement (including it).
 - Ctrl-click one or several requirements: This adds the requirements you Ctrl-clicked to the selection.
- 3 Drag one selected requirement and drop it at its new location.

**TIPS**

- Ctrl-clicking a selected chapter or requirement removes it from the selection.
- If you have a large block of chapters or requirements with just some exclusions, it may be quicker to select the block with Shift-click and deselecting some chapters or requirements with Ctrl-click rather than Ctrl-clicking all chapters or requirements you want to move.

Adding Requirements to a Document

To add a requirement, you search for existing requirements and then add them to a chapter or document. If a requirement is selected when you issue the **Add** command, you have the option of adding the requirements that are returned as subrequirements of the selected requirement.

To add requirements:

- 1 Open the document to the Document work page, if it is not already open. See ["Opening a Document to the Document Work Page" on page 139](#).
- 2 In the Navigation pane, select the chapter to which you want to add the requirements.

- 3 Click **Add to Chapter** in the Requirements group of the Actions pane. The **Add to Chapter** dialog opens.
- 4 Select a class in the **Look for class** list.
- 5 **Constraints:** As needed, specify criteria to locate the desired requirements. See ["Attribute Constraints Tab" on page 28](#) and ["Relationship Constraints Tab" on page 31](#).
- 6 **Display Options:** As needed, specify how to display the results. See ["Display Options Tab" on page 34](#).
- 7 Select the **Case sensitive search** check box if you want the search results to exactly match the capitalization of the specified attribute values.
- 8 **Find Now:** Click this button to run the search. The results are displayed in the lower pane of the dialog.
- 9 **New Search:** Click this button to clear the current search criteria and results.
- 10 Select the desired requirements in the search results. For multi-selection of requirements, see chapter ["Selecting Multiple Requirements" on page 23](#).



NOTE

- A chapter icon is displayed next to a requirement if the requirement is in the chapter (including the root of the document) to which you are adding requirements.
- A document icon is displayed next to a requirement if the requirement is included in the document but is not in the chapter to which you are adding requirements.

- 11 **Add as subrequirement:** Select this checkbox if you want the requirements to be added as subrequirements of the requirement currently selected in the Navigation pane. This checkbox is available only if a requirement is selected in the Navigation pane.
- 12 Do any of the following:
 - **Add:** Click this button to add the selected requirements to the document.
 - **Remove:** Click this button to remove the selected requirements from the document.




TIP To manually change the version of a specific requirement that is included in the document, see ["Change which Requirement Version Is Included in a Document" on page 141](#).

Assigning an ECP to a Document

ECPs are a high-level change management class type (Engineering Change Proposal) that can be used to collect multiple change requests into a single package.

If ECP Control is enabled on the document, the name of current ECP is displayed to the right of the Project Bread Crumb.



If ECP Control is in effect, but the current user has not assigned an ECP, the document will be Read-Only until he assigns an ECP to it. Instead of the name of an ECP, you will see this message: **(No ECP, document is read-only)**.



NOTE To enable ECP Control on a document, see ["Editing Document Attributes" on page 140](#).

To assign an ECP:

- 1 Open the document to the Document work page, if it is not already open. See ["Opening a Document to the Document Work Page" on page 139](#).
- 2 Click **Assign ECP** in the Documents group of the Actions pane. The Assign ECP dialog opens.
- 3 Select **ECPs** in the **Look for class** list.
- 4 **Constraints:** As needed, specify criteria to locate the desired ECP. See ["Attribute Constraints Tab" on page 28](#) and ["Relationship Constraints Tab" on page 31](#).
- 5 **Display Options:** As needed, specify how to display the results. See ["Display Options Tab" on page 34](#).
- 6 Select the **Case sensitive search** check box if you want the search results to exactly match the capitalization of the specified attribute values.
- 7 **Find Now:** Click this button to run the search. The results are displayed in the lower pane of the dialog.
- 8 **New Search:** Click this button to clear the current search criteria and results.
- 9 Select the desired ECP in the search results.
- 10 Do any of the following:
 - **Assign:** Click this button to assign the selected ECP to the document.
 - **Clear:** Click this button to remove the selected ECP from the document.

Finding and Replacing Character Strings

You can find and replace character strings in chapters and requirements in an open document. You can find and replace character strings in the following:

- An entire document or a selected chapter


- Title and Description attributes or all alphanumeric, list or user attributes




NOTE

- The **Find and Replace** menu item is disabled while you are comparing a document and its snapshot (see ["Comparing Documents and Snapshots" on page 144](#)).
- For read-only objects (snapshots and ECP-controlled documents without an ECP assigned), the **Replace** and **Replace All** buttons are not shown. With these objects, you only Search feature of the dialog works.
- To use the **Replace** and **Replace All** commands, you must have permission to replace a requirement or chapter. If only some attributes can be changed, they are changed, and you receive a message saying that you do not have permission to replace the string in all attributes.


To find and replace character strings:

- 1 Open the document to the Document work page, if it is not already open. See ["Opening a Document to the Document Work Page" on page 139](#).
- 2 If you wish to search within a specific chapter, select it in the Navigation pane.
- 3 Click the **Find and replace** () button. The Find and Replace dialog opens.



- 4 **Find what:** Enter the string you want to find.
- 5 **Replace with:** If you want to replace the string, enter the replacement string here.
- 6 **Match case:** Enable this check box to include the case of the string in the match criteria.
- 7 Select one of the following:
 - **Selected chapter:** To search only the selected chapter and any subchapters and requirements it contains.
 - **All chapters:** To search all chapters and their contents.

- 8 Select one of the following:
 - **Title and description:** To search only Title and Description attributes.
 - **All attributes:** To search all alphanumeric, list and user attributes.
- 9 Click any of the following buttons:
 - **Find Next:** This button to displays the first chapter or requirement containing one or more instances of the string. The chapter or requirement is selected in the Navigation pane, and the found string is highlighted in the Detail pane. To display the next match, click the button again.



- **Replace:** The chapter or requirement that is currently selected is replaced, and the new version contains the string you specified in the **Replace with** box.
- **Replace All:** This button replaces all chapters and requirements containing the string you specified in the **Find what** field with the string you specified in the **Replace with** field.


The Find and Replace dialog closes, and a "Replacing all strings" message is displayed. After this operation finishes, a dialog displays how many chapters and requirements were replaced and reports any errors.

Working with Limited Permissions

If you navigate to a Document work page and one or more of the requirements in the chapter belongs to a class to which you do not have "read" permission, or if one or more requirements belong to a category to which you do not have permission, the following occurs:

- The chapter or requirement icon is displayed as being torn.
 - A torn chapter icon means that the user does not have permission to read one or more requirements within that chapter.
 - A torn requirement icon means that the user does not have permission to read one or more subrequirements under that requirement.
- A message informs you that not all requirements in the document are displayed due to permissions issues.

The following illustration shows this scenario.



Merging Document Changes

The configuration is set through the **Project Settings** dialog, which is available to administrators. For more information, see the *Serena Dimensions RM Administrator's Guide*.



NOTE RM Browser can be configured to use locking or merging to handle the situation where multiple users edit a requirement or chapter at the same time. This section describes document merging (the "root chapter" of a document is the document itself).

If RM Browser is configured to use merging, document changes must be merged when two users edit the same document at the same time.

Changes can be *automatic* or *conflicting*, as described in the following table.

Change Type	Description
Automatic	When the change made by the first user is the same as the change made by the second user or when the change made by the first user is distinct from any change made by the second user, automatic merging can occur because a review of the change is not strictly necessary. However, it is recommended that the second user review the change made by the first user before accepting it.
Conflicting	When the change the second user makes conflicts with the change the first user made, the second user must review the changes and do one of the following: <ul style="list-style-type: none"> ■ Accept the change the second user made ■ Accept the change the first user made ■ Accept the original value ■ Combine the changes manually by editing the value directly in the main part of the dialog


The following scenario summarizes the actions that lead to document merging.

- 1 Two users edit the same document at the same time.
- 2 The first user clicks **OK** in the **Edit Document** dialog. The **Edit Document** dialog closes.
- 3 The second user clicks **OK** in the **Edit Document** dialog.
- 4 The second user is notified that the first user made one or more changes to the document. The notification either tells the second user that the merge can be done automatically (because the change the first user made does not conflict with the change the second user made) or that the changes conflict and must be resolved before the second user can replace the document.
- 5 The second user clicks **OK** on the notification message. The **Edit Document** dialog becomes the **Merge Document** dialog. The **Merge Document** dialog box differs from the **Edit Document** dialog in that the **Merge Document** dialog:
 - Has a section at the top that summarizes the changes and provides a user interface for merging the changes

- Has visual indications next to its attributes that identify the type of merge that the second user selected
- 6 The second user uses the merge section at the top of the **Merge Document** dialog to resolve the changes as described in "Viewing Prior Versions of the Document" on page 161 and "Merging Changes" on page 162.

Merge Status

The merge status of the changes made by Mary and Joe are highlighted in the **Changed Attributes** section at the top of the **Merge Document** dialog box.





Mary made the first change when she changed "Requirements" to "Requirement Document" in the *Name* attribute. In the **Merge Status** column, **Automatic** is selected in the list, because the change does not involve a conflict with a change that Joe made. The icon that represents an automatic merge is a diamond shape with a merge arrow in it and is displayed to the left of the **Merge Status** list and to the left of the *Name* attribute box in the main part of the dialog box.

The second change involves a conflict. In the second change, Mary changed the Foreword to "Mary's requirements" but Joe changed this attribute value to "Joe's requirements." In the **Merge Status** column, **Conflict** is selected in the list. The icon that represents a conflict is a triangle with an exclamation point in it and is displayed to the left of the **Merge Status** list and to the left of the *Foreword* attribute in the main part of the dialog.

Viewing Prior Versions of the Document

It can be useful to view prior versions of the document before you resolve changes.



The second user can view the original version of the document by clicking the **View original version of the document** button  or by clicking **Original** in the appropriate **Merge Status** column list.

The second user can view the document in the state it was in after the first user made changes but before the second user made changes by clicking the **New version of document prior to your changes** button .

Merging Changes

After the second user has decided how to resolve the changes, he or she can merge them.

To merge changes:

- 1 If **Automatic** is selected in the **Merge Status** column list, perform one of the following steps:
 - Retain the **Automatic** selection to accept the change.
 - Select the name of the user who made the change to accept the change.
 - Select **Original** to restore the attribute to its original value.
- 2 If **Conflict** is selected in the **Merge Status** column list box, perform one of the following steps:
 - Select the name of the user whose change you want to accept.
 - Select **Original** to restore the attribute to its original value.
 - Edit the value manually in the main form so that it matches the value you want to accept.
- 3 If you want to accept all changes made by particular user (for example, Mary or Joe), click the **Accept all changes by Mary** button  or the **Accept all changes by Joe** button .
- 4 Click **OK**.

Merging Chapter Changes

The configuration is set through the **Project Settings** dialog box, which is available to administrators. For more information, see the *Serena Dimensions RM Administrator's Guide*.



NOTE RM Browser can be configured to use locking or merging to handle the situation where multiple users edit a requirement or chapter at the same time. This section describes chapter merging.

If RM Browser is configured to use merging, chapter changes must be merged when two users edit the same chapter at the same time.

Changes can be *automatic* or *conflicting*, as described in the following table.


Change Type	Description
Automatic	When the change made by the first user is the same as the change made by the second user or when the change made by the first user is distinct from any change made by the second user, automatic merging can occur because a review of the change is not strictly necessary. However, it is recommended that the second user review the change made by the first user before accepting it.
Conflicting	When the change the second user makes conflicts with the change the first user made, the second user must review the changes and do one of the following: <ul style="list-style-type: none"> ■ Accept the change the second user made ■ Accept the change the first user made ■ Accept the original value ■ Combine the changes manually by editing the value directly in the main part of the dialog box.


The following scenario summarizes the actions that lead to chapter merging.


- 1 Two users edit the same chapter at the same time.
- 2 The first user clicks **OK** in the **Edit Chapter** dialog.
- 3 The second user clicks **OK** in the **Edit Chapter** dialog.
- 4 The second user is notified that the first user made one or more changes to the chapter. The notification either tells the second user that the merge can be done automatically (because the change the first user made does not conflict with the change the second user made) or that the changes conflict and must be resolved before the second user can replace the chapter.
- 5 The second user clicks **OK** on the notification message. The **Edit Chapter** dialog becomes the Merge Chapter dialog. The **Merge Chapter** dialog differs from the **Edit Chapter** dialog in that the **Merge Chapter** dialog:
 - Has a section at the top that summarizes the changes and provides a user interface for merging the changes
 - Has visual indications next to its attributes that identify the type of merge that the second user selected
- 6 The second user uses the merge section at the top of the **Merge Chapter** dialog to resolve the changes as described in ["Viewing Prior Versions of the Chapter" on page 164](#) and ["Merging Changes" on page 164](#).

Merge Status

The merge status of the changes made by Joe and Mary are highlighted in the **Changed Attributes** section at the top of the **Merge Chapter** dialog.





Joe made the first change when he changed the *Title* attribute from "Document Scope" to "Scope." This change involves a conflict, because Mary changed the *Title* attribute from "Document Scope" to "Scope of Document." In the **Merge Status** column, **Conflict** is selected in the list. The icon that represents a conflict is a triangle with an exclamation point in it  and is displayed to the left of the **Merge Status** list and to the left of the box in the main part of the dialog.

Mary made the second change when she changed "office functions" to "office operations." In the **Merge Status** column, **Automatic** is selected in the list, because the change does not involve a conflict with a change that Joe made. The icon that represents an automatic merge is a diamond shape with a merge arrow in it  and is displayed to the left of the **Merge Status** list and the box in the main part of the dialog.

Viewing Prior Versions of the Chapter



It can be useful to view prior versions of the chapter before you resolve changes.

- The second user can view the original version of the chapter by clicking the **View original version of the chapter** button  or by clicking **Original** in the appropriate **Merge Status** column list.
- The second user can view the chapter in the state it was in after the first user made changes but before the second user made changes by clicking the **New version of chapter prior to your changes** button .

Merging Changes

After the second user has decided how to resolve the changes, he or she can merge them.

To merge changes:

- 1 If **Automatic** is selected in the **Merge Status** column list box, perform one of the following steps:
 - Retain the **Automatic** selection to accept the change.
 - Select the name of the user who made the change to accept the change.
 - Select **Original** to restore the attribute to its original value.
- 2 If **Conflict** is selected in the **Merge Status** column list box, perform one of the following steps:
 - Select the name of the user whose change you want to accept.
 - Select **Original** to restore the attribute to its original value.
 - Edit the value manually in the main form so that it matches the value you want to accept.
- 3 If you want to accept all changes made by a particular user (for example, Joe or Mary), click the **Accept all changes by Joe** button  or the **Accept all changes by Mary** button .
- 4 Click **OK**.

Copying the URL of a Document to the Clipboard

You can copy the URL of a document or snapshot and paste it into a file for future use and reference. When that URL is later invoked, it will open RM Browser to that document or snapshot. See the appropriate section below.

Copying the URL of an Open Document or Snapshot

To copy the URL of an open document or snapshot:

- 1 With the document or snapshot open in a work page, click **Open in New Window** from the Documents group in the Actions pane. The document or snapshot opens in a new browser window.
- 2 Click on and select the URL in the new browser window.
- 3 Press **Ctrl + C**, or right-click on the highlighted URL and select **Copy**. The URL is now on the Windows clipboard.
- 4 Close the new browser window.
- 5 Use **Ctrl + V**, or the relevant application-specific menu command, to paste the URL into the file or application where you wish to use it.

Copying the URL of a Closed Document


To copy the URL of a closed document:

- 1 Select the desired document in the Documents tab of the Home View.

- 2 Click **Create direct URL** in the Documents group of the Actions pane. A dialog opens with the URL selected.
- 3 Press **Ctrl + C**, or right-click on the highlighted URL and select **Copy**. The URL is now on the Windows clipboard.
- 4 Click **OK** to dismiss the dialog.
- 5 Use **Ctrl + V**, or the relevant application-specific menu command, to paste the URL into the file or application where you wish to use it.

Copying the URL of a Closed Snapshot


To copy the URL of a closed snapshot

- 1 Open the document to the Document work page, if it is not already open. See ["Opening a Document to the Document Work Page" on page 139](#).
- 2 Click **Create/View Snapshots** in the Documents group of the Actions pane. The Snapshots dialog opens.
- 3 Right-click the link  icon next to the desired snapshot.
- 4 Select **Copy Shortcut** (or a similar menu item, depending upon the browser you are using).

The URL is now on the Windows clipboard. You can now paste it into the file or application where you wish to use it.

Moving a Document or Snapshot to a different Category

To move a document to a different category, do the following:

- 1 Open the Home View by clicking .
- 2 Select the **Documents** tab.
- 3 If you want to move a snapshot, click **Show Snapshots**.
- 4 Drag the document or snapshot and drop it at the desired category in the **Categories** tree.

Alternatively, you can use the **Move Containers to category** dialog as described in chapter ["Moving Containers by dialog" on page 187](#).

Chapter 6

Working with Reports

Running Reports	168
Editing a Report	168
Creating a Class Report	170
Creating a Relationship Report	172
Creating a Traceability Report	173
Creating a Graphical Report	177
Working in the Traceability Work Page	175
Moving and Copying Reports to a Different Category	180
Renaming Reports	181
Deleting Reports	181
Copying the URL of a Report to the Clipboard	182

Running Reports

To run a report:

- 1 Double-click the desired report in the Reports tab of the Home View.
- 2 If the script has prompts, enter the information that is requested.
- 3 Click the **Run** button.



NOTE For Traceability Reports, you can change between Gap view and Outline view by clicking on the **Switch to Gap View** or **Switch to Outline View** in the **Actions** pane.



TIP

- The description of a report can be displayed as a tool tip when you hover your cursor over the report name.
- For multi-selection of requirements in class reports and relationship reports, see chapter "[Selecting Multiple Requirements](#)" on page 23.

Editing a Report

To edit a report:

- 1 Double-click the desired report in the Reports tab of the Home View.
- 2 Click **Edit** in the Reports group of the Actions pane. The **Query By ReportType** or **Query By Script** dialog opens. The former is the wizard version of the dialog and is the default; the latter allows direct editing of the SQL-like script, and opens if the script cannot be edited with the wizard.
- 3 If you want to save the report:
 - a Enter a name in the **Name** box. The **Run** button changes to **Run and Save**.
 - b Select **Filter** or **Script** to identify the query type.



NOTE

- A filter includes only one class. A script includes one or more classes.
 - If you want to include the query on your My Work page, save the report as a script, even if it contains only one class. You can create a query if you do not have Create permission for scripts, but you cannot save it.
- c Type a description of the query in the **Description** box. The maximum number of characters is 1024.
 - d In the **Category** list, select the category in which the query will be saved.
- 4 As needed, modify the fields specific to the type of report you are editing:

- **Public Report:** Select this box to make the report public, otherwise the report is private.
- **Visible for:** This option is only available if **Public Report** is selected. If selected, you can choose which groups can access the report. If unselected, only the user who created the report can access it.
- **Editable for:** This option is only available if **Public Report** is selected. By default, this box has all groups selected which have the **Create Public** right. To allow members of groups without this right to edit this report, select the desired groups. If selected, you can choose which groups can edit the report. If unselected, only the user who created the report can modify it.
- **Class Report - Class:** Select the desired class from the list.



NOTE If a requirement of a class was selected when you invoked the dialog, then a class is already selected.

- **Relationship Report - Relationship:** Select the relationship you want to report on.
- **Relationship Report - Report Type tab:** Select a report type:

Report Type	Description
Full (compliance and non-compliance)	The report lists all requirements in the primary and secondary class, whether or not they are linked to each other.
Compliance only	The report lists either: <ul style="list-style-type: none"> ■ All matching requirements in the primary class that have links to matching requirements in the secondary class ■ All matching requirements in the secondary class that have links to matching requirements in the primary class
Non-Compliance only	The reports lists either: <ul style="list-style-type: none"> ■ All matching requirements in the primary class that have no links to matching requirements in the secondary class ■ All matching requirements in the secondary class that have no links to matching requirements in the primary class

A sample of the selected report type is displayed on the right side of the dialog.

- **Traceability Report - Top-level class:** Select the root class for the report.
- **Traceability Report - Related Classes to Display tab:**

- Select the check boxes next to the classes to specify the relationships that should be displayed in the traceability report.

**NOTE**

- The check box next to the top-level class is always selected and disabled.
- To avoid cyclic dependencies, the check boxes next to relationships that are already used are also selected and disabled.
- You do not have to select consecutive classes.

- 5 Constraints:** As needed, specify criteria to locate the desired requirements. See "[Attribute Constraints Tab](#)" on page 28 and "[Relationship Constraints Tab](#)" on page 31.
- 6 Display Options:** As needed, specify how to display the results. See "[Display Options Tab](#)" on page 34.
- 7 View Script / View Wizard:** Click to toggle between the Wizard and Script views of the dialog.



NOTE The tabs are visible only in the Wizard view.

- 8** Do any of the following:
 - **Preview:** Click this button to run the report without saving the report or closing the dialog.
 - **Run:** Click this button to run the report and close the dialog without saving the report.
 - **Save As and Run:** Click this button to run and save the report. The dialog will close.

Creating a Class Report

Complete these steps to create a class report.



CAUTION! If you do not have "read" permission in a category, the requirements in that category are not returned in the query results, even if they satisfy the query requirements.

To create a class report:

- 1** Select **Class Report** from the **New** menu. The *Query By Class* dialog opens.
- 2 Class:** Select the desired class from the list.



NOTE If a requirement of a class was selected when you invoked the dialog, then a class is already selected.

- 3** If you want to save the query:
 - a** Enter a name in the **Name** box. The **Run** button changes to **Run and Save**.

- b Select **Filter** or **Script** to identify the query type.



NOTE

- A filter includes only one class. A script includes one or more classes.
- If you want to include the query on your My Work page, save the report as a script, even if it contains only one class. You can create a query if you do not have Create permission for scripts, but you cannot save it.

- c Type a description of the query in the **Description** box. The maximum number of characters is 1024.

- d In the **Category** list, select the category in which the query will be saved.

- 4 **Constraints:** As needed, specify criteria to locate the desired requirements. See ["Attribute Constraints Tab" on page 28](#) and ["Relationship Constraints Tab" on page 31](#).
- 5 **Display Options:** As needed, specify how to display the results. See ["Display Options Tab" on page 34](#).
- 6 **View Script / View Wizard:** Click to toggle between the Wizard and Script views of the dialog.



NOTE The tabs are visible only in the Wizard view.

- 7 Do any of the following:
- **Public Report:** Select this box to make the report public, otherwise the report is private.
 - **Visible for:** This option is only available if **Public Report** is selected. If selected, you can choose which groups can access the report. If unselected, only the user who created the report can access it.
 - **Editable for:** This option is only available if **Public Report** is selected. By default, this box has all groups selected which have the **Create Public** right. To allow members of groups without this right to edit this report, select the desired groups. If selected, you can choose which groups can edit the report. If unselected, only the user who created the report can modify it.
 - **Preview:** Click this button to run the report without saving the report or closing the dialog.
 - **Run:** Click this button to run the report and close the dialog without saving the report.
 - **Save As and Run:** Click this button to run and save the report. The dialog will close.

Creating a Relationship Report

Complete these steps to create a relationship report.



NOTES You can create a report if you do not have Create permission for scripts, but you cannot save it.



CAUTION! If you do not have the "read" permission in a category, the requirements in that category are not returned in the report results, even though they satisfy the report requirements.

To create a relationship report:

- 1 Select **Relationship Report** from the **New** menu. The *Query By Relationship* dialog opens.
- 2 **Relationship:** Select the relationship you want to report on.
- 3 If you want to save the report:
 - a Enter a name in the **Name** box. The **Run** button changes to **Save As and Run**.
 - b Type a description of the query in the **Description** box. The maximum number of characters is 1024.
 - c In the **Category** list, select the category in which the query will be saved.
- 4 **Report Type tab:** Select a report type:

Report Type	Description
Full (compliance and non-compliance)	The report lists all requirements in the primary and secondary class, whether or not they are linked to each other.
Compliance only	The report lists either: <ul style="list-style-type: none"> ■ All matching requirements in the primary class that have links to matching requirements in the secondary class ■ All matching requirements in the secondary class that have links to matching requirements in the primary class
Non-Compliance only	The reports lists either: <ul style="list-style-type: none"> ■ All matching requirements in the primary class that have no links to matching requirements in the secondary class ■ All matching requirements in the secondary class that have no links to matching requirements in the primary class

A sample of the selected report type is displayed on the right hand side of the dialog.

- 5 **Constraints:** As needed, specify criteria to locate the desired requirements. There are these constraint tabs:
 - **Constraints - Source** and **Constraints - Target** (see "[Attribute Constraints Tab](#)" on page 28)
 - **Container - Source** and **Container - Target** (see "[Relationship Constraints Tab](#)" on page 31)

- 6 **Display Options:** As needed, specify how to display the results. See "[Display Options Tab](#)" on page 34.
- 7 **View Script / View Wizard:** Click to toggle between the Wizard and Script views of the dialog.



NOTE The tabs are visible only in the Wizard view.

- 8 Do any of the following:
 - **Public Report:** Select this box to make the report public, otherwise the report is private.
 - **Visible for:** This option is only available if **Public Report** is selected. If selected, you can choose which groups can access the report. If unselected, only the user who created the report can access it.
 - **Editable for:** This option is only available if **Public Report** is selected. By default, this box has all groups selected which have the **Create Public** right. To allow members of groups without this right to edit this report, select the desired groups. If selected, you can choose which groups can edit the report. If unselected, only the user who created the report can modify it.
 - **Preview:** Click this button to run the report without saving the report or closing the dialog.
 - **Run:** Click this button to run the report and close the dialog without saving the report.
 - **Save As and Run:** Click this button to run and save the report. The dialog will close.

Creating a Traceability Report

Complete these steps to create a Traceability Report.



NOTE Permissions for traceability reports are treated the same way as permissions for scripts. If you do not have permission to create a script on the project level, then you will be unable to create a traceability report. If you do not have permission to read a script on a project level, then you will be unable to open a traceability report, unless you created the report.

- 1 Select **Traceability Report** from the **New** menu. The *New Traceability Report* dialog opens.
- 2 **Top-level class:** Select the root class for the report.
- 3 **Type:** Select one of the following:
 - a **Matrix:** The report shows the values for the related classes.
 - b **Coverage:** The report shows in percent how many requirements of a class are linked to the selected child class.
- 4 If you want to save the report:

- a Enter a name in the **Name** box. The **Run** button changes to **Save As and Run**.
- b Type a description of the query in the **Description** box. The maximum number of characters is 1024.
- c In the **Category** list, select the category in which the query will be saved.

5 Related Classes to Display tab:

- Select the check boxes next to the classes to specify the relationships that should be displayed in the traceability report.



NOTE

- The check box next to the top-level class is always selected and disabled.
- To avoid cyclic dependencies, the check boxes next to relationships that are already used are also selected and disabled.
- You do not have to select consecutive classes.

- 6 **Constraints:** As needed, specify criteria to locate the desired requirements. See ["Attribute Constraints Tab" on page 28](#) and ["Relationship Constraints Tab" on page 31](#).
- 7 **Display Options:** As needed, specify how to display the results. See ["Display Options Tab" on page 34](#).



NOTE The **Display Options** tab is only visible if the selected **Type** is **Matrix**.

- 8 **Group By:** Contains these sections: **Collections**, **Baselines**, **Documents** and **Snapshots**. By selecting one or several entries from the lists, the result will be calculated in separate columns, one column for each selection.



NOTE The **Group By** tab is only visible if the selected **Type** is **Coverage**.

- 9 **View Script / View Wizard:** Click to toggle between the Wizard and Script views of the dialog.



NOTE The tabs are visible only in the Wizard view.

- 10 Do any of the following:


- **Public Report:** Select this box to make the report public, otherwise the report is private.
- **Visible for:** This option is only available if **Public Report** is selected. If selected, you can choose which groups can access the report. If unselected, only the user who created the report can access it.
- **Editable for:** This option is only available if **Public Report** is selected. By default, this box has all groups selected which have the **Create Public** right. To allow members of groups without this right to edit this report, select the desired groups. If selected, you can choose which groups can edit the report. If unselected, only the user who created the report can modify it.

- **Preview:** Click this button to run the report without saving the report or closing the dialog.
- **Run:** Click this button to run the report and close the dialog without saving the report.
- **Save As and Run:** Click this button to run and save the report. The dialog will close.

Working in the Traceability Work Page

Traceability is a way to analyze the linkages between requirements. It provides a way to select the relationships you want to trace, browse through the requirements that are part of the relationships, and then print traceability reports that display the information in a visual format that is easy to analyze.

Requirements in collections that are associated with Dimensions CM projects can be included in traceability reports. The following diagram illustrates such traceability.



The Traceability work page consists of a two panes: the left pane is the traceability tree with a top-level class from which related classes and requirements flow in a hierarchical format. The right pane displays information based on what you selected in the traceability tree.





NOTE Permissions for traceability reports are treated the same way as permissions for scripts. If you do not have permission to create a script on the project level, then you will be unable to create a traceability report. If you do not have permission to read a script on a project level, then you will be unable to open a traceability report, unless you created the report.

The Traceability work page includes the components described in the following table.

Component	Description
Traceability Tree	Contains a hierarchical presentation of requirements that belong to classes you selected when creating the traceability report. For more information about the traceability tree, see "Understanding the Traceability Tree" on page 176 .
Detail Pane	Shows the List view of the selected requirement, or the name and description of the selected report.

Understanding the Traceability Tree

Note the following points about the traceability tree:


- If you hover over a class that is not the top-level class, a tool tip displays the name of the relationship between that class and its parent class.
- Class labels show the relationship in parentheses if there is more than one label with the same class name but a different relationship.
- If you hover over a requirement, by default, a tool tip displays class and requirement ID of the requirement. You can add attributes that are displayed in the tool tip. For more information, see ["Customizing the Traceability Tree" on page 177](#).
- You can configure which attributes that you want to see in the traceability tree for each requirement. By default, the PUID and title of the requirement are displayed. For more information, see ["Customizing the Traceability Tree" on page 177](#).
- If you double-click a requirement, the **Edit Attributes** dialog box opens. However, if you double-click in an attribute in the requirements details in the right pane, you can edit the requirement content directly in place.
- A Dimensions CM indicator  is displayed next to each requirement in a collection that is associated with a Dimensions CM project. If a parent requirement is collapsed, and it has child requirements that are related to Dimensions CM, this indicator is shown on the parent requirement, even if the parent requirement itself is not related to Dimensions CM. When you expand the parent requirement, the indicator is shown on the child requirement, but is removed from the parent requirement.
- A suspect link indicator  is displayed next to each requirement that has suspect links. This indicator is informational only; clicking it does not remove the suspect status from the links.
- You can use the drag-and-drop operation to change parents within the tree. You can only change to a parent that has the same class and same path as the original parent. Be sure to drop the requirement on the new parent, not on a child requirement of the new parent.
- You can press the CTRL key and use the drag-and-drop operation to copy a requirement to another parent.
- To reload the tree, click the refresh icon at the top right of the tree.
- If the report was created in release 10.1.2.0 or earlier, a warning is displayed at the top of the tree informing you that changes you made in the **Traceability Properties** dialog box do not take effect until you save the report again.

Customizing the Traceability Tree

By default, the only attributes that are displayed in the traceability tree are the requirement PUID and title. You can configure the attributes that are displayed in the traceability tree for each class and for each project. For example, it might be useful to see the associated TeamTrack issue number, owner, and status. You can also configure tooltips to display attributes such as the requirement title instead of using space in the traceability tree to display this information.

To customize the traceability tree:

- 1 Click the **Report Properties** button. The **Properties for traceability reports** dialog box opens.



NOTE If the report was created in release 10.1.2.0 or earlier, a warning is displayed at the top of the dialog box that tells you that you need to save the report again before changes take effect.

- 2 Initially, the **Choose a class** list is the only field that is displayed. Select a class in the **Choose a class** list.
- 3 **Attributes to Display in the Tree:** To specify which attributes to display in the report, see chapter "[Attributes to Display List](#)" on page 25.
- 4 **Attributes to Display in the Tooltip:** To specify which attributes to show in the tooltip, see chapter "[Attributes to Display List](#)" on page 25.
- 5 In the **Separator** box, type the character you want to separate the attributes in the traceability tree and in the tooltips. The default character is a colon (:).

Creating a Graphical Report

Graphical Reports can use two report types:

- [Distribution Reports](#)

- **Trend Reports**

A Distribution Report presents the data at that moment the report was run.

A Trend Report presents the data over a time period.

Distribution Reports

Complete these steps to create a distribution report:

- 1 Select **Graphical Report** from the **New** menu. The *Graphical Report* dialog opens.
- 2 **Class:** Select the desired class from the list.



NOTE If a requirement of a class was selected when you invoked the dialog, then a class is already selected.

- 3 In the **required to save** group, select **Distribution Report** from the **Type** box.
- 4 If you want to save the report:
 - a Enter a name in the **Name** box. The **Run** button changes to **Save As and Run**.
 - b Type a description of the report in the **Description** box. The maximum number of characters is 1024.
- 5 In the **Category** list, select the category in which the report will be saved.
- 6 **Constraints:** As needed, specify criteria to locate the desired requirements. See ["Attribute Constraints Tab" on page 28](#) and ["Relationship Constraints Tab" on page 31](#).
- 7 **Display Options:** Select a style in the **Report Style** list and attributes in the **Row** and **Column** boxes in the *Chart Content* area. For Pie reports, only the **Row** box is available.



NOTE Note that the **Row** and **Column** boxes do not include these attributes:

- Multi Line attributes
- HTML enabled attributes
- Date attributes

- 8 Do any of the following:
 - **Public Report:** Select this box to make the report public, otherwise the report is private.
 - **Visible for:** This option is only available if **Public Report** is selected. If selected, you can choose which groups can access the report. If unselected, only the user who created the report can access it.
 - **Editable for:** This option is only available if **Public Report** is selected. By default, this box has all groups selected which have the **Create Public** right. To allow members of groups without this right to edit this report, select the desired groups. If selected, you can choose which groups can edit the report. If unselected, only the user who created the report can modify it.

- **Preview:** Click this button to run the report without saving the report or closing the dialog.
- **Run:** Click this button to run the report and close the dialog without saving the report.
- **Save As and Run:** Click this button to run and save the report. The dialog will close.



TIP You can show the drill down of the data used in the report. If your report is a bar report, clicking on a bar in the report opens a list with the requirements which provided the data for that bar. This functionality is also available in all other graphical reports.

Trend Reports

Complete these steps to create a trend report:

- 1 Select **Graphical Report** from the **New** menu. The *Graphical Report* dialog opens.
- 2 **Class:** Select the desired class from the list.



NOTE If a requirement of a class was selected when you invoked the dialog, then a class is already selected.

- 3 In the **required to save** group, select **Trend Report** from the **Type** box.
- 4 If you want to save the report:
 - a Enter a name in the **Name** box. The **Run** button changes to **Save As and Run**.
 - b Type a description of the report in the **Description** box. The maximum number of characters is 1024.
- 5 In the **Category** list, select the category in which the report will be saved.
- 6 **Constraints:** As needed, specify criteria to locate the desired requirements. See ["Attribute Constraints Tab" on page 28](#) and ["Relationship Constraints Tab" on page 31](#).
- 7 **Display Options:** Select a style in the **Report Style** list.
- 8 Select attributes in the **1st Field** and **2nd Field** boxes in the *Chart Content* area.



NOTE Note that the **1st Field** and **2nd Field** boxes do not include these attributes:

- Multi Line attributes
- HTML enabled attributes
- Date attributes
- Attributes which are surrounded with <> (e.g. <Collections>)

- 9 Select the start date for your report from the **Start Date** box. The list contains a number of entries which define the start date in relation to the current date. This

means that if you start a report on a different day, it will provide different data. To define a fixed start date, follow these steps:

- a Select **Since** from the **Start Date** box. This shows a date box next to the **Start Date** box.
 - b Click the calendar symbol in the date box.
 - c Select the desired date.
- 10** Select the end date for your report from the **End Date** box. You can select **Today** or **Until**. To define a fixed end date, follow these steps:
- a Select **Until** from the **End Date** box. This shows a date box next to the **End Date** box.
 - b Click the calendar symbol in the date box.
 - c Select the desired date. Note that the date must not be in the future.
- 11** Do any of the following:
- **Public Report:** Select this box to make the report public, otherwise the report is private.
 - **Visible for:** This option is only available if **Public Report** is selected. If selected, you can choose which groups can access the report. If unselected, only the user who created the report can access it.
 - **Editable for:** This option is only available if **Public Report** is selected. By default, this box has all groups selected which have the **Create Public** right. To allow members of groups without this right to edit this report, select the desired groups. If selected, you can choose which groups can edit the report. If unselected, only the user who created the report can modify it.
 - **Preview:** Click this button to run the report without saving the report or closing the dialog.
 - **Run:** Click this button to run the report and close the dialog without saving the report.
 - **Save As and Run:** Click this button to run and save the report. The dialog will close.



NOTE To allow the Trend report to perform its calculations, it is essential that you **always use Replace** when editing a requirement. For further information about Replace and Update, see chapter "[Explaining Update and Delete Functions](#)" on page 80.



TIP You can show the drill down of the data used in the report. If your report is a bar report, clicking on a bar in the report opens a list with the requirements which provided the data for that bar. This functionality is also available in all other graphical reports.

Moving and Copying Reports to a Different Category

You can move, or save a copy of, a report to another category.

To move/copy a report to another category:

- 1 Double-click the desired report in the Reports tab of the Home View. The report opens in a work page.
- 2 Click **Edit** in the Reports group of the Actions pane. An edit dialog opens.
- 3 **Category:** Select the desired category.
- 4 Do one of the following:
 - To save a *copy* of the report to the selected category, modify the **Name** of the report and click the **Save As and Run** button.
 - To *move* the existing report to the selected category, click the **Save and Run** button.

Renaming Reports

To rename a report follow these steps:

- 1 Open the **Reports tab** on the Home View.
- 2 Select the report
- 3 Click on **Rename** in the **Actions** pane
- 4 Enter the new name in the **Name** text box
- 5 Click on **Save**

**NOTE**

- For renaming relationship and traceability reports you need to have the **Rename permission for scripts** or you must be the owner of the report.
- For renaming class reports, you need to have the **Rename permission for filters** or you must be the owner of the report.

Deleting Reports

To delete a report:


- 1 Select the desired report in the **Reports tab** of the Home View.
- 2 Click **Delete** in the Reports group of the Actions pane. A confirmation dialog opens.
- 3 Click the **OK** button.

Copying the URL of a Report to the Clipboard

You can copy the URL of a report and paste it into a file for future use and reference. When that URL is later invoked, it will open RM Browser to that report.

Copying the URL of a Report to the Clipboard

To copy the URL of a report:

- 1 Open the Home View by clicking .
- 2 Select the **Reports** tab.
- 3 Select a report.
- 4 Click **Create direct URL** in the **Reports** section of the Actions pane. This opens a dialog with the URL.
- 5 Select the URL and press **Ctrl + C**, or right-click on the highlighted URL and select **Copy** from the shortcut menu to copy the URL to the Clipboard.
- 6 Click **Cancel** to close the dialog.
- 7 Press **Ctrl + V**, or the relevant application-specific menu command, to paste the URL into the file or application where you wish to use it.

Modifying the URL of a Report

After pasting the URL into a file or application, you can also add parameters to it, which allows additional features. If you do not supply run-time parameters in the URL, you can specify them when running the report.

Function	Description	Example URL
Hide Title Bar	By default, the report shows a title bar with information about database, project and path to the report. To hide the title, add &hideTitleBar=true to the URL.	<code>http://myserver:8080/rtmBrowser/cgi-bin/rtmBrowser.exe?goto=report&db=ORCL&proj=RMDEMO&reportID=1141&hideTitleBar=true</code>
Show Trace Report in Outline View	To view a trace report in Outline View, add &outlineView=1 to the URL.	<code>http://myserver:8080/rtmBrowser/cgi-bin/rtmBrowser.exe?goto=report&db=ORCL&proj=RMDEMO&reportID=1141&outlineView=1</code>

Function	Description	Example URL
Using Run-time Parameters	<p>You can filter report results by using run-time parameters. These parameters can be used on any report. To add a run-time parameter, add &<Parameter Name>=<value> to the URL.</p> <p>When providing run-time parameters, the value must be URL encoded (e.g. Café translates to Caf%C3%A9).</p>	<pre>http:// myserver:8080/ rtmBrowser/cgi-bin/ rtmBrowser.exe?goto =report&db=ORCL&pro j=RMDEMO&reportID=3 522&RTP__VERIFICATI ON_LEVEL_1=System</pre>
Using Multiple Values for a Run-time Parameter	<p>You can use several values for a run-time parameter by combining the values with a symbol, e.g. &TRP__VERIFICATION_LEVEL_1=System Module.</p>	<pre>http:// myserver:8080/ rtmBrowser/cgi-bin/ rtmBrowser.exe?goto =report&db=ORCL&pro j=RMDEMO&reportID=3 522&RTP__VERIFICATI ON_LEVEL_1=System M odule</pre>

Retrieving Run-Time Parameter Names

To get the names of the run-time parameters used in a report:

- 1 Paste the URL of the report into a text editor, e.g. Notepad. This URL will be referenced as **Report URL**.
Example URL: `http://myserver:8080/rtmBrowser/cgi-bin/rtmBrowser.exe?goto=report&db=ORCL&proj=RMDEMO&reportID=3522`
- 2 Copy the following URL to into a text editor: `http://host:port/rtmBrowser/RestServices/Report?id=<REPORT_ID>&db=<DATABASE>&proj=<PROJECT>`
This URL will be referenced as **Rest URL**.
- 3 Adjust protocol (http or https), host and port of the Rest URL to match those of the Report URL.
- 4 Select the value of the **db** parameter of the **Report URL** and press **Ctrl + C**, or right-click on the highlighted value and select **Copy** from the shortcut menu to copy it to the Clipboard. In the example URL this value is *ORCL*.
- 5 Select **<DATABASE>** in the **Rest URL** and press **Ctrl + V**, or the relevant application-specific menu command, to replace it with the value you copied from the Report URL.
- 6 Select the value of the **proj** parameter of the **Report URL** and press **Ctrl + C**, or right-click on the highlighted value and select **Copy** from the shortcut menu to copy it to the Clipboard. In the example URL this value is *RMDEMO*.
- 7 Select **<PROJECT>** in the **Rest URL** and press **Ctrl + V**, or the relevant application-specific menu command, to replace it with the value you copied from the Report URL.
- 8 Select the value of the **reportID** parameter of the **Report URL** and press **Ctrl + C**, or right-click on the highlighted value and select **Copy** from the shortcut menu to copy it to the Clipboard. In the example URL this value is *3522*.
- 9 Select **<REPORT_ID>** in the **Rest URL** and press **Ctrl + V**, or the relevant application-specific menu command, to replace it with the value you copied from the

Report URL.

If you executed these steps with the example URL, the Rest URL would look like this:
`http://myserver:8080/rtmBrowser/RestServices/
Report?id=3522&db=ORCL&proj=RMDEMO`

- 10** Select the complete **Rest URL** and press **Ctrl + C**, or right-click on the highlighted URL and select **Copy** from the shortcut menu to copy it to the Clipboard.
- 11** Open your preferred web browser and paste the URL into the address bar by pressing **Ctrl + V**. Then press **Enter**.
- 12** If you receive a dialog which requests user name and password, enter your RM user name and the associated password and confirm the dialog. In Internet Explorer, you might have to execute the following steps:
 - a** Click Open in the **Do you want to open or save Report.json** bar.
 - b** In the next dialog select the **Select a program from a list of installed programs** option and click **OK**.
 - c** In the **Open with** dialog, select **Notepad** or another plain text editor.
 - d** Clear the checkbox **Always use the selected program to open this kind of file**.
 - e** Click **OK**.
- 13** Search for **RTP__** (note that there are 2 underscores).
- 14** Select the full parameter (e.g. *RTP__VERIFICATION_LEVEL_1*) and add it to your Report URL.
- 15** Add an equal sign and the URL encoded value (e.g. translates to Caf%C3%A9).
If you executed these steps with the example URL, the Report URL would like this:
`http://myserver:8080/rtmBrowser/cgi-bin/
rtmBrowser.exe?goto=report&db=ORCL&proj=RMDEMO&reportID=3522&RTP__VE
RIFICATION_LEVEL_1=System`
- 16** You can now use the Report URL in your file or application.

Chapter 7

Managing Containers and Collections

About Containers	186
Deleting a Container	186
Updating Container Properties	186
Moving Containers to a Different Category	187
Comparing Containers	188
Refreshing the Contents of a Container	188
Copying the URL of a Container to the Clipboard	188
About Collections	189
Opening a Collection to the Collection Work Page	190
Managing Requirements in a Collection	190
Creating a New Collection	191
Baselining a Collection	192

About Containers

A *container* is the generic term for the various types of sets of requirements in RM. A requirement may belong to one or any number of named containers, or may exist outside all containers. Containers are not restricted by class and may span the entire project. Multiple versions of a requirement may exist in the same container, but typically only one version is utilized in a given container.

Types of Containers

You can store requirements in the following types of containers:

- **Collection:** A dynamic set of requirements with rules that determine new version membership. By default, the newest version of a requirement becomes a member of the collection and the previous version is removed from the collection. In concept, this is similar to a floating version label.
- **Baseline:** A fixed set of version specific requirements that optionally include their relationship to each other. Baselines are created from a selection of containers or a query. Once created, a baseline cannot be changed. In concept, this is similar to a fixed version label.
- **Document:** A set of requirements plus document structure and formatting. See [Chapter 5, "Working with Documents" on page 127](#).
- **Snapshot:** A snapshot is a read-only copy of a document. It preserves the current state of the document for future reference. While creating a snapshot, you can also create a baseline of the requirement versions currently in the document. See ["Creating a Snapshot of a Document" on page 142](#).

Deleting a Container

To delete a collection:

- 1 Select **Manage Containers** from the Containers menu. The Manage Containers dialog opens.
- 2 Select the collection you want to delete, and then click **Delete Container**.
- 3 When prompted to confirm the deletion, click **OK**.



TIP To quickly locate a container in the list, type its name or part of it into the **Find Container** box.

Updating Container Properties

You can rename and change the description for a collection, and modify the collection rules that define how and whether new child objects should be included in the collection.

To rename a collection:

- 1 Select **Manage Containers** from the Containers menu. The Manage Containers dialog opens.
- 2 Select the desired container.
- 3 Click **Container Properties**. Modify the Name and Description as needed.
- 4 If the container is a collection, you can modify the Collection Rules. See "[Creating a New Collection](#)" on page 191 for information on defining collection rules.




TIP To quickly locate a container in the list, type its name or part of it into the **Find Container** box.

Moving Containers to a Different Category

When you create a container, you can assign it to a category. The following procedure describes how to change the category assignment of an existing container.

Moving Containers by Drag & Drop

- 1 Open the Home View by clicking .
- 2 Select the desired tab: **Documents**, **Collections**, or **Baselines**.
- 3 If you want to move a snapshot, click **Show Snapshots**.
- 4 Drag the object and drop it at the desired category in the **Categories** tree.

Moving Containers by dialog

To move containers to a different category:

- 1 Select **Move containers to category** from the Containers menu. The Move Containers to category dialog opens.
- 2 **Look for container:** Select the type of container to be moved. A table appears that is populated with the selected container type.
- 3 Select the container(s) that you wish to move. CTRL-Click to select multiple containers from the table.
- 4 **Category:** Select the category to which you wish to move the containers.



TIP To quickly locate a category in the list, type the name of the category in the **Find** box of the expanded **Category** list.

- 5 Click the **Move** button.

Comparing Containers

To compare the contents of two containers:

- 1 Select **Compare containers** from the Containers menu. The Compare Containers dialog opens.
- 2 **Select Container:** Click the Browse (...) button to select the containers to compare.
- 3 **Description:** Select this checkbox to display each container's description in the results.
- 4 Click the **Compare** button. The Requirement Difference Summary dialog opens. The summary lists the Requirement ID, Title, Description (if the Description check box is selected in the Find Container dialog box), and the Class for the following results:
 - **Requirements only in container:** This is a list of the requirements that are in the first container, but not in the second container.
 - **Requirements only in container:** This is a list of the requirements that are in the second container, but not in the first container.
 - **Changed requirements:** This is a list of the changed requirements in both containers. This list includes items for which the Object Version ID is different, even if the Requirement ID is the same.
 - **Unchanged Requirements:** This is a list of the unchanged requirements in both containers.
- 5 To open a Details view of a requirement, double-click on it.
- 6 **Print:** Click this button to print the Requirement Difference Summary.

Refreshing the Contents of a Container

If a collection is based on a query or script, you may need to manually refresh the content of the collection. You can set a project-wide option to automatically refresh all collections that are based on queries or scripts, however if this is not set for performance reasons then you can refresh the content of the collection by selecting the collection and pressing the **Refresh Container** link on the Manage Containers dialog box.

Copying the URL of a Container to the Clipboard

You can copy the URL of a container and paste it into a file for future use and reference. When that URL is later invoked, it will open RM Browser to that container.

Copying the URL of a Container to the Clipboard

To copy the URL of a container:

- 1 Go to the **Home View**.

- 2 Select either the **Collections** tab or the **Baselines** tab.
- 3 Select the desired collection or baseline.
- 4 Click **Create direct URL** in the associated group of the Actions pane. A dialog opens with the URL selected.
- 5 Press **Ctrl + C**, or right-click the highlighted URL and select **Copy**. The URL is now on the Windows clipboard.
- 6 Click **OK** to close the dialog.
- 7 Use **Ctrl + V**, or the relevant application-specific menu command, to paste the URL into the file or application where you wish to use it.

Modifying the URL of a Collection or Baseline

After pasting the URL into a file or application, you can also add parameters to it, which allows additional features. If you do not supply run-time parameters in the URL, you can specify them when running the report.

Function	Description	Example URL
Editable Grid	By default, the requirements of collection or baseline are shown in a normal table. To use an editable grid instead, add &editableGrid=true to the URL.	<code>http://myserver:8080/rtmBrowser/cgi-bin/rtmBrowser.exe?goto=collection&db=ORCL&proj=RMDEMO&collectionId=5&editableGrid=true</code>
Hide Title Bar	By default, the collection or baseline shows a title bar with information about database, project and path to the report. To hide the title, add &hideTitleBar=true to the URL.	<code>http://myserver:8080/rtmBrowser/cgi-bin/rtmBrowser.exe?goto=collection&db=ORCL&proj=RMDEMO&collectionId=5&hideTitleBar=true</code>

About Collections


Collections are named groups of requirements from one or more classes. Collections provide a simple way to gather and organize requirements. Each requirement can be linked to many different collections, and each collection to many different requirements. In RM Browser, you can add requirements to a collection, remove requirements from a collection, and add, delete, rename, or baseline a collection.



CAUTION! When you display the content of a collection, you only see the requirements for which you have permissions in the category to which the requirements belong.

Opening a Collection to the Collection Work Page

To open a collection:

- 1 Open the Home View by clicking .
- 2 Double-click the desired collection in the Collections tab of the Selection pane. The Collection work page opens.

Managing Requirements in a Collection

You search for requirements from the **Organize by Collection** dialog box and then select the ones you want to add to or remove from a collection. You can specify search criteria on any or all of the three tabs on the **Organize by Collection** dialog box if you want to narrow search results or specify how the search results are displayed. You can run the search from any of the tabs.



TIP For a small and/or simple set of requirements, you can simply select them in a work page and click a button to add them to a collection. See ["Adding Requirements to an Existing Collection" on page 106](#).

To add/remove requirements to/from a collection:

- 1 If the collection is not already open, open it to a work page.
- 2 Select **Organize by Collection** from the Collections group of the Actions pane. The **Organize by Collection** dialog opens.
- 3 **Look for Class:** Select the class in which you want to search for requirements.
- 4 **Constraints:** As needed, specify criteria to locate the desired requirements. See ["Attribute Constraints Tab" on page 28](#) and ["Relationship Constraints Tab" on page 31](#).
- 5 **Display Options:** As needed, specify how to display the results. See ["Display Options Tab" on page 34](#).
- 6 **Find Now:** Click this button to run the search. The results are displayed in the lower pane of the dialog.
- 7 **New Search:** Click this button to clear the current search criteria and results.
- 8 Select the desired requirements in the search results. For multi-selection of requirements, see chapter ["Selecting Multiple Requirements" on page 23](#).
- 9 **Collection:** Select the collection to which you want to add or remove requirements.
- 10 Click one of the following buttons:
 - **Add:** To add the selected requirements to the collection.
 - **Remove:** To remove the selected requirements from the collection.

Creating a New Collection

To create a collection:

- 1 Select **Collection** from the New menu. The Manage Containers -> New dialog opens.
- 2 **Collection Name:** Enter the name of the new collection.



NOTE

- Do not use Oracle reserved words in collection names.
- A collection name can contain a maximum of 256 characters.

- 3 **Description:** Enter a description of the collection. The maximum length of the description is 512 characters.
- 4 **Category:** Select an owning category from the list.
- 5 **Collection Rules:** Define the collection link rules to determine what happens to object links when you edit objects included in the collection. The options include the following:
 - **Transfer to child:** When you edit the primary object and create a new child object, the links from the primary object are transferred to the new child object.
 - **Delete from parent:** When you edit the project object and create a new child object, the links from the primary (parent) object are deleted.
 - **Transfer to parent on deletion of child:** If you delete a child object, links are transferred to the parent.
 - **Objects can be added/removed:** Select to allow requirements to be added or removed to the collection.
 - **Use these rules as the default for new collections:** Select to automatically apply the above collection rules to all new collections in the future.
- 6 **Based on:** Select one of the following options to determine how the collection is initially populated:
 - **Empty Collection:** Select this if you do not want to base the new collection on an existing container.
 - **Selected Container(s):** Select this if you want to base the new collection on one of more existing containers. Then select one or more containers in the list. To select multiple containers, hold down the Control key while you select the containers. To select a range of containers, select the first container, press the Shift key, and then select the last container. When the new collection is created, all requirements of the selected container(s) are associated with it.
 - **Query:** Select this if you want to place the results of a query in the new collection. Then select the desired report.



TIP To limit the listed reports to those of a specific category, select a category from the **Query** category list. To quickly locate a category in the list, type the name of the category in the **Find** box of the expanded category list.

- 7 Click the **Add** button.

Baselining a Collection

In Dimensions RM, baselines are stable, unchangeable groups of requirements. In other words, baselines are collections that have been "frozen."

Note the following:

- Baselines and collections are separate entities. A baseline is a copy of a collection with special controls that keep the requirements in the baseline from being updated. A baseline is always referred to as a "baseline." A collection is referred to as a "collection."
- After a baseline is created, you can rename or delete it if you have permission to do so.



NOTE You cannot rename a baseline that was created from Dimensions CM using the ALM integration.

- You can create a baseline based on a collection, or a collection based on a baseline.
- The original collection from which the baseline was created remains unchanged and can be modified later.
- If you try to edit a requirement in a baseline, a message informs you that you cannot change the requirement, and that your changes will create a new version of the requirement.
- When you create a collection from an existing collection, the latest versions of the requirements are used.
- By default, links between objects in the baseline are also included in the baseline, and cannot be modified once the baseline is created. You may be able to modify links in a baseline depending on how your administrator has configured the project.
- Requirements with suspect links remain suspect even after they are baselined.
- You can clear suspect links from a requirement even if the requirement is baselined.
- Even if the administrator denied you the Delete Baseline and Rename Baseline permissions, you can delete and rename a baseline if you created it. In other words, in this situation, the permissions that are denied by the administrator are overridden.
- A baselined requirement has a lock icon in its banner in the **Edit Attributes** dialog, and the **Update** button is disabled. If you mouse over the icon a popup will appear that says: Baseline Locked.
- You can base a baseline on a query, that will generate dynamically when you run it.

To baseline a collection:

- 1 Select **Baseline** from the New menu. The Manage Containers dialog opens.
- 2 **Baseline Name:** Enter a name for the baseline.



NOTE

- Do not use Oracle reserved words in baseline names.
- A baseline name can contain a maximum of 256 characters.

- 3 **Description:** Enter a description of the baseline. The maximum length of the description is 512 characters.
- 4 **Category:** Select the category where you will store the baseline. You can add a baseline to any category to which you have access.



TIP To quickly locate a category in the list, type the name of the category in the **Find** box of the expanded **Category** list.

- 5 Select one of the following options:
 - **Based on Selection Container(s):** Select this if you want to baseline one or more collections or baselines. Then select one or more collections or baselines or a combination of collections and baselines from the list of containers. To select multiple containers, hold down the Control key while you select the containers. To select a range of containers, select the first container, press the Shift key, and then select the last container. When the new baseline is created, all requirements of the selected container(s) are associated with it.
 - **Based on Query:** Select this if you want to baseline the results of a query. Then select the desired report.



TIP To limit the listed reports to those of a specific category, select a category from the **Based on Query** category list. To quickly locate a category in the list, type the name of the category in the **Find** box of the expanded category list.

- 6 Click the **Create Baseline** button.

Chapter 8

Importing Requirements

Importing Requirements from Microsoft Word Documents	196
Importing Requirements from an XML File	200
Importing Requirements from a CSV File	202
Importing Test Case and Test Run Requirements	207
Importing Requirements from IBM Rational DOORS	208
Importing Requirements from IBM Rational DOORS	208
Importing Baselines from IBM Rational DOORS	211
Importing Previously Exported Requirements	211

Importing Requirements from Microsoft Word Documents

RM Browser can import content from a Microsoft Word document and use it to:

- Create new requirements
- Create new requirements and an RM document
- Update or Replace existing requirement versions

When importing a Word document, you can choose to import:

- The entire document (creating an RM document)
- Only the requirements (that are in the proper table format)
- Only the selected text (into attributes you specify at run time)

Should I Use RM Browser or RM Import?

Layout/Format: The import feature of RM Browser requires that the Word document be of the expected layout and format (as described in the following sections). Whereas RM Import requires that you create an import template that defines the layout and format that is to be expected. The latter is more flexible, but also more time consuming to setup.

Subrequirements: Only RM Import can import subrequirements or tables within tables.



NOTE

- Importing Microsoft Word documents through RM Browser is only possible if Microsoft Word is installed on the server. For further information on installing Microsoft Office on the server see chapter "Support for Publishing / Word Import" in *Dimensions RM Installation Guide*.
- RM Import requires Microsoft Word and Microsoft Excel to be installed on the client.

Formatting Requirements for Import

The requirements in your document must be in tables that use the correct layout and formatting in order to be recognized as requirements.

There are two main layout options when creating tables for requirements:

- Each row is a requirement:

Title	Text	Category	Delivery Phase
EPhoto will be an online photo album	This ePhoto system shall enable the user to browse an on-line photo album.	RMDEMO/Functional/Design	Build1 Build4
Displaying stored photo info	The ePhoto system shall allow users to display any of the information stored with the photo.	RMDEMO/Availability/Cost	TBD Build3

- Each table is a requirement:

TITLE	Runs on "standard" home PC		
Priority	Paragraph Title	Document ID	
1	Feature 3	Marketing Rqmts	
Category	RMDEMO/Power	Delivery Phase	Build1 TBD
Text			
The ePhoto system shall be accessible to the user from a regular home PC environment running standard Windows software. It is envisaged that this is a software-only application from the user's perspective.			

And there are two ways to organize the requirements by class:

- Specify the class for the entire table in the first row:

Class Name	Marketing_Requirements		
Rqmt ID	Title	Text	
MRKT_000001	EPhoto will be an online photo album	This ePhoto system shall enable the user to browse an on-line photo album.	
MRKT_000023	Displaying stored photo info	The ePhoto system shall allow users to display any of the information stored with the photo.	

- Specify the class of each requirement:

Class Name	Rqmt ID	Title	Text
Marketing_Requirements	MRKT_000001	EPhoto will be an online photo album	This ePhoto system shall enable the user to browse an on-line photo album.
Marketing_Requirements	PROD_000023	Load time less than 5 seconds	The load time for an individual photo load shall be less than 5 seconds.



NOTE The following rules apply when formatting requirement tables:

- Pay attention to **bold/regular** formatting:
 - **Attribute names** (*not* values) **must use bold** formatting.
 - **All values** (requirement content) **must not use bold** formatting. Even a single bold formatted blank space in the midst of properly formatted text will cause the text to be treated as an attribute name rather than as an attribute value.
 - When adding the class name above the attribute names (as in above example), both, **Class Identifier** and **attribute name** ("Class Name" in the above example) **must not use bold** formatting.
- General text formatting (color, underline, italic, etc.) is imported for text attributes and ignored for others. (As noted above, bold must not be used in attribute values.)
- **Class Name** is the attribute name for class used in the above examples; however, you can specify a different attribute name in the **Class Identifier** field when importing the document.
- **Category** must match the supported formats (see chapter "[Category Import Formats](#)" on page 200).
- The document may contain any number of tables.
- Tables may contain any number of rows (requirements) and any number of columns (attributes).
- To specify multiple values for a list attribute, separate the values with the pipe (|) character. For example: Build1|Build4
- To Update/Replace an existing RM requirement, include its **Rqmt ID** attribute (PUID).
- The Group attribute type is not supported for import.
- During import, you will be prompted for any mandatory attribute values that are not included in the tables.
- Images can be imported into the body of an RM document, but not into requirements.

Formatting an Entire Word Document for Import

If you choose to import an entire Word document:

- Requirement data will be imported from properly formatted tables (as described in "[Formatting Requirements for Import](#)" on page 196).

- Chapters and sub chapters will be created based upon the heading hierarchy of the Word document.

Word Document	RM Document
Heading 1	Chapter
Heading 2	Sub-chapter
Heading 3	Sub-sub-chapter
etc.	

- Images will be imported into body content (not into requirements).
- General text formatting will be imported.

Importing a Word File

For clarity, the modes of import (**Table[s] only** and **Entire Document**) are described separately in the following sections. However, these modes begin the same way, that portion is described only once, below.

To initiate the import of a Word document:

- In RM Browser, select **Word document** from the **Import** menu. The MS Word Import dialog opens.
- File Name:** Click the **Browse** button to navigate to and select the Word file, and then click the **Open** button.
- Choose whether to **Create**, **Update**, or **Replace** content from the Word document.
 - Create** will create new requirements in Dimensions RM.
 - Update** will update existing versions of requirements with new content from the Word document, *without* creating new versions. Only existing requirements that have new values in the Word document will be updated.
 - Replace** will create new versions of existing requirements using the new content from the Word document. Only existing requirements that have new values in the Word document will be replaced.
- Proceed to the relevant import mode section below:
 - ["Table\[s\] only Import Mode" on page 199](#)
 - ["Entire Document Import Mode" on page 200](#)

Table[s] only Import Mode

Continued from ["Importing a Word File" on page 199](#).

- Select **Table[s] only** from the drop-down list.
- Class Identifier:** Specify the attribute name you used to identify the class. For example, `Class Name`.
- Click the **Import** button. A second MS Word Import dialog opens. This one includes a information about the requirements that were created and a summary of the import results. Click the **Close** button to dismiss the results.

- 4 Click the **Close** button on the remaining MS Word Import dialog.
- 5 Click the **Close** button on the MS Word Import - Dimension RM dialog.

Entire Document Import Mode

Continued from ["Importing a Word File" on page 199](#).

- 1 Select **Entire Document** from the drop-down list.
- 2 **Class Identifier:** Specify the attribute name you used to identify the class. For example, `Class Name`.
- 3 **Document Name:** Specify a name for the RM document that is to be created or revised.
- 4 Click the **Import** button. A second MS Word Import dialog opens. This one includes a information about the requirements that were created and a summary of the import results. Click the **Close** button to dismiss the results.
- 5 Click the **Close** button on the remaining MS Word Import dialog.

Category Import Formats

For Word import, categories can be specified in these formats:

- Full path with forward slash, e.g. `RMDEMO/Data`
- Full path with backslash, e.g. `RMDEMO\Data`
- Unique category name, e.g. `Data`
Note that there must be no other category or sub-category "Data".

Date Import Formats

Word import requires that the date specified in a Word document matches the format for the attribute of the requirement class you wish to import.

Importing Requirements from an XML File

You can easily add, update, or replace large batches of requirements. Save your query results as an XML file, make changes to the requirements with an editor such as Microsoft Word or Notepad, and then import your changes using the XML import feature.


For example:

A requirements manager wants to change the "priority" attribute of 100 requirements from "Must" to "Hope." She opens RM Browser and runs the desired script. She saves the query results as an XML file. In the XML file, she changes the "priority" attribute and saves the updated XML file.

The requirements manager now imports the XML file by completing the **Import XML** dialog box. After the import process completes, an import results page opens that displays the class name, PUID, status, and error details for each requirement.

To import an XML file:

- 1 Click **XML file** from the **Import** menu. The **Import XML** dialog opens.



- 2 In the **Import File** field, type the path and file name of the XML file you want to import or click **Browse** to navigate to the file.
- 3 In the **Import Data Into** list, select the class into which you are importing the file.
- 4 In the **Import Mode** list, select one of the following options:

Mode	Description
Create	Creates a new requirement if the object node in the XML file does not exist.
Update	Updates the attributes that have changed for each object node in the XML file.
Replace	Creates a new current revision for each object node in the XML file with the changes to the attributes specified in the XML file.

- 5 If you want to create a new requirement when a requirement in the XML file has an object ID that does not match the object ID of a requirement in the database, select the **Create new requirement if requirement is not found** check box. This option is only available for the **Update** and **Replace** modes.

- 6 Under **Import Options**, select one or more options as described in the following table:

Option	Description
Use default value if no value is specified	If no value is specified for a mandatory attribute, its default value is used. If the attribute has no default value, an error message is displayed in the import results output page.
Truncate if value is too long	If the value is longer than the maximum value for the attribute, the value is truncated before the requirement is saved.
Don't propagate suspect links	Links are not marked as suspect when the requirement is updated or replaced. NOTE: This option is not available for the Create mode.
Break lock if requirement is already locked	User locks are removed before attempting to update or replace the requirement. Otherwise, a message is displayed in the import results output page. NOTE 1: This option does not remove CM locks. NOTE 2: This option is not available for the Create mode.

Category Import Formats

For XML import, categories can be specified in these formats:

- Full path with forward slash, e.g. RMDemo/Data
- Full path with backslash, e.g. RMDemo\Data
- Unique category name, e.g. Data
Note that there must be no other category or sub-category "Data".

Date Import Formats

XML import requires that the date specified in a XML file matches the format for the attribute of the requirement class you wish to import.

Importing Requirements from a CSV File

You can import requirements text from CSV files. When you import from a CSV file, you can map fields (rows) in the CSV file to specific requirements and attributes in Dimensions RM. You can create new requirements, update existing requirements with new data, and delete or undelete existing requirements.



IMPORTANT! DO NOT modify the CSV file in Microsoft Excel or any other non-text editor! Doing so may alter the data in the file and cause CSV import to fail.

To import requirements and requirement data from a CSV file:

- 1 Display the **My Work** view.
- 2 Select **CSV file** from the Import menu. The CSV Import dialog opens.



CAUTION! When importing *Test Case* or *Test Run* requirements (as defined for "[Test Case Management](#)" on page 213), you **must** have an ID column in your CSV data which matches the attribute name for that class. If your CSV file does not have an ID column, all requirements will be merged into one requirement. For further information about importing *Test Case* or *Test Run* requirements, see chapter "[Importing Test Case and Test Run Requirements](#)" on page 207.

- 3 In the **File Name** field, enter or browse to select the path to the CSV file you want to import.
- 4 From the **Import Mode** list, choose one of the following import options:
 - **Create:** Create new requirements from the rows in the CSV file.
 - **Update:** Update attributes in existing requirements with new data from the CSV file. The attributes are updated in requirements that match the specified criteria.
 - **Replace:** Replace attributes in existing requirements with new data from the CSV file, creating a new current version of the requirement. The attributes are replaced in requirements that match the specified criteria.
 - **Delete:** Delete data in requirements that match the specified criteria.
 - **Undelete:** Restore deleted data in requirements that match the specified criteria.
 - **Remove:** Remove data in requirements that match the specified criteria.
 - **Link:** Create relationships between requirements that match the specified primary class criteria to requirements that match the specified secondary class criteria. In this way you can use the CSV import functionality just to create links in RM.



NOTE TEXT type attributes are not valid for Link mode so they will not be included in the attribute list when in Link mode.

- **Delete Link:** Deletes the selected link. Delete Link is available if the user has the *Link* right for classes and the *Delete* right for relationships.
- **Remove Link:** Permanently removes a link. Remove Link is available if the user has the *Link* right for classes and the *Remove* right for relationships.



CAUTION! You cannot restore a removed link.

- 5 From the **Field Separator** list choose **Comma** or **Semi-colon**, depending on what separator is used in the CSV file.
- 6 To limit the range of rows to import, select **From** from the **Rows to Be Imported** option and enter the range. Otherwise, leave **All** selected to imported data from all rows in the file. If the file has a header row, you can omit this by selecting the **File has header row** option.
- 7 From the **Log Level** list you can choose the level of detail in the summary report that displays after you start the import. Choose **Terse** or **Verbose**.

- 8 Under the **RM Mapping** heading, you must enter criteria to define how data from the CSV file will be imported to Dimensions RM. The mapping configuration differs significantly depending on the import mode that you selected. Carefully review the following to understand how to use the RM Mapping options.

Import Mode	Mapping Guidelines
Create	<ul style="list-style-type: none"> ■ You must map columns from the CSV file to requirements attributes in RM. Data from the columns you select will be imported to the attributes you map the columns to, in the new requirements. ■ First select the requirements class from the RM Class field. Then, select the column from the CSV Column List field and the corresponding attribute from the RM Attribute list. Click the right arrow button to add the mapped pair to the Mapped List field.
Update	<ul style="list-style-type: none"> ■ You must first define criteria to locate the requirements to update, under Mapping Should Be Used to Locate Objects. You do this by matching values from columns in the CSV file to values from attributes in the requirements in RM. Every requirement with matching attribute values will be updated. First, select the requirement class from the RM Class field. Then, choose the CSV column to match from the CSV Column List field and the corresponding attribute from the RM Attribute list. Click the right arrow button to add the matched pair to the Mapped List field. ■ You must then define the attributes to update under Mapping to Be Used to Populate Data. Data from the CSV columns you select here will be imported to the attributes you map the columns to, in the requirements that are located by the criteria you defined under Mapping Should Be Used to Locate Objects. Select the column from the CSV Column List field and the corresponding attribute from the RM Attribute List field, then click the right arrow button to add the mapped pair to the Mapped List field. ■ You can optionally choose to only include rows from the CSV file that uniquely match one object in Dimensions RM. Select the Ignore rows matching multiple objects option to do this. For example, if a Title value from the CSV column matches the value of the Title attribute from several requirements, then this CSV row and corresponding requirements will be ignored. ■ You can also optionally create new requirements if no requirements matching the criteria you specified are found, and populate the new requirements with the data mapping defined under Mapping to Be Used to Populate Data.
Replace	See the above information on Update.

Import Mode	Mapping Guidelines
Delete	<ul style="list-style-type: none"> ■ You must define criteria to identify the attributes from which data will be deleted. Do this by matching columns from the CSV file to attributes in the RM requirements. First choose the requirements class from the RM Class field. Then, select the CSV column from the CSV Column List field and the corresponding RM attribute from the RM Attribute List field. Click the right arrow to add the mapped pair to the Mapped List field. Any attributes with values that match the value of the corresponding CSV column will be deleted. ■ You can optionally choose to only include rows from the CSV file that uniquely match one object in Dimensions RM. Select the Ignore rows matching multiple objects option to do this. For example, if a Title value from the CSV column matches the value of the Title attribute from several requirements, then this CSV row and corresponding requirements will be ignored.
Undelete	<ul style="list-style-type: none"> ■ You must define criteria to identify the attributes from which data will be undeleted. Do this by matching columns from the CSV file to attributes in the RM requirements. First choose the requirements class from the RM Class field. Then, select the CSV column from the CSV Column List field and the corresponding RM attribute from the RM Attribute List field. Click the right arrow to add the mapped pair to the Mapped List field. Any attributes with values that match the value of the corresponding CSV column will be undeleted. ■ You can optionally choose to only include rows from the CSV file that uniquely match one object in Dimensions RM. Select the Ignore rows matching multiple objects option to do this. For example, if a Title value from the CSV column matches the value of the Title attribute from several requirements, then this CSV row and corresponding requirements will be ignored.
Remove	<ul style="list-style-type: none"> ■ You must define criteria to identify the attributes from which data will be removed. Do this by matching columns from the CSV file to attributes in the RM requirements. First choose the requirements class from the RM Class field. Then, select the CSV column from the CSV Column List field and the corresponding RM attribute from the RM Attribute List field. Click the right arrow to add the mapped pair to the Mapped List field. Any attributes with values that match the value of the corresponding CSV column will be removed. ■ You can optionally choose to only include rows from the CSV file that uniquely match one object in Dimensions RM. Select the Ignore rows matching multiple objects option to do this. For example, if a Title value from the CSV column matches the value of the Title attribute from several requirements, then this CSV row and corresponding requirements will be ignored.

Import Mode	Mapping Guidelines
Link	<ul style="list-style-type: none"> ■ You must define criteria to locate the requirements to link. You must locate two requirements, a primary class and secondary class requirement. The resulting relationship is created between the primary and secondary requirement. ■ First choose the type of relationship from the RM Relation field. ■ To define the criteria for the first requirement, match columns from the CSV Column List field under Primary Class to attributes in the RM Attribute List field. Select the values and click the right arrow button to add the mapped pair to the Mapped List field. ■ To define the criteria for the second requirement, match columns from the CSV Column List field under Secondary Class to attributes in the RM Attribute List field. Select the values and click the right arrow button to add the mapped pair to the Mapped List field. ■ You can optionally choose to only include rows from the CSV file that uniquely match one object in Dimensions RM. Select the Ignore rows matching multiple objects option to do this. For example, if a Title value from the CSV column matches the value of the Title attribute from several requirements, then this CSV row and corresponding requirements will be ignored.
Unlink	<ul style="list-style-type: none"> ■ You must define criteria to locate the requirements to unlink. You must locate two requirements, a primary class and secondary class requirement. The relationship is removed between the primary and secondary requirement. ■ First choose the type of relationship from the RM Relation field. ■ To define the criteria for the first requirement, match columns from the CSV Column List field under Primary Class to attributes in the RM Attribute List field. Select the values and click the right arrow button to add the mapped pair to the Mapped List field. ■ To define the criteria for the second requirement, match columns from the CSV Column List field under Secondary Class to attributes in the RM Attribute List field. Select the values and click the right arrow button to add the mapped pair to the Mapped List field. ■ You can optionally choose to only include rows from the CSV file that uniquely match one object in Dimensions RM. Select the Ignore rows matching multiple objects option to do this. For example, if a Title value from the CSV column matches the value of the Title attribute from several requirements, then this CSV row and corresponding requirements will be ignored.

- 9 When you are done defining the mappings, click the **Import** button.

Category Import Formats

For CSV import, categories can be specified in these formats:

- Full path with forward slash, e.g. RMDemo/Data
- Full path with backslash, e.g. RMDemo\Data
- Unique category name, e.g. Data
Note that there must be no other category or sub-category "Data".
- Category ID, e.g. 21

Date Import Formats

CSV import requires that the date specified in a CSV file matches the format for the attribute of the requirement class you wish to import.

Importing Test Case and Test Run Requirements

Test Case or *Test Run* requirements (as defined for "[Test Case Management](#)" on page 213) are imported through CSV import (see chapter "[Importing Requirements from a CSV File](#)" on page 202). However, note the following:

- 1 Import expects that for Create, Update or Replace, there is always an ID (*PUID* or *OBJECT_ID*) present.
PUID: Must match the display name of the PUID attribute of the class.
OBJECT_ID: Must have the name *OBJECT_ID*.
- 2 For Create, the ID may be an existing ID or an imaginary ID.
- 3 The ID (*PUID* or *OBJECT_ID*) must be only on the line the requirement starts.
- 4 The first line of the CSV file must have field names.
- 5 The "Test Steps" attribute is split into columns with these names:
 - Test Steps - Description
 - Test Steps - Expected Result
 - Test Steps - Actual Result



CAUTION! Only specify this column for *Test Run* requirements.

- 6 The step number (e.g. "Step 3") is generated from the position within the CSV file.

Example

```

Test ID,Test Name,Test Steps - Description,Test Steps - Expected Result
TC_0001,Login RM,Click Login,Opens the Home View
,,Click Requirements,Opens Requirements View
TC_0002,Open Test Requirement,Enter 'Test' and click 'Search',Shows 10 requirements
,,Double-click requirement from search result,Opens 'Edit Attributes' dialog for the requirement

```

The above example represents 2 *Test Case* requirements, TC_0001 and TC_0002. Note that the "Test Steps" attribute has been split and Step 2 (Description and Expected Result) is on a separate line without any other field values.

Importing Requirements from a ReqIF File

A ReqIF file allows exchanging requirements between applications of different vendors. The following chapters describe how to import requirements and documents from a ReqIF file to Dimensions RM.

Importing Requirements from IBM Rational DOORS

In order to import requirements from DOORS, the data from DOORS need to be exported into a file in ReqIF format. Then, the ReqIF file is imported by RM Browser.

Prerequisites

- 1 Export your module or modules from DOORS into a single ReqIF file. For more information about the DOORS ReqIF export see the DOORS manual.
- 2 If your DOORS module contains pictures or other attachments, these are exported by DOORS into the same directory as the ReqIF file. Put these files together with the ReqIF file into a single ZIP file. This ZIP file can then be imported by RM Browser.



IMPORTANT! The import class in Dimensions RM needs to have attributes to store these attributes:

- **DOORS ID** (Type: Alphanumeric)
- **ReqIF ID** (Type: Alphanumeric)
- **Owner** (Type: Alphanumeric)
- **File attachment** (Type: File Attachment)

For all alphanumeric attributes, the length needs to be defined according to the longest value.

Starting the Import

To start the import:

- 1 Click **ReqIF** from the **Import** menu. The **Import ReqIF** wizard opens.
- 2 Select **Import DOORS Modules** and click on the **OK** button. This opens the first page of the *Import ReqIF* wizard.


- 3 Press the **Browse...** button and choose the ZIP file that contains your ReqIF file.
- 4 **RM Class:** Select the class to convert the requirements to. Every requirement object in your ReqIF file will be converted and imported into this RM Class type.
- 5 **DOORS ID:** Select the attribute which holds the DOORS ID of your requirements. This is necessary to transfer your module correctly to Dimensions RM and create the links between your requirements.
- 6 **ReqIF ID:** Select an attribute that will hold the ReqIF ID of your requirements. This is necessary to transfer your module correctly to Dimensions RM and create the links between your requirements.
- 7 **Attachment Field:** Select an attribute that will hold the attachments of your requirements such as images or other files.
- 8 **Owner Field:** Select an attribute that will hold the name of the owner module of your requirements. This is necessary to build your module correctly in Serena RM.
- 9 **Table As:** If your module contains DOORS tables, they can be imported either as HTML table or as single requirements.
 - **HTML:** Creates an HTML table and saves in a text attribute. The conversion to HTML will drop any attributes which are not visible. To keep these attributes choose **Requirement**.
 - **Requirement:** Saves every cell of your table as single requirement.
- 10 **Module Structure:** You can import a document (module) with or without chapters.
 - **Create Chapters:** The resulting RM document will contain chapters which contain either sub-chapters or requirements.
 - **Create Requirements Only:** The resulting RM document will contain only requirements. That means that the document structure is built with requirements instead of chapters.
- 11 **ReqIF Document(s) / Selected Document(s):** Here, you can define which documents (modules) you want to import.

Adding a document (module) for Import:

- a Select the documents (modules) you want to import in the list **ReqIF Document(s)**.



NOTE If a document has one or several baselines, you find these baselines in the list as separate document entries. Adding these entries to the list **Selected Document(s)** adds these baselines as snapshots of the parent document.

- b Click the  button. This adds the document to the list **Selected Document(s)**.

Renaming a Selected Document:

- a Select the documents (modules) you want to import in the list **Selected Document(s)**.
- b Click on the **Rename** link. This adds the document to the list **Selected Document(s)**. This opens the *Rename document* dialog.
- c Enter the new name into the textbox.

- d Click on the **OK** button.

Removing a document (module) from Import:

- a Select the documents (modules) you want to remove in the list **Selected Document(s)**
- b Click the ➔ button.

- 12 Click **Next**. This opens the *RM Attribute Mapping* page. Here, you can map ReqIF attributes to RM attributes.

- 13 **RM Attribute Mapping:** An attribute mapping defines which Dimensions RM attribute receives the value of a ReqIF attribute.

Mapping an Attribute:

- a Select a ReqIF attribute in the list **ReqIF Attribute(s)**.
- b Select an RM attribute in the list **RM Attribute(s)**.
- c Click the ➔ button. The mapping appears in the list **Mapped Attribute(s)**. Repeat these steps for further attributes you want to map.

Removing an Attribute Mapping:

- a Select the attribute you want to remove in the list **Mapped Attribute(s)**.
- b Click the ➔ button.



IMPORTANT! Requirements in Dimensions RM have mandatory attributes (e.g. *Title* and *Text*). Depending on the class, other attributes might be mandatory as well. If no mapping is defined for a mandatory attribute, it will receive the default value *not defined*.

- 14 **RM Attribute Value Mapping:** A value mapping defines how to convert a value of multi value attribute (e.g. list attribute).

Mapping a Value:

- a Select a ReqIF value in the list **ReqIF Value(s)**.
- b Select an RM value in the list **RM Value(s)**.
- c Click the ➔ button. The mapping appears in the list **Mapped Value(s)**. Repeat these steps for further values you want to map.

Removing a Value Mapping:

- a Select the value you want to remove in the list **Mapped Value(s)**.
- b Click the ➔ button



NOTE

- If a value for a mandatory attribute is not mapped, it will receive the default value *not defined*.
- If a value for an optional attribute is not mapped, it will remain empty.

- 15 Click **Import** to start the import.

Importing Baselines from IBM Rational DOORS

In order to import baselines, you need to have documents in Dimensions RM which originate from DOORS. The import will update a single Dimensions RM document only. If you do not have imported any DOORS documents (modules), first perform the import as described in chapter ["Importing Requirements from IBM Rational DOORS" on page 208](#).

Prerequisites

- 1 Export your module or modules from DOORS into a single ReqIF file. For more information about the DOORS ReqIF export see the DOORS manual.
- 2 If your DOORS module contains pictures or other attachments, these are exported by DOORS into the same directory as the ReqIF file. Put these files together with the ReqIF file into a single ZIP file. This ZIP file can then be imported by RM Browser.



IMPORTANT! The import class in Dimensions RM needs to have attributes to store these attributes:

- **DOORS ID** (Type: Alphanumeric)
- **ReqIF ID** (Type: Alphanumeric)
- **Owner** (Type: Alphanumeric)
- **File attachment** (Type: File Attachment)

For all alphanumeric attributes, the length needs to be defined according to the longest value.

Starting the Import

To start the import:

- 1 Click **ReqIF** from the **Import** menu. The **Import ReqIF** wizard opens.
- 2 Select **Import DOORS Baselines** and click on the **OK** button. This opens the first page of the *Import ReqIF* wizard.
- 3 **RM Document:** Select the RM document you want to update. Please note that completing the process will replace the content of the selected document.
- 4 Continue with [Step 3 on page 209](#).

Importing Previously Exported Requirements

For importing previously exported requirements, there are two options:

- 1 Importing a document created by **Export As** function of Quick Search

2 Importing a Word document created by **Publish** function of a RM document



IMPORTANT! You can import any of these file formats:

- Word documents
- XML files
- CSV files



CAUTION! When importing user attributes, the setting must be **Show User ID**. For further information see chapter "[Display Settings for User Attributes](#)" on page 52.

In general, importing requirements which have been previously exported works as described in the chapters above. However, when using Word documents, the requirements need to be imported from tables. For each format, the document needs to be prepared for import by executing the following steps:

- 1 For Word documents: Ensure that all mandatory fields are included and contain values. If not, add a column with the missing attribute name and fill each cell with values.
- 2 For Word documents:
 - a Ensure that the attribute names of the class match the column headers of the document
 - b Remove all fields which cannot be filled (e.g. creation date). Remove the ID column only when creating new requirements.
 - c Remove the **Row Count** row.
- 3 For XML files:
 - a Remove all fields which cannot be filled (e.g. creation date). Remove the ID column only when creating new requirements.
 - b Remove requirement attributes **id**, **version** and **puid** and the **attribute** element with the **id** value **PUID**.
- 4 For CSV files: Remove the **Row Count** row.
- 5 Save the document under a new name.
- 6 Start the import as described in:
 - "[Importing Requirements from Microsoft Word Documents](#)" on page 196
 - "[Importing Requirements from an XML File](#)" on page 200
 - "[Importing Requirements from a CSV File](#)" on page 202

Chapter 9

Test Case Management

Overview	214
Creating a Test Case	214
Creating a Test Run	214
Test Step Functions	215


Overview

Test Case Management allows creation of test cases and one or several test runs which are related to one test case. A test case defines the overall goal of a test and the procedure. A test run shows the executed tasks along with the results. The following chapters describe the default installation of Test Case Management. Please note that the class names and form layouts are not necessarily identical with your installation.

Creating a Test Case

A test case allows you to define the overall goal of a test (e.g. Dimensions RM Client installation) and which steps to perform (e.g. start Setup.exe).


To create a test case, follow these steps:

- 1 Select **Requirement** from the **New** menu. The **New** dialog opens.
- 2 **Class:** Select the class to which represents the test case, e.g. Test_Case. This list includes all of the classes for which you have "create" or "submit" permission.
- 3 **Test Name:** Enter a name for your test case.
- 4 Open the **Test Design** group.
- 5 Fill out or select from the boxes, expect **Test Steps**.
- 6 Click the  button to add a new step.
- 7 Double-click the cell in the **Description** column to edit the description.
- 8 Double-click the cell in the **Expected Result** column to edit the expected result.
- 9 Repeat steps 6 through 8 to add additional steps.
- 10 Click the **Save**, or **Save & Copy** or **Save & New** button.

Creating a Test Run

A test run is related to a testcase and allows the tester to provide the results of the executed tests.

To create a test run, follow these steps:

- 1 Open the test case of which you want to create a test run. For details on opening requirements, see chapter ["Exporting Requirements" on page 76](#).
- 2 In the **Edit Attributes** dialog, open the **Links** group.
- 3 Click the  button. This opens the **New Test_Run** dialog.








- 4 In the **New Test_Run** dialog, open the groups **Test Planning** and **Test Execution** and fill them out as required.
- 5 Click the **Save**, or **Save & Copy** or **Save & New** button.

Test Step Functions

The **Test Steps** table contains a list of all test steps. It contains these columns:

- **Unnamed column:** Contains a check box for remove and move (up/down) operations.
- **Step:** Contains the step name, e.g. Step 1.
- **Description:** Empty by default. Enter the instructions to the tester.
- **Expected Result:** Empty by default. Specify under which conditions the step is considered successful.
- **Result:** This column only exists in the *Test_Run* class. The tester enters the actual result of the test step.

The Test Steps table provides these functions:

	Creates a new step in the Test Steps table.
	Removes one or several selected test steps.
	Moves one selected step one position up.
	Moves one selected step one position down.
	Expands the Test Steps table to fill the window.
	Only available in expanded Test Steps mode. Transfers your changes to the New Test_Cases window.
	Only available in expanded Test Steps mode. Cancels your changes and returns to the New Test_Cases window.

Chapter 10

Agile

Before you start	218
Agile Basics	218
Display Options	222
Agile Tabs	222
Using Agile	227

Before you start

Before you can start using Agile with Dimensions RM, the following tasks must be executed:

- 1 Create classes and relationships (see chapter "Agile" in *Dimensions RM Administrator's Guide*).
- 2 Enable Agile for the project (see chapter "Agile" on page 52).
- 3 Configure Agile (see chapter "Configuring Agile" on page 243).

Agile Basics

About Agile

Dimensions RM provides agile capabilities like backlogs, story boards and burndowns. Agile as well as traditional artifacts can be visualized within these views and even linked together to support hybrid approaches at organization and project level. Agile can only be enabled by a user with Administrator rights. To enable Agile, see chapter "Agile" on page 52.


Agile Features

Agile in Dimensions RM allows:

- **Agile artifacts and agile views**
 - Agile artifacts based on RM classes
 - Backlogs and Story Boards
 - Product/Release/Sprint breakdown
 - Calculations and visualizations on priority, effort, and progress
 - Burndown reports on Release and Sprint level
- **Support of hybrid approaches**
 - Requirements and agile artifacts
 - Traceability throughout all artifact types
 - Non-functional requirements
 - Re-use of Backlog and Story Boards for traditional artifacts
- **Integration into development**
 - Story to be provided to (agile) development tool
 - Feedback on development progress back to RM boards


Comparing Requirements Management and Agile Approaches




The following images compare the different approaches or requirement management.



- **Pure RM:** The pure RM approach allows to define the different requirement types, but does not allow the development department to break down requirements into individual tasks.
- **Pure Agile:** The pure Agile approach allows the development to maintain different tasks and changes between different releases, but does not connect these tasks with the requirement.
- **RM/Agile Hybrid:** The RM/Agile hybrid approach combines the best of both worlds. The different requirement types are connected with the tasks and changes of the development department.

Accessing Agile

To access Agile, click the **Agile** icon  in the menu bar. This opens the Agile view. On the right hand side, underneath the menu bar, you find these controls:

- **Product** drop-down list 
- Edit button 
- Display Options menu 
- **New** menu


Then, select a product (to add a product, see chapter ["Adding Products" on page 227](#)). This opens the following tabs for the selected product:

- [Overview Tab](#)
- [Product Backlog Tab](#)
- [Product Storyboard Tab](#)
- [Sprint Planning Tab](#)
- [Sprint Storyboard Tab](#)

About Products


A "Product" is an item to which you can assign epics, features or stories. This represents a complete product, a module or a component.

About Releases


A "Release" is linked to one product. Each release contains the epics, features, stories and sprints, which are relevant for the version. As an example, release 1.1 contains only those features, which have changed since release 1.0. A feature of such a release would also just contain those stories, which have changed since release 1.0. A release is marked .

About Stories

A "Story" describes the function to be implemented. However, a story may include several tasks. If a story were "Install database", this would require several settings to be made during the installation process. These settings could be specified within the story's description. However, a story should not be something like "Install operation system and database". This should be split into two stories.


In lists, stories may show the badges described in chapter ["About Badges" on page 221](#). A story is marked .

About Sprints

A "Sprint" defines in which time frame the assigned stories should be completed. A sprint is marked .


About Features

A "Feature" groups several stories logically together and will be assigned to a release. The description describes what the assigned stories should accomplish. In lists, features may show the badges described in chapter ["About Badges" on page 221](#).

A feature is marked .



About Epics

An "Epic" groups several features and stories logically together and will be assigned to a release. In lists, epics may show the badges described in chapter ["About Badges" on page](#)

221. An epic is marked .






NOTE If you add the Epics class after products have been created, do the following for each product you want to use Epics with:

- 1 Select the product in the **Product** drop-down list .
- 2 Click the edit button .
- 3 Ensure that **Epic** is enabled in the **Shown mapped classes** area.
- 4 Click **Replace**.

About Badges

In lists, epics, features, and stories provide additional information by using these badges:

- User or group, e.g.  JOE
- Priority, e.g.  High
- **Stories:** Effort, e.g.  3/8 (format: remaining effort/estimated effort)

About Capacity

For a release or sprint, you can specify the **Capacity**. This numeric value specifies how long the release or sprint needs to be completed.







On the **Overview** tab, you see a progress bar for each release or sprint if the capacity has been specified.

On the **Product Backlog** tab, you see a progress bar next to the selected release. It shows how much of the capacity is used by all assigned features based on their estimated effort.


On the **Sprint Planning** tab, you see a progress bar next to the selected sprint. It shows how much of the capacity is used by all assigned stories based on their estimated effort.

Tool Tips

For getting a quick info about products, releases, features, sprints or stories, you can use the tool tip functionality in Agile. This tool tip shows all relevant information for the related class. It is available in lists or drop-down lists which show these icons:

-  Shows the tool tip for a product.
-  Shows the tool tip for a release.
-  Shows the tool tip for a sprint.
-  Shows the tool tip for an epic.
-  Shows the tool tip for a feature.
-  Shows the tool tip for story.

Display Options

Next to the Product drop-down list, you find the Display Options menu . It provides these settings:

Setting	Description
Show my stories only	Shows only the stories, which are assigned to the current user.
Show full descriptions	Shows the full description of all stories and features underneath the title.
Hide "assigned to" badge	Hides the badge of the user or group to which a story is assigned.
Hide "effort" badge	Hides the effort badge of a story.
Hide "priority" badge	Hides the priority badge of a story.
Assigned features/stories	Gray: Shows those features and stories which are assigned to a release, with a gray background. Hide: Hides those features and stories which are assigned to a release.
Story progress	Show: The progress is shown by changing the background of an item into a progress bar. Hide: No progress is shown.

Agile Tabs

Overview Tab

The Overview tab displays relevant items in hierarchical lists and allows easy filtering. By using the Overview, you can easily find out which sprints are related to which feature and product.

The Overview tab is divided into these sections:

- [Burndown Diagram](#)
- [Release List](#)
- [Sprint List](#)
- [Stories List](#)

Burndown Diagram

The Burndown diagram is shown if you select a release or sprint.

Release Burndown Diagram: Shows the remaining effort and estimated effort for the related sprints.

Sprint Burndown Diagram: Shows the remaining effort and estimated effort for the related stories.

Both diagrams allow you to easily recognize if the deadline can be met.

Based on the previous values, the burndown diagram forecasts the future development. For easy recognition, the forecasted values are shown in a different color.

You can choose between these different diagram types:

- Line chart
- Area chart
- Bar chart
- Column chart

Release List

The release list shows all releases for the selected product. If the capacity has been specified, a progress bar is shown for each release. Selecting a release loads the burndown diagram and the sprint list.

Sprint List

The sprint list shows all sprints for the selected release. If the capacity has been specified, a progress bar is shown for each sprint. Selecting a sprint loads the assigned stories and the Burndown diagram.

Stories List

The stories list shows all stories for the selected sprint or release. If no sprint is selected, click **Load Stories** to load the stories for the selected release.

Product Backlog Tab

On the **Product Backlog** tab, you can do the following:

- Define features, stories or other artefacts for one product
- Group stories
- Prioritize
- Define acceptance criteria
- Scope items to one or more product releases

The **Product Backlog** tab is divided into these sections:

- **Product Backlog:** Shows features and stories, which are not assigned to any release.
- **Release:** Shows epics, features and stories, which are assigned to the selected release.

Depending on the **Assigned features/stories** setting in the Display Options menu (see ["Display Options" on page 222](#)), you may also see assigned features or stories in the **Product Backlog** list.

Assigning and Un-Assigning Features or Epics


To assign a feature or epic to a release, drag it from the **Product Backlog** list to the **Release** list and drop it there. After assigning a feature or epic to a release, the related stories are assigned to the selected release and become available in the **Product Storyboard**.

Alternatively, you can assign a feature or epic to a release by executing these steps:

- 1 Double-click the feature or epic you want to assign. This opens the edit dialog for that feature or epic.
- 2 In the **Release** box, select the desired release.
- 3 Click **Replace**.

To un-assign a feature or epic, drag it from the **Release** list to the **Product Backlog list** and drop it there. This un-assigns the stories from the selected release.

Alternatively, you can un-assign a feature or epic from release by executing these steps:

- 1 Double-click the feature or epic you want to un-assign. This opens the edit dialog for that feature or epic.
- 2 Click  next to the **Release** box.
- 3 Click **Replace**.

Assigning Stories

To assign a story to a release, drag it from the **Product Backlog** list or from a feature in the **Product Backlog** list and drop it on the **Release** list or on a feature in the **Release** list.


Alternatively, you can assign a story to a release by executing these steps:


- 1 Double-click the story you want to assign. This opens the edit dialog for that story.
- 2 In the **Release** box, select the desired release.
- 3 If desired, select the feature in the **Feature** box.
- 4 Click **Replace**.

Un-Assigning Stories

To un-assign a story from a release, drag it from the **Release** list or from a feature in the **Release** list and drop it on the **Product Backlog** list or on a feature in the **Product Backlog** list.

Alternatively, you can un-assign a story from release by executing these steps:

- 1 Double-click the story you want to un-assign. This opens the edit dialog for that story.
- 2 Click  next to the **Release** box.

- 3 If desired, select a feature from the Feature box or click  next to the Feature box to un-assign the feature.
- 4 Click **Replace**.

Product Storyboard Tab

On the **Product Storyboard** tab, you can do the following:

- Elaborate Stories
- Move stories through analysis stages
- Estimate effort
- Review
- Approve for sprint readiness

The **Product Storyboard** tab is divided into these sections:

- **Elaborated:** Contains stories which have been assigned to a release, but have not been planned for sprint assignment or assigned to a sprint.
- **Pre-Planning:** An optional intermediate step which contains all stories you want to assign to a sprint (in the future).
- **Sprint-Ready:** Contains stories which can be assigned to a sprint.

To change the planning status of a story, you can drag it to the desired state and drop it there.

Alternatively, you can change the planning status by executing these steps:

- 1 Double-click the story for which you want to change the Planning Status. This opens the edit dialog for that story.
- 2 In the **Planning Status** box, select the desired state.
- 3 Click **Replace**.

Sprint Planning Tab


On the **Sprint Planning** tab, you can do the following:

- Scope stories into sprints
- Prioritize
- Assign stories

The **Sprint Planning** tab is divided into these section:

Product Backlog: Contains stories which have not been assigned to a sprint.

Sprint: Contains stories which have been assigned to the selected sprint.

By default, the Sprint Planning tab shows all sprints. To show the stories assigned to a sprint, click  next to the sprint name.

To show only one sprint, select a sprint from the **Sprint** box. If you want to show all sprints again, click **Show all**.

Sprint Capacity

If one sprint is selected in the **Sprint** box, the **Capacity** progress bar is located next to it. If all sprints are shown, the capacity progress bar is shown for each sprint individually.

For more information about the capacity progress bar see chapter ["About Capacity" on page 221](#).

Assigning Stories to Sprints


To assign a story to the selected sprint, drag it from the **Product Backlog** list to the **Sprint** list and drop it there. If you show all sprints, drop it onto the desired sprint in the **Sprint** list.

Alternatively, you can assign a story to a sprint by executing these steps:

- 1 Double-click the story you want to assign or un-assign. This opens the edit dialog for that story.
- 2 In the **Sprint** box, select the desired sprint.
- 3 Click **Replace**.

To **un-assign a story**, drag it from the **Sprint** list to the **Product Backlog list** and drop it there.

Alternatively, you can un-assign a story from sprint by executing these steps:

- 1 Double-click the story you want to un-assign. This opens the edit dialog for that story.
- 2 Click  next to the **Sprint** box.
- 3 Click **Replace**.

Sprint Storyboard Tab

On the **Sprint Storyboard** tab, you can do the following:

- Move stories through lifecycle stages
- Re-assign stories
- Can also be used for requirements analysis sprints

The **Sprint Storyboard** tab is divided into these sections:

- **Not Started:** Contains stories on which implementation has not yet started.
- **In Development:** Contains stories which are currently in development.

- **In Test:** Contains stories which have been developed and are now being tested.
- **In Review:** Contains stories which have been developed and are now under review.
- **Accepted:** Contains stories which have passed the review phase successfully.

To change the Sprint status of a story, you can drag it to the desired state and drop it there.

Alternatively, you can change the Sprint Status by executing these steps:

- 1 Double-click the story for which you want to change the Sprint Status. This opens the edit dialog for that story.
- 2 In the **Sprint Status** box, select the desired state.
- 3 Click **Replace**.

Using Agile

Using Products



Adding Products

To add a product, execute these steps:

- 1 In Agile's **New** menu, select **Product**. This opens the *New Products* dialog.
- 2 Complete the fields of the dialog as needed.
- 3 To specify the visible views, you can enable or disable and specify the tab headers on the following options:
 - **Overview**
 - **Product Backlog**
 - **Product Storyboard**
 - **Sprint Planning**
 - **Sprint Storyboard**By default, all above options are selected.
- 4 Click one of the following buttons:
 - **Save:** Saves the new product and closes the dialog.
 - **Save & New:** Saves the new product and opens a new empty *New Products* dialog to create a new product.



Editing Products

To edit a product, execute these steps:

- 1 In the **Product** drop-down , select the product you want to edit.
- 2 Click the Edit button  next to the Product drop-down. This opens the Products dialog.
- 3 Edit the product as desired.
- 4 Click **Replace**.

Deleting Products


To delete a product, execute these steps:

- 1 In the **Product** drop-down , select the product you want to delete.
- 2 Click the Edit button  next to the **Product** drop-down. This opens the Products dialog.
- 3 Click **Delete**.
- 4 Confirm the deletion dialog by clicking **OK**.

Using Releases

Adding Releases


To add a release, execute these steps:

- 1 In the **Product** drop-down , select the product for which you want to add a release.
- 2 In Agile's **New** menu, select **Release**. This opens the *New Releases* dialog.
- 3 Complete the fields of the dialog as needed.
- 4 In the **Capacity** box, specify the maximum duration (e.g. days) in which the release must be completed.
- 5 Click one of the following buttons:
 - **Save:** Saves the new release and closes the dialog.
 - **Save & New:** Saves the new release and opens a new empty *New Releases* dialog to create a new release.

Editing Releases

Releases are available on several tabs and can be edited on any of those tabs. For simplification, the following steps describe the process only for the **Overview** tab.

To edit a release, execute these steps:


- 1 In the **Product** drop-down , select the product for which you want to edit a release.
- 2 Select the **Overview** tab.
- 3 Double-click the release you want to edit. This opens the Releases dialog.
- 4 Edit the release as desired.

- 5 Click **Replace**.

Deleting Releases

Releases are available on several tabs and can be deleted on any of those tabs. For simplification, the following steps describe the process only for the **Overview** tab.


To delete a release, execute these steps:

- 1 In the **Product** drop-down , select the product for which you want to delete a release.
- 2 Select the **Overview** tab.
- 3 Double-click the release you want to delete. This opens the Releases dialog.
- 4 Click **Delete**.
- 5 Confirm the deletion dialog by clicking **OK**.

Using Epics



Adding Epics

To add an epic, execute these steps:

- 1 In the **Product** drop-down , select the product for which you want to add an epic.
- 2 In Agile's **New** menu, select **Epic**. This opens the *New Epics* dialog.
- 3 Complete the fields of the dialog as needed.
- 4 Click one of the following buttons:
 - **Save:** Saves the new feature and closes the dialog.
 - **Save & New:** Saves the new feature and opens a new empty *New Epics* dialog to create a new epic.



Editing Epics

To edit an epic, execute these steps:

- 1 In the **Product** drop-down , select the product for which you want to edit an epic.
- 2 Select the **Product Backlog** tab.
- 3 If the epic is assigned to a release, select the release in the **Release** drop-down .
- 4 Double-click the epic you want to edit. This opens the Epics dialog.
- 5 Edit the epic as desired.
- 6 Click **Replace**.

Deleting Epics


To delete an epic, execute these steps:

- 1 In the **Product** drop-down , select the product for which you want to edit an epic.
- 2 Select the **Product Backlog** tab.
- 3 If the epic is assigned to a release, select the release in the **Release** drop-down .
- 4 Double-click the epic you want to delete. This opens the Epics dialog.
- 5 Click **Delete**.
- 6 Confirm the deletion dialog by clicking **OK**.

Using Features


Adding Features

To add a feature, execute these steps:

- 1 In the **Product** drop-down , select the product for which you want to add a feature.
- 2 In Agile's **New** menu, select **Feature**. This opens the *New Features* dialog.
- 3 Complete the fields of the dialog as needed.
- 4 Click one of the following buttons:
 - **Save:** Saves the new feature and closes the dialog.
 - **Save & New:** Saves the new feature and opens a new empty *New Features* dialog to create a new feature.


Editing Features

To edit a feature, execute these steps:

- 1 In the **Product** drop-down , select the product for which you want to edit a feature.
- 2 Select the **Product Backlog** tab.
- 3 Double-click the feature you want to edit. This opens the Features dialog.
- 4 Edit the feature as desired.
- 5 Click **Replace**.

Deleting Features


To delete a feature, execute these steps:

- 1 In the **Product** drop-down , select the product for which you want to delete a feature.
- 2 Select the **Product Backlog** tab.
- 3 Double-click the feature you want to delete. This opens the Features dialog.
- 4 Click **Delete**.
- 5 Confirm the deletion dialog by clicking **OK**.

Using Stories

Adding Stories


To add a story, execute these steps:

- 1 In the **Product** drop-down , select the product for which you want to add a story.
- 2 In Agile's **New** menu, select **Story**. This opens the *New Stories* dialog.
- 3 Complete the fields of the dialog as needed.
- 4 Click one of the following buttons:
 - **Save:** Saves the new story and closes the dialog.
 - **Save & New:** Saves the new story and opens a new empty *New Stories* dialog to create a new story.

Editing Stories

Stories are available on several tabs and can be edited on any of those tabs. For simplification, the following steps describe the process only for the **Overview** tab.


To edit a story, execute these steps:

- 1 In the **Product** drop-down , select the product for which you want to edit a story.
- 2 Select the **Overview** tab.
- 3 Select a release and a sprint.
- 4 Double-click the story you want to edit. This opens the Stories dialog.
- 5 Edit the story as desired.
- 6 Click **Replace**.

Deleting Stories

Stories are available on several tabs and can be deleted on any of those tabs. For simplification, the following steps describe the process only for the **Overview** tab.


To delete a story, execute these steps:

- 1 In the **Product** drop-down , select the product for which you want to delete a story.
- 2 Select the **Overview** tab.
- 3 Select a release and a sprint.
- 4 Double-click the story you want to delete. This opens the Stories dialog.
- 5 Click **Delete**.
- 6 Confirm the deletion dialog by clicking **OK**.

Using Sprints

Adding Sprints


To add a sprint, execute these steps:

- 1 In the **Product** drop-down , select the product for which you want to add a sprint.
- 2 In Agile's **New** menu, select **Sprint**. This opens the *New Sprints* dialog.
- 3 Complete the fields of the dialog as needed.
- 4 In the **Capacity** box, specify the maximum duration (e.g. days) in which the sprint must be completed.
- 5 Click one of the following buttons:
 - **Save:** Saves the new sprint and closes the dialog.
 - **Save & New:** Saves the new sprint and opens a new empty *New Sprints* dialog to create a new sprint.

Editing Sprints

Sprints are available on the **Overview** tab, **Sprint Planning** tab, and **Sprint Storyboard** tab. You can edit sprints on any of those tabs. For simplification, the following steps describe the process only for the **Overview** tab.


To edit a sprint, execute these steps:

- 1 In the **Product** drop-down , select the product for which you want to edit a sprint.
- 2 Select the **Overview** tab.
- 3 Select a release.
- 4 Double-click the sprint you want to edit. This opens the Sprints dialog.
- 5 Edit the story as desired.
- 6 Click **Replace**.

Deleting Sprints

Sprints are available on several tabs and can be deleted on any of those tabs. For simplification, the following steps describe the process only for the **Overview** tab.

To delete a sprint, execute these steps:

- 1 In the **Product** drop-down , select the product for which you want to edit a sprint.
- 2 Select the **Overview** tab.
- 3 Select a release.
- 4 Double-click the sprint you want to delete. This opens the Sprints dialog.
- 5 Click **Delete**.
- 6 Confirm the deletion dialog by clicking **OK**.

Chapter 11

Administration

Managing Users	234
Managing Groups	237
Managing Categories	238
Moving Requirements Between Categories	241
Managing Document Locks	242
Managing Requirement Locks	243
Configuring Project Settings	243
Configuring Agile	243

Managing Users

The following sections describe how to add, edit or delete users in RM Browser. Only users who belong to the Administrators group can open the **User Management** dialog. The User Management dialog consists of these columns:

- User list
- User details

Creating a New User

To create a new user:

- 1 Select **User Management** from the **Administration** menu. This opens the **User Management** dialog.
- 2 Click **New**. This opens the **New user name** dialog.
- 3 Enter the user name for the new user into the provided box.
- 4 Click **OK**. This creates the user and closes the **New user name** dialog.
- 5 In the user details section, do the following:
 - a Specify a password in the **Password** box.
 - b Enter the same password in the **Confirm Password** box.
 - c If desired, fill out the other boxes.
 - d Select one or more of the following password options:
 - **User Must Change Password at Next Logon**
 - **User Cannot Change Password**
 - **Password Never Expires**
 - **Account Disabled**



NOTE If you do not select a password option, users must change their passwords every 60 days. Users get a warning that gives them the opportunity to change their password 14 days before their current password is due to expire. The warning is displayed every time users log in using any Dimensions RM tool.

- e If you are using LDAP or SSO for login, select the Login Source.
- 6 Click **Save**.

Copying an Existing User

To copy an existing user:

- 1 Select **User Management** from the **Administration** menu. This opens the **User Management** dialog.
- 2 Select the user you want to copy in the user list.

- 3 Click **Copy**. This opens the **New user name** dialog.
- 4 Enter the user name for the new user into the provided box.
- 5 Click **OK**. This creates the user with all data of the user you copied from and closes the **New user name** dialog.
- 6 In the user details section, do the following:
 - a Specify a password in the **Password** box.
 - b Enter the same password in the **Confirm Password** box.
 - c If desired, fill out the other boxes.
 - d Select one or more of the following password options:
 - **User Must Change Password at Next Logon**
 - **User Cannot Change Password**
 - **Password Never Expires**
 - **Account Disabled**



NOTE If you do not select a password option, users must change their passwords every 60 days. Users get a warning that gives them the opportunity to change their password 14 days before their current password is due to expire. The warning is displayed every time users log in using any Dimensions RM tool.



NOTE Copying a user copies permissions (e.g. the "Create Class" right), assigned groups, project assignments and the user info.

Editing a User

To edit a user:

- 1 Select **User Management** from the **Administration** menu. This opens the **User Management** dialog.
- 2 Select a user in the user list.
- 3 In the user details section, do any the following:
 - a To change the password, specify a password in the **Password** box and enter the same password in the **Confirm Password** box.
 - b Edit the content of the other boxes.
 - c Select one or more of the following password options:
 - **User Must Change Password at Next Logon**
 - **User Cannot Change Password**
 - **Password Never Expires**

- **Account Disabled**





NOTE If you do not select a password option, users must change their passwords every 60 days. Users get a warning that gives them the opportunity to change their password 14 days before their current password is due to expire. The warning is displayed every time users log in using any Dimensions RM tool.

- 4 Click **Save**.



Assigning a User to one or several Groups

To assign a user to one or several groups:

- 1 Select **User Management** from the **Administration** menu. This opens the **User Management** dialog.
- 2 Select a user in the user list.
- 3 Click . This opens the **Group Assignment** dialog.
- 4 Select one or several groups in the **Not a member of** list.
- 5 Click .
- 6 Click **Save**.

Un-Assigning a User from one or several Groups

To un-assign a user from one or several groups:

- 1 Select **User Management** from the **Administration** menu. This opens the **User Management** dialog.
- 2 Select a user in the user list.
- 3 Click . This opens the **Group Assignment** dialog.
- 4 Select one or several groups in the **Member of** list.
- 5 Click .
- 6 Click **Save**.

Deleting a User

To delete a user:


- 1 Select **User Management** from the **Administration** menu. This opens the **User Management** dialog.
- 2 Select the user you want to delete in the user list.
- 3 Click **Delete**. This opens the **Confirm user delete** dialog.
- 4 Click **OK** to delete the user.

Managing Groups

The following sections describe how to add a user to a group and how to remove a user from a group using RM Browser.


Assigning Users to a Group

To assign users to a group:

- 1 Select **User Management** from the **Administration** menu. This opens the **User Management** dialog.
- 2 In the left column, select **Group Assignment**.
- 3 Select the group you want to assign users to from the Group box.
- 4 In the **Not assigned** list, select the user or users you want to assign.
- 5 Select the category assignment method:
 - **Automatically assign user(s) to group categories:** Adds the user to all categories the group has access and **grants** access.
 - **Assign user(s) to categories selectively:** Adds the user to all categories the group has access and **denies** access.
- 6 Click  .
- 7 Click **Save**.
- 8 If you have selected **Assign user(s) to categories selectively**, select **Category Assignment** in the left column and follow the instructions in chapter ["Managing Access Rights"](#) on page 239.

Un-Assigning Users from a Group

To un-assign users from a group:

- 1 Select **User Management** from the **Administration** menu. This opens the **User Management** dialog.
- 2 In the left column, select **Group Assignment**.
- 3 Select the group you want to un-assign users from in the Group box.
- 4 In the **Assigned** list, select the user or users you want to un-assign.
- 5 Click  .
- 6 Click **Save**.

Managing Categories

The following sections describe ways you can manage categories in RM Browser. Only users who belong to the Administrators group can open the **Manage Categories** dialog.

Adding a Category

To add a category:

- 1 Select **Manage categories** from the **Administration** menu. This opens the **Manage Categories** dialog.
- 2 Click **New Category**.
- 3 In the **Category Name** field, type the name of the new category. You can enter a maximum of 64 characters.
- 4 In the **Description** field, type an optional category description. This description appears as a tooltip when you hover over the category in the category tree.
- 5 In the **Parent Category** tree, select the parent category for the new category.
- 6 Click the **Add** button.

Deleting a Category

To delete a category:

- 1 Select **Manage categories** from the Administration menu. The Manage Categories dialog opens.
- 2 Select the category you want to delete and click **Delete Category**.
- 3 When prompted to confirm the deletion, click **OK**.



NOTES You cannot delete the root category or any category that has subcategories. To delete a category with subcategories, delete the subcategories first. You cannot delete a subcategory if it contains objects, scripts, or filters.

Renaming a Category

To rename a category or its description:

- 1 Select **Manage categories** from the Administration menu. The Manage Categories dialog opens.
- 2 Select the category you want to rename.
- 3 Click **Rename Category**.
- 4 In the **Category Name** field, type the new name. You can enter a maximum of 64 characters.
- 5 In the **Description** field, enter an optional category description. This description appears as a tooltip when you hover over the category in the category tree.

- 6 Click the **Rename** button.

Moving a Category

To move a category:

- 1 Select **Manage categories** from the Administration menu. The **Manage Categories** dialog opens.
- 2 Drag and drop the category to the desired location in the tree.

Managing Access Rights

By managing access rights for a category, you define which user or group is assigned as a role for a category and the rights (e.g. read, replace, update) they have. This affects access and rights on requirements, dashboards, documents, reports, collections or baselines in this category. The **Access Rights** dialog provides the following functions:

- **Show All:** Shows access for all users.
- **Show access for User:** Shows access for a single user.
- **Find category:** Filters the category tree for the entered category.
- **Find user:** Filters the access rights tree for the entered user name.
- **Inherit access rights from parent category:** If enabled, the rights of a category are identical with the rights of the parent category. If disabled, you can set individual access rights for that category.
- **Copy User Access:** Opens a dialog which allows to copy access rights for all category from the selected user to another user.
- **Remove All Assignments:** Removes access to all category for the selected user.

Changing Access Rights for a Category

To change the access rights for a category:

- 1 Select **Manage categories** from the **Administration** menu to open the **Manage Categories** dialog.
- 2 Click **Access Rights**.
- 3 Ensure that the **Show All** option is selected.
- 4 Select the category for which you want to change the access rights.



TIP To quickly locate a category in the tree, type its name or part of it into the **Find category** box.

- 5 Ensure that the **Inherit access rights from parent category** box is clear.

- 6 Select the users or groups you want to grant access or deselect the users or groups you want to deny access.




TIP To quickly locate a user or group in the tree, type its name or part of it into the **Find user** box.

- 7 If required, modify access rights for other categories.
- 8 Click **OK**.

Viewing Access Rights for a Single User Account

To view the access rights for a single user account:

- 1 Select **Manage categories** from the **Administration** menu to open the **Manage Categories** dialog.
- 2 Click **Access Rights**.
- 3 Select the **Show access for User** option.
- 4 Select a user from the drop-down list or find a user by doing the following:
 - a Click . This opens the **Find & Select User** dialog.
 - b Fill **User ID**, **First Name** or **Last Name** box as desired to filter the user list.
 - c Click **OK**.
- 5 For categories, the selected user has access, the category tree shows the group which allows access next to the category name.


Copying Access Rights to Another User Account

When you create a user account, the new user has access to all categories for which his groups allow access. If you want to limit (or grant for existing users) the access rights, you may just copy from an existing user.



TIP If you have several different access right setups, you may want to create a user account which acts as a template. This account should be named that it identifies the purpose and - for security reasons - be disabled. For further information on how to create user accounts, see chapter "[Creating a New User](#)" on page 234.

To copy access rights to another user account:


- 1 Select **Manage categories** from the **Administration** menu to open the **Manage Categories** dialog.
- 2 Click **Access Rights**.
- 3 Select the **Show access for User** option.
- 4 Select a user from the drop-down list or find a user by doing the following:
 - a Click . This opens the **Find & Select User** dialog.
 - b Fill **User ID**, **First Name** or **Last Name** box as desired to filter the user list.
 - c Click **OK**.

- 5 Click **Copy User Access...** to open the **Copy Category Group Assignment to** dialog. This dialog contains only users which are in the same group(s) as the selected user.
- 6 Select one or several users.
- 7 Click **OK** to close the **Copy Category Group Assignment to** dialog.
- 8 Click **OK** to close the **Access Rights** dialog.

Removing Access Rights for a User Account

If you want to remove all access rights for a user account, this means that the user can still log on to RM Browser, but is unable to view or edit any object (e.g. requirements).

To remove access rights for a user account:

- 1 Select **Manage categories** from the **Administration** menu to open the **Manage Categories** dialog.
- 2 Click **Access Rights**.
- 3 Select the **Show access for User** option.
- 4 Select a user from the drop-down list or find a user by doing the following:
 - a Click . This opens the **Find & Select User** dialog.
 - b Fill **User ID**, **First Name** or **Last Name** box as desired to filter the user list.
 - c Click **OK**.
- 5 Click **Remove All Assignments...**
- 6 Confirm the dialog to remove all category/group assignments.
- 7 Click **OK** to close the **Access Rights** dialog.

Moving Requirements Between Categories

A requirement can exist in only one category at a time, so moving a requirement to a different category also removes it from the category it was in before. The Organize by Category dialog allows you to specify search criteria to locate the requirements that you wish to move.



NOTE For information on the administrative functions you can perform with categories, see the *Serena Dimensions RM Administrator's Guide*.

To move requirements between categories:

- 1 Select **Organize by Category** from the Administration menu. The **Organize by Category** dialog opens.
- 2 **Look for class:** Select a class in which to search for requirements. If an object was selected when you invoked the dialog, this field will be pre-populated; change it as needed.

- 3 Manage Categories:** Click this link if you want to create, rename, or delete any categories before proceeding with the move procedure. The Manage Categories dialog opens. See ["Managing Users" on page 234](#).
- 4 Remember these options:** Select this checkbox to retain the current settings as the default for future invocations of the dialog.
- 5 Constraints:** As needed, specify criteria to locate the desired requirements. See ["Attribute Constraints Tab" on page 28](#) and ["Relationship Constraints Tab" on page 31](#).
- 6 Display Options:** As needed, specify how to display the results. See ["Display Options Tab" on page 34](#).
- 7 Find Now:** Click this button to run the search. The results are displayed in the lower pane of the dialog.
- 8 New Search:** Click this button to clear the current search criteria and results.
- 9** Select the desired requirements in the search results. For multi-selection of requirements, see chapter ["Selecting Multiple Requirements" on page 23](#).
- 10 Category:** Select the category to which you want to move the selected requirements.
- 11** Click the **Move** button.

Managing Document Locks


To break locks on documents:

- 1** Select **Document Locks** from the Administration menu. The Document Locks dialog opens.
- 2 Unlock All:** Click this button to unlock all locked documents.
- 3 Unlock Selected:** Click this button to unlock only the selected documents. Ctrl-click to select multiple documents.
- 4 Refresh:** Click this button to update the display of locked documents.

Managing Requirement Locks

To break locks on requirements:

- 1 Select **Requirement Locks** from the Administration menu. The Requirement Locks dialog opens.



- 2 **Unlock All:** Click this button to unlock all locked requirements.
- 3 **Unlock Selected:** Click this button to unlock only the selected requirements. Ctrl-click to select multiple requirements.
- 4 **Refresh:** Click this button to update the display of locked requirements.

Configuring Project Settings

To open the Project Settings dialog:

Select **Project Settings** from the **Administration** menu. You can select **Project Settings** only if your user account is in the Administrator group.

For information on configuring project settings, refer to chapter "[Configuring User Settings and Project Settings](#)" on page 50.

Configuring Agile

To allow the configuration of Agile, classes and relationships must be created by the administrator and Agile must be enabled for the project. For further information on creating classes and relationships see chapter "[Agile](#)" in *Dimensions RM Administrator's Guide*. To enable Agile, see chapter "[Agile](#)" on page 52.

To open the Agile Settings dialog:

Select **Agile Settings** from the Administration menu. You can select **Agile Settings** only if your user account is in the Administrator group.

Products

The Products mapping is a required setting.

To edit the Products mapping do the following:

- 1 Select **Agile Settings** from the Administration menu. This opens the Agile Settings dialog.
- 2 Select **Products**.
- 3 In the **Products Mapping** section, select the class you wish to use with assign to Agile's Products functionality from the **Products** box.
- 4 In the **Choose field equivalents** section, select the attributes which should be used on Agile's Product attributes.
- 5 Click **Save**.
- 6 Click **Close**.

Releases

The Releases mapping is an optional setting. If this setting is not configured, you cannot use releases with Agile.

To edit the Releases mapping do the following:

- 1 Select **Agile Settings** from the Administration menu. This opens the Agile Settings dialog.
- 2 Select **Releases**.
- 3 In the **Releases Mapping** section, select the class you wish to use with assign to Agile's Releases functionality from the **Releases** box.
- 4 In the **Choose field equivalents** section, select the attributes which should be used on Agile's Releases attributes.
- 5 Click **Save**.
- 6 Click **Close**.

Sprints

The Sprints mapping is an optional setting. If this setting is not configured, you cannot use sprints with Agile.

To edit the Sprints mapping do the following:

- 1 Select **Agile Settings** from the Administration menu. This opens the Agile Settings dialog.
- 2 Select **Sprints**.
- 3 In the **Sprints Mapping** section, select the class you wish to use with assign to Agile's Sprints functionality from the **Sprints** box.
- 4 In the **Choose field equivalents** section, select the attributes which should be used on Agile's Sprints attributes.
- 5 Click **Save**.

- 6 Click **Close**.

Epics

The Epics mapping is an optional setting. If this setting is not configured, you cannot use epics with Agile.

To edit the Epics mapping do the following:

- 1 Select **Agile Settings** from the Administration menu. This opens the Agile Settings dialog.
- 2 Select **Epics**.
- 3 In the **Epics Mapping** section, select the class you wish to use with assign to Agile's Epics functionality from the **Epics** box.
- 4 In the **Choose field equivalents** section, select the attributes which should be used on Agile's Epics attributes.
- 5 Click **Save**.
- 6 Click **Close**.

Features

The Features mapping is an optional setting. If this setting is not configured, you cannot use features with Agile.

To edit the Features mapping do the following:

- 1 Select **Agile Settings** from the Administration menu. This opens the Agile Settings dialog.
- 2 Select **Features**.
- 3 In the **Features Mapping** section, select the class you wish to use with assign to Agile's Features functionality from the **Features** box.
- 4 In the **Choose field equivalents** section, select the attributes which should be used on Agile's Features attributes.
- 5 Click **Save**.
- 6 Click **Close**.

Stories

The Stories mapping is an optional setting. If this setting is not configured, you cannot use features with Agile.


To edit the Stories mapping do the following:

- 1 Select **Agile Settings** from the Administration menu. This opens the Agile Settings dialog.
- 2 Select **Stories**.

- 3 In the **Stories Mapping** section, select the class you wish to use with assign to Agile's Stories functionality from the **Stories** box.
- 4 In the **Choose field equivalents** section, select the attributes which should be used on Agile's Stories attributes.
- 5 Click **Save**.
- 6 Click **Close**.

Clearing Agile Mappings

To clear one Agile mapping, do the following:

- 1 Select **Agile Settings** from the Administration menu. This opens the Agile Settings dialog.
- 2 Click  .
- 3 Confirm the following message by clicking **Reset**.

To clear all Agile mappings, do the following:

- 1 Select **Agile Settings** from the Administration menu. This opens the Agile Settings dialog.
- 2 Click **Reset**.
- 3 Confirm the following message by clicking **Reset**.

Chapter 12

Script Syntax

Overview	248
SELECT Statement	248
CALCULATE Statement	260
XREF Statement	261
PLUS Statement	263
COMMENT Statement	263
Adding Rich Format Text to Query Prompts	265

Overview

Scripts contain commands for extracting data from the Serena® Dimensions® RM database and for formatting the results. This appendix describes the syntax of the Dimensions RM script language. If you are familiar with SQL, you will note the similarity between that standard language and the variant of it that has been tailored specifically for Dimensions RM.



IMPORTANT! The Dimensions RM scripting language is **NOT** SQL. Though *similar* to SQL, it is in fact unique to Dimensions RM. Please read this chapter to understand its usage.

The RM scripting language:

- Is an interpreted language. This helps to prevent SQL injection attacks.
- Uses a database meta model so class names are *not* real database table names.



NOTE This section describes the full language and identifies the script generator limitations. In many cases, scripts work equally well interactively and from the command line with `doc_out`. There are some cases, however, such as with variables and prompts, in which a script can only be used in one context. For example, scripts that reference variables cannot be used interactively; scripts that use prompts cannot be used from the command line.

A Dimensions RM reporting script contains commands that tell Dimensions RM what data to extract from the project and how to format it. The following types of commands can be included in a script:

- **SELECT** defines the data (object attributes) to be extracted.
- **CALCULATE** performs computations based on the extracted data.
- **XREF** controls cross references that follow links between objects.
- **PLUS** concatenates **SELECT** statements.
- **COMMENT** provides descriptive information that is not interpreted by Dimensions RM.



NOTE You cannot save a script unless you have the "Create" permission for scripts

SELECT Statement

For those familiar with SQL (Structured Query Language), the **SELECT** statement in a script appears similar in many ways to the SQL **SELECT** statement.

A **SELECT** statement may contain the following elements (mandatory elements are indicated in bold print):

- The reserved word **SELECT**
- A list of display elements (attributes) each preceded by a `<DTPtag>`. The `DTPtag` specifies a column heading for tabular displays or, when the script results are saved in

a formatted file, a paragraph style or format for desktop publishing tools. At least one attribute must be selected. If you do not want a column header or a paragraph style, you must indicate that with empty delimiters, as in <>.

- The reserved word FROM
- The RM class name
- The reserved word WHERE
- Conditions under which to make the extraction
- The reserved words ORDER BY
- A list of fields by which to order extraction
- Metrics computations to be performed

Note the format of this statement – SELECT <>'attribute' FROM 'class'. The display attributes must be preceded by the characters '<' and '>'. If these characters are not present, the attribute is not included in the report document.

A SELECT statement may contain as many display elements as required, but each element must be defined as an attribute of the given class.

For example:

```
SELECT <>TEST_ID <>TEST_DESCRIPTION <>TEST_NOTES <>REQUIRED_RESULT
FROM TEST
```

This SELECT statement produces a list of all the objects of class TEST in the Dimensions RM database, in Dimensions RM key order. The test identifier, description, notes, and required result attributes appear in the output in the same order as they appear in the display list.

```
SELECT <Requirement ID>REQ_ID <Status> STATUS <Text>Text FROM
CustomerRequirements WHERE STATUS != 'Deleted' ORDER BY STATUS
```

This select statement produces a list of all objects in class CustomerRequirements that have not been deleted. The list is intended for tabular output on the screen or in a CSV file, so the column headings are included. The result will be ordered by the STATUS attribute value in alphabetical order.

DTPtag

You can specify a DTPtag for each attribute in your report to control output formatting. For tabular output, the DTPtag is used as a column heading. For document format, such as RTF, the DTPtag is used to identify a paragraph style to be associated with the attribute value. The tag name is placed between the < and > characters that precede a display list element. The tag name may be up to 19 characters in length.

The tag name can only include the '#' character if it is preceded by a backslash (\).

When used with a table, the tag name appears as the column heading, with a column width determined by Dimensions RM. You can specify the column width by preceding the tag with '!n', where n is the desired column width in characters. Column widths are not supported in the script generator wizard.

For example (DTPtags are shown in **bold**):

```
SELECT !8<Test ID>TEST_ID !25<Description>TEST_DESCRIPTION
!25<Test Notes>TEST_NOTES !25<Results>REQUIRED_RESULT FROM TEST
```

DTP_TEXT Display Item

Dimensions RM supports a display list element, called DTP_TEXT, which does not correspond to an attribute. For tabular output, DTP_TEXT can be used to insert a blank column into the output. For document output, its purpose is to insert a "blank" component tag (that is, a DTP tag with no text or data attached). This enables the inclusion into documents of headers and footers, and repeated text strings.

As many DTP_TEXT items as desired may be included in the display list, and their position within the display list is significant.

For example, to separate each TEST record in a list with a marker (for example, a separator line):

```
SELECT <Test ID>TEST_ID <Description>TEST_DESCRIPTION <Test
Notes>TEST_NOTES <Result>REQUIRED_RESULT <separator>DTP_TEXT FROM
TEST
```

Within RM Word, the tag separator must be defined to produce a paragraph of the required type, for example, a line of hyphens or asterisks.

RTM_KEYWORD Display Item

Dimensions RM supports another display list item that does not correspond to an attribute. Use RTM_KEYWORD to request Dimensions RM to return a list of linked collections for each object. For example:

```
SELECT <Test ID>TEST_ID <Description>TEST_DESCRIPTION <Test
Notes>TEST_NOTES <Result>REQUIRED_RESULT
<Linked Collections>RTM_KEYWORD FROM TEST
```

WHERE Clause

For many reporting purposes, only a subset of the objects in a class is required. The WHERE reserved word is used in conjunction with a SELECT statement to specify selection constraints in terms of attribute values, collection membership, or relationship linkages. The WHERE clause syntax is of the general form:

WHERE ConditionalExpression

where ConditionalExpression is a logical expression whose elements are of the form:

- AttributeName Operator Valuelist
- Direction Relationship
- Group {in | not in} (collectionList)
- SpecialConstraint

The elements of a conditional expression are combined using the logical operators AND and OR. Any number of conditions may be applied to a SELECT statement which can be combined using the reserved words AND and OR. Both AND and OR have the same precedence and are left associative. Parentheses may be used to change the precedence.

The following table describes attribute types used in Dimensions RM project schemas and their allowed operators.

Attribute Type	Operators	Notes
Alphanumeric	INITIALIZED, NOT INITIALIZED, IN, NOT IN, =, !=, <, >, <=, >=	For further information, see chapter "Comparing Text" on page 252.
Date	INITIALIZED, NOT INITIALIZED, =, !=, <, >, <=, >=	For further information, see chapter "Comparing Dates" on page 254.
File Attachment		Not supported
Group	INITIALIZED, NOT INITIALIZED, IN, NOT IN, =, !=, <, >, <=, >=	For further information, see chapter "Comparing Text" on page 252.
List	INITIALIZED, NOT INITIALIZED, IN, NOT IN, =, !=, <, >, <=, >=	For further information, see chapter "Comparing Text" on page 252.
Numeric	INITIALIZED, NOT INITIALIZED, IN, NOT IN, =, !=, <, >, <=, >=	For further information, see chapter "Comparing Numbers" on page 252.
Text	INITIALIZED, NOT INITIALIZED, IN, NOT IN, =, !=, <, >, <=, >=	For further information, see chapter "Comparing Text" on page 252.

Comparing Numbers

Operator	Description
INITIALIZED	The attribute contains a value. Example: TEST_ATTRIBUTE INITIALIZED
NOT INITIALIZED	The attribute contains no value. Example: TEST_ATTRIBUTE NOT INITIALIZED
=	The attribute value must be identical with the specified value. Example: TEST_ATTRIBUTE = 5
!=	The attribute value must not be identical with the specified value. Example: TEST_ATTRIBUTE != 5
<	The attribute value must be less than the specified value. Example: TEST_ATTRIBUTE < 5
>	The attribute value must be larger than the specified value. Example: TEST_ATTRIBUTE > 5
<=	The attribute value must be less or identical with the specified value. Example: TEST_ATTRIBUTE <= 5
>=	The attribute value must be larger or identical with the specified value. Example: TEST_ATTRIBUTE >= 5
IN	The attribute value must be identical to one of those provided Example: TEST_ATTRIBUTE IN (3, 4, 5)
NOT IN	The attribute value must not be identical to one of those provided Example: TEST_ATTRIBUTE NOT IN (3, 4, 5)

Comparing Text

When comparing text, the casing of a word is very important. This is because for a computer, a text is represented by numbers. All capital letters have a lower value than lowercase letters, i.e. "A" has the value of 65, while "a" has the value of 97. For the following table (except for operators INITIALIZED and NOT INITIALIZED), it is assumed that there are two requirements, REQ1 and REQ2. For REQ1, the attribute TEST_ATTRIBUTE has the value "Test". For REQ2, the attribute TEST_ATTRIBUTE has the value "test".

Operator	Description
INITIALIZED	The attribute contains a value. Example: TEST_ATTRIBUTE INITIALIZED
NOT INITIALIZED	The attribute contains no value. Example: TEST_ATTRIBUTE NOT INITIALIZED
=	The attribute value must be identical with the specified value. Example: TEST_ATTRIBUTE = 'Test' The example returns REQ1.

Operator	Description
!=	The attribute value must not be identical with the specified value. Example: TEST_ATTRIBUTE != 'Test' The example returns REQ2.
<	The attribute value must be less than the specified value. Example: TEST_ATTRIBUTE < 'test' The example returns REQ1.
>	The attribute value must be larger than the specified value. Example: TEST_ATTRIBUTE > 'Test' The example returns REQ2.
<=	The attribute value must be less or identical with the specified value. Example: TEST_ATTRIBUTE <= 'test' The example returns REQ1 and REQ2.
>=	The attribute value must be larger or identical with the specified value. Example: TEST_ATTRIBUTE >= 'Test' The example returns REQ1 and REQ2.
IN	The attribute value must be identical to one of those provided Example: TEST_ATTRIBUTE IN ('Test', 'test') The example returns REQ1 and REQ2.
NOT IN	The attribute value must not be identical to one of those provided Example: TEST_ATTRIBUTE NOT IN ('Test', 'test') The example returns no requirements

Operator	Description
LIKE	<p>The attribute value must match the specified search pattern. Note that the text casing is relevant.</p> <p>Examples:</p> <ul style="list-style-type: none"> ■ TEST_ATTRIBUTE LIKE 'Business*' <ul style="list-style-type: none"> The value must start with the word "Business". ■ TEST_ATTRIBUTE LIKE '*business.' <ul style="list-style-type: none"> The value must end with "business.". ■ TEST_ATTRIBUTE LIKE ~'*business*' <ul style="list-style-type: none"> The value must contain the word "business". <p>*: A wildcard for any set of characters. %: A wildcard for a single character.</p>
NOT LIKE	<p>The attribute value must not match the specified search pattern. Note that the text casing is relevant.</p> <p>Examples:</p> <ul style="list-style-type: none"> ■ TEST_ATTRIBUTE NOT LIKE 'Business*' <ul style="list-style-type: none"> The value must not start with the word "Business". ■ TEST_ATTRIBUTE NOT LIKE '* business.' <ul style="list-style-type: none"> The value must not end with "business.". ■ TEST_ATTRIBUTE NOT LIKE ~'*business*' <ul style="list-style-type: none"> The value must not contain the word "business". <p>*: A wildcard for any set of characters. %: A wildcard for a single character.</p>

Comparing Dates

The syntax for comparing dates is similar to the syntax of comparing strings. However, important for comparing dates is that the query format matches the format of the attribute. When starting a new script, you might prefer selecting dates through the wizard.

Operator	Description
INITIALIZED	<p>The attribute contains a value.</p> <p>Example: TEST_ATTRIBUTE INITIALIZED</p>
NOT INITIALIZED	<p>The attribute contains no value.</p> <p>Example: TEST_ATTRIBUTE NOT INITIALIZED</p>
=	<p>The attribute value must be identical with the specified value.</p> <p>Examples:</p> <ul style="list-style-type: none"> ■ TEST_ATTRIBUTE = '01-SEP-2015' ■ TEST_ATTRIBUTE = '01-SEP-2015@01:02:03'

Operator	Description
!=	<p>The attribute value must not be identical with the specified value.</p> <p>Examples:</p> <ul style="list-style-type: none"> ■ TEST_ATTRIBUTE != '01-SEP-2015' Any date which is not September 1st, 2015 matches this criterion, e.g. August 30th, 2015; December 31st, 2014 or September 2nd, 2015. ■ TEST_ATTRIBUTE != '01-SEP-2015@01:02:03' Any which is not September 1st, 2015 at 01:02:03 matches this criterion, e.g. August 30th, 2015 at 12:05:45; September 1st, 2015 at 01:02:02 or September 2nd, 2015 at 02:03:04.
<	<p>The attribute value must be less than the specified value.</p> <p>Examples:</p> <ul style="list-style-type: none"> ■ TEST_ATTRIBUTE < '01-SEP-2015' Any date before September 1st, 2015 matches this criterion, e.g. August 30th, 2015 or December 31st, 2014. ■ TEST_ATTRIBUTE < '01-SEP-2015@01:02:03' Any date before September 1st, 2015 at 01:02:03 matches this criterion, e.g. August 30th, 2015 at 12:05:45 or September 1st, 2015 at 01:02:02.
>	<p>The attribute value must be larger than the specified value.</p> <p>Examples:</p> <ul style="list-style-type: none"> ■ TEST_ATTRIBUTE > '01-SEP-2015' Any date after September 1st, 2015 matches this criterion, e.g. September 2nd, 2015 or January 1st, 2016. ■ TEST_ATTRIBUTE > '01-SEP-2015@01:02:03' Any date after September 1st, 2015 at 01:02:03 matches this criterion, e.g. September 2nd, 2015 at 12:05:45 or September 1st, 2015 at 01:02:04.
<=	<p>The attribute value must be less or identical with the specified value.</p> <p>Examples:</p> <ul style="list-style-type: none"> ■ TEST_ATTRIBUTE <= '01-SEP-2015' The date must be September 1st, 2015 or before to match this criterion, e.g. August 30th, 2015 or December 31st, 2014. ■ TEST_ATTRIBUTE <= '01-SEP-2015@01:02:03' The date must be September 1st, 2015 at 01:02:03 or before to match this criterion, e.g. August 30th, 2015 at 12:05:45 or September 1st, 2015 at 01:02:02.

Operator	Description
>=	<p>The attribute value must be larger or identical with the specified value.</p> <p>Examples:</p> <ul style="list-style-type: none"> ■ TEST_ATTRIBUTE > '01-SEP-2015' The date must be September 1st, 2015 or after to match this criterion, e.g. September 2nd, 2015 or January 1st, 2016. ■ TEST_ATTRIBUTE > '01-SEP-2015@01:02:03' The date must be September 1st, 2015 at 01:02:03 or after to match this criterion, e.g. September 2nd, 2015 at 12:05:45 or September 1st, 2015 at 01:02:04.
LIKE	<p>The attribute value must match the specified search pattern.</p> <p>Examples:</p> <ul style="list-style-type: none"> ■ TEST_ATTRIBUTE LIKE ~'17-*-2015' The date must be 17th of any month in 2015. ■ TEST_ATTRIBUTE LIKE ~'*-SEP-2015' The date must be any day in September 2015. ■ TEST_ATTRIBUTE LIKE ~'*-SEP-%' The date must be any day in September of any year. ■ TEST_ATTRIBUTE LIKE '01-SEP-2015@*' The date must be September 1st, 2015; the time is irrelevant. <p>*: A wildcard for any set of characters. %: A wildcard for a single character.</p>
NOT LIKE	<p>The attribute value must not match the specified search pattern.</p> <p>Examples:</p> <ul style="list-style-type: none"> ■ TEST_ATTRIBUTE NOT LIKE ~'17-*-2015' The date must not be 17th of any month in 2015. ■ TEST_ATTRIBUTE NOT LIKE ~'*-SEP-2015' The date must not be any day in September 2015. ■ TEST_ATTRIBUTE NOT LIKE ~'*-SEP-*' The date must not be any day in September of any year. ■ TEST_ATTRIBUTE NOT LIKE '01-SEP-2015@%' The date must not be September 1st, 2015. <p>*: A wildcard for any set of characters. %: A wildcard for a single character.</p>

Direction Relationship

This constraint form is used to identify linked objects within a particular relationship. For example, given a relationship between classes SystemRequirement (the primary class) and Test (the secondary class), you could search for system requirement objects that are linked to test objects. Alternatively, finding those that are not linked can help you identify work that is yet to be completed. The following “directions” are defined:

- PRIMARY_IN

- NOT_PRIMARY_IN
- SECONDARY_IN
- NOT_SECONDARY_IN

These operators are used to extract only those objects which have links (or not) in a named relationship, and can therefore be used to create 'compliance' lists (such as a list of tests which have or have not been linked to requirements)

Following are Direction Relationship examples (based on a relationship named Tested_By with SystemRequirements as the primary and Test as the secondary class).

- PRIMARY_IN Tested_By
Finds SystemRequirements that are linked to at least one Test object.
- NOT_SECONDARY_IN Tested_By
Finds Test objects that are not associated with any SystemRequirement objects

For SELECT statements involving requirements, there are two pre-defined relationships that may also be used. These are SOURCE and IMMEDIATE. The effect of using each of the relationship operators with each of the SOURCE and IMMEDIATE relationships is described in the following table.

Operator	IMMEDIATE	SOURCE
PRIMARY_IN	Requirements that have children (not the lowest level requirements)	Requirements that have no parents (the source requirements)
SECONDARY_IN	Requirements that have parents (derived requirements)	Requirements that have no children (the lowest level requirements)
NOT_PRIMARY_IN	Requirements that have no children (the lowest level requirements)	Requirements that have parents (derived requirements)
NOT_SECONDARY_IN	Requirements that have no parents (the source requirements)	Requirements that have children (not the lowest level requirements)

Group {in | not in} (collectionList)

This constraint form is used to identify objects with respect to their linkage to one or more collections. For example, you can define collections to help you manage prioritization. A parent collection, named Priorities could have child collections named Priority 1, Priority 2, and so on. You can use these collections to organize reports focused on specific priorities or to find items that have yet to be prioritized:

Following are collection constraint examples.

- GROUP IN ('Priority 1', 'Priority 2')
Finds objects linked to either Priority 1 or Priority 2 collections.
- GROUP NOT IN ('Priorities')
Finds objects not yet prioritized.

SpecialConstraint

This constraint form supports built-in attributes of classes based on the requirement class type. These classes include built-in text attributes named Query and Clarification, which are intended for use with questions and answers to do with the requirement itself. The SpecialConstraint keywords listed below take no additional operands:

- `HAVING_CLARIFICATION_TEXT`
- `HAVING_NO_CLARIFICATION_TEXT`
- `HAVING_QUERY_TEXT`
- `HAVING_NO_QUERY_TEXT`

Following is a SpecialConstraint example:

- `SELECT <Requirement ID>REQ_ID <Status> STATUS <Text>Text FROM CustomerRequirements WHERE HAVING_QUERY_TEXT`

Finds identifier, status, and text from objects of class CustomerRequirements with non-empty Query attribute.

Variables

Variables can be used when running scripts from the command line, using `doc_out`, to allow the same script to be used for different values. Variables are not supported in the script generator wizard except when used in conjunction with prompting (see ["Prompting" on page 258](#)).

For example:

```
SELECT <>TEXT FROM REQS WHERE REQUIREMENT_KEY = REQ_KEY_VALUE
```

The value of `REQ_KEY_VALUE` may be supplied from the command line for each execution of the script. The name of the variable must be given in upper case.

Prompting

Scripts can also contain specially formatted prompts that will be displayed when the script is run interactively to prompt users for information. The syntax for prompting in scripts is:

```
<#prompt#> anywhere in the script. For example: select <id>object_id from ECP where object_id = '<#enter id#>'
```

This prompting syntax also allows for prompted values to be used as variables in multiple places within a script. For example:

- `select <id>object_id from CR where object_id='<#enter id^var1#>'`
`xref`
- `select <id>object_id from SR where object_id='<#^var1#>'`

The value entered by the user for the object ID of the CR class will also be used in the where clause of the SR class select. The `^^` indicates that the value should be stored in the variable following the `^^` and that variable name can be used without a prompt elsewhere. If a second prompt `^` variable name is found with the same variable name, the variable's value will be changed.

ORDER BY Clause

The `ORDER BY` clause can be added to the `SELECT` statement to specify the order in which the records should be returned. The `ORDER BY` clause is added after the `WHERE` clause or after the class name if no `WHERE` clause is included. The reserved words `ORDER BY` must be followed by a comma separated list of attributes. Any number of attributes of a class can be used to qualify the order of extraction.

Sorting in Ascending Order

By default, the `ORDER BY` clause sorts in ascending order.

Examples:

- `SELECT <>TEST_SETUP FROM TEST
ORDER BY TEST_ID, TEST_DATE`
- `SELECT <>TEST_SETUP FROM TEST
WHERE TEST_ID = '7'
ORDER BY TEST_DATE, REQUIRED_RESULT`



NOTE When the `ORDER BY` attribute has a `NULL` value, it is placed at the end of the list (that is, it is considered to have the highest value).

Sorting in Descending Order

To sort in descending order, append `|DESC|` to the attribute name.

Examples:

- `SELECT <>TEST_SETUP FROM TEST
ORDER BY TEST_ID|DESC|, TEST_DATE|DESC|`
- `SELECT <>TEST_SETUP FROM TEST
WHERE TEST_ID = '7'
ORDER BY TEST_DATE|DESC|, REQUIRED_RESULT|DESC|`



NOTE When the `ORDER BY` attribute has a `NULL` value, it is placed at the top of the list (that is, it is considered to have the highest value).

Sorting Dewey Decimal Formatted Values

It is common for reports to be ordered by attributes that have a Dewey decimal format (e.g. 1.2.3.12). Often the `PARAGRAPH_ID` attribute will have this kind of format. A straightforward ASCII sort on these codes will not return a correct order, since it is performed on a character-by-character basis, rather than by the numbering.

A Dewey decimal code needs to have letters (upper or lower case) and numbers separated by a decimal point or a hyphen. The following examples are legal Dewey decimal codes:

- 1.2.5

- a.b
- 3
- d
- d-1-2

There is no restriction on the length of the code.

To perform a Dewey decimal ordering, precede the appropriate attribute with the @ symbol.

Example:

```
SELECT <PUID>PUID <Title>TITLE <Paragraph ID>PARAGRAPH_ID FROM REQ  
ORDER BY @PARAGRAPH_ID
```

Descending sorting can also be used for attributes which contain dewey decimal formatted values by adding **|DESC|**.

CALCULATE Statement

Metrics can be performed upon select statements in scripts run from doc_out. The available calculations are as follows:

- A **count** of records selected on any field
- The **total** of the values of records selected on numeric fields
- The **average** value of records selected on numeric fields
- The **minimum** value selected on numeric fields
- The **maximum** value selected on numeric fields
- **Normalization** of values selected by a simple arithmetic expression

The results of the count, total, average, minimum and maximum metrics are displayed at the bottom of the report. Normalization causes each record value in the body of the report to be changed according to the arithmetic expression.

NULL fields are handled in two ways:

- If only records with values in them are to be used (POPULATED), the NULL fields are ignored (this is the default)
- If all records are to be used regardless of their content (ALL), NULL fields are treated as having the value 0 (zero).

The format of the CALCULATE statement is as follows:

- The CALCULATE keyword appears first to indicate that metrics will be performed.
- A list of calculation types (COUNT, TOTAL, AVERAGE, MINIMIZE, MAXIMIZE or NORMALIZE) and the fields applicable (the fields should be separated by commas).
- Each calculation type keyword can be prefixed by an ALL or POPULATED flag. If none is supplied, the default of POPULATED is used.

For TOTAL, COUNT, AVERAGE, MINIMUM and MAXIMUM:

- The field name should be prefixed by a mandatory "tag" in the format [string] which defines a string to be used in the report to identify that particular value. Note that [] is valid.
- Each separate [tag] field entry in the list may be prefixed by the ALL or POPULATED flag.

For normalization:

- Each entry has the form "fieldname operator value", where operator is any of '+', '-', '*', '/' and value is a real or integer number. No tags are applicable for normalization.
- Each separate [tag] field entry in the list may be prefixed by the ALL or POPULATED flag.

For example:

```
SELECT <number>PARTS_AVAILABLE FROM REQ
CALCULATE COUNT [count]PARTS_AVAILABLE
TOTAL [total]PARTS_AVAILABLE
AVERAGE [average]PARTS_AVAILABLE
MINIMIZE [min]PARTS_AVAILABLE
MAXIMIZE [max]PARTS_AVAILABLE
```

To modify the values of the attribute PARTS_AVAILABLE in the report, you can use the NORMALIZE metric:

```
SELECT <id>REQUIREMENT_KEY <number>PARTS_AVAILABLE FROM REQ CALCULATE
NORMALIZE ALL PARTS_AVAILABLE + 5
```

XREF Statement

The XREF statement lets you show the linkage or traceability between objects. XREF links the SELECT statement, immediately following it with a previous SELECT statement.

The XREF statement must contain the reserved word XREF and the name of the relationship that defines the traceability. It may also contain the reserved words PRIMARY, SECONDARY, PRIMARY_HISTORY, SECONDARY_HISTORY and either FIRST, SECOND, THIRD, FOURTH, or a number.

If both SELECT statements select from the same class, then the XREF statement must be modified with either the PRIMARY or SECONDARY reserved words. Use PRIMARY if the second SELECT statement refers to the primary side of the relationship. Use SECONDARY if the second SELECT statement refers to the secondary side of the relationship.



NOTE The script generator wizard does not support the reserved words PRIMARY_HISTORY, SECONDARY_HISTORY, FIRST, SECOND, THIRD, and FOURTH, and the use of a number to refer to SELECT statements.

The XREF statement must appear between two SELECT statements, the latter of which must be for a class defined to be a member of the relationship named in the XREF statement. Also required is that at least one of the SELECT statements preceding the XREF statement must concern the other class named in the relationship.

For example, suppose a relationship has been defined called REQ_TEST that links the REQ class of type requirement (as the PRIMARY object in the relationship) to a class called TEST (the SECONDARY object), and traceability links have been created between objects in the classes. A list of requirements showing their related TESTs can be created using:

```
SELECT <ID>REQ_ID <>TEXT FROM REQ WHERE STATUS='CURRENT'  
XREF REQ_TEST  
SELECT <TEST ID>TEST_ID <>TEST_DESCRIPTION FROM TEST
```

This script produces a list of every requirement from the REQ class where the STATUS attribute has the value "Current", and if a requirement participates in the relationship REQ_TEST, its corresponding TESTs are extracted. Note that this form of the script extracts each of the requirements that match the condition, then the TESTs that are linked to them. If the condition was such that more than one requirement complied, and a TEST is linked to more than one requirement, it may appear more than once in the output.

To list only those requirements that are related to TESTs, append a condition as follows:

```
SELECT <ID>REQ_ID <>TEXT FROM REQ WHERE STATUS='CURRENT'  
AND PRIMARY_IN REQ_TEST  
XREF REQ_TEST  
SELECT <TEST ID>TEST_ID <>TEST_DESCRIPTION FROM TEST
```

The PRIMARY_IN operator has been used since REQ was defined as primary in the REQ_TEST relationship.

Using the NOT_PRIMARY_IN operator:

```
SELECT <ID>REQ_ID <>TEXT FROM REQ WHERE STATUS='CURRENT'  
AND NOT PRIMARY_IN REQ_TEST  
XREF REQ_TEST  
SELECT <TEST ID>TEST_ID <>TEST_DESCRIPTION FROM TEST
```

This produces a list containing only requirements, since any requirement not related to any TESTs, by definition will not cause any TESTs to be extracted.

The following script poses a problem:

```
SELECT <original>REQ_ID FROM REQ XREF REQ_TEST SELECT  
<test>TEST_DESCRIPTION FROM TEST XREF SOURCE SECONDARY SELECT <low  
child>REQUIREMENT_KEY FROM REQ XREF REQ_EVENT SELECT  
<events>EVENT_TEXT FROM EVENT
```

It is valid (providing the objects, attributes, and relationships have been defined), but the third XREF statement (XREF REQ_EVENT) implies the class named in the next SELECT statement (EVENT) must be linked in the relationship REQ_EVENT. Since the relationship links REQs to EVENTS and the next class is EVENT, they must be linked to REQs in a previous SELECT statement.

The script contains two instances of REQ in SELECT statements (SELECT statements 1 and 3). **By default, the first SELECT statement for a matching class is used.** So in the example the EVENTS are those linked to the first set of REQs (the original requirements).

There are four reserved words that allow you to choose where the linkage must exist in the event of duplication of objects in the script:

- FIRST
- SECOND

- THIRD
- FOURTH



NOTE These reserved words are for compatibility with earlier versions of RM, but they are not supported in the script generator wizard.

The reserved words express the number of the SELECT statement to which the next SELECT statement is linked. One of these reserved words may appear as the final word in an XREF statement. It may be necessary to refer to a SELECT statement later in the script than the fourth one. This can be specified using a positive integer.

To change the previous script so that the EVENTS linked to the source REQUIREMENTS are displayed, append the reserved word THIRD or the number 3 to the final XREF statement.

```
SELECT <original>REQUIREMENT_KEY FROM REQ XREF REQ_TEST SELECT
<test>TEST_DESCRIPTION FROM TEST XREF SOURCE SECONDARY SELECT <low
child>REQUIREMENT_KEY FROM REQ XREF REQ_EVENT THIRD SELECT
<events>EVENT_TEXT FROM EVENT
```

The final XREF statement now means the class named in the next SELECT statement (EVENT) must be linked in the relationship REQ_EVENT to the objects extracted by the third SELECT statement. Since the relationship REQ_EVENT links REQs to EVENTS and both are represented in the SELECT statements, this is a valid script and produces the desired output.

PLUS Statement

The PLUS statement can be used to join multiple scripts into one script. The outcome of the extraction using the resultant script is multiple reports produced in one data extraction run.

For example:

```
SELECT <4.1_Title>DTP_TEXT <>TEXT FROM REQ WHERE
PRIMARY_IN IS_ALLOCATED TO HARDWARE
PLUS SELECT <4.2_Title>DTP_TEXT <>TEXT FROM REQ WHERE
PRIMARY_IN IS_ALLOCATED TO SOFTWARE
PLUS SELECT <4.3_Title>DTP_TEXT <>TEXT FROM REQ WHERE
PRIMARY_IN IS_ALLOCATED TO MANUAL_OPERATION
```

COMMENT Statement

You can use comments to provide documentation within scripts to be used from the command line. The script generator wizard does not support comments. Comments can be inserted into a script in several formats:

- Characters after ##, -- or \$! are ignored until the start of a new line.
- Multiple line comments can be enclosed within pairs of comment delimiters {}, /* */ or (* *).

For example:

```
/* Version 1.0
   Date: 14th May 2006*/
SELECT <key>REQUIREMENT_KEY ## extract RMs no.
FROM REQ-- for the req class
WHERE SOURCE_REQUIREMENTS = 'Y'#! of all original requirements
{Now find all derived requirements}
XREF SOURCE SECONDARY
(* and extract the RM nos *)
SELECT REQUIREMENT_KEY FROM REQ
```


Adding Rich Format Text to Query Prompts


Using Rich Text in a query prompt can provide extra information to the user. For example, the following is a standard query prompting for a Marketing Requirement ID:

This is the layout we want to achieve:

The following steps describe how to modify a query prompt to provide this extra information:

- 1 Select **Class Report** from the **New** menu.
- 2 Select the desired class ("Marketing Requirements" in this example).
- 3 Specify a query name.
- 4 Select the **Script** radio button.
- 5 Select the **Attribute Constraints** tab.
- 6 Click on the arrow for the **Rqmt ID** field and select **Enter at runtime**.
- 7 In the main window, select **Requirement** from the **New** menu.
- 8 Select a class with an HTML enabled attribute and click into such an attribute.
- 9 Enter the text you want to use with the query prompt.

- 10** From the **Tools** menu, select **Source code** to get the raw HTML code. Select all then copy this text/html.



- 11** Close the *HTML Source Editor* window and the *New Marketing_Requirements* window.
- 12** In the *Query By Class: Marketing_Requirements* window, click on the **View Script** button which is located at the left window corner at the bottom. The script looks like this:

```
select <Rqmt ID>PUID <Title>TITLE from Marketing_Requirements where PUID LIKE ~'<#Enter Rqmt ID#>' and STATUS IN ('Current') order by PUID calculate all count[Row Count:]PUID
```

- 13** Locate the prompt '<#Enter Rqmt ID#>' and delete the text between the two "#" characters so that only '<##>' remains.
- 14** Put the cursor between the two "#" characters and press the "Enter" key twice. Your script should look like this:

```
Script:
select <Rqmt ID>PUID <Title>TITLE from Marketing_Requirements where PUID LIKE ~'<#
#>' and STATUS IN ('Current') order by PUID calculate all count[Row Count:]PUID
```

- 15** Paste the HTML code into the blank line, so it looks like this:

```
Script:
select <Rqmt ID>PUID <Title>TITLE from Marketing_Requirements where PUID LIKE ~'<#
<p style="PADDING-LEFT: 30px"><span style="color: #006600; font-weight:
bold;">Please Enter the Requirement IDs in the field/box to the right</span></p>
<p style="PADDING-LEFT: 30px"><span style="color: #006600; font-weight:
bold;"></span>&nbsp;</p>
<ol style="PADDING-LEFT: 30px">
<li style="COLOR: "><span style="color: #0000ff;">Each requirement ID must be
enclosed in single quotes</span></li>
<li style="COLOR: "><span style="color: #0000ff;">If multiple IDs are requested,
separate them with commas</span></li>
<li style="COLOR: "><span style="color: #0000ff;">Please note values are CASE
```

- 16** Click on **Save and Run**.

Glossary

Accept	A command that accepts a proposed change. The current status of the proposed requirement becomes "accepted," and a copy of the requirement is created with the Current Status of "current."
accepted	Current Status of a change request that was accepted.
access rights	The set of tasks that can be performed on a resource by a user.
alias	A set of keywords defined as variants or synonyms of a main keyword. For example, aliases of the keyword "calibrate" might be "calibrated," "calibrating," or even the wild card string "cal*". Unlike pseudonyms, which exist only while a particular Dimensions RM tool is active, aliases exist for the duration of the project or until they are deleted.
alphanumeric attribute	An attribute that represents one line of alphanumeric text, such as the title of an acceptance test. It can be up to 1000 characters in length.
alphabetic sort	A simple alphabetical sort. Contrast with <i>numeric sort</i> .
attribute	Information that is logically associated with a class of information to further specify the information content. See also <i>class attribute</i> , <i>evaluated attribute</i> , <i>implicit attribute</i> , <i>relationship attribute</i> , <i>user-defined attribute</i> .
attribute constraint	A rule that permits a link to be created only if some attribute of the primary or secondary object obeys a specific constraint. See also <i>primary object</i> .
attribute type	The nature or data type of an attribute: e.g. alphanumeric string, free text field, or date.
audit trail	An historical trace of the various versions of requirements that lets you reconstruct requirement evolution. The Visual Network tool lets you view the audit trail graphically.
auto link	A utility that lets you create or break links between objects of the primary and secondary class in the selected relationship.
baseline	A stable, unchangeable group of requirements. Baselining a collection ensures that the collection will never change.
baseline lock	A lock on a specific version of an item that indicates that the version is part of a baseline and thus cannot be modified.
batch update	A utility that lets you change attribute values for all requirements that match a set of attribute constraints for any one class defined in the project schema.
category	A method for organizing objects so you can create views of requirements, scripts, and filters for a subset of users. A requirement can belong to only one category.

cardinality rule	A rule that specifies the maximum number of links that can lead to and from primary or secondary objects. For example, a cardinality of 2:3 means that no more than two links can lead to a secondary object, and no more than three to the primary object.
change request	A proposal to change one or more requirement attributes.
child collection	Object hierarchies are created from the top down, from parent to child, while collection hierarchies are created in the opposite direction, by grouping child collections to form a parent collection, and so on. A child collection may be directly linked to an object. When a collection is created, it is a child collection by default.
child object	Whenever an object is edited and replaced, a new object is produced. The original object is called the parent object, and the new object is its child object. If this process is repeated, a child can itself be a parent of another child.
class	A container for related types of information. After classes are defined, requirements are entered into the class.
class attribute	A property of a class, as defined by the project administrator, that further breaks down the information in the class. By specifying attributes for a class, the project administrator can define the exact nature of the information represented by the class. This allows Dimensions RM users to make complex searches on their project information. Without defined attributes, classes model information at only a relatively high level of abstraction and lack internal detail. In such cases, the resulting diagram simply shows an overview of the abstract data types pertaining to the project, together with their interdependencies.
class definition	The initial Dimensions RM information modeling procedure the project administrator uses to configure Dimensions RM with respect to the information to be generated and traced within the project. This is represented graphically as a class definition diagram.
class definition diagram	A graphical representation of the information classes that exist in a project, along with the relationships between the classes.
Class Definition	A Dimensions RM tool that lets users with special privileges (such as project administrators) define various classes of information, attributes of those classes, and the relationships between the classes. By specifying the project structure in this way, a class definition both constrains and supports the systems engineer in the way that instances of classes, attributes and relationships can be created during the lifetime of the project. Systems engineers and other ordinary users can use Class Definition to view the class definition diagram for the project. See also class definition diagram .
CM Lock	Configuration Management Lock. A security feature that makes objects read-only and stops them from being updated. You can lock requirements, collections, and documents.
collection	A way to group requirements of any class. Once a collection is created, it can be associated with a requirement by linking the requirement to the collection. Each requirement can be linked to many different collections, and each collection can be linked to many different requirements. Parent collections contain child collections. Child collections contain requirements. Parent collections are not directly linked to any requirements, only linked indirectly through their child collections. See also baseline .

collection linkability	An occurrence of the association defined by a relationship. It connects two objects.
command line tools	Dimensions RM tools (doc_out) that let you to run scripts from the DOS prompt. Doc_out lets you run a Dimensions RM reporting script to generate output to a variety of formats. With doc_tool, you can prepare scripts before extraction for batch processing of reports.
compliance check	A process in which Dimensions RM searches the database and produces a report specifying which objects do not contain links across a defined relationship.
compliance report	A report that lists requirements that are or are not linked to objects in the other class in a relationship. A full compliance report lists all requirements in the primary and secondary class, whether or not they are linked to each other. A compliance-only report lists either all matching requirements in the primary class that have links to matching requirements in the secondary class, or all matching requirements in the secondary class that have links to matching requirements in the primary class. A non-compliance report lists either all matching requirements in the primary class that have no links to matching requirements in the secondary class, or all matching requirements in the secondary class that have no links to matching requirements in the primary class.
CSV import	A utility that lets you import data from a comma separated value file into the Dimensions RM project database.
current	Current Status of a requirement that is the most recent or current version.
Current Status	A special implicit attribute that identifies the state of a requirement.
cyclic relationship	Relationship in which the relationship points from one class back to the same class.
database	In the Dimensions RM environment, an instance of Oracle. The databases that are displayed in the Dimensions RM tools are determined by the contents of the tnsnames.ora file (an Oracle file).
date attribute	A user-defined attribute type that stores values that are based on user-defined date formats.
Delete	A command that changes the Current Status of a requirement to "deleted," but leaves the requirement in the project.
deleted	Current Status of a requirement that was deleted. A deleted requirement remains in the project. The prior version of the requirement, if any, receives a status of "current."
derivation	The analysis process in which an object is changed or translated into a form suitable for lower-level analysis and design.
derived object	A lower-level object that is necessary for the implementation of a higher-level object. When an object changes form, it becomes a derived object. In general, a derived object is directed toward some sub-element and is more specific than the original object.
Dimensions RM	A suite of multi-user, configurable tools that support the capture, management, traceability and documentation of systems engineering information.

Dimensions RM project administrator	The person responsible for maintaining the data that is accessible to a particular project. This includes using the Class Definition tool to implement the information model and, in some cases, the Database Management Utility to manage project information.
Dimensions RM third-party integrator	Person responsible for using the API functions to integrate third-party tools with Dimensions RM.
doc_out	A command line tool that lets you run a reporting script and generate the output to a variety of formats.
Doctool	A Dimensions RM tool that interprets a documentation script and generates an on-screen report.
document	In the Documents View perspective in RM Browser, a hierarchical arrangement of chapters and requirements that can be edited. You can create a document from within Documents View or open one that was imported by the RM Import tool. From Documents View, you can publish a document as a Microsoft Word document or Adobe PDF document.
Documents View	An RM Browser view that provides a document-like presentation of requirements, with a table of contents, chapters, and subchapters. Requirements are contained within the chapters and subchapters. Document View allows you to easily add, delete, move, and edit chapters and requirements. Microsoft Word documents that you imported through RM Import are displayed in Document View. You can easily add, delete, move, and edit chapters and requirements from the imported Word document in Document View. See also Requirements View , My Work View , Traceability View .
ECP	Engineering Change Proposal. A class type. As you create a set of related proposed requirements, you can link them to an ECP object so that they are easily accessible for review as a group.
e-mail notification	A feature that lets you register interest in certain types of changes within the project data and to receive electronic notices of those changes.
evaluated attribute	An attribute that takes its value from the external environment. Such an attribute can be specified as the default value for alphanumeric, numeric or date attributes. At run time, the specified script or command is executed and the resulting value is set for the attribute.
expanding	A process in which a single parent object is edited to produce one or more child objects.
export utility	A utility that can be used to back up a project or database. The package can be created as a collection of files in a single directory or as a single file, ready for transfer to the destination site.
file attachment attribute	A user-defined attribute type that holds a single file that can be accessed through RM Browser

filter	A query against a single class. Form filters are the simplest kind of filter, but they are limited in terms of the complexity of the selection criteria. Complex filters provide greater expressive power for the selection criteria. With complex filters, you can construct detailed logical expressions that use attribute values, ranges of attribute values, and membership in relationships as selection criteria. Contrast with <i>script</i> .
flowdown	A systematic process in which objects are decomposed into allocated and derived objects, and then assigned to low-level model components. This flowdown process generates a hierarchical structure of refined objects derived from the objects captured for the system.
focusing	A process in which two or more parent objects are edited to produce a single child object.
form	A structure that displays requirement information for classes and relationships. A form is created for each class and relationship. You can create new forms by customizing the form that Dimensions RM generates, and can designate any form to be used as the default form.
form view	A view that displays requirements one at a time. From the form view you can edit requirement attributes.
genealogical links	Links between parent objects and child objects, or between parent collections and child collections.
generic links	Links that must span a relationship.
grid view	A view that lets you view multiple requirements in a table-like list. The column headings represent attributes of the requirements.
group	A collection of individual users grouped into a functional category. Access rights can be assigned to a group and all members of the group. If users have been assigned to a project through a group, they inherit the group access rights, unless they have been explicitly granted or denied access.
group attribute	A group attribute is like a list attribute in that it provides a predefined list of values for user selection. But unlike a simple list attribute, a group attribute is composed of a series of sub attributes. The choices available to the user depend upon the selections they made in the higher level, or parent, attributes within the group attribute.
My Work View	An RM Browser view that you can customize to include up to seven expandable sections. Each section contains the results of a query. RM My Work allows you to quickly view and modify requirements that you refer to on a regular basis. See also <i>Documents View</i> , <i>Requirements View</i> , <i>Traceability View</i> .
immediate child	The object that was created when the original object was replaced, focused, or expanded. Immediate children are the next version of objects in the line of descent and may be current objects or objects with another status.
immediate parent	The object that was used to create the currently selected object. Parent objects never have a status of "current."
immediate relationship	A relationship that refers to the immediate predecessor or successor of an object. Contrast with <i>source relationship</i> .

implicit attribute	An attribute that is used to maintain the integrity of project information. Implicit attributes include intrinsic information such as the project unique identifiers (PUIDs), object IDs, and modification times. You cannot modify implicit attributes. Implicit attributes are supplied for each class and relationship. Contrast with <i>user-defined attribute</i> .
import utility	A utility that can be used to restore a project or database from backup.
lifecycle	The phases of a project from its initial requirements specification through its implementation.
link	An instance of a relationship. You can link two requirements together if a relationship between their corresponding classes is defined.
list attribute	A user-defined attribute type that provides a list of values from which the Dimensions RM user can make a selection. For example, if you require the Dimensions RM user to choose one of a given set of values for the attribute <i>test_result</i> , specify the attribute as a list attribute, and define <i>pass</i> , <i>fail</i> , and <i>untested</i> as the set of allowed values. See also <i>group attribute</i> , which functions like an interdependent group of list attributes.
lock manager	A Dimensions RM tool used to lock and unlock Dimensions RM database elements such as source documents, tools, objects, and collections.
lowest level child	A current object that is descended from the selected object. The objects contained in the lowest-level children list may skip generations of an object; that is, they need not be immediate children of the selected object.
mandatory attribute	An attribute for which users must specify values. Contrast with <i>optional attribute</i> .
NOT_PRIMARY_IN	A relationship operator that is used to identify requirements that can be at the origin of a link, but do not.
NOT_SECONDARY_IN	A relationship operator that is used to identify requirements that can be at the termination of a link, but do not.
numeric attribute	A user-defined attribute type that holds numeric values, such as reference numbers. The numbers can include decimal points.
numeric sort	A method of sorting that is used for alphanumeric attributes such as paragraph numbers in outlines. For example, with a numeric sort, the numbers (10, 20, 1, and 2) are sorted as (1, 2, 10, 20) instead of (1, 10, 2, 20). Contrast with <i>alphabetic sort</i> .
object	Synonymous with <i>requirement</i> .
Object Editor	A Dimensions RM dialog used to modify attributes and edit, focus, and expand class information.
OLE	Object Linking and Embedding. A technology for transferring and sharing information among applications.
optional attribute	An attribute for which you can use the default values or leave blank. Contrast with <i>mandatory attribute</i> .

ORACLE_HOME	The logical pathname of the file system or network location of your Oracle installation.
parent collection	A collection that links child collections. Parent collections cannot be linked directly to an object.
parent object	An original object that produces a new object when the original object is edited. The original object is called the immediate parent object, and the new object is its immediate child object. If this process is repeated, a child object can itself be a parent object of another child object. In this way, the original parent object can spawn multiple levels of descendants, including both immediate child objects and lowest-level child objects. One or more parent objects can produce one or more child objects.
pending change request	A change request that has not yet been accepted or rejected. A pending change request has a Current Status of "proposed."
polling	A feature of RM Browser that lets you solicit feedback about a requirement from selected users. Polls are typically used to decide whether a specific requirement should be accepted, or to reach consensus concerning the content of a requirement.
primary class	The first class in a direct relationship between two classes. For example, in the relationship <i>Is_Tested_By</i> that connects class <i>Code_Module</i> and class <i>Acceptance_Tests</i> , <i>Code_Module</i> is the primary class, <i>Is_Tested_By</i> is the relationship, and <i>Acceptance_Tests</i> is the secondary class. The direction of the relationship arrow is always from the primary to the secondary class in the class definition diagram. This direction and positioning on the diagram defines the direction of the relationship. Contrast with <i>secondary class</i> .
PRIMARY_IN	A relationship operator that is used to identify requirements that are at the origin of a link.
primary object	An instance of a primary class to which objects are linked.
project	A Dimensions RM work area where information is created and maintained.
proposed	Current Status of a requirement for which a change request has been made to either change the current requirement or create a new requirement.
pseudonym	Text pattern used to locate objects to be linked to a collection. For example, pseudonyms of the keyword "calibrate" might be "calibrated," "calibrating," or even the wildcarded string "cal*". Unlike aliases, which exist for the duration of the project or until they are deleted, pseudonyms exist only during the linking process. See also <i>alias</i> .
PUID	Project Unique Identifier. An intrinsic attribute.
query	A filter or script, expressed in terms of the project schema, that you use to retrieve selected requirements.
Quick Search	A feature of the Requirements View in RM Browser that lets you quickly create a query to see the content of any category.
Reject	A command that rejects a proposed change. The Current Status of the proposed requirement becomes "rejected," and a copy of the requirement is created with the Current Status of "current."

rejected	Current Status of a change request that has been rejected.
relationship	An association between two classes. It is also an entity in its own right, in terms of having its own attributes and associated user access rights. See also link .
relationship attribute	A property of a relationship, such as its cardinality and its inheritance characteristics. Relationship attributes, defined by the Project Administrator, can control how traceability is established across different relationships. Project Administrators can specify that links be created between two objects according to the value of one or more of the class attributes. For example, it can be specified that links can be created from a change request object to a requirement object only if the value of the change request object's attribute APPROVAL_STATUS is APPROVED. See also cardinality rule .
relationship rule	Circumstances under which links between objects will be permitted. See also cardinality rule .
Remove	A command that physically removes a requirement from a project. Only requirements with a status of "current" can be removed.
Replace	A command that creates a new version of a requirement with the changes you made. The Current Status of the original requirement is changed from current to replaced, a parent-child link is created from the original requirement to the new requirement, and the current status of the new requirement is set to current.
replaced	Current Status of a requirement that has been replaced by a newer version.
resource category	A grouping of resources into a class of items. For example, a unique document name falls into the category of Documents. Resource categories are important when assigning default permissions because defaults are assigned to entire class of resources rather than an individual resource. Resource categories are also important when assigning appropriate transaction for a class of resources. Certain transactions are appropriate only for certain categories of resources.
requirement	An instance of a class. A description of a set of conditions applicable to a product or process; this description must be capable of being validated for success. A requirement object is satisfied by a product or process if a test reveals that the described conditions are met by the product or process. Synonymous with object.
Requirements View	An RM Browser view that lets you view and modify requirements that are organized by category. From this view, you can run an existing filter, run an existing script, run a quick search to create a new query, and add queries that you access frequently to a favorites folder. See also Documents View , My Work View , Traceability View .
RM Browser	A Dimensions RM tool that provides Web access to a core set of Dimensions RM functions.
RM Import	A Dimensions RM tool that lets you preview a Microsoft Word document as a draft document, change the description of chapters, reorganize the chapters, change the values of attributes, move attributes between chapters, and so on. When satisfied with the draft document, you can import the document into Dimensions RM as a document that can be viewed and modified in the Document View of RM Browser.
RM Import Designer	A Dimensions RM tool that lets administrators design templates that users select when importing Word documents from RM Import. Templates define how to identify classes, attributes, chapters, requirements, and categories.

RM Manage	A Dimensions RM tool that lets project administrators define users and groups, administer project security, configure the project database, organize data, and control user access and data routing.
RTM_HOME	A logical name for the file system location of Dimensions RM programs and data.
schema diagram	See <i>class definition diagram</i> .
script	A query against one or more classes. Scripts are the most comprehensive way to perform searches. They can be used to combine the selection criteria capabilities provided by complex filters, with complex link traversal, parameterization, basic calculations, and output formats. Contrast with <i>filter</i> .
script generator wizard	A Dimensions RM wizard that provides a graphical interface allowing the user to specify the contents of a given report.
secondary class	An object class that is the destination of the relationship arrow from a primary class in a class definition diagram. The relationship arrow points to the secondary class. Contrast with <i>primary class</i> .
SECONDARY_IN	A relationship operator that is used to identify requirements that are at the termination of a link.
snapshot	In the Document View of RM Browser, a read-only baseline of a document.
source document	A document, typically provided by the customer, which is input to the system being developed. A source document can also be written in Dimensions RM by using an empty document and inserting objects.
source relationship	A relationship that refers to the original object in a chain of versions. Contrast with <i>immediate relationship</i> .
suspect link	A link that becomes questionable after one of the requirements in the link changes. The change could render other requirements questionable, or "suspect."
tablespace	A logical storage unit. Your project data is physically stored in one or more data files associated with a tablespace. Initially, only one file is associated with the tablespace, but you can add more files as you need them. The size of a tablespace is determined by the size of the data file or combined data files that make up the tablespace.
template	A set of rules defined by an administrator in RM Import Designer that determines how a document will be imported into Dimensions RM using the RM Import tool.
text attribute	A user-defined attribute type that holds up to 64 KB of alphanumeric, ASCII text that can span more than one line. It is suitable for long descriptions, such as the description of an acceptance test.
transactions	Actions associated with a category of resources that represent what can be done with that resource. For example, an update transaction is associated with a class definition. A user that has the update transaction for a particular class definition can change characteristics of that class definition and store them in the database.
traceability	The process of making explicit links between requirements and other entities. Traceability lets you trace the evolution of a project.

Traceability View	An RM Browser view that provides a way to select the relationships you want to trace, with requirements limited to selected baselines, documents, collections, or categories; browse through the requirements that are part of the relationships; and then print traceability reports that display the information in a visual format that is easy to analyze. See also Documents View , My Work View , Requirements View
type	A definition of the basic properties of a set of instances of a class, relationship, or attribute.
Undelete	A command that changes a the Current Status of a requirement from "deleted" to "current."
Update	A command that overwrites the content of the requirement. No history of the change is maintained. This is only recommended if previous versions of a requirement must be deleted. All other attributes, including Current Status, remain intact.
user	An individual responsible for performing basic information management tasks, such as capturing objects, including generic and CASE tool data in the Dimensions RM database, creating traceability links among requirements and other data, engineering and categorizing objects, and producing reports. An individual Dimensions RM user.
user attribute	A user-defined attribute type that provides a list of user names from which the Dimensions RM user can make a selection. A user attribute can contain all users, members of one or several groups or individual users.
user-defined attribute	An attribute that you can create for use in a specific class. See also alphanumeric attribute , date attribute , file attachment attribute , group attribute , list attribute , numeric attribute , text attribute , user attribute . Contrast with implicit attribute .

Index

- A**
- Actions pane 18
 - Agile 217
 - display options 222
 - features
 - add 230
 - delete 230
 - edit 230
 - Overview tab 222
 - Product Backlog tab 223
 - Product Storyboard tab 225
 - products
 - add 227
 - delete 228
 - edit 227
 - releases
 - add 228
 - delete 229
 - edit 228
 - Sprint Planning tab 225
 - Sprint Storyboard tab 226
 - sprints
 - add 232
 - delete 232
 - edit 232
 - stories
 - add 231
 - delete 231
 - edit 231
 - alphabetic sort 25
 - assigning a user to groups 236
 - assigning users to groups 237
 - attachments 146
 - attributes
 - copying 86
 - group 73
 - attributes, formatting text with HTML 26
 - attributes, group 118
 - auditability 80
 - Auto load document check box 54
 - autoloading documents, setting 54
- B**
- Baseline Lock 267
 - Baseline Locked 192
 - baselines
 - importing from DOORS 211
 - baselining 192
 - bread crumb 16
 - browse links 115
- C**
- categories
 - access rights 239
 - adding 238
 - deleting 238
 - managing 238
 - maximum name length 238
 - moving 239
 - renaming 238
 - categories in RM Browser 29
 - Categories pane 17
 - categories, moving requirements between 241
 - change requests
 - proposing a new requirement 87
 - requesting a new requirement 87
 - reviewing 93
 - submitting 87, 92
 - Chapter Layout
 - Editable Grid 132
 - Grid 131
 - Paragraph 131
 - chapters
 - creating 151
 - deleting 154
 - editing 153
 - formatting 136
 - moving 154
 - class report, create 170
 - collection 103
 - collections
 - baselining 192
 - creating 191
 - deleting 186
 - comments
 - adding 125
 - replying to 125
 - reviewing 125
 - comparing a document and its snapshot 144
 - concurrent editing mode 50
 - contacting technical support 11
 - container 103, 104
 - inherited 105
-

- container properties 105
- container URL, copying to clipboard 188
- copying container URL to clipboard 188
- copying document URL to clipboard 165
- copying report URL to clipboard 182
- copying requirement URL to clipboard 84
- copying requirements 86, 89, 90
- copying URL
 - of container 188
 - of document 165
 - of report 182
 - of requirement 84
- copying users 234
- creating a new document 137
- creating users 234

D

- dashboard
 - add graphical report 64
 - add standard report 64
 - add website 65
 - copy 66
 - create 62
 - delete 66
 - rename 66
 - runtime parameter 65
 - using reports 62
- default requirement layout 55
- deleting requirements 80, 90
- deleting users 236
- demonstration projects 42
- dependent attributes 118
- discussions 125
- distribution report, create 178
- document settings 54
- document URL, copying to clipboard 165
- Documents
 - Create snapshot 142
- documents
 - adding a requirement 155
 - comparing 144
 - creating 137
 - creating a chapter 151
 - creating PDF 148
 - creating Word 146
 - default requirement layout 55
 - deleting 141
 - deleting a chapter 154
 - deleting a requirement 142
 - document differences report 145
 - document properties 149
 - editing 140
 - editing a chapter 153
 - editing a document 140

- finding and replacing character strings 157
- limited permissions 159
- moving chapters 154
- moving requirements 154
- opening 139
- preventing title numbers from being published 54
- printing 133
- publishing Adobe PDF documents 148
- publishing Microsoft Word documents 146
- requirement difference summary 144
- requirement versions 97
- restricting requirement classes 151
- setting autoloading of 54
- viewing attachments 146

documents, formatting 133

DOORS 208, 211

E

- Editable Grid view 20
- editing mode 50
- editing users 235
- expanding requirements 90
- export
 - CSV 76
 - Test Case 77
 - Test Run 77
 - Excel 76
 - HTML 76
 - PDF 76
 - Test Case 77
 - Test Run 77
 - Text 76
 - Word 76
 - XML 76

F

- find and replace, Document work page 157
- finding requirements 72
- focusing objects 46
- Form view 20
- formatting chapters 136
- formatting documents 133
- formatting text attributes with HTML 26

G

- general settings 50
- graphical report, create 177
- Grid view 20, 22
- group assignment 236, 237

group attributes 30, 73, 118

H

Help 41
 history, requirement 94
 HTML formatting toolbar 26

I

Import 195
 CSV 202
 Test Case 203, 207
 Test Run 203, 207
 DOORS 208, 211
 previously exported requirements 211
 ReqIF 208
 Round Trip 211
 Test Case 203, 207
 Test Run 203, 207
 Word 196, 199
 XML 200
 inherited containers 105
 inherited links 114

L

limitations of RM Browser 46
 Link Browser 115
 Link Browser settings 56
 links
 inherited 114
 suspect 112
 lock, baseline 267

M

menu bar 16
 merging requirement changes 100
 moving requirements between categories 241
 My Work page
 customizing 57
 using 57

N

navigation 15
 numbering, preventing from being published 54
 numeric sort 25

O

objects focusing 46
 operators in RM Browser 30

P

padlock icon 192
 passwords, changing 40
 passwords, demonstration projects 42
 Pedigree View 98
 polls
 built-in queries 125
 closing 123
 creating 121
 modifying 123
 overview 121
 viewing results 124
 voting 124
 printing 91, 133
 project bread crumb 16
 project settings 50
 projects
 demonstration 42
 proposed requirements
 reviewing 93
 Publish
 As PDF document 148
 As Word document 146

Q

QLARIUS_RM project 42
 Quick Search 72
 Quick Search settings 53

R

refreshing
 data 76
 Relationship Constraints tab 31
 relationship report, create 172
 removing requirements 80, 91
 replacing requirements 80
 report
 create class report 170
 create distribution report 178
 create graphical report 177
 create relationship report 172
 create traceability report 173
 create trend report 179
 edit 168
 run 168

- report settings 55
- report URL, copying to clipboard 182
- ReqIF 208
- requirement URL, copying to clipboard 84
- requirements
 - add to container 104
 - collection 103
 - container 103
 - copying 86, 89, 90
 - creating 87
 - deleting 80, 90, 142
 - editing 88
 - expanding 90
 - exporting Quick Search results 76
 - finding 72
 - history 94, 97
 - history, Pedigree View 98
 - importing from DOORS 208
 - importing from ReqIF files 208
 - importing from XML files 200
 - inherited containers 105
 - inherited links 114
 - merging changes 100
 - moving between categories 241
 - moving in documents 154
 - multiple selection 23
 - open container 104
 - printing 91
 - Quick Search 72
 - remove from container 104
 - removing 80, 91
 - replacing 80
 - restricting classes in documents 151
 - selecting multiple 23
 - undeleting 80, 91
 - updating 80
 - versions 81, 97
 - workflow elements 82
- restricting requirement classes in documents 151
- RM Browser 31
 - Attribute Constraints tab 28
 - basics 14
 - categories used in queries 29
 - changing your password 40
 - creating a new object 85
 - deleting requirements 90
 - editing requirements 88
 - getting Help 41
 - limitations 46
 - logging in 38
 - logging out 40
 - My Work page 57
 - operators used in queries 30
 - organizing collections 189
 - overview 37
 - participating in discussions 125

- polling 121
- refreshing data 76
- removing requirements 91
- reviewing change requests 93
- submitting change requests 92
- switching to another project 39
- Traceability View 175
- undeleting requirements 91
- viewing contact information 42
- viewing system information 42
- viewing version information 42
- RM Browser interface 14
- RM Browser, navigating 15
- RMDEMO project 42

S

- selection
 - multiple requirements 23
- settings
 - document 54
 - general 50
 - Link Browser 56
 - project settings 50
 - Quick Search 53
 - report 55
 - Split View 56
 - user attribute 52
 - user settings 50
- Snapshot
 - Create from document 142
 - Delete 143
 - Modify 143
 - Save as new document 143
 - View 143
- spell check
 - Chrome 45
 - Firefox 44
 - Internet Explorer 44
- Split View settings 56
- SQL 248
- suspect links 112

T

- technical support
 - contacting 11
- Test Case
 - CSV export 77
 - CSV import 203, 207
- Test Case Management
 - test case 214
 - test run 214
 - test steps 215

- Test Run
 - CSV export 77
 - CSV import 203, 207
- text attributes, formatting 26
- Traceability
 - customizing the tree 177
 - overview 175
 - understanding the traceability tree 176
- traceability report, create 173
- trend report 80
- trend report, create 179

U

- un-assigning a user from groups 236
- un-assigning users from groups 237
- undeleting requirements 80, 91
- updating requirements 80
- URL
 - container, copying to clipboard 188
 - document, copying to clipboard 165
 - report, copying to clipboard 182
 - requirement, copying to clipboard 84
- user management 234
 - copying users 234
 - creating users 234
 - deleting users 236
 - editing users 235
 - group assignment 236, 237
- user settings 50

V

- views
 - Editable Grid 20
 - Form 20
 - Grid 20
- voting in a poll 124

W

- Welcome menu 15
- workflow
 - elements 82

X

- XML files, importing 200

