



# Host Access for the Cloud Documentation

October 2020

© Copyright 2020 Micro Focus or one of its affiliates.

The only warranties for products and services of Micro Focus and its affiliates and licensors (“Micro Focus”) are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Micro Focus shall not be liable for technical or editorial errors or omissions contained herein. The information contained herein is subject to change without notice.

Contains Confidential Information. Except as specifically indicated otherwise, a valid license is required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

For information about legal notices, trademarks, disclaimers, warranties, export and other use restrictions, U.S. Government rights, patent policy, and FIPS compliance, see <https://www.microfocus.com/about/legal/>

---

# Contents

<b>About Host Access for the Cloud</b>	<b>7</b>
<b>1 Release Notes</b>	<b>9</b>
What's New	9
Changes in Behavior and Usage	10
Known Issues	10
Contacting Micro Focus	10
Legal Notice	10
<b>2 Getting Started</b>	<b>13</b>
How it works	13
Components	14
Browser and operating system support	14
Security considerations	14
Getting Host Access for the Cloud	15
Evaluation system requirements	15
Basic install	15
Walk through	16
Steps you will follow	16
Provide end users access to sessions	21
<b>3 Deploying</b>	<b>23</b>
About MSS	23
System Requirements	23
Planning for Deployment	24
About Authentication	25
Scaling and High Availability	25
Deployment Options	27
Using Load Balancers	27
Terminal ID Manager	28
High Availability Deployment Blueprint	28
Architecture	28
Installing and Upgrading	33
Installing on different platforms	33
Using an unattended installation	34
Configuring an incomplete installation	35
Upgrading from previous versions	35
Troubleshooting the Installation	36
Ports	37
Configuring your Deployment	37
How to Set Up the Terminal ID Manager	38
How to Set Up Metering	38
How to Set Up Automated Single Sign-On for Mainframe	39
How to Configure X.509 Authentication	40

How to Configure Single Sign-on through IIS. . . . .	42
How to use the IIS Reverse Proxy with Host Access for the Cloud. . . . .	43
Securing connections . . . . .	43
Overview . . . . .	44
Your default secure installation . . . . .	44
Tools . . . . .	45
How do I...? . . . . .	45
Using Docker . . . . .	54
Why Docker? . . . . .	54
What are the benefits? . . . . .	54
Terminology . . . . .	55
Getting Started with Docker and Host Access for the Cloud . . . . .	55
Examples. . . . .	58

## **4 Managing 63**

Connecting to the Host. . . . .	63
Common connection settings . . . . .	64
3270 and 5250 connection settings . . . . .	65
How to test Terminal ID Manager criteria . . . . .	68
VT connection settings . . . . .	68
UTS connection settings . . . . .	70
T27 connection settings . . . . .	71
ALC connection settings . . . . .	72
Providing Access to Sessions . . . . .	73
Single session mode . . . . .	73
Logging. . . . .	74
Locating log files . . . . .	74
Configuring log rotation . . . . .	74
Setting logging levels. . . . .	74
Web client to session server logging . . . . .	75

## **5 Using HACloud 77**

Display Settings . . . . .	77
Color mapping . . . . .	77
Configure hotspots . . . . .	79
Configure screen dimensions for VT, UTS and T27 hosts . . . . .	79
Set cursor options . . . . .	80
Set font options . . . . .	80
Set VT scrollbar buffer options. . . . .	81
Set keyboard options. . . . .	82
Terminal Settings . . . . .	83
Set other display options . . . . .	84
Map Keys . . . . .	85
Host Keyboard Mapping . . . . .	87
Configure User Macros . . . . .	99
Transfer Files . . . . .	99
IND\$FILE . . . . .	100
AS/400 . . . . .	104
FTP . . . . .	107
Batch transfers . . . . .	109
Specify Copy and Paste Options. . . . .	111
Working with Sessions . . . . .	112

Using Quick Keys . . . . .	113
Copying and Pasting . . . . .	113
Logging Out . . . . .	113
Creating Macros . . . . .	114
Working with macros . . . . .	114
Debugging macros . . . . .	116
Using the Macro API . . . . .	118
Printing. . . . .	162
Capture a screen . . . . .	162
Print a screen . . . . .	163
Host printing . . . . .	163
Customize Sessions . . . . .	167
Use Plus to customize screens . . . . .	168
Use server side events. . . . .	169
Set User Preferences. . . . .	169
<b>6 Developing</b>	<b>171</b>
Using the Java SDK . . . . .	171
Examples and documentation . . . . .	172
Using the Connector for Windows. . . . .	172
Examples and connector documentation . . . . .	173
Using the connector with Microsoft Visual Studio . . . . .	173
Using the JavaScript API . . . . .	173
Extending the Web Client. . . . .	174
Adding an extension . . . . .	174
Extension sample. . . . .	175
<b>7 Technical References</b>	<b>177</b>
Monitoring Session Servers using Prometheus and Grafana. . . . .	177
Modifying the Size Limit on Upload File Transfer Operations . . . . .	180
Copying Sessions between Management and Security Servers . . . . .	180
How to Change Ports . . . . .	181
How to Start and Stop Services Automatically . . . . .	182
Allowing Session Server Access via HTTP . . . . .	183
Connecting to MSS using HTTP . . . . .	184
Adjusting the URL Path for the Session Server . . . . .	184
Configuring User Names when Using Anonymous Access Control . . . . .	185
Configuration options . . . . .	185
Troubleshooting the configuration. . . . .	186
Accessing Host Access for the Cloud using the IIS Reverse Proxy . . . . .	186
Configure the IIS Reverse Proxy for Host Access for the Cloud . . . . .	186
Improving Connection Times on Non-Windows Platforms . . . . .	189
Advanced Settings. . . . .	189
How to Adjust HTTP Session Timeout . . . . .	189
How to enable FIPS level security. . . . .	190
Known Issues. . . . .	190
Browser issues . . . . .	190
Host specific issues . . . . .	193
Installation issues. . . . .	193
MSS Administrative Console Reference . . . . .	195



# About Host Access for the Cloud

The Host Access for the Cloud web client provides browser-based HTML5 access to 3270, 5250, VT, UTS, ALC, and T27 host applications. The Host Access for the Cloud product eliminates the need to touch the desktop; no software to deploy, patches to apply, or configurations to make. You can provide platform-independent user access to all your host applications.

The web client operates with complete session protection using SSL/TLS to secure communication with your mainframe systems.







# 1 Release Notes

The Host Access for the Cloud version 2.5.2 released October 2020. These release notes list the features and known issues in this release and information on how to obtain the product. Host Access for the Cloud provides terminal emulation for 3270, 5250, VT, ALC, UTS, and T27 host types, while requiring only an HTML 5-capable browser.

## Management and Security Server

[Host Access for the Cloud 2.5.2 released with Management and Security Server version 12.6 SP1 Update 2.](#)

---

**NOTE:** The End User License Agreement (EULA) is available in English, Spanish, French, Italian and German in the `<install location>\licenses` directory.

---

## What's New

All releases are cumulative and this release of Host Access for the Cloud contains everything released in all prior versions of Host Access for the Cloud and Reflection ZFE.

Features and fixes include:

- This version of Host Access for the Cloud benefits from improvements made to Management and Security Server 12.6 SP1 Update 2. (2.5.2)

See [MSS Release Notes](#) for more information.

Improvements include:

- ◆ Improvements to the Assigned Sessions list.
- ◆ Support for additional authentication modes when accessing the MSS Administrative Console.
- Users of Host Access for the Cloud, Reflection Desktop, and InfoConnect Desktop can now launch all their sessions from a new consolidated HTML-based portal (No Java required). See [MSS Release Notes](#) for more information. (2.5.1)
- With this release, Host Access for the Cloud now contains updated styling. (2.5)
- Printing capabilities have been added for both UTS and AS/400 host types. See [Printing](#) for information. (2.5)
- AS/400 file transfer has been added to this release. You can now transfer data between your computer and an iSeries 5250 host. See the [Transfer Files](#) documentation. (2.5)
- The ability to **Restore Defaults** is now available to administrators and end users. This option makes it easier to return settings and display options to their original state. See [Set User Preferences](#). (2.5)
- Multiple bug fixes and security updates.

## Changes in Behavior and Usage

These changes may affect your existing installation of Host Access for the Cloud.

- ♦ The SAML callback URL format has been adjusted to improve compatibility with SAML providers going forward. See [MSS Release Notes](#) for more information. (2.5.2)
- ♦ As of Chrome version 80, accessing HACloud using the JavaScript SDK is now limited to HTTPS. This is due to new security constraints related to third party cookies (Samesite) put in place by the Chrome browser team. Also as a result, using Chrome version 80 or greater no longer works for accessing HACloud using the JavaScript Connector before version 2.4.3 (via HTTPS or HTTP).

## Known Issues

[Micro Focus Technical Support](#) is always available to help you with any issues you may encounter in Host Access for the Cloud.

- ♦ After a session is launched from the Assigned Sessions list, to successfully logout, the user must log out of both the HACloud web client and the Assigned Sessions list. If a user just logs out of one or the other, the user's session will only be partially logged out and the session will remain in that state until an inactivity timeout is triggered and the user is completely logged out by the system.

Unresolved issues from previous releases are listed in [Technical References](#) under [Known Issues](#).

## Contacting Micro Focus

For specific product issues, contact [Micro Focus Support \(https://www.microfocus.com/support-and-services/\)](https://www.microfocus.com/support-and-services/).

Additional technical information or advice is available from several sources:

- ♦ Product documentation, Knowledge Base articles and videos - see [Support for Host Access for the Cloud](#).
- ♦ The Micro Focus Community pages – see [Micro Focus Communities](#).

## Legal Notice

For information about legal notices, trademarks, disclaimers, warranties, export and other use restrictions, U.S. Government rights, patent policy, and FIPS compliance, see <https://www.microfocus.com/about/legal/>.

© Copyright 2020 Micro Focus or one of its affiliates.

The only warranties for this product and any associated updates or services are those that may be described in express warranty statements accompanying the product or in an applicable license agreement you have entered into. Nothing in this document should be construed as creating any warranty for a product, updates, or services. The information contained in this document is subject to change without notice and is provided “AS IS” without any express or implied warranties or

conditions. Micro Focus shall not be liable for any technical or other errors or omissions in this document. Please see the product's applicable end user license agreement for details regarding the license terms and conditions, warranties, and limitations of liability.

Any links to third-party websites take you outside Micro Focus websites, and Micro Focus has no control over and is not responsible for information on third party sites.




# 2 Getting Started

Host Access for the Cloud provides zero-footprint terminal emulation that delivers browser-based HTML5 access to 3270, 5250, VT, UTS, ALC and T27 host applications without the need to touch the desktop or install and manage Java runtime environments. A centralized administrative location reduces IT costs and desktop management time while efficiently providing and delivering host access to end users. Communication is protected using HTTPS, SSL/TLS, and SSH security.

### Next steps

- ✓ [How it works](#)
- ✓ [Getting Host Access for the Cloud](#)
- ✓ [Walk-through Host Access for the Cloud](#)


## How it works



## Components

Familiarize yourself with the three components:

- ◆ **Host Access Management and Security Server**

The Host Access Management and Security Server (MSS) provides an Administrative Console, a web-based centralized location where you can add, edit, and delete terminal sessions. MSS is part of the broader Micro Focus story and is compatible with other Micro Focus products. This icon  which you will see throughout the documentation indicates where additional configuration in the MSS Administrative Console is required.

- ◆ **Session Server**

The session server is an NT service or UNIX daemon that provides the engine that runs host sessions. Multiple session servers can serve up tens of thousands of sessions and provide efficient and rapid access to your host data.

- ◆ **Web Client**

The web client is the web-based terminal emulator where your users can easily access authorized sessions from any platform and from any location.

The Web client provides macros, keyboard and color mapping, on-screen keyboard, copy/paste functionality, host-initiated screen updates, and file transfer capabilities.

## Administrator and end user roles

Both administrator and end user roles are represented in the documentation and work flow. The administrator creates sessions, assigns users to those sessions, and sets user preferences. The end user accesses his assigned sessions, interacts with the web client to connect to the host, and accomplishes his tasks.

## Browser and operating system support

Host Access for the Cloud is a 64-bit based product and supports Google Chrome, Mozilla Firefox, and Microsoft Internet Explorer and Edge browsers. The use of Docker containers makes vertical and horizontal scaling possible and supports cloud-based technologies. A complete list of supported platforms and other installation requirements is available in [Evaluation system requirements](#).

## Security considerations

When you open up your legacy hosts to users outside the corporate firewall - business partners, remote users, mobile sales personnel, and others - you need to shield your information from known security threats. With Host Access for the Cloud, you can provide secure web-to-host access to all your users, whether they're around the corner or around the world. Host Access for the Cloud, along with the MSS, provides HTTPS connections and a variety of authorization and authentication options.

Host Access for the Cloud supports the TLS and SSH protocols to protect mission-critical data. To secure your passwords and other sensitive data, use the HTTPS protocol, which provides TLS encryption.

Host Access for the Cloud can be connected securely to the browser, the host, and the management server. See [Securing connections](#) for information on securing those connections.

## Getting Host Access for the Cloud

### Evaluation system requirements

To successfully install and evaluate Host Access for the Cloud your system needs:

- ◆ 8 GB of memory
- ◆ A supported browser and operating system.

See [System Requirements](#) for a comprehensive list of supported environments.

### Downloading the evaluation software

If you don't have our software yet, visit our site and fill out an evaluation request form. You'll be sent an e-mail message with instructions to download and install an evaluation copy of Host Access for the Cloud good for 120 days. Using this evaluation copy you can open and close host sessions and maintain 5 active host connections at a time. The trial site has all the information you need to take the next step.

The Micro Focus download site contains the compressed files necessary to install all supported platforms, including the Windows connector. Different activation files will enable different editions/platforms of Host Access for the Cloud.

### Basic install

The following instructions provide you with the basic default installation. This means that all components are installed locally and are using default ports. With this installation in place you can follow the [walk through](#) and familiarize yourself with Host Access for the Cloud and MSS.

1. From the Micro Focus download site, download your product install package. The package includes support for all supported platforms.
2. Following the install program prompts, install Host Access for the Cloud and Management and Security Server (MSS).

MSS uses activation files (activation.jaw) to enable product functionality. The install program contains the needed activation file and it is activated as part of the install process.

---

**NOTE:** During a basic install a self-signed certificate is used to ensure secure connections. When you move into a production environment you can provide your own certificates.

---

Now you can take the next step; walking through Host Access for the Cloud.

# Walk through

The following instructions are based on a basic default installation. This means that all components are installed locally and are using default ports. With this installation in place you can follow the steps and familiarize yourself with Host Access for the Cloud and MSS.

See [Deploying](#) for information about installing into production environments and different production scenarios.

## Steps you will follow

- ✓ Open the MSS Administrative Console.
- ✓ Create and launch a new session. This opens a new browser window and the web client **Connection** panel displays.
- ✓ Configure settings, including key and color mapping, enabling hotspots and macros, and other connection and user preference options.
- ✓ Assign users to sessions.
- ✓ Provide access to sessions.

## Open the Administrative Console

1. In a Windows environment, from the Start menu, under Micro Focus Host Access for the Cloud, click Administrative Console or open the URL for the administrator login page in your web browser. The URL uses this format: `https://myserver.mycompany.com:443/adminconsole`.
2. If you connect using HTTPS and your server has a self-signed certificate, your browser will warn you about the certificate you created. This is expected behavior; you can accept the self-signed certificate or choose to proceed and the administrator login page will open. After you purchase a CA-signed certificate or import the self-signed certificate into your certificate store, these warnings will stop.
3. The administrative account has a built-in password, **admin**. Log on as an administrator using this password or by entering the password that you specified when you installed MSS.

## Create a new session



See [Add a Session](#) in the MSS Administrator Guide for complete instructions.

You can add and update session settings from the Manage Sessions panel of the Administrative Console. When you add a session it becomes available in the session list of this panel.

1. From the Manage Sessions panel, click **ADD** to create a new session.



## Manage Sessions - Add New Session

### Configure Session

Product

Host Access for the Cloud

Session name \*

test

Session Server Address \*

https://release-ldap.zfe-ci.attachmate.com

**CANCEL** **LAUNCH**

2. If it is not already selected, select Host Access for the Cloud, enter a session name, and click **Launch** to open a new browser window and start configuring the session for the server listed at the session server address.
3. On the Create New Session dialog box, select the host type from the drop down list and click Next.

### Create New Session

Name **test2**

Type

Select session type

Select session type

ALC

IBM 3270

IBM 5250

T27


UTS

VT

## Configure settings and connect

You configure different settings and options for the session, as well as connect to the host, in the web client browser window.

1. On the **Connection** panel, for the session you are creating, enter the needed connection information.



The screenshot shows the 'Connection' settings panel in a web client browser window. The panel is titled 'CONNECTION' and has a help icon (?) in the top right corner. On the left side, there is a dark sidebar with a 'Connection' header and several menu items: Display, Key Mappings, Macros, File Transfer, Copy / Paste, Print, Customization, and User Preference Rules. The main area of the panel contains a list of settings, each with a label and a corresponding input field or dropdown menu:

Setting	Value
Host	Hostname
Port	23
Connect at startup	Yes
Reconnect when host terminates connection	No
Protocol	TN3270E
Terminal model	Model 2 - 24x80 Extended
Terminal ID	
TLS/SSL security	None
Send keep alive packets	None
Device name	Specify device name
	Device name

At the bottom right of the panel, there are two buttons: 'Cancel' and 'Save'.

2. Connection settings vary depending on the type of host connection. For detailed descriptions of the setting options for each host type, see the web client help. Setting options include mapping keystrokes to selected keys, mapping host colors to match your preferences, and recording session macros.

### Mapping keys

3. To map keys to selected keys, open **Key Mappings**.
4. Press the key or key combination you want to use to trigger the selected action.

## Key Mappings



Q Send text  Show only modified mappings

▲ Key	Action	Value	
<Press keystrok	<Select action>		
Ctrl + Alt + E	Send text	€	
Ctrl + B	Send text	\u0002	
Ctrl + D	Send text	\u0004	
Ctrl + E	Send text	\u0005	
Ctrl + F	Send text	\u0006	
Ctrl + G	Send text	\u0007	

5. From the **Action** drop down list select the action you want mapped to the selected keystroke. Click to complete the key mapping. You can continue adding and mapping keys.
6. Click **Save** to complete mapping keys.  
**Change host colors and other options**
7. From the left navigation panel, you can map host colors, set font and keyboard options, and enable hotspots by opening the **Display** panel. Color choices are specific to each session.
8. Open **User Preference Rules** to extend configuration options to your end users.
9. Click **Exit** to return to the Administrative Console browser window to authenticate and assign users to sessions.

## Configure authentication and assign users to sessions

Now that sessions are created, you need to grant users access to those sessions. Users are authenticated and assigned to sessions in the MSS Administrative Console. A user can be assigned to multiple sessions.

1. Authentication and authorization validates the identity of a user and the method you want to use to map sessions to individual users or groups of users. From the left navigation panel, select **Configure Authentication**.
2. Choose an authentication method. Your options change depending on your selection.

## Configure Settings - Authentication & Authorization

Choose Authentication Method

Authentication method

None

LDAP

Single sign-on through IIS


Single sign-on through Windows authentication

X.509

SiteMinder (see help to enable)

Micro Focus Advanced Authentication (not activated, see help to enable)

SAML

3. There are descriptions of the various options in the MSS documentation. Click .
4. Click **Apply** to complete the process.
5. Open **Assign Access** to map sessions to individual users or groups of users.

### Assign Access - Search & Assign

Domain:

Sessions  Packages

Search by:

Search Results

Sessions

Filter

dallas

Dallas (live) privileged user

dallas with macros

is-embed-edk-resentation-...-test

Allow access to Administrative Console

Allow user to inherit (\* ) access to sessions

6. Map the sessions to the users you want to access the sessions and click **Apply**. You can also choose to allow users to inherit access to sessions and to the Administrative Console.

 See [Select a method to authenticate users](#) in the MSS Administrators Guide.

## Provide end users access to sessions

The final step is to share a URL to your session server with your users. The URL usually looks something like this:

```
https://myserver.mycompany.com:port
```

When they access the session server, your users will be prompted to log in as needed, and then they will be given access to their assigned sessions.

In more complex deployments the URL you provide will be to a load balancer and not the session server itself. These links are often embedded in corporate portals or other proprietary web sites.

---

### Related Topics

[Providing Access to Sessions](#)

[Deploying](#)

[Managing](#)



# 3 Deploying

This section goes beyond the basic evaluation setup and assumes you are moving into production. See [Getting Host Access for the Cloud](#) for information on a simple installation.

## In this section

- ◆ [About MSS](#)
- ◆ [System Requirements](#)
- ◆ [Planning for Deployment](#)
- ◆ [High Availability Deployment Blueprint](#)
- ◆ [Installing and Upgrading](#)
- ◆ [Ports](#)
- ◆ [Configuring your Deployment](#)
- ◆ [Securing connections](#)
- ◆ [Using Docker](#)

## About MSS

Host Access Management & Security Server (MSS) centrally secures, manages, and monitors your user's access to host connections. Creating sessions, setting up metering, and configuring terminal IDs are all accomplished by working with MSS.

Documentation for MSS:

- ◆ [12.6.SP1 Update 2 Release Notes](#)
- ◆ [Evaluation Guide](#)
- ◆ [Installation Guide](#)
- ◆ [Administrative Guide](#)
- ◆ [Automated Sign-On for Mainframe - Administrator Guide](#)

## System Requirements

These platforms and higher are supported by Host Access for the Cloud versions 2.5 and higher. Requirements do not take into account other applications and resources that may be installed on your system.

## Component

### Web browsers

## Supported

- ◆ Google Chrome v62 (recommended)
- ◆ Mozilla Firefox v57(recommended)
- ◆ Microsoft Edge 41
- ◆ Microsoft Internet Explorer 11 (not recommended)  
See [Browser issues](#) for information on performance issues when using Internet Explorer.
- ◆ Apple iOS Safari 11

### Session server

## Hardware

- ◆ CPU - 2 cores (4 cores is recommended)
- ◆ Free memory - 4 GB (6 GB recommended)

## Operating system (64-bit)

- ◆ Windows 2012 Server
- ◆ SUSE Linux Enterprise Server (SLES) v11 SP4
- ◆ Red Hat Enterprise Linux 6
- ◆ Linux on z Systems
  - ◆ SUSE Linux Enterprise Server (SLES) v11
  - ◆ Red Hat Enterprise Linux 6

## Additional requirements

- ◆ See [MSS Installation Guide](#) for system requirements for MSS.
- ◆ **Load balancers** for MSS and Host Access for the Cloud must support sticky sessions and Web Sockets.

# Planning for Deployment

How many session servers do you need to deploy? How many MSS servers? What authentication method are you employing? Are there other considerations? In this section learn how to optimize your session server and MSS server deployment.

## In this section:

- ◆ [About Authentication](#)
- ◆ [Scaling and High Availability](#)
- ◆ [Deployment Options](#)
- ◆ [Using Load Balancers](#)
- ◆ [Terminal ID Manager](#)



## About Authentication

Before you begin deployment, you should determine what authentication mode you want to use. Authentication validates the user's identity based on some credentials, such as a username/password combination or a client certificate.

HACloud supports these authentication modes: LDAP, Single Sign-on through IIS, Single Sign-on through Windows, X.509, SiteMinder, and SAML.

You have the option to not require users to authenticate. Select **None** to allow any user to access their assigned sessions without being prompted for credentials.



You can find more information on authentication in [Select a method to authenticate users](#).

## Scaling and High Availability

Determining how many session servers and MSS servers you require to meet your needs is the first task in planning for deployment. Whatever your needs Host Access for the Cloud can be deployed to provide both capacity and high availability.

Your solution depends on your needs, but read [High Availability Deployment Blueprint](#) for an illustration of a scalable and highly available deployment.

The main questions that you need to answer are:

- ◆ What is the peak number of host sessions that will be used concurrently?
- ◆ How many users will be using the system?
- ◆ How available does the system need to be in the event of a failure in various areas of the system?

### Scaling

Scalability is a system's ability to handle various amounts of load. To increase capacity, a system can be scaled up (vertically) by running on a more powerful server or scaled out (horizontally) by adding more servers or nodes.

There are trade offs to consider with each case:

- ◆ **Scaling up** offers the simplicity of fewer servers, however it also increases the risk of a significant failure if a server goes down.
- ◆ **Scaling out** involves more servers but spreads the risk over many servers so when one goes down, a smaller number of users are affected.

Due to the increased resiliency, **we recommend scaling out** by adding more servers or nodes when increasing capacity.

### High Availability

High availability (HA) is a system's ability to continue providing services when a failure occurs somewhere in the system. HA is achieved by adding redundancy to key components of the system.

---

**NOTE:** This guide discusses providing high availability of the core Host Access for the Cloud services, however true high availability relies on redundancy at many layers in all areas of the systems, which is beyond the scope of this document.

---

High availability in Host Access for the Cloud is achieved by:

- ◆ Deploying enough session servers and MSS servers to provide the needed capacity, with headroom (free capacity) for failures
- ◆ Ensuring proper headroom so when a server does fail and the load fails over to the remaining servers, they are not compromised by the extra load
- ◆ Using load balancers to distribute the load and direct users to other servers in the event of a failure
- ◆ Replication of data between MSS servers, which is handled by MSS clustering

See the [High Availability Deployment Blueprint](#) section for an illustration of how to accomplish these requirements.

## Session Server Sizing

The number of session servers you need is determined by the **number of concurrent host sessions** you are running. Host sessions generate more load on the session server than users do, therefore we are focusing on the number of required host sessions instead of the number of users.

---

Number of concurrent host sessions	Number of session servers required
Up to 3000	2 session servers
More than 3000	$(\text{Number of host sessions needed}) / 2000 + 1$ (Minimum of three)

---

- ◆ A single session server supports 2000 concurrent host sessions.
- ◆ A session server has built-in headroom to handle 1000 additional host sessions in the event of a failover scenario.
- ◆ A minimum of two session servers are required for high availability.

## MSS Server Sizing

The number of MSS servers you need is determined by the number of **concurrent users**.

---

Number of concurrent users	Number of MSS servers required
Up to 30,000	3 MSS servers
More than 30,000	$(\text{Number of users needed}) / 10,000 + 1$ (must be an odd number)

---

- ◆ A single MSS server supports 10,000 concurrent users.
- ◆ A MSS server has built-in headroom for an additional 5000 users in the event of a failover scenario.

- ♦ A minimum of 3 MSS servers are required for high availability.
- ♦ An odd number of MSS servers are required for high availability due to the need for a database quorum.

## Deployment Options

You can deploy session servers in one of two ways:

1. Using the traditional method of installing each session server onto a dedicated server
2. Using Docker to run each session server in a container. Docker provides a number of benefits including more flexibility around how many session servers you can run on a single server. See [Using Docker](#) for more information.

## Using Load Balancers

You will need to provide load balancers for both session servers and MSS. There are common settings you should be aware of:

- ♦ **Load Balancing Algorithm** - The algorithm determines which server to send new traffic to. We recommend “Least Connections” or something similar. Verifying this setting is properly distributing load is essential for overall system stability. If the load balancer is not configured properly or working effectively, you run the risk of an individual server becoming overloaded.
- ♦ **Session Persistence (Affinity/Sticky Sessions)** - This is the ability to send the same user to the same server through multiple requests. Both the session server and MSS are stateful applications and require sticky sessions to be enabled on their load balancers. Noted below.
- ♦ **Health Check Endpoint** - This is the URL on the target service that is used to determine if the instance is healthy and should remain in service. Each server type provides its own health URL.

The [High Availability Deployment Blueprint](#) section provides recommended setting values for each load balancer.

## TLS/SSL options

There are three typical options for handling TLS/SSL on a load balancer. The option you choose depends on your needs.

Your certificate needs to be installed on the load balancer in the first two options. The third option, TLS passthrough, does not require a certificate on the load balancer. The HA Blueprint uses TLS Bridging to provide end-to-end TLS while still allowing cookie-based persistence. The options are:

- ♦ **TLS Termination/Offloading** - This option ends the HTTPS connection at the load balancer and continues to the service by means of HTTP.
- ♦ **TLS Bridging (Re-encryption)** - This option ends the HTTPS connection at the load balancer and re-establishes a new HTTPS connection between the load balancer and the service. This provides end-to-end TLS while still allowing the load balancer to inject a cookie for session persistence.
- ♦ **TLS Passthrough (Required for X.509)** - The load balancer proxies the TLS connection without decrypting it. The downside to this option is that since no cookie can be injected, persistence must be based on source IP or something similar.

## TLS/SSL with X.509 Single Sign-On

When using X.509 authentication, the TLS Passthrough option is required on Host Access for the Cloud and MSS load balancers since client certificates must be presented to the servers in the backend. Because TLS Passthrough is required, you will need a non-cookie based method for session persistence, such as source IP for both the session server and MSS load balancers. This is necessary because with TLS Passthrough there is no chance for the load balancer to decrypt the connection to set or even view a cookie.


## Terminal ID Manager

The Terminal ID Manager does not currently support HA. You can set up a passive server, but the state of the IDS will not be replicated from the active server. When the active server is unavailable, you will still be able to access the passive server, but the IDs will not maintain their current state.

## High Availability Deployment Blueprint

The following is an example of how to deploy Host Access for the Cloud in a highly available, scalable, and secure manner. While the details of every deployment will differ, for example you may be deploying three or more session servers, the goal here is to provide a known good starting point and to answer common deployment questions.

### Architecture



This deployment consists of:

- ◆ Session server load balancer
- ◆ Two or more session servers
- ◆ MSS load balancer
- ◆ Three or more MSS servers
- ◆ Terminal ID Manager
- ◆ LDAP or identity management server
- ◆ Host/mainframe

## Deployment benefits

With this example, you will see:

- ◆ Capacity for up to three thousand host sessions and the ability to be scaled as needed
- ◆ High availability of key services; minimizing single points of failure and distributing load by means of load balancers
- ◆ The ability to handle the failure of one session server and one MSS simultaneously without a significant drop in the performance of the web client, due to built-in headroom
- ◆ Authentication and authorization options for MSS
- ◆ Secure communication through HTTPS

## Steps when deploying

We recommend you follow these steps when deploying:

1. Learn about the basics of deployment
2. Provision resources based on system requirements and sizing guidelines
3. Install MSS and create a cluster
4. Configure MSS load balancer
5. Install session servers
6. Configure session server load balancer
7. Verify deployment
8. Configure single sign-on (optional)
9. Configure Terminal ID Manager (optional)

You've learned about the basics of deployment, system requirements and sizing guidelines in previous sections.

## Installing MSS

Install three MSS servers and configure each of them for clustering. There is documentation that can step you through the process:

1. Open ports on the firewall. Ports used by MSS and Host Access for the Cloud are listed [here](#).
2. Install MSS and then the Host Access for the Cloud components for MSS by running the Host Access for the Cloud install program on each MSS server.
3. Add each server to a cluster.
4. On each MSS server, configure general settings, security settings, and other settings as required.

### Additional resources:

- ◆ [Ports](#)
- ◆ [Installation Guide](#)
- ◆ [MSS Clustering](#)

## Configuring a MSS load balancer

As described in the [Using Load Balancers](#) section of this guide, use these values when configuring the MSS load balancer for high availability:

- ♦ **Load balancing algorithm:** Least Connections (or something similar)
- ♦ **Session persistence:** Enabled - use existing JSESSIONID cookie

Because cookies are not stored in the session server when it is acting as a client to MSS, the MSS load balancer must use either the existing JSESSIONID cookie or source IP (or something similar) for persistence. If you are using the Assign Sessions list, see [Configuring the Assigned Sessions list](#) for additional information.

- ♦ **Health check endpoint:** `https://<mss-server>/mss/`
- ♦ **TLS:** Configure TLS and install certificates as needed.

## Installing session servers

Install two or more session servers.

For each session server:

1. Open ports on the firewall. Ports used by MSS and Host Access for the Cloud are listed [here](#)
2. Install the session server. During installation, choose to use a remote MSS server, and enter the MSS load balancer address and port.
3. Import the session server certificate into each MSS's trusted subsystem trust store: `system-trustcerts.bcfks`.

---

**TIP:** This is done automatically for you on the MSS server that the load balancer chose during installation, but must be done manually on the other servers. It is best practice to import or verify its presence on each MSS server.

---

### Additional resources:

- ♦ [Ports](#)
- ♦ [Installing and Upgrading](#)
- ♦ [Securing connections](#)

## Configuring session server load balancer

Use these values to configure the load balancer:

- ♦ **Load balancing algorithm:** Least Connections (or something similar)
- ♦ **Session persistence:** Enabled - use JSESSIONID or a new cookie. Unlike the MSS load balancer you are not required to use the existing JSESSIONID cookie.
- ♦ **Health check endpoint:** `https://<session-server>/actuator/health`

For the session server in particular, be cautious when you are configuring how to determine a node has failed and what to do once it has failed. If there are users still connected to the instance, those users may lose their host connections. To avoid marking an instance as failed

too early, consider increasing timeouts or retries. Some load balancers provide a “drain mode”, which allows existing users to stay connected, but will direct new users to other instances.

- ♦ **TLS:** Configure TLS and install certificates as needed.

## Configuring the MSS callback address

MSS provides a callback address to the session server each time it creates or edits a session. By default, it uses the address specified in `management.server.url`.

If the MSS server is behind a proxy and the session server cannot reach the address:

- ♦ Set the `management.server.callback.address` property in each MSS `container.properties` file to an address that the session server, for a specific MSS, can reach.

---

**NOTE:** If HTTP is used for the session server to connect to the MSS callback address, set the `management.server.callback.address.http` property to *True* in each session server’s `container.properties` file.

---

- ♦ Restart the server for the new property values to take effect.

## Verifying the installation

After installing and configuring all components, you’ll want to:

- ♦ Log into the MSS Administrative Console (through the MSS load balancer).
- ♦ Navigate to Manage Sessions > Add a New Session and create a test session.
- ♦ Assign the test session to a test user.
- ♦ Log into the session server as the test user, through the session server load balancer.
- ♦ Verify that the assigned session is available, opens, and can connect.

## Configuring Single Sign-on (optional)


Following are a few additional considerations when configuring single sign-on in an high availability deployment.

### SAML (Security Assertion Markup Language)

1. Import the MSS load balancer certificate into each MSS `servletcontainer.bcfs` as a trusted certificate.
2. Update the `management.server.url` in each MSS `container.properties` file to use the MSS load balancer address.
3. Set the `management.server.callback.address` property in each MSS `container.properties` file to an address that the session server, for a specific MSS, can reach.
4. Restart the MSS servers.

5. Log on to the Administrative Console of the active MSS server to configure the [SAML Authentication](#).


Confirm that the MSS load balancer DNS is used in the **Assertion consumer service prefix URL** field and add the MSS load balancer and Host Access for the Cloud load balancer DNS to the SAML whitelist.

 The MSS Administrator Guide has [SAML Authentication](#) instructions.

## X.509

In each case the certificate used must have a Subject Alternative Name (SAN) that contains all MSS server DNS names, along with the load balancer DNS name.

1. Verify that the firewall on the MSS server allows HTTP traffic on the mutual authentication port; 8003 is the default.
2. In each MSS:
  - ♦ Replace the certificate of the servlet-engine entry in the `servletcontainer.bcfks` files.
  - ♦ Replace the certificate of the system entry in `system-keystore.bcfks` files.
3. Import the certificate into each session server's:
  - ♦ `trustcerts.bcfks` file as a trusted certificate.
4. Restart MSS and session servers.
5. Configure both the MSS and HACloud load balancers for TLS passthrough.
6. Configure X.509 authentication as documented here: [How to Configure X.509 Authentication](#).

 The MSS Administrator Guide [X.509 Configuration](#) has instructions.

## Configuring the Assigned Sessions list

To use the Assigned Sessions list to launch new sessions, additional configuration is needed:

- ♦ Configure the MSS load balancer to stick on first the SESSIONID and then the JSESSIONID cookies. It is important to configure the stickiness in that specific order.
- ♦ Access to the Assigned Sessions list must be through the same MSS load balancer that the HACloud session server uses to connect to MSS.

See [Using Load Balancers](#) for additional information.



# Installing and Upgrading



The MSS Administration Console help has information on [Product Activation](#).

- ◆ [Installing on different platforms](#)
- ◆ [Using an unattended installation](#)
- ◆ [Configuring an incomplete installation](#)
- ◆ [Upgrading from previous versions](#)
- ◆ [Troubleshooting the Installation](#)

Keep these things in mind when installing:

- ◆ **Activation files**

Activation files (activation.jaw) are used to enable product functionality. For example, The install package contains the needed activation file to enable communication between Host Access for the Cloud and MSS. It is typically activated as part of the install process. Activation files are downloaded from the Micro Focus download site and are specific for the different editions and platforms supported by Host Access for the Cloud. To work in a production environment, activation is required.

If activation was not part of the installation, you need to open the Administrative Console and complete the activation process (Configure Settings > Product Activation). See [Upgrading from previous versions](#) for information on handling activation files when you upgrade.

- ◆ **IIS Reverse Proxy with Host Access for the Cloud**

If you plan on using the IIS Reverse Proxy, read [Accessing Host Access for the Cloud using the IIS Reverse Proxy](#) for prerequisites and configuration instructions.

- ◆ **Security**

Host Access for the Cloud supports TLS and SSH protocols to protect mission-critical data. To secure your passwords and other sensitive data, you should require browsers to use the HTTPS protocol.

## Installing on different platforms

### Host Access for the Cloud and Java

The session server requires a Java JDK version 8 or higher and MSS requires a Java JRE version 8 or higher. This Java requirement is met during installation, except for systems, such as Linux on System Z that require an IBM JDK. Information on using the *nojdk* option is available under [Installing on z/Linux](#).

Both Host Access for the Cloud and MSS require that the Java installation support unlimited strength encryption. More information is available on the Java web site.

If necessary, you can use the environment variables specified in the *nojdk* option and `INSTALL4J_JAVA_HOME_OVERRIDE` to specify a specific Java installation.

## Windows

A basic Windows installation is described in [Getting Host Access for the Cloud](#).

## UNIX

- ◆ You must either install as “root” or use a user account with root privileges to complete successfully. When the installation has successfully completed, the installed application can be started and managed by “root” or someone running as ‘root’.
- ◆ If you are running on Linux platforms, [follow these steps](#) to set the session server to start automatically when your system first boots up.
- ◆ Elevated privileges are needed to open any application ports lower than 1024. Host Access for the Cloud will not start using a lower port number unless you have system privileges to open low numbered ports.
- ◆ You can use the `chmod` command to assign application privileges to users other than root.
- ◆ If you are installing on a headless Linux system and there are no fonts installed on the system, you may encounter this font-related error: `java.lang.Error: Probable fatal error: No fonts found`. Ensure that `fontconfig` or at least one font is installed on the system in order to proceed with the installation.

## z/Linux (SUSE E11.x and RHEL 6.x)

For systems, such as Linux on System Z, that require an IBM JDK, you can use the “*nojdk*” installer media, which does not include a bundled JDK.

- The installation must be able to locate a Java executable to start. If a Java executable cannot be found by the installer, then you can set the `INSTALL4J_JAVA_HOME` environment variable to refer to a Java installation’s `bin` directory.
- When started, the installation program will automatically search for version-compatible JDKs on the system. If more than one JDK is found, a list is displayed from which you can choose. If only a JRE is found on the system, you can continue with the installation, but the Host Access for the Cloud server will not run correctly until you have updated the `wrapper.java.command` property located in `sessionserver/conf/container.conf` to refer to a JDK installation.

If necessary, you can use the environment variables named above and `INSTALL4J_JAVA_HOME_OVERRIDE` to specify a specific Java installation.

## Using an unattended installation

The Host Access for the Cloud installation is based on `install4j` technology, which supports unattended mode. Unattended installation enables you to install the product the same way on a series of computers.

To use unattended installation:

1. Install the session server on a machine using the automated installer. You can use the graphical interface or console mode (`-c`) to install the product.

The installation process creates a text file, `response.varfile`, that contains the selected installation options. The file is located in `[sessionserver Install]\.install4j\response.varfile`

2. Copy `response.varfile` to another machine where you would like to install the session server.
3. Locate the appropriate executable to install the product. Launch the installation program using the `-q` argument and a `-varfile` argument that specifies the location of `response.varfile`.

For example, to install the session server on a 64-bit Linux platform with a `response.varfile` located in the same directory, use this command, where `<2.5.x.nnnn>` is the product version and build number:

```
hacloud-<2.5.x.nnnnn>-linuxx64.sh -q -varfile response.varfile
```

You could also add the `-c` option to install in console mode, which would provide feedback such as "Extracting Files" and "Finishing Installation."

## Configuring an incomplete installation

When the session server is either unable to retrieve a certificate from MSS or is unable to complete the registration process, an incomplete installation can occur. Follow the steps for [adding additional session servers](#) to complete the install.

If you are connecting to a remote MSS using HTTP, complete these additional steps:

1. Open the session server `container.properties` file and update the address in the following properties, replacing `localhost:80` with a resolvable address to the MSS server:
  - ♦ `management.server.url`
  - ♦ `metering.server.url`
  - ♦ `id.manager.server.url`
2. Set the `management.server.callback.address.http` property to `True` in the session server `container.properties` file.

## Upgrading from previous versions

---

**WARNING:** If you are upgrading, it is important that you remove any activation files from MSS associated with prior versions of Host Access for the Cloud. Leaving obsolete activation files in place may result in limited access to sessions.

---

1. Before proceeding, backup any changes you made to `hacloud\sessionserver\conf\container.properties` or `hacloud\sessionserver\conf\container.conf`
2. Install Host Access for the Cloud.
3. Restore the files you backed up in Step One and restart the session server.
4. If not handled during the installation process, install the new activation file or files into MSS using Administrative Console > Configure Settings > Product Activation.

## Additional configuration

To continue using server side events created in Reflection ZFE versions 2.3.2 or earlier, copy your server-side event JAR files located in `/webapps/zfe/WEB-INF/lib` to `/microservices/sessionserver/extensions/server`, and re-enable extensions.

## Troubleshooting the Installation

To complete a successful installation, make sure that you have taken care of these common issues:

### ✓ ***Are the activation files installed and activated in the Administrative Console?***

MSS uses activation files to enable product functionality. With your installation you received an activation file associated with the type of host you are connecting to. For example, if you are licensed for the Unisys Edition, if not handled as part of the install process, you will need to open the Administrative Console, go to Configure Settings > Product Activation and verify that the Host Access for the Cloud Unisys activation file is in place.

### ✓ ***Is MSS configured for HTTPS?***

Connect to the system where the Administrative Server is installed and log in to the Administrative Server. In the Administrative Console, open the Security Setup section and note the protocol selection.

### ✓ ***Verify that both MSS and Host Access for the Cloud are using trusted certificates.***

MSS imports certificates and private keys to `C:\ProgramData\Micro Focus\MSS\MSSData\certificates`. See [Securing connections](#).

If you are not using trusted certificates, have you configured Host Access for the Cloud to run using HTTP?

### ✓ ***Are your connection properties configured properly?***

In the unlikely event that you have to verify connection information, the `container.properties` file for both the management component and the session server contains the connection properties needed to make the session server to MSS connection as well as the browser to session server connection.

You can find the file in the Host Access for the Cloud installation at `<install-dir>/sessionserver/conf/container.properties`.

### ✓ ***Install does not complete on UNIX or Linux platforms***

The install program may stall on UNIX or Linux systems, particularly headless ones. This stall is caused by an insufficient amount of entropy in the system, typically due to a lack of interaction with the operating system's UI (or lack of UI).

**To remedy the issue:**

1. Stop the installation process.
2. On the installer's command line, prepend `-J` to the Java System property: `./hacloud-xxxx-linux-x64.sh -J-Djava.security.egd=file:///dev/urandom`
3. Run the installation program containing the added argument.



**Is the server on which you're installing secured to prevent access to the temp directory?**

See [Installation fails due to server preventing access to TEMP directory](#) under Known Issues for information on this issue.

---

**TIP:** For other known issues and troubleshooting information see [Technical References](#).

---

## Ports

Configure your firewall to allow connections on the following TCP listening ports:

Component	Default Port Numbers
Host Access for the Cloud session server	◆ 7443
MSS	◆ 80* - HTTP - Administrative Console, Terminal ID Management, Metering Management ◆ 443* - HTTPS - Administrative Console, Terminal ID Management, Metering Management ◆ 7000** - Database replication ◆ 7001** - Database replication TLS ◆ 8003* - X.509 Trusted subsystem ◆ 8761* - Service Registry ◆ 8089*** - Metering server

\* Host Access for the Cloud session server and MSS make requests on this port

\*\* MSS makes requests on this port

\*\*\* Host Access for the Cloud session server makes requests on this port

Both the Host Access for the Cloud and the MSS Administrative Server ports can be changed depending on your network needs. To modify the session server ports, see [How to Change Ports](#).

## Configuring your Deployment

When you begin to configure a deployment of Host Access for the Cloud there are a number of post-installation options to consider, as well as security concerns.

- ◆ [How to Set Up the Terminal ID Manager](#)
- ◆ [How to Set Up Metering](#)
- ◆ [How to Set Up Automated Single Sign-On for Mainframe](#)
- ◆ [How to Configure X.509 Authentication](#)
- ◆ [How to Configure Single Sign-on through IIS](#)
- ◆ [How to use the IIS Reverse Proxy with Host Access for the Cloud](#)

# How to Set Up the Terminal ID Manager

**MSS** Setting up the [Terminal ID Manager](#) requires that this feature is enabled in MSS.

The Management and Security Server provides a Terminal ID Manager to pool terminal IDs, track ID usage, and manage inactivity timeout values for specific users, thus conserving terminal ID resources and significantly reducing operating expenses.

The Terminal ID Manager Add-On requires a separate license.

Before you configure the Terminal ID Manager for Host Access for the Cloud, verify that you have this option enabled for MSS. There are complete instructions in the [MSS Installation Guide](#).

---

**TIP:** If MSS and Host Access for the Cloud are installed on the same machine and using port 80, no additional configuration is needed.

---

## Configuring Terminal ID Manager for Host Access for the Cloud

To configure the Terminal ID Manager for Host Access for the Cloud, you must provide the correct address to the Terminal ID Manager.

- 1 Open the `sessionserver/conf/container.properties` file.
- 2 Update `id.manager.server.url=http://localhost:80/tidm` to reflect the address of the Terminal ID Manager configured in Management and Security Server.
- 3 Restart the session server.

# How to Set Up Metering

**MSS** MSS provides metering capabilities to monitor host sessions. See [Metering](#).

The Management and Security Server provides metering capabilities to monitor host sessions.

Before you configure metering for Host Access for the Cloud, verify that you have metering enabled for MSS. There are complete instructions in the [Installation Guide](#).

In Host Access for the Cloud, metering is set globally for all emulation sessions created by the session server. Settings are configured in the `sessionserver/conf/container.properties` file.

**Table 3-1** Metering options

Property	Description
<code>metering.enabled</code>	Turns metering on or off, with a value of "true" or "false". Any value other than "true" turns metering off.
<code>metering.host.required</code>	Determines whether the session can connect to the host even if the metering server cannot be contacted. "True" means that session connections will fail if the metering host is unavailable. "False" means that session connections will still work even if the metering host is unavailable.
<code>metering.server.url</code>	Specifies the name or address of the metering server, the port, the protocol, and the webapp context. The syntax is "host:port protocol context". This syntax is the same as that used by the MSS server in the <code>MssData/serverconfig.props</code> file to register metering servers. The host:port section of the URL must escape the ":" character. For example, <code>test990.attachmate.com\:8080</code> .


```
#Example additions to sessionserver/conf/container.properties
metering.enabled=true
metering.host.required=false
metering.server.url=10.10.11.55\:80|http|meter
```

---

**NOTE:** In the event that all licenses are in use and you attempt to make a connection, the session will be disconnected. To determine whether the host has disconnected or the metering service has stopped the connection, see the `<install_dir>/sessionserver/logs/sessionserver.log` file.

---

## How to Set Up Automated Single Sign-On for Mainframe

 [Automated Sign-On for Mainframe - Administrator Guide](#) has complete information on configuring this option.

Automated Sign-On for Mainframe is an add-on product to Management and Security Server that enables an end user to authenticate to a terminal emulation client and be automatically logged on to a host application on the z/OS mainframe.

- 1 Install and configure the Automated Sign-On for Mainframe add-on for Management and Security Server. You can find complete instructions [here](#).
- 2 After the Management and Security Server setup is complete, open the Administrative Console to add sessions and map users to those sessions. During that process, you can complete the additional configuration needed to implement automated sign-on.

- 3 A Host Access for the Cloud macro sends the user's mainframe username and pass ticket to the host application. The user is then automatically logged in. To help create the macro:
  - ◆ The Macro API contains the [AutoSignon](#) object that provides the methods needed to create a Host Access for the Cloud login to use with the Automated Sign-On for Mainframe feature.
  - ◆ You can also reference the sample macro [Automatic Sign-On Macro for Mainframes](#) that uses the AutoSignon object to create a macro that uses the credentials associated with a user to obtain a pass ticket from the Digital Certificate Access Server (DCAS).

## How to Configure X.509 Authentication

X.509 client authentication allows clients to authenticate to servers with certificates rather than with a user name and password by leveraging the X.509 public key infrastructure (PKI) standard.



MSS has detailed information on [X.509 Configuration](#).

When you enable X.509 client authentication:

- ◆ When the user accesses the web client using TLS the browser sends a certificate to the session server identifying the end user and completing the TLS handshake.
- ◆ The session server refers to its truststore to check the client's certificate and verify its trust.
- ◆ Once the TLS negotiation is complete (the session server trusts the end user), the session server sends the end user's public certificate to MSS for further validation.
- ◆ MSS also verifies that it trusts the end users certificate using its trust store.
- ◆ When MSS finishes the validation, the end user will have successfully authenticated.

The client's full certificate chain needs to be present in the session server and MSS truststores or alternatively signed by a Certificate Authority that is present in the truststores.

How the browser determines the client certificate to send is a browser or smart card specific configuration.

### Basic steps:

1. Trust certificates in the session server and MSS if they have not already been trusted.
2. Restart the servers.
3. Configure X.509 in the MSS Administrative Console.

### Step 1. Trust the certificate in MSS and the session server

- ◆ **Trust the certificate in MSS**

MSS' trusted store may already contain your signing authority certificate. This is often the case with well-known certificate signing authorities, and if so, then you can skip this step.

To check:

Open the Administrative Console, click Configure Settings, and open the Trusted Certificates tab. Open [Trusted Root Certificate Authorities](#) to see a list of available certificates.



If your certificate is not listed you need to install your signing root CA into MSS following the prompts and documentation in the Administrative Console.

- ◆ **Trust the certificate in the session server**

To install the certificate into the session server:

```
In <install_directory>\sessionserver\etc import the certificate: keytool -
importcert -file <cert-file> -alias <alias-to-store-cert-under> -
keystore trustcerts.bcfks -storetype bcfks -providertype BCFIPS -
providerclass org.bouncycastle.jcajce.provider.BouncyCastleFipsProvider
-providerpath ../lib/bc-fips-*.jar -storepass changeit
```

## Step 2. Restart all the servers

For the configuration to take effect, you must restart all servers.

## Step 3. Configuring X.509 with LDAP fail over in the MSS Administrative Console

Once the certificates are in place, you can enable X.509 with the Fallback to LDAP authentication option in [Management and Security Server Administrative Console | Configure Settings | Authentication & Authorization](#). See the Administrative Console online help for descriptions of the configuration options.

## Using X.509 authentication through a load balancer configured for TLS termination

In this configuration, the load balancer provides end user authentication by validating their client certificate. However, the client certificate still needs to be sent to all the MSS systems in order to identify the incoming user.

If the load balancer is configured to terminate the TLS connection, the user's certificate can be added to an HTTP header, extracted by the session server, and then passed to MSS for authorization. In order to pass the certificate in a header, first set the header name in the HACloud Session Server's container.properties file:

### To pass the certificate in a header

1. Set the header name in the HACloud session server's container.properties file:

```
x509.header.client.cert=X-SSL-Client-Cert
```

2. Set the header value to the user's certificate in the load balancer configuration. For example, using a BigIP iRule:

```
HTTP::header insert X-SSL-Client-Cert [URI::encode $client_cert]
```

This assumes that \$client\_cert has been set to the user's certificate in PEM format. If the user's certificate is in DER format, use Base64 encoding:

```
HTTP::header insert X-SSL-Client-Cert [b64encode $client_cert]
```

Encoding the certificate ensures that the header value is one line of ASCII text. This is required for the HACloud session server to read the value.

---

**NOTE:** The client certificate authentication must still take place between the load balancer and the session server. The load balancer needs to be configured to send its certificate to the session server and the load balancer's CA must be present in the session server's trust store.

---

3. After configuring the load balancer to send its certificate to the HACloud session server and configuring the user's certificate to be passed in the header, restart the session server.

Connecting with a certificate or smart card through the load balancer will result in successful authentication and authorization as the user represented by the certificate. To verify proper operation, set the session server's log level to DEBUG and examine the `sessionserver.log` file for entries like these:

```
Attempting to extract certificate from X-SSL-Client-Cert header.  
User <DN value> has been preauthenticated from <IP address>
```

### Additional configuration

By default, the HACloud session server's trust store contains the Java CA certificates. As a result, the HACloud session server will accept any client certificate signed by well-known CAs. In order to ensure that only the desired load balancers connect to the session server, you must remove the Java CA certificates from the trust store and ensure only the necessary certificates are installed in the trust store.

To filter the allowed client certificates by issuer DN, set the following properties in the HACloud session server's `container.properties` file:

```
X509.client.cert.issuer=<DN value>  
X509.client.cert.subject=<Subject DN value>  
X509.client.cert.serial=<Serial number>  
X509.client.cert.shal=<SHA1 fingerprint>  
X509.client.cert.sha256=<SHA256 fingerprint>
```

DN values must match the load balancer's certificate issuer or subject DN exactly. The serial number value should be a decimal (base 10) value. SHA1 and SHA256 fingerprint values should be entered in hexadecimal. When any of these properties are set, the incoming certificate's attributes will be checked to ensure they match the specified property values. Authorization will fail if any values do not match.

## How to Configure Single Sign-on through IIS



See [Single Sign-on through IIS](#) in the MSS Administrative Console documentation if you need further information.

This option uses Microsoft IIS web server.

To enable Host Access for the Cloud to work with this authentication method, add the following property in the `<install dir>/sessionserver/conf/container.properties` file:

```
management.server.iis.url= <url>
```

The value of this property is the IIS web server address and port along with the /MSS path. For example: `http://server/mss`. If authentication fails, you may need to remove the domain name in order for the domain credentials to be passed to IIS: `http://server/mss`.

---

#### Related Topics

[How to use the IIS Reverse Proxy with Host Access for the Cloud](#)

## How to use the IIS Reverse Proxy with Host Access for the Cloud

Before configuring, read [Accessing Host Access for the Cloud using the IIS Reverse Proxy](#) for prerequisites and configuration instructions.

### Using the IIS Reverse Proxy with Host Access for the Cloud

---

**NOTE:** To comply with Common Criteria security requirements it may be necessary to place the session server behind a proxy by following the instructions in [Accessing Host Access for the Cloud using the IIS Reverse Proxy](#).

---

To proxy Host Access for the Cloud through IIS, when using IIS single sign-on, you need to set an additional property in the same `container.properties` file:

```
servletengine.iis.url=<url>
```

The value takes the same form as the URL above, but uses the Host Access for the Cloud address. For example: `http://server/`. It is not necessary to use the short host name form in this URL.

After you have completed this configuration, you choose this authentication option in **Management and Security Server Administrative Console | Assign Access**. See the Administrative Console online help for descriptions of the configuration options.

---

#### Related Topics

[How to Configure Single Sign-on through IIS](#)

## Securing connections

Host Access for the Cloud uses Transport Layer Security (TLS) to cryptographically secure communication between client web browsers, session server, MSS and backend hosts.

### In this section:

- ◆ [Overview](#)
- ◆ [Your default secure installation](#)
- ◆ [Tools](#)
- ◆ [How do I...?](#)

# Overview

## Public Key Infrastructure (PKI)

TLS uses Public Key Infrastructure (PKI) to implement security. PKI uses keys, both public and private, to secure client and server communication. Public and private keys are mathematically related, but they are not the same. This means that a message encrypted with a public key can only be decrypted using the private key. Together, these keys are known as a key pair.

## Certificates

Digital certificates are credentials that verify the identities of individuals, computers, and networks. They provide the link between a public key and a business that has been verified (signed) by a trusted third party, known as a certificate authority (CA). Digital certificates provide a convenient way to distribute trusted public encryption keys.

## Keystores

Certificates and private keys are stored in Java keystores. Keystore entries are identified using a unique identifier, known as an **alias**. Often private keys and certificates, with their corresponding public key, are stored separately from those certificates received from other parties that you are using for trust purposes. This separate keystore is referred to as a **truststore**. A truststore contains certificates from parties that you expect to communicate with or from Certificate Authorities that you trust to identify other parties.

## Your default secure installation

During the installation of HACloud and MSS, self-signed certificates are generated, exchanged, and then used to secure all communication between the session server, web browsers and MSS. Self-signed certificates are identity certificates that are signed by the same entity whose identity they certify.

Both session servers and MSS servers use their generated self-signed certificates to identify themselves to remote clients such as web browsers and other session servers and MSS servers. These self-signed certificates and their private keys are stored in their respective keystores.



The MSS Administrative Console help has detailed information on [General Security and Certificates](#).

To complete secure communication between clients (web browsers, session servers and MSS servers), the clients must trust the generated self-signed certificate. The session server trusts MSS' certificate during installation and stores it in its truststore. Likewise, during installation MSS retrieves and trust the session server's certificate and stores it in its truststore.

### Default values:

- ◆ Password - **changeit**
- ◆ Keystore type - **bcfks (Bouncy Castle FIPS keystore)**
- ◆ Location of self-signed MSS certificate - `MSS/server/etc/<computer-name>.cer`
- ◆ Location of self-signed HACloud session server certificate - `HACloud/sessionserver/etc/keystore.cer`

## Tools

- ♦ **KeyStore Explorer** - You can take advantage of the KeyStore Explorer utility to provide a simple user interface to create signing requests (CSR) and import CA-signed certificates into Host Access for the Cloud.
  - To launch KeyStore Explorer on Windows - run `\HACloud\utilities\keystore-explorer.bat` as an administrator or with administrative rights.
  - To launch KeyStore Explorer on UNIX - run `hacloud\utilities\keystore-explorer.sh` as an administrator or with administrative rights.

The utility has an online Help system available to walk you through the user interface.

- ♦ **Java Keytool** - The Java Key and Certificate Management Tool manages a keystore of cryptographic keys, X.509 certificate chains, and trusted certificates. It uses a command line interface. The Java Key and Certificate Management Tool documentation is available for both Unix and Windows platforms:
  - [Unix \(http://docs.oracle.com/javase/8/docs/technotes/tools/unix/keytool.html\)](http://docs.oracle.com/javase/8/docs/technotes/tools/unix/keytool.html)
  - [Windows \(http://docs.oracle.com/javase/8/docs/technotes/tools/windows/keytool.html\)](http://docs.oracle.com/javase/8/docs/technotes/tools/windows/keytool.html)
- ♦ **Entropy and encryption** - Entropy is the randomness collected by an operating system for use in cryptography. This randomness is often collected from hardware sources, like mouse movements. A lack of entropy can have a negative impact on performance and security and will be more apparent in headless server-based installations.

Solutions to improve entropy generation:

- Keytool parameter – to change how entropy is generated, add an additional parameter to the linux keytool command line. `-J-Djava.security.egd=file:/dev/urandom`
- *Haveged* tool – this is a tool to help remedy low-entropy conditions in the Linux random device, which can occur under some workloads, and especially on headless servers. See <https://wiki.archlinux.org/index.php/Haveged> for information on this tool.

## How do I...?

- ♦ [Apply for a digital identity certificate \(Certificate Signing Request\)](#)
  - ♦ [Replace the session server certificate](#)
  - ♦ [Replace the MSS certificate](#)
  - ♦ [Make a secure emulation connection to a trusted host](#)
  - ♦ [Configure X.509 client authentication from the end user's browser to the session server](#)
  - ♦ [Set up server side events to make outbound TLS calls from the session server](#)
  - ♦ [Add more MSS servers to my installation](#)
  - ♦ [Add additional session servers to my multi-MSS installation](#)
  - ♦ [Import a certificate into the session server's truststore](#)
-

## Apply for a digital identity certificate (Certificate Signing Request)

### Terms used:

- ♦ private key - a secret key known only to the owner, used with an algorithm to encrypt/decrypt data
- ♦ key pair - private key and its associated certificate chain
- ♦ distinguished name - the identifying information in a certificate. A certificate contains DN information for both the owner / requester of the certificate (called the Subject distinguished name) and the CA that issued the certificate (called the Issuer distinguished name)
- ♦ X.509 certificate - a digital certificate that uses the widely accepted international X.509 public key infrastructure (PKI) standard to verify that a public key belongs to the user

Before creating a Certificate Signing Request (CSR), the applicant first generates a key pair, keeping the private key secret. The CSR contains information that identifies the applicant (such as a *distinguished name* in the case of an X.509 certificate) which must be signed using the applicant's private key. The CSR also contains the applicant's chosen public key.

### How to create a CSR using KeyStore Explorer

To create a CSR you will create a key pair and then generate a certificate request. If you do not need to update certificate information, you can skip creating the key pair and proceed to generating the certificate request.

- ♦ Create a new key pair
  - From the Tools menu, select Generate Key Pair.
  - On the Generate Key Pair dialog box, enter the algorithm information and certificate details. Click OK.
  - Specify the relevant alias (servlet-engine) and default password (changeit).
- ♦ Generate a certificate request
  - Select the key pair you just created.
  - From the right-click menu, select Generate CSR.
  - Browse to the file location where you want to generate the CSR and enter the file name. Click OK.

### How to create a CSR using Java Keytool

**Create Key Pair** (replace the `dname` parameter with your own) in the `sessionserver/etc` folder:

```
..\..\java\bin\keytool.exe -genkeypair -dname "CN=hacloud-1.microfocus.com, O=Micro Focus, C=US" -alias servlet-engine -keyalg RSA -keysize 2048 -keystore keystore.bcfks -validity 1095 -storetype bcfks -storepass changeit -keypass changeit -providername BCFIPS -providerpath ../lib/bc-fips-*.jar -providerclass org.bouncycastle.jcajce.provider.BouncyCastleFipsProvider
```

### Generate Certificate Request:

```
..\..\java\bin\keytool -certreq -alias servlet-engine -keystore
keystore.bcfks -file cert_request.csr -ext ExtendedkeyUsage=serverAuth -
storetype bcfks -storepass changeit -providername BCFIPS -providerpath ../
lib/bc-fips-*.jar -providerclass
org.bouncycastle.jcajce.provider.BouncyCastleFipsProvider
```

After you receive the certificate from the CA, you will import the certificate into Host Access for the Cloud.

## Replace the session server certificate

Your installation is secured using self-signed certificates. Self-signed certificates, while just as secure as commercial certificates, aren't automatically trusted. This makes them hard to manage. Commercial certificates are necessary when you need widespread support for your certificate and fortunately, most web browsers and operating systems already support many commercial certificate authorities.

### Information you must know:

- ♦ **keystore location** - /etc/keystore.bcfks
- ♦ **keystore format** - bcfks (Bouncy Castle FIPS)
- ♦ **default password** - changeit
- ♦ **key pair alias** - servlet-engine

How to replace the self-signed certificate varies depending on whether you are replacing the self-signed certificate with one obtained through a CSR into the default keystore or whether you are replacing it with your own non-default keystore and certificate.

## Replace self-signed certificate with certificate reply from Certificate Authority (CA)

- 1 Create a [Certificate Signing Request \(CSR\)](#) for the session server and send it to the CA of your choice. When you receive the signed certificate from the CA, then:
- 2 Import the CA-signed certificate/chain into the session server's keystore.

You can accomplish this task using either KeyStore Explorer or the Java Keytool command line instructions. Whatever tool you decide to use, if the CA Reply contains separate root and intermediate certificate files, import the root certificate into the keystore first, followed by the intermediate certificate.

### Using this tool

### Do this...

#### Keystore Explorer

1. Open `keystore.bcfks` in KeyStore Explorer. Use the password **changeit**.
2. If separate root and intermediate certificate files are available, from the tool bar, select **Import Trusted Certificate** to import certificates.
3. Select the `servlet-engine` key pair. Right-click and select **Import CA Reply** to import the file into the key pair.
4. If prompted, enter the password, **changeit**.
5. Browse to the location where the CA Reply file is stored, select the file, and click Import.

## Using this tool

### JavaKeytool

These examples use keytool command at the sessionserver\etc directory.

## Do this...

### Windows

#### Import Root CA and intermediate certificates

```
..\..\java\bin\keytool.exe -importcert -alias rootca -trustcacerts -file <RootCA.cer> -keystore keystore.bcfks -storetype bcfks -storepass changeit
```

```
..\..\java\bin\keytool.exe -importcert -alias intermediateca -trustcacerts -file <IntermediateCA.cer> -keystore keystore.bcfks -storetype bcfks -storepass changeit -providername BCFIPS -providerpath ../lib/bcfips-*.jar -providerclass org.bouncycastle.jcajce.provider.BouncyCastleFipsProvider
```

#### Import CA Reply

```
..\..\java\bin\keytool.exe -importcert -alias servlet-engine -trustcacerts -file <CertChainFromCA.p7b> -keystore keystore.bcfks -storetype bcfks -storepass changeit -providername BCFIPS -providerpath ../lib/bcfips-*.jar -providerclass org.bouncycastle.jcajce.provider.BouncyCastleFipsProvider
```



**Import Root CA and intermediate certificates**

```

../../java/bin/keytool -importcert -alias rootca -
trustcacerts -file <RootCA.cer> -keystore
keystore.bcfks -storetype bcfks -storepass changeit -
providertype BCFIPS -providerpath ../lib/bc-fips-*.jar
-providerclass
org.bouncycastle.jcajce.provider.BouncyCastleFipsProvid
er

```

```

../../java/bin/keytool -importcert -alias
intermediateca -trustcacerts -file <IntermediateCA.cer>
-keystore keystore.bcfks -storetype bcfks -storepass
changeit -providertype BCFIPS -providerpath ../lib/bc-
fips-*.jar -providerclass
org.bouncycastle.jcajce.provider.BouncyCastleFipsProvid
er

```

**Import CA Reply**

```

../../java/bin/keytool -importcert -alias servlet-
engine -trustcacerts -file <CertChainFromCA.p7b> -
keystore keystore.bcfks -storetype bcfks -storepass
changeit -providertype BCFIPS -providerpath ../lib/bc-
fips-*.jar -providerclass
org.bouncycastle.jcajce.provider.BouncyCastleFipsProvid
er

```

**3 Trust the new certificate in MSS.**

- ◆ As the administrator, log into MSS.
- ◆ From the left panel, click **Configure Settings > Trusted Certificates**.
- ◆ Select **Trusted Sub-System**. The list contains the certificates that are trusted by MSS.
- ◆ Click **IMPORT** to add the session server certificate to the list.
- ◆ There is no need to repeat the procedure for each MSS. Changes are automatically replicated to other MSS in the cluster.

There is detailed help available in the Administrative Console help [-General Security and Certificates](#).

**Replace the certificate with your non-default keystore**

You can use a keystore other than the default (`sessionserver/etc/keystore.bcfks`) to store your CA-signed certificates.

Specify the following properties in `sessionserver/conf/container.properties`:

```

server.ssl.key-store
server.ssl.key-store-password

```

Where the keystore path is set to the non-default keystore file name and the keystore password is set to the obfuscated value generated by the following command from the `sessionserver` directory:

```
../java/jre/bin/java -cp ./lib/jetty-util-<version>.jar  
org.eclipse.jetty.util.security.Password passwordToObfuscate
```

For example:

```
server.ssl.key-store=${server.home}/etc/custom.bcfks  
server.ssl.key-store-password=OBF:1vn2lugulsa1v9ilv941sarlugwlv0
```

To avoid confusion, delete the default keystore.

To prevent the default keystore from being generated when the server starts up, open `/conf/product-core-ctx.xml` in a text editor and either remove or comment out the `servletEngineKeystoreGenerator` section. Restart the session server.

## Replace the MSS certificate



Review how to replace the MSS certificate in the [General Security and Certificates](#) topic.

During installation, to establish secure communication, the session server trusted the existing MSS certificate. If the MSS certificate is updated, it must be re-trusted by all the HACloud session servers.

### To replace the MSS certificate

- ◆ To trust the new MSS certificate, import it into the session server's truststore using the alias `mss`. See [Import a certificate into the session server's truststore](#)
- ◆ You must import the new MSS certificate into each session server.

## Make a secure emulation connection to a trusted host

Follow these steps to configure a TLS connection between the Host Access for the Cloud session server and a host that supports TLS:

1. Configure the trusted keystore in MSS.
2. Configure the terminal session.

### How to configure the keystore in MSS



Open the MSS Administrative Console > Configure Settings > Trusted Certificates and choose **Terminal Emulator Clients**. You can access the documentation for the Administrative Console by clicking the Help icon in the upper right of the page.

For a session to trust the TLS host it connects to, the public certificate of the host must be added to a trusted keystore using the Management and Security Server (MSS). The Host Access for the Cloud session retrieves this certificate the first time a session connects.

When the certificate is successfully added to the MSS server's trusted keystore, you are returned to the list of certificates and you should see the new host.

## How to configure a HACloud terminal session

Depending on your host type, you can configure a terminal session using different security protocols.

Type	Procedure
Using TLS	To connect to the new trusted host using TLS, configure a terminal session as usual, and in the Settings dialog box, specify TLS as the security protocol. Make sure to specify the correct TLS port for the connection.
Using Secure Shell (SSH) with VT host types	<p>Secure shell provides encrypted communications between the client and a VT host.</p> <p>MSS has a known hosts list that contains the public keys of hosts that you can connect to using SSH. SSH connections can be made only to hosts already trusted by an administrator.</p> <p>The first time an SSH connection is made from a session to a host, the known hosts file is downloaded from MSS to the session server.</p> <p>When you attempt to create or edit a session using SSH in the session management panel, you will be notified if the key is not recognized as trusted and asked if you want to trust the key and continue.</p> <ul style="list-style-type: none"><li>◆ If you enter yes, the host will be trusted and added to the known host list, and you will be prompted for the SSH host password.</li><li>◆ If you do not answer yes, then the host will remain untrusted and the session will be disconnected.</li></ul> <p>You can also configure the SSH known hosts file manually by establishing an SSH connection from a session to the host, and adding the remote host's key fingerprint to the known hosts list in MSS.</p>

Type	Procedure
Configure the known hosts file for SSH connections in MSS	<ol style="list-style-type: none"> <li>1. Connect to the system where MSS is installed and navigate to the server's certificates folder: C:\ProgramData\Micro Focus\Mss\MssData\certificates (Windows) or /var/opt/microfocus/mss/Mssdata/certificates (UNIX).</li> <li>2. Copy the public certificate file of the new SSH host into the MssData/certificates (Windows) or /etc/ssh/ssh_host_rsa_key.pub (UNIX) folder described above. Only ssh-rsa and ssh-dss are valid as public key types for MSS known_hosts entries.  The host's public key format can be OpenSSH, Base64-encode,.DER, or.PFX. The file should follow this format: hostname, IP-address key-type key. For example, a public key entry might look like this: alpsuse132, 10.117.16.232 ssh-rsa AAAAB3NzaC1yc2EAAAADAQAB.....</li> <li>3. Log in to MSS (for example, http://mycompany.com/adminconsole).</li> <li>4. Open the <b>Administrative Console</b>.</li> <li>5. Click Configure Settings &gt; Secure Shell.  After the public key is imported into the known hosts file, you will return to the Secure Shell Known Hosts page and the new host will appear in the list.</li> <li>6. Follow the directions in MSS to import a known host. After the public key is imported into the known hosts file, you will return to the Secure Shell Known Hosts page and the new host will appear in the list.</li> </ol>

## Configure X.509 client authentication from the end user's browser to the session server

There are complete instruction on [How to Configure X.509 Authentication](#) to follow.

## Set up server side events to make outbound TLS calls from the session server

When writing Java code that runs in your server side events, you may want to make outbound calls to remote servers using TLS. If the remote server is well known it may already be trusted by the session server and there isn't anything more to setup. However, often times the remote server isn't well known and you will need to trust it by importing its certificate into the session server's truststore.

### To trust the remote server

Import its public certificate into the session server's truststore following these instructions, [Import a certificate into the session server's truststore](#)

## Add more MSS servers to my installation

During installation both the MSS and HACloud servers have exchanged and trusted their certificates. When you add additional MSS servers, their certificates also need to be trusted.



Configuration is required in the MSS Administrative Console > Configure Settings > Trusted Certificates > Trusted Sub-System.

### To setup trust between MSS and the session servers

- ♦ Trust the new MSS server by importing the MSS certificate into the session server's truststore. See [Import a certificate into the session server's truststore](#)
- ♦ The new MSS needs to trust each of the session servers.
  - As the administrator, log into MSS.
  - From the left panel, click **Configure Settings > Trusted Certificates**.
  - Select **Trusted Sub-System**. The list contains the certificates that are trusted by MSS.
  - Click **IMPORT** to add the session server certificate to the list.
  - Repeat this process for each session server.

## Add additional session servers to my multi-MSS installation

During the installation the session server and MSS have already exchanged and trusted their certificates, all MSS servers already trust all existing session servers. However, when you add more session servers, a trust relationship needs to be established between the new session servers and the existing MSS servers

### To add more session servers

1. Import the MSS server certificate into the session server truststore. See [Import a certificate into the session server's truststore](#).
2. Import the session server certificate into the MSS server truststore. See [Trusted Certificates](#) in the MSS documentation.
3. Retrieve the `service.registry.password` from the MSS server `container.properties` file.
4. Set the `service.registry.password` in the session server `container.properties` file.

## Import a certificate into the session server's truststore

When the session server attempts to make outbound secure connections to remote servers it verifies the identity of the remote server using the certificates in its truststore. Any certificate imported into this truststore will be trusted.

### Information you must know:

- ♦ **keystore location** - `/etc/trustcerts.bcfks`
- ♦ **keystore format** - bcfks (Bouncy Castle FIPS)
- ♦ **default password** - `changeit`

### Using KeyStore Explorer

1. Open `trustcerts.bcfks` using the password `changeit`.
2. From the toolbar, select **Import Trusted Certificate**.

## Using Java Keytool

From the `sessionserver/etc` directory:

```
../../java/bin/keytool -importcert -alias <import-cert> -trustcacerts -  
file <import-cert.cer> -keystore trustcerts.bcfks -storetype bcfks -  
storepass changeit -providername BCFIPS -providerpath ../lib/bc-fips-*.jar  
-providerclass org.bouncycastle.jcajce.provider.BouncyCastleFipsProvider
```

# Using Docker

The Docker open platform has [excellent documentation](#) which you should read and understand.

- ♦ [Why Docker?](#)
- ♦ [What are the benefits?](#)
- ♦ [Terminology](#)
- ♦ [Getting Started with Docker and Host Access for the Cloud](#)
- ♦ [Examples](#)

## Why Docker?

Docker is a container-based platform that enables you to develop, deploy, and run applications within a container. Your application, plus any dependencies your application requires, such as binaries and libraries, and configuration information are held within the container. You can deploy multiple containers, all of which run in Docker and on top of the operating system.

Using Docker you can scale your applications vertically, meaning multiple instances of the session server can exist on one server and each instance will perform exactly as it did when you created and tested it.

## What are the benefits?

Containerization delivers multiple benefits:

- ♦ **Performance**  
Virtual machines are an alternative to containers, however containers do not contain an operating system (unlike VMs). This means containers are faster to create, quicker to start, and have a much smaller footprint.
- ♦ **Agility**  
Because containers are more portable and have better performance, you can take advantage of more agile and responsive development practices.
- ♦ **Isolation**  
Docker containers are independent of one another. This is important because a Docker container containing one application, including the required versions of any supporting software, will not interfere with another container of the same application which requires different supporting software. You can have total confidence that at each stage of development and deployment the image you create will perform exactly as expected.

- ◆ **Scalability**

Creating new containers is simple and quick. The [Docker documentation](#) has information on how to manage multiple containers.

## Terminology

There are basic terms you need to be familiar with when working with Docker. For more information see the [Docker Documentation](#) site.

### Container

A run-time instance of an image. A container is usually completely isolated from the host environment, only able to access host files and ports if it has been configured to do so. To run an image in a container you use the `docker run` command.

### Docker Hub

A cloud-based community resource for working with Docker. Docker Hub is typically used for hosting images, but can be used for user authentication and automating the building of images. Anyone can publish images to Docker Hub.

### Docker Compose

Compose is a tool that uses YAML files to configure your application services and then define and run multi-container Docker applications. To learn more about Compose visit the [Docker Compose documentation](#).

### Dockerfile

A text document containing the commands to build a Docker image. You can specify complex commands (such as specifying an existing image to use as a base) or simple ones (such as copying files from one directory to another). To build an image from a Dockerfile you use the `docker build` command.

### Image

A standalone, executable package that runs in a container. A Docker image is a binary that includes everything needed to run a single Docker container, including its metadata. You can build your own images (using a Dockerfile) or use images that have been built by others and then made available in a registry (such as Docker Hub). To build an image from a Dockerfile you use the `docker build` command. To run an image in a container you use the `docker run` command.

## Getting Started with Docker and Host Access for the Cloud

When you install HACloud, if you choose to use Docker, the install package contains an initial Dockerfile and accompanying application jar file to get you started using the session server in containers. These files are available prior to your installation.

There are examples located in the `docker/samples` folder. See [Examples](#) for instructions.

There are four steps involved in creating the base image:

1. Install Docker. Follow the instructions on the Docker web site.
  - ◆ [Install Docker](#)
2. Extract the download package file and locate `Dockerfile`, `entrypoint.sh` and `sessionserver.jar` in the `Docker` folder

3. Build the Docker image
4. Run the Docker image

## Build the session server Docker image

Assuming you have followed steps one and two; installed Docker and extracted and located Dockerfile and sessionserver.jar, the next step is to build the base Docker image of the session server.

1. Run this command from the folder containing the Dockerfile:

```
docker build -t hacloud/sessionserver:<version> .
```

Replace <version> with the version of the session server. If a version is not available, the default tag (-t) is latest.

2. Verify that the image was successfully created. Run:

```
docker images
```

The output should contain information about the image you just built.

## Run the image

Before you can run the session server image in a Docker container, you must complete the following steps:

- ◆ [Specify the address of the MSS server](#)
- ◆ [Specify the service registry password](#)
- ◆ [Tell MSS to trust the session server's identity certificate](#)
- ◆ [Provide the keystore containing the session server's identity certificate](#)
- ◆ [Provide the truststore containing the MSS certificate](#)
- ◆ [Mapping your keystore and truststore to the ones in the container](#)
- ◆ [Specify Docker host name and port](#)

---

### Specify the address of the MSS server

To specify the location of your MSS server, pass in an environment variable to the session server through Docker. For example, `--env MSS_SERVER=mss.server.com`

### Specify the service registry password

To specify the service registry password, pass in an environment variable to the session server through Docker. For example, `--env SERVICE_REGISTRY_PASSWORD=<your_password>`.

You can retrieve the password from the `service.registry.password` property located in `./mss/server/conf/container.properties` on the MSS server. Use the entire `service.registry.password` property.



## Tell MSS to trust the session server's identity certificate

You accomplish this step using the Administrative Console > Configure Settings > Trusted Certificates. See the MSS Administrative Console documentation, [To add a server certificate to the MSS trust store](#). The session server's certificate is available in the `sessionserver/etc` directory.

## Provide the keystore containing the session server's identity certificate

The session server identifies itself using a certificate. The certificate is expected to be present in the Java keystore `/sessionserver/etc/keystore.bcfks` located in the container.

## Provide the truststore containing the MSS certificate

When the session server makes outbound TLS connections, it verifies the trust of the remote servers (such as MSS) using certificates in its truststore. The certificates present in the Java keystore `/sessionserver/etc/trustcerts.bcfks` located in the container will be trusted.

## Mapping your keystore and truststore to the ones in the container

You have two options to provide these keystores into the container:

- ◆ [Using a volume mount](#)
- ◆ [Extending an existing Docker image](#)

### *Using a volume mount*

A volume mount mounts a file or directory on the host machine into a container. The file or directory is referenced by its full or relative path on the host machine.

This volume mounts the keystore and truststore files on the host to the Docker container.

```
docker run --env MSS_SERVER=localhost \
--env SERVICE_REGISTRY_PASSWORD=<enter password here> \
--volume ~/demo_keystore.bcfks:/sessionserver/etc/keystore.bcfks \
--volume ~/demo_truststore.bcfks:/sessionserver/etc/trustcerts.bcfks \
--publish 7443:7443 \
sessionserver
```

There is a downside to using a volume mount. Since keystore stores must be located on each Docker host where a container is running, your Docker container will not be very portable.

### *Extending an existing Docker image*

With this method you create a new Dockerfile to copy the files you need into the Docker image. This makes your Docker image more portable.

First, create a Dockerfile that will extend from the `hacloud/sessionserver` Docker image.

```
FROM hacloud/sessionserver:<for example, hacloud/sessionserver:latest or
hacloud/sessionserver:version>
```

```
COPY <your-path>/keystore.bcfks /sessionserver/etc/keystore.bcfks
COPY <your-path>/truststore.bcfks /sessionserver/etc/trustcerts.bcfks
```

Next, create the extended Docker image, naming it **demo**.

```
docker build -t demo .
```

Finally, run the demo image.

```
docker run --env MSS_SERVER=localhost \  
--env SERVICE_REGISTRY_PASSWORD=<enter password here> \  
--publish 7443:7443 \  
demo
```

## Specify Docker host name and port

The session server needs to broadcast its host name for MSS to find it. Because Docker generates a random unique name that isn't reachable outside the container, you need to specify your Docker host's name for MSS. It is also necessary to tell the session server which port you are publishing on your Docker host. Clients accessing the session server will end up hitting `<docker_host_name>:<docker_published_port>`.

```
--env HOST_NAME=docker_host_name  
--env SERVER_PORT=docker_published_port
```

## Examples

The examples, located in the `docker/samples` folder, walk you through four scenarios using Docker Compose. Compose is a tool that uses a YAML file to configure and run your applications with a single command.

### Prerequisites

To run the examples:

- ◆ Install Docker Compose. Review the [Docker documentation](#) on Docker Compose before proceeding.
- ◆ A running MSS server
- ◆ [A keystore file to secure TLS connections to the session server](#) that is trusted by MSS.
- ◆ [A truststore file that has the MSS server certificate in place](#)
- ◆ To [Build the session server Docker image](#)

The examples include:

- ◆ [Basic](#) - A basic example providing a demo keystore and truststore files in which you can import a MSS server certificate.
- ◆ [Hybrid](#) - An hybrid example which assumes a local Host Access for the Cloud installation and mounts existing, on disk, keystore and truststore files to the Docker container.
- ◆ [Extensions](#) - An extension example showing how to update, modify, and customize the web client.
- ◆ [Load Balance](#) - A load balancer example illustrating how to balance between linked containers.

## Basic

This basic example illustrates how to run the session server Docker image in Docker Compose. For this example you will need to import your MSS server's certificate into the provided sample `./certs/demo_truststore.bcfks` using something like KeyStore Explorer. Your MSS certificate, by default, is located at `/mss/server/etc/<computer-name>.cer`. See [Securing connections](#).

Before running the example, update the `MSS_SERVER`, `HOST_NAME`, and `SERVICE_REGISTRY_PASSWORD` values in `docker-compose.yml`.

- ♦ To start the session server service:

```
docker-compose up
```

- ♦ To run the service in a daemon (detached mode):

```
docker-compose up -d
```

- ♦ To look at running containers:

```
docker ps
```

## Hybrid

In this example a local installation of Host Access for the Cloud, with existing keystore and truststore files on disk is present. These files will be mounted (copied) to the Docker container.

Before running the example, update the `MSS_SERVER`, `HOST_NAME`, `SERVER_PORT`, and `SERVICE_REGISTRY_PASSWORD` values in the `.env` file.

To start the session server service:

- ♦ Copy `.env` and `docker-compose.yml` to `sessionserver/microservices/sessionserver/`.
- ♦ From this directory, run: `docker-compose up -d`

## Extensions

Using extensions and your own HTML, CSS, or JavaScript, you can update, modify, and customize the presentation of the web client from within the browser. See [Extending the Web Client](#) for more information.

This example sets `SPRING_PROFILES_ACTIVE` to **extensions-enabled** and maps the location of the extensions in `docker-compose.yml`.

Before running the example, update the `MSS_SERVER`, `HOST_NAME`, and `SERVICE_REGISTRY_PASSWORD` values in the `.env` file.

To start the session server service:

```
docker-compose up -d
```

You could also choose to extend the base `hacloud/sessionserver` Docker image and copy the extension files into the Docker container:

1. Create the Dockerfile that extends from the `hacloud/sessionserver` Docker image.

```
FROM hacloud/sessionserver
```

```
COPY ./certs/keystore.bcfks /sessionserver/etc/keystore.bcfks
COPY ./certs/trustcerts.bcfks /sessionserver/etc/trustcerts.bcfks
COPY ./extensions /sessionserver/extensions/
```

2. Create the extended Docker image and name it **extensions**.

```
docker build -t extensions
```

3. Update `docker-compose.yml` to use the new `extensions` image

```
version: '3'
services:
  sessionserver:
    image: extensions
    environment:
      - LOGGING_FILE=./logs/sessionserver.log
      - LOGGING_FILE_MAXSIZE=10MB
      - LOGGING_FILE_MAXHISTORY=10
      - MSS_SERVER=${MSS_SERVER}
      - SERVICE_REGISTRY_PASSWORD=${SERVICE_REGISTRY_PASSWORD}
      - SPRING_PROFILES_ACTIVE=extensions-enabled
    ports:
      - ${SERVER_PORT}:7443
```

## Load Balance

HAProxy is a load balancer. Learn more about [HAProxy](#) on their web site.

In this example, an **haproxy** service is included in the `docker-compose.yml` file. The example uses an `haproxy` image to balance between linked containers. This example uses SSL Bridging to link the containers.

To provide secure communication between the clients and the load balancer, you must update the `LOAD_BALANCER_CERT` property in the `.env` file with the location of the load balancer certificate.

To help you test, you can generate a self-signed certificate:

1. Generate a unique private key (KEY):

```
sudo openssl genrsa -out mydomain.key 2048
```

2. Generate a Certificate Signing Request (CSR):

```
sudo openssl req -new -key mydomain.key -out mydomain.csr
```

3. Create a Self-Signed Certificate (CRT):

```
sudo openssl x509 -req -days 365 -in mydomain.csr -signkey mydomain.key
-out mydomain.crt
```

4. Append KEY and CERT to `loadbalancer.pem`:

```
sudo cat mydomain.key mydomain.crt > ./etc/loadbalancer.pem
```

To start the session server and haproxy services:

```
docker-compose up -d
```

-or-

```
docker-compose up --scale sessionserver=n -d
```

Where  $n$  is the number of session server instances.

You can change the number of session server instances after the services start:

```
docker-compose scale sessionserver=n
```

**To access the session server and HAProxy stats page:**

- ♦ `https://server:7443`
- ♦ `http://server:1936/haproxy?stats`

Using:

- ♦ user: **admin**
- ♦ password: **password**



# 4 Managing

Creating and configuring sessions and making sure everything runs smoothly and securely means that your users will be successful. The following should help you administer and manage your sessions and host connections.

- ♦ [Connecting to the Host](#)
- ♦ [Providing Access to Sessions](#)
- ♦ [Logging](#)

## Connecting to the Host

Host Access for the Cloud supports IBM 3270, 5250 and VT hosts as well as UTS, T27 and ALC host types.

---

**NOTE:** You will first add and launch a session from the MSS Administrative Console before you complete the following steps.

---

### To connect to the host:

- 1 On the **Create New Session** dialog box, select the type of host you are connecting to from the drop down list.
- 2 On the Connection panel, identify the name of the host to which you want to connect. You can use a full host name or its IP address.
- 3 Type the number of the port you want to use.
- 4 Complete the information needed for the host connection.
- 5 Save your connection settings.

Your users gain access to the host through sessions that you create and configure. Sessions are created by an administrator in the MSS Administrative Console. When you launch a session from the Administrative Console, the web client Connection panel opens in a separate browser window. You configure connection options from this panel. Options vary depending on your host type.

- ♦ [Common connection settings](#)
- ♦ [3270 and 5250 connection settings](#)
- ♦ [How to test Terminal ID Manager criteria](#)
- ♦ [VT connection settings](#)
- ♦ [UTS connection settings](#)
- ♦ [T27 connection settings](#)
- ♦ [ALC connection settings](#)

## Common connection settings

These options are common to all supported host types.

- ◆ **Connect at startup**

By default, sessions are configured to connect to the host automatically when you create or open a session. However, you can set up a session so that it doesn't automatically connect to the host. Choose **NO** to manually connect to the host.

- ◆ **Reconnect when host terminates connection**

When set to Yes, Host Access for the Cloud attempts to reconnect as soon as the host connection terminates.

- ◆ **Protocol**

From the drop down list, select the protocol you want to use to communicate with the host. To establish a host connection, both the web client and the host computer must use the same network protocol. The available values are dependent on the host to which you are connecting. They are:

*Table 4-1 Protocol Descriptions*

Protocol	Description
TN3270	TN3270 is a form of the Telnet protocol, which is a set of specifications for general communication between desktop and host systems. It uses TCP/IP as the transport between desktop computers and IBM mainframes.
TN3270E	TN3270E or Telnet Extended is for users of TCP/IP who connect to their IBM mainframe through a Telnet gateway that implements RFC 1647. The TN3270E protocol allows you to specify the connection device name (also known as LU name), and provides support for the ATTN key, the SYSREQ key, and SNA response handling. If you try to use Telnet Extended to connect to a gateway that doesn't support this protocol, standard TN3270 will be used instead.
TN5250	TN5250 is a form of the Telnet protocol, which is a set of specifications for general communication between desktop and host systems. It uses TCP/IP as the transport between desktop computers and AS/400 computers.
Secure Shell (VT)	You can configure SSH connections when you need secure, encrypted communications between a trusted VT host and your computer over an insecure network. SSH connections ensure that both the client user and the host computer are authenticated; and that all data is encrypted

There are two authentication options available:

- ◆ **Keyboard Interactive** - You can use this authentication method to implement different types of authentication mechanisms. Any currently supported authentication method that requires only the user's input can be performed with Keyboard Interactive.
- ◆ **Password** - This option prompts the client for a password to the host after a host connection is made. The password is sent to the host through the encrypted channel.



Protocol	Description
Telnet (VT)	Telnet is a protocol in the TCP/IP suite of open protocols. As a character stream protocol, Telnet transmits user input from character mode applications over the network to the host one character at a time, where it is processed and echoed back over the network.
INT1 (UTS)	Provides access to Unisys 1100/1200 hosts using the TCP/IP network protocol.
TCPA (T27)	Use this protocol to connect to Unisys ClearPath NX/LX series or A Series hosts. TCPA Authentication is the process of verifying user login information. When properly configured, you can request a security credential from your application's credential server and send the credential back to the server. If the credential is valid, your application will be logged in; you do not have to enter a user ID or password. If the credential is not valid however, you will be prompted for a user ID and a password.
MATIP (ALC)	Mapping of Airline Traffic Over Internet Protocol (MATIP) uses TCP/IP for airline reservation, ticketing, and messaging traffic.

- ◆ **Enable emulation tracing**

You can choose to generate host traces for a session. **No** is the default. Select **Yes** to create a new emulation host trace each time the session is launched. The trace file is stored in `<install directory>/sessionserver/logs/hosttraces/<date (yyyymmdd)>/<trace-file>`.

## 3270 and 5250 connection settings

In addition to the common configuration settings, 3270 and 5250 host types require these specific settings.

- ◆ **Terminal model**

Specify the terminal model (also known as a display station) you want Host Access for the Cloud to emulate. There are different terminal models available depending on the host type.

If you choose **Custom Model**, you can set the number of columns and rows to customize the terminal model.

- ◆ **Use Kerberos automatic sign-on (5250 only)** **MSS** When set to **Yes** the user does not have to enter sign-on credentials. Kerberos automatic sign-on is configured in the MSS Administrative Console > Host Access for the Cloud. In configuring HACloud to use the Kerberos authentication protocol there are terms that you should understand and prerequisites to adhere to in advance of configuring this option. These options are explained in detail in the MSS Administrative Console > Host Access for the Cloud panel documentation, available from the Help button.

- ◆ **Terminal ID (3270 only)**

When Host Access for the Cloud connects to a Telnet host, the Telnet protocol and the host negotiate a terminal ID to use during the initial Telnet connection. In general, this negotiation will result in the use of the correct terminal ID, and so you should leave this box empty.

- ◆ **TLS/SSL Security**

SSL and TLS protocols allow a client and server to establish a secure, encrypted connection over a public network. When you connect using SSL/TLS, Host Access for the Cloud authenticates the server before opening a session, and all data passed between and the host is encrypted using the selected encryption level. The following options are available:

**Table 4-2** TLS/SSL Descriptions

Security options	Description
None	No secure connection is required.
TLS 1.2 - 1.0	Allow connection through TLS 1.2, TLS 1.1, TLS 1.0 depending on the capabilities of the host or server to which you are connecting. When <b>Verify server identity</b> is set to Yes, the client checks the server or host name against the name on the server certificate.
TLS 1.2	Select this value to connect using TLS. As part of the TLS protocol, the client checks the server or host name against the name on the server certificate when <b>Verify server identity</b> is set to Yes. This is highly recommended.

---

**NOTE:** See the section on [Securing connections](#) for information on adding trusted certificates, key stores, using SSH, and other advanced security information.

---

- ◆ **Verify server identity**


When TLS/SSL security is set to TLS 1.2 or TLS 1.2-1.0, you have the option to verify the host name against the name on the server certificate. It is highly recommended that you enable host name verification for all sessions.

- ◆ **Device name**

If you selected TN3270, TN3270E, or TN5250 as the protocol, specify the device name to use when the session connects to the host. The device name is also known as the host LU or pool. You can also choose to:

- ◆ **Generate a unique device name.** An unique device name will be automatically generated.
- ◆ **Use Terminal ID Manager** which displays additional settings to complete.
- ◆ **Prompt User.** When you select this option the end user will be prompted for the device ID each time a connection is attempted.

If you do not specify a device name for the session, the host dynamically assigns one to the session. A device name that is set within a macro will override this setting.

 To use Terminal ID Manager, you must have a Terminal ID Manager server configured. See [Terminal ID Manager](#) in the Management and Security Server Installation Guide.

If you selected **Terminal ID Manager** you can use it to provide IDs to client applications at runtime. You can use the Terminal ID Manager to manage pooled IDs for different host types. An ID is connection data that is unique for an individual host session.

If you decide to use Terminal ID Manager and have configured the Terminal ID Manager server, then you can select from the options below to configure the criteria for acquiring an ID. All criteria must be met in order for an ID to be returned.

---

**NOTE:** Keep in mind that by specifying a criterion, you are indicating that the ID should be allocated only when an ID that has that specific value is found. The set of criteria selected here must be an exact match of the set of criteria specified on at least one Pool of IDs in Terminal ID Manager before the ID request can succeed.

---

**Table 4-3** Terminal ID Manager Criteria

Criterion	Description
Pool name	Include this attribute and enter the name of the pool to limit the ID search to a specified pool.
Client IP address	The IP address of the client machine will be included as part of the request for an ID.
Host address	The address of the host configured for this session will be included as part of the request for an ID.
Host port	The port for the host configured for this session will be included as part of the request for an ID.
Session name	When selected, requires that the ID is configured to be used by this session exclusively.
Session type	The session type (for example, IBM 3270, IBM 5250, UTS, ALC or T27) is always included as part of any request for an ID.
User name	<p>Use this criterion to ensure that only IDs created for exclusive use by specific users will be allocated. The current user's name, which must be found on an ID before it can be allocated, is the name of the user that the session is allocated to at runtime.</p> <p>To configure a session based on user names, a default place holder user name is available: <b>tidm-setup</b>.</p> <p>For the administrator to configure sessions using <b>tidm-setup</b>, the Terminal ID Manager needs to have IDs provisioned for <b>tidm-setup</b>. You can override the default name with one of your own by modifying the <code>&lt;install-dir&gt;/sessionserver/conf/container.properties</code> file as follows:</p> <pre>id.manager.user.name=custom-username</pre> <p>Where <code>custom-username</code> is replaced by the name you want to use.</p>
Application name (UTS)	The name of the host application will be used as part of the request for an ID.

To determine the connection attempt behavior if Terminal ID Manager does not successfully allocate an ID to this session, use **If ID is not allocated**:

- ◆ **Fail connection attempt** -If selected, the session will not attempt to connect when an ID is not allocated.
- ◆ **Allow connection attempt** -If selected, the session will attempt to connect when an ID is not allocated. The attempt may be rejected by the host. There are some host types that permit a user to connect without an ID.

To confirm that Terminal ID Manager can provide an ID using the criterion and value selections you have made, click [Test](#).

- ♦ **Send keep alive packets** - Use this setting to provide a constant check between your session and the host so that you become aware of connection problems as they occur. Choose from the following types of keep alive packets:

This option	Does this....
None	The default. No packets are sent.
System	The TCP/IP stack keeps track of the host connection and sends keep alive packets infrequently. This option uses fewer system resources than the Send NOP Packets or Send Timing Mark Packets options.
Send NOP packets	Periodically a No Operation (NOP) command is sent to the host. The host is not required to respond to these commands, but the TCP/IP stack can detect if there is a problem delivering the packet.
Send timing mark packets	Periodically a Timing Mark Command is sent to the host to determine if the connection is still active. The host should respond to these commands. If a response is not received or there is an error sending the packet, the connection shuts down.

**Keep alive timeout (seconds)** - If you choose to use either the Send NOP packets or the Send timing mark packets option, select the interval between the keep alive requests set. The values range from 1 to 36000 seconds (1 hour); the default is 600 seconds.

## How to test Terminal ID Manager criteria

The Terminal ID Manager provides IDs to client applications at runtime. To confirm that Terminal ID Manager can provide an ID using the criteria and value selections you selected use this test option.

Criteria for the current session are specified on the Connection panel after selecting **Use Terminal ID Manager** from either the Device Name (3270, 5250 host types), the Terminal ID (UTS) field, or the Station ID (T27) field. By default, the selected criteria for the current session are displayed.

Click **Test** to confirm that Terminal ID Manager can provide an ID matching the configured criterion and value selections. The test returns the name of an available ID that satisfies the selected attribute values.

### Testing for other criteria and values

You can also use this panel to test criteria different from those associated with the current session.

1. Select any of the session types from the Session type list, and select the criteria you want to test. You can test alternate values that you want to use in a sample Terminal ID Manager request.
2. Click **Test** to confirm that Terminal ID Manager can provide an ID matching the criterion and value selections. The test returns the name of an available ID that satisfies the selected values.

## VT connection settings

In addition to the **Common connection settings**, VT hosts require additional settings. These settings vary depending on the protocol you are using; Telnet or SSH. The settings are applicable to both protocols unless noted.

**Table 4-4** VT session configuration options

<b>VT Settings</b>	<b>Description</b>
Terminal ID	This setting determines the response that Host Access for the Cloud sends to the host after a primary device attributes (DA) request. This response lets the host know what terminal functions it can perform. The Host Access for the Cloud response for each Terminal ID is exactly the same as the VT terminal's response; some applications may require a specific DA response. This terminal ID setting is independent of the Terminal type setting. The options are: VT220, VT420, VT100, DEC-VT100, and VT52.
Allow unknown hosts (SSH)	This setting provides the administrator with the ability to decide whether the web client will allow unknown hosts. Options are: <ul style="list-style-type: none"><li>◆ <b>Yes</b> - Unknown hosts and all SSH connections are permitted. Web client users are not prompted about whether hosts should be trusted.</li><li>◆ <b>Ask</b>- The web client user is prompted whether the host should be trusted when they connect to an unknown host they haven't encountered before. If they choose to trust the host, then its public key is stored in their user preferences and subsequent connections will not elicit a prompt unless the host key changes.</li><li>◆ <b>No</b>- No unknown hosts are permitted. Only those hosts the administrator chooses to trust when configuring the session are permitted. End users are never prompted and the session will either connect or not connect depending on the administrator's choices.</li></ul>
Suppress banner messages (SSH)	When enabled, the SSH banner is not displayed. This option is useful when recording SSH login macros.
Local Echo (Telnet)	Automatic (default). How Host Access for the Cloud responds to remote echo from a Telnet host: Automatic attempts to negotiate remote echo, but does what the host commands. Yes means Host Access for the Cloud negotiates local echo with the host, but always echoes, while No means Host Access for the Cloud negotiates remote echo with the host, but does not echo.
Renegotiate Echo (Telnet)	No (default). When set to Yes, passwords are not displayed on the local screen, but all other typed text is visible. Host Access for the Cloud supports the Telnet Suppress Local Echo (SLE) option when connected to a host in half-duplex mode. This means that Host Access for the Cloud will suppress character echo to the host computer, and with SLE support Host Access for the Cloud can be instructed to suppress echo locally.
Set Host Window Size	Yes (default). This setting sends the number of rows and columns to the Telnet host whenever they change. This enables the Telnet host to properly control the cursor if the window size is changed.
Request Binary (Telnet)	No (default). Telnet defines a 7-bit data path between the host and the terminal. This type of data path is not compatible with certain national character sets. Fortunately, many hosts allow for 8-bit data without zeroing the 8th bit, which resolves this problem. In some cases, however, it may be necessary to force the host to use an 8-bit data path by selecting this check box.

VT Settings	Description
Send LF after CR (Telnet)	No (default). A "true" Telnet host expects to see a CrNu (carriage return/null) character sequence to indicate the end of a line sent from a terminal. There are some hosts on the Internet that are not true Telnet hosts, and they expect to see a Lf (linefeed) character following the Cr at the end of a line. If you're connecting to this type of Telnet host, select Yes.
Ctrl-break sends (Telnet)	Choose what sequence Ctrl-break sends to the host when pressed. Options are: Telnet break sequence (the default), Interrupt process, or Nothing.
Host Character Set	The default value for the Host character set depends on the type of terminal you are emulating. This setting reflects the current terminal state of VT Host Character Set, which can be changed by the host. The associated default setting, saved with the model is DEC Supplemental.
Auto Answerback	No (default). This setting specifies whether the answerback message (set with the Answerback property) is automatically sent to the host after a communications line connection.
Answerback String	<p>This setting allows you to enter an answerback message if the host expects an answer in response to an ENQ character.</p> <p>The answerback string supports characters with codes less than or equal to 0xFFFF via Unicode escape sequences. The escape sequence begins with \u followed by exactly four hexadecimal digits. You can embed Unicode escape sequences in any string. For example, this embedded \u0045 will be interpreted as this embedded E, since 45 is the hexadecimal code for the character E.</p> <p>To pass Unicode escape sequences to the host, escape the sequence with a leading backslash. For example, to send the string literal \u001C to the host, map a key to \\u001C. Host Access for the Cloud will convert this to the string \u001C when that key is pressed and send the 6 characters of the resulting string to the host.</p>

## UTS connection settings

In addition to the common connection settings, UTS hosts require these additional settings:

**Table 4-5** UTS INT1 session configuration options

UTS INT1 options	Description
Application	<p>The name of the host application or host operating mode to be accessed.</p> <p>This is the word or phrase that the local machine sends to the host when you first establish communication with the host. If you were using a host terminal, this would be the \$\$OPEN name of the application. The application name is typically the same as the environment name. However, they can be different. For example, the environment name might be MAPPER, and the application might be UDSSRC. During a terminal emulation session, you would type \$\$OPEN MAPPER at the prompt, and INT1 would send UDSSRC to the host once the connection is established.</p>

UTS INT1 options	Description
TSAP	The desired Transport Service Access Point (TSAP), up to 32 characters (such as TIPCSU for TIP connections, RSDCSU for Demand connections).A TSAP is required only if you are connecting to a Host LAN Controller (HLC) or to a Distributed Communications Processor (DCP) in IP router mode. If you're not sure which value to use, contact your host administrator.
Initial transaction	The character, word, or phrase that the local machine will send to the host when communication with the host is first established (up to 15 characters).This parameter is optional and is primarily used with TIP. For example, you might type ^ to run MAPPER. This parameter can also be used to transmit passwords.
Start transaction	When you configure an initial transaction, by default, the data is sent as soon as the session connection is established. You can decide when to send an initial transaction by using a particular string to trigger the initial transaction.  For example, to wait for a successful login before sending initial transaction data, type in a string to be used to identify a successful login.  You can use this setting in combination with <b>Send initial transaction</b> .
Send initial transaction	You can determine when the initial transaction is sent: <ul style="list-style-type: none"> <li>◆ <b>Immediately</b> - Default.</li> <li>◆ <b>When start of entry (SOE) character is received</b> - Useful when multi-line transactions must be completed before sending the string.</li> <li>◆ <b>After specified milliseconds</b></li> </ul>
Terminal ID	Choose whether to specify a terminal ID or use the Terminal ID Manager. To specify a terminal ID, type it in the <b>Specify Terminal ID</b> field.  If you choose <b>Use Terminal ID Manager</b> , you are prompted to select the Terminal ID attributes you want to use to obtain an ID. See <a href="#">Terminal ID Manager Attributes</a> .  To test the attributes, click <b>Test</b> .
Specify Terminal ID	The Terminal ID, a terminal identifier (typically up to 8 alphanumeric characters) to use for the communication session associated with this path. Also known as a TID or PID, each terminal ID should be unique to the host.

## T27 connection settings

Along with the common connection settings, you can configure these additional T27 connection options:

**Table 4-6** T27 Connection Settings

T27 options	Description
Terminal type	Select the type of terminal to emulate during the session. T27 emulation supports Unisys TD830, TD830 ASCII, TD830 INTL, and TD830 NDL terminal types

<b>T27 options</b>	<b>Description</b>
Request binary	<p>You must enable the Request binary option when you require pass through printing. The default is No.</p> <p>TCPA defines a 7-bit data path between the host and the terminal emulator. This type of data path is not compatible with certain national character sets. However, many hosts allow for 8-bit data without zeroing the 8th bit, which resolves this problem. However, it may be necessary to force the host to use an 8-bit data path; you can do so by selecting this option.</p>
Line width	Select the number of characters the host will send to the client. The default is 80 characters.
TLS/SSL security	See <a href="#">Table 4-2</a> TLS/SSL Descriptions for a description of the various options.
Station ID	<p>Choose whether to specify a station ID or use the Terminal ID Manager. To specify a station ID, choose <b>Specify Station ID</b> and type the name in the Station ID field.</p> <p>Each station id should be unique to the host and typically consists of up to eight alphanumeric characters.</p> <p>If you do not specify a station id for the session, the host dynamically assigns one to the session.</p> <p>If you select Use Terminal ID Manager, you will see a number of Terminal ID criteria to configure. See <a href="#">Terminal Manager ID Criteria</a> for descriptions of the various options.</p>

## ALC connection settings

In addition to the common connection settings, ALC hosts require these additional settings:

**Table 4-7** ALC Connection Settings


<b>ALC options</b>	<b>Description</b>
TLS/SSL security	See <a href="#">Table 4-2</a> TLS/SSL Descriptions for a description of the various options.
Character encoding	Choose ASCII, EBCDIC, or IPARS (default) as the code set.
Configuration file	Enter the configuration (CNF) file that associates configuration information appropriate for a specific host type.



ALC options	Description
Terminal address	<p>Select whether you want to specify the terminal address or use the Terminal ID Manager.</p> <ul style="list-style-type: none"> <li>Terminal address - Specify whether to use 2-byte or 4-byte addressing mode.</li> </ul> <p>Although a unique 5-byte address is required when you specify the terminal ID instead of using ID Manager, this option specifies how many bytes of the 5-byte terminal ID address are sent with each message for the purposes of multiplexing. If you specify 2-byte addressing mode, only the last 2 bytes of the ASCU (Agent Set Control Unit) cluster address (A1, A2) are sent. If you specify 4-byte addressing mode, the full ASCU cluster address (H1, H2, A1, A2) is sent.</p> <p>Specify the unique 5-byte terminal address for this session. The terminal address is made up of five 2-hex-digit values in this order: H1, H2, A1, A2, and TA (terminal address). This unique address is usually assigned by the network administrator.</p> <ul style="list-style-type: none"> <li><b>Terminal ID Manager</b>- Provides IDs to client applications at runtime. If you choose this option, there are additional configuration options to complete. See <a href="#">Terminal ID Manager Criteria</a> for descriptions of those options.</li> </ul>

## Providing Access to Sessions

Your users have access to their assigned sessions through a URL you provide (for example, `https://<sessionserver>:7443/`). From this URL users select which session to open from the list of available sessions you have configured for them.




Your users can switch between sessions, open additional sessions and close sessions with which they are no longer working.

### Single session mode

Alternatively, you can use **single session mode** and provide URLs to particular sessions that are launched using the name parameter, (for example a direct link on a company portal page). To enable the launch of a single session use the query parameter `singleSession`. You can use this parameter on its own to just launch the web client in single session mode, for example, `http://<sessionserver>:7443/?singleSession`, or it can be used in conjunction with a named

session parameter to launch a particular named session in single session mode: `http://<sessionserver>:7443/?singleSession&name=HumanResources`. The order of the parameters does not matter.

When your users access a single session, they cannot switch between open sessions and cannot open new sessions. A new session will not be launched if the specified session already exists when the user opens the link.



If you want all sessions on the session server to run in single session mode:

- Open `<install-dir>/sessionserver/conf/container.properties`
- Add `webclient.singleSession=true` to the file.

## Logging

### Locating log files

There are two log files available:

- `<install_dir>/sessionserver/sessionserver.log` - the log file for the session server application.
- `<install_dir>/sessionserver/container.log` - the log file for the container that hosts the Host Access for the Cloud application.

### Configuring log rotation

You can configure log rotation by editing these values in

`<install_dir>\sessionserver\microservices\sessionserver\service.yml`:

```
logging.file.max-size  
logging.file.max-history
```

### Setting logging levels

There are various types of logging levels you can use to produce different types of information. You can configure logging levels in

`<install_dir>\sessionserver\microservices\sessionserver\service.yml`.

---

**NOTE:** Lines in `service.yml` must be indented using spaces.

---

Use the following format to set logging levels:

```
- name: logging.level.<logger>
  value: "<log level>"
```

Where `<logger>` is the name of the logger to adjust and `<log level>` is one of the following:

- ♦ Trace - designates finer-grained informational events than Debug
- ♦ Debug - designates fine-grained informational events that are most useful to debug an application.
- ♦ Info - designates informational messages that highlight the progress of the application at coarse-grained level.
- ♦ Warn - designates potentially harmful situations.
- ♦ Error - designates error events that might still allow the application to continue running.
- ♦ Fatal - designates very severe error events that will presumably lead the application to terminate.

---

**NOTE:** You must restart the session server after any changes to `service.yml`.

---

## Web client to session server logging

While the browser provides a basic mechanism for logging to its JavaScript console, the Web Client extends this capability and, with some configuration, you can log events to the session server for viewing by an administrator.

By default, nothing is logged to the session server. You must set the log level, following the instructions below, in order to enable this feature.

The available log levels are: debug, info, warn, error, or off. The default log level is off.

## Adjusting the logging level for all Web client users

To adjust the logging level for all Web clients, add the following entry to

```
<install_dir>\sessionserver\microservices\sessionserver\service.yml
```

```
- name: <logger>
  value: "<log level>"
```

Where `<logger>` is:

```
logging.level.com.microfocus.zfe.webclient.core.handler.ClientLoggingHandler-webclient
```

---

**NOTE:** Use caution when increasing the logging level for all Web Client users in a production environment due to a potential increase in network traffic.

---

## Adjusting the logging level for an individual user

There are two options for adjusting the logging level for individual users:

To temporarily adjust the logging level for a particular user's Web client instance without requiring a session server restart, instruct the user to add the following URL parameter when loading the Web client in their browser:

```
https://mysessionserver.com:7443/?log=<log level>
```

To adjust the logging level for an individual user without requiring them to make changes, add the following entry to `service.yml`:

```
- name: <logger>  
  value: "<log level>"
```

Where `<logger>` is:

```
logging.level.com.microfocus.zfe.webclient.core.handler.ClientLoggingHandler-webclient-<username>
```

Where `<username>` is the user name of the person whose logging levels you are adjusting.

---

**NOTE:** Logging based on a username requires an authentication mode that involves usernames.

---

# 5 Using HACloud

There are multiple session and display options available so you can personalize your session and make sure you are working efficiently.

- ◆ [Display Settings](#)
- ◆ [Map Keys](#)
- ◆ [Configure User Macros](#)
- ◆ [Transfer Files](#)
- ◆ [Specify Copy and Paste Options](#)
- ◆ [Working with Sessions](#)
- ◆ [Creating Macros](#)
- ◆ [Printing](#)
- ◆ [Customize Sessions](#)
- ◆ [Set User Preferences](#)

## Display Settings

Display settings vary depending on the host type and are specific to the session you are configuring.

- ◆ [Color mapping](#)
- ◆ [Configure hotspots](#)
- ◆ [Configure screen dimensions for VT, UTS and T27 hosts](#)
- ◆ [Set cursor options](#)
- ◆ [Set font options](#)
- ◆ [Set VT scrollbar buffer options](#)
- ◆ [Set keyboard options](#)
- ◆ [Terminal Settings](#)
- ◆ [Set other display options](#)

## Color mapping

You can customize the color of your screen and the appearance of different host attributes in the terminal window. For each item, you can select a color for the foreground and the background colors for all supported host connections. Colors are specified using the color grid or by entering the Hex code format.

There are many web sites that list available Hex colors, for an example see [w3schools.com HTML Color Picker](http://w3schools.com/html/color-picker/)

You may see different options depending on the type of host connection.

### Options specific to UTS hosts:

- ◆ **Use color information from the host** - To use the colors specified here rather than any colors specified by the host, clear this option.
- ◆ **Enable blink** - To disable blinking, clear this option.
- ◆ **Select attribute to edit** - In UTS emulation, colors are set directly by the host. You can specify colors for text associated with specific screen display options. Including the following and available combinations:  
Plain, Underline(UND), Strikethru (STK), Left Column Separator (LCS), Control Page, and Status Line (OIA).
- ◆ **Video intensity** - The video intensities, Blink, Dim, Protected, and Reverse are combined with the attributes to create additional combinations. For example, you could map foreground or background colors to all cells with Dim + Blink + Underline or Reverse + Protected + Strikethru + Underline.  
When you select a video intensity (or combination of intensities), those intensities are combined with the value of the attribute drop down list to form a single color mapping.

### Options specific to VT and T27 hosts:

- ◆ **Enable blink** - To disable blinking, clear this option.
- ◆ **Enable bold** - Displays text set with bold attributes as bold text in the terminal window. To display bold characters as plain text, clear this option.
- ◆ **Enable underline** - Displays text with underline.
- ◆ **Inverse video** (VT-only) - This option reverses the foreground and background colors when the VT host sends an inverse video escape sequence. If this option is not enabled, the inverse video sequences sent from the host are ignored.

### To customize colors for all host types:

- 1 From the left navigation panel, click **Display**.
- 2 Under **Color Mappings**, click the background color field to open the color grid. From the color grid, select the color you want to use as the host background color. Alternatively, type the Hex color number for the color you want to use.
- 3 From the drop down list, select the default host color you want to change.  
For example, if you select **host pink** from the drop down list and then change the foreground color to red, whenever you encounter pink text it will appear as red.
- 4 Open the color grid for the **Foreground** to choose a color to map the new color for the text or type the Hex code you want to use. Select **Background** to map the new color to the background field.
- 5 Click **Save** to close the Display panel and resume configuring your host connection.

**Restore defaults** clears any changes you made and resets the colors to the default host settings.

## Configure hotspots

Hotspots are buttons that appear over common host commands in terminal sessions. When you use hotspots you can control the terminal session using a mouse or a finger-tap instead of the keyboard. The hotspot transmits a terminal key or command to the host. By default, hotspots are configured for the most common 3270, 5250, and VT commands.

Hotspots are enabled and visible by default, however you can disable hotspots for a particular session or choose to hide them.

- ◆ **Enable hotspots**

Choose **No** to disable hotspots for the session you are connecting to.

- ◆ **Show hotspots**

Choose **No** to hide hotspots on the screen. Hotspots remain functional.

*Table 5-1 Hotspots for 3270 Hosts*

Hotspot	Description
PF1...PF24	Transmits a PF1...PF24 to the host
PA1, PA2, or PA3	Transmits a PA1, PA2, or PA3 to the host
enter	Transmits an Enter key to the host
more	Transmits a Clear key to the host

*Table 5-2 Hotspots for 5250 Hosts*

Hotspot	Description
enter	Transmits an Enter key to the host
more...	Transmits a Roll Up key to the host (scrolls down one page)
PF1 - PF24	Transmits a PF1...PF24 to the host

*Table 5-3 Hotspots for VT Hosts*

Hotspot	Description
F1 - F20	Transmits a F1...F20 to the host

## Configure screen dimensions for VT, UTS and T27 hosts

As an administrator you can select the number of columns and rows for VT, UTS and T27 sessions.

- 1 Open the Display panel.
- 2 Under **Dimensions**, specify the number of columns and rows you want each screen to possess. The default values are 80 columns by 24 rows.

There are some host-specific settings available:

- ◆ **Pages** - If you are connecting to a T27 host screen, you can set the number of pages to display. The default is 2.
- ◆ **Clear on host change** - If you are connecting to a VT host screen, select this option to clear the terminal window and move the contents to the scrollbar buffer when the column size changes.

3 Click **Save**.

## Set cursor options

Use the cursor options to configure the appearance and behavior of the cursor and ruler.

This option	Does this....
Cursor type	<ul style="list-style-type: none"><li>◆ <b>Underline</b> displays the text cursor as an underline.</li><li>◆ <b>Vertical bar</b> displays the cursor as a vertical line.</li><li>◆ <b>Block</b> displays the text cursor as an inverse video block.</li></ul>
Ruler type	<ul style="list-style-type: none"><li>◆ <b>Vertical</b> displays a vertical ruler at the cursor position.</li><li>◆ <b>Horizontal</b> displays a horizontal ruler at the cursor position.</li><li>◆ <b>Crosshair</b> displays both a horizontal and vertical ruler at the cursor position.</li></ul>
Cursor color	Click the color field to open the color grid. From the color grid, select the color you want to use as the color of both the cursor and ruler. Alternatively, type the Hex color number for the color you want to use.
Cursor blinks	By default, the cursor (whether in block or underline mode) blinks. Clear this option to display a visible non-blinking cursor.

## Set font options

Use these font options to make sure that your terminal characters display with your preferred font size and style.



<b>This option</b>	<b>Does this...</b>
Font size	<ul style="list-style-type: none"> <li>◆ <b>Auto</b> (default) The font scales automatically according to the size of the window.</li> </ul> <p>With this option selected, you can choose to <b>Preserve the aspect ratio</b> which means that the font size will be adjusted dynamically but the terminal display will not be stretched or scaled to fill the available space.</p> <ul style="list-style-type: none"> <li>◆ <b>Fixed</b> Specify the size, in pixels, for the terminal window display.</li> </ul>
Zero character	<p>To differentiate the default zero character from the letter O, select one of the following options:</p> <ul style="list-style-type: none"> <li>◆ <b>Default</b></li> <li>◆ <b>Zero with a slash</b></li> <li>◆ <b>Zero with a dot</b></li> </ul>

## Set VT scrollback buffer options

The VT scrollback buffer contains the data that has scrolled off the display and is no longer accessible by the host computer. When a scrollback buffer exists, you can view it by using the vertical scroll bar.

The scrollback buffer is enabled by default. When enabled, the session maintains a buffer of lines that have scrolled off the terminal screen. This option is available to all users when they are granted permission to modify **Terminal Display Settings** by the administrator.

<b>This option</b>	<b>Does this...</b>
Scrollback row limit	Limits the number of rows held in the scrollback buffer. The default setting is 500 rows.
Save display before clearing	When selected (the default), the data on the terminal display moves into the scrollback buffer when you, or the host, clear the terminal display. If you prefer not to have the terminal display saved to the scrollback buffer, clear this option; when the terminal display is cleared, the data is discarded.
Save from scrolling regions	When top and bottom screen margins are set (for example, by a text editor such as EDT or TPU, or with the DECSTBM function) the area within the margins is called the scrolling region. When this option is cleared, scrolling text within this region isn't saved to the scrollback buffer. Select this option to save information within scrolling regions to the scrollback buffer. <b>Note:</b> This can cause display memory to fill quickly.
Save before clearing from any row	This setting specifies whether data that has been cleared from a portion of the terminal window is saved in display memory.
Compress blank rows	Select this option to save room in display memory by compressing multiple blank rows into a single blank row.

## Set keyboard options

You can set the following keyboard options:

### 3270 keyboard options

- ◆ **Typeahead**

When this option is selected, Host Access for the Cloud buffers the characters that you type in the terminal window. Typeahead allows you to keep typing after you send data to the host. Without typeahead, characters you type are ignored until the host is ready for more data.

- ◆ **Word wrap**

When this option is selected, word wrap functionality is enabled within a multi-line, unprotected field. In word wrap mode, some of the blank spaces between words are replaced by line breaks so that each line is visible in the terminal window and can be read without horizontal scrolling.

- ◆ **Attention key sends**

Specifies what is sent when the ATTN key is pressed. The options are Telnet break, Abort output, and Interrupt process.

### 5250 keyboard options

- ◆ **Typeahead**

When this option is selected, Host Access for the Cloud buffers the characters that you type in the terminal window. Typeahead allows you to keep typing after you send data to the host. Without typeahead, characters you type are ignored until the host is ready for more data.

- ◆ **Error auto reset**

When selected, the next key pressed after a keyboard error clears the error, restores the previous error line data, and attempts to execute the keystroke as follows:

- ◆ If the cursor is in a valid input field and the key is a data key, the data is entered there if it is valid data for that field (for example, a numeric character in an input field that only accepts numbers).
- ◆ If the cursor is in a valid input field and the key is a function key, the key operation is executed.
- ◆ If the current cursor position is not in a valid input field and the key is a data key, the cursor is moved to the next valid input field and the data is entered there if it is valid data for that field.
- ◆ If the current cursor position is not in a valid input field and the key is a function key, the cursor is moved to the next valid input field and the key is ignored.
- ◆ If the current screen contains no valid input fields, you'll see an error message with each keystroke you press, and no keystrokes are executed

When cleared, you must press Reset to clear the error message from the error line before you can resume data entry.

By default, this option is not selected.

- ◆ **Waive field checks for PF key**

Select this option to allow PF keys to be sent to the host from restricted fields. This option is cleared by default.

## VT keyboard options

- ◆ **Backspace sends**

Configures the function that the Backspace key sends. On the VT terminal keyboard the back arrow key (<x) is configurable: it can send either a delete (ASCII 127) or a backspace (ASCII 8) character.

- ◆ **Local echo (VT)**

This option causes each character typed at the keyboard to be displayed on the screen. This option is cleared by default, because most hosts echo back received characters.

- ◆ **Cursor keys**

Controls the characters that the four arrow keys (on both the numeric and editing keypad) transmit. This setting is typically set by the host. In general, you should keep this set to **Normal**.

If the arrow keys aren't working properly, it may mean that this option remained incorrectly set to **Application** when a host program terminated abnormally. Changing this setting back to **Normal** should fix the problem with the arrow keys.

- ◆ **Keypad**

Controls the characters that the numeric keypad keys transmit. This setting is typically set by the host. In general, you should keep this set to **Numeric**.

If the number or PF keys aren't working properly, it may mean that this option was incorrectly left set to **Application** when a host program terminated abnormally. Changing this setting back to **Numeric** should fix the numeric keypad.

## T27 keyboard options

- ◆ **Enable lower case (T27)**

Enables lower case, as well as upper case letters to be displayed on the screen. Default. If this is option is disabled only upper case letters will display.

## Terminal Settings

Terminal settings vary depending on your host type.

### 3270 and 5250 terminal settings

- ◆ **Host character set**

Select the 3270 or 5250 host character set you want to use. This setting chooses a conversion table to convert host characters (EBCDIC) into PC characters (ANSI). This setting should match the national character set used by your host system. If it doesn't match, then some characters, such as accents, may not display correctly. See your host documentation for definitions of the characters in each set. The default value is US English (037).

- ◆ **Country extended graphics code** (3270 only)

With this option selected (the default), additional characters are available in the configured National character set. See your host documentation for details

## VT terminal settings

- ◆ **Terminal type** (VT)

Specifies which terminal should be emulated. These choices affect the codes generated by the numeric keypad, the interpretation of control functions, and the response to terminal identification requests.

- ◆ **Terminal ID** (VT)

Specifies the response that Host Access for the Cloud sends to the host after a primary device attributes (DA) request. This response lets the host know what terminal functions it can perform. This setting is independent of the terminal type setting. When set to the default value of Reflection, Host Access for the Cloud responds to a primary DA request with the set of features it supports. If your host requires a more specific terminal ID, select another value from the list.

- ◆ **New line** (VT)

Select this option to send both a carriage return and linefeed when you press Enter. When Host Access for the Cloud receives a linefeed, form feed, or vertical tab, it moves the cursor to the first column of the next line. When this option is cleared (default), the Enter key sends only a carriage return. A linefeed, form feed, or vertical tab received from the host moves the cursor down one line in the current column. If lines on the display keep getting overwritten (that is, the host is not sending a linefeed along with a carriage return), select this option. If the New line option is selected but the host does not expect to receive a linefeed with each carriage return, lines will be double-spaced on the display.

## T27 terminal settings

- ◆ **Host character set** (T27)

Using this option you can specify host to screen translation. Select the language used to convert characters received from the host before they are displayed on the local machine. The default is No translation.

## Set other display options

Some display options are host-specific as noted below. When the host type is not indicated, the options apply to all supported host types.

This option	Does this....
Column separator style (5250)	Use this option to specify which character (if any) should be used to render column separators in 5250 terminal sessions. The options are: <ul style="list-style-type: none"> <li>◆ <b>Dots</b>- Dots are used to separate columns. The default.</li> <li>◆ <b>Vertical bars</b> - Vertical lines are used to separate columns.</li> <li>◆ <b>None</b> - No characters are used to separate columns</li> </ul>
Input field underlining (3270, 5250)	You can determine how the underlining of host input fields is handled: <ul style="list-style-type: none"> <li>◆ <b>Host controls underlining</b> (Default)</li> <li>◆ <b>Always underline input fields</b></li> <li>◆ <b>Never underline input fields</b></li> </ul>
Status line (VT)	To enable a status line at the bottom of the display. <p>Choose:</p> <ul style="list-style-type: none"> <li>◆ <b>None</b> to disable the status line. (Default)</li> <li>◆ <b>Indicator</b> to display the page, cursor position, and printer status.</li> <li>◆ <b>Host Writable</b> to have the host application display information in the status line.</li> </ul>
Preserve aspect ratio	Select this option to maintain the host screen aspect ratio regardless of the size of the browser window. Aspect ratio describes the proportional relationship between the width of an image and its height.
Display OIA (3270, 5250)	Select this option to display the operation and status messages in the Operator Information Area (OIA) at the bottom of the terminal window . By default, OIA display is enabled.
Display status line (ALC)	Turns on a status line at the bottom of the display.
Ignore mouse click on window activation	When a mouse click activates the terminal window, this option specifies whether actions such as updating the terminal cursor position, clearing a selection, or executing a hotspot are also performed. By default, these actions are not performed.
Auto wrap (VT)	When selected, characters automatically wrap at the right margin and continue on the next line. When cleared, characters do not wrap when they reach the right margin of the display. New characters overwrite the character at the right margin until a carriage return is entered.

## Map Keys

You can create keyboard shortcuts that perform any assignable action during a session. The Key Mappings settings page provides a view of the default keyboard map for each host type and the mapped custom keys, indicated in boldface type, for that session.



### Mapping keys as an administrator and as an end-user

There are a few differences in behavior between the administrator and the end-user when mapping keys.

- ♦ End users can only add or modify key mappings if they are granted permission by the administrator using the **User Preference Rules** panel.
- ♦ Any changes the administrator makes show up to the end user as indistinguishable from default host key mappings. Once granted permission, the person can modify, add or delete any mappings regardless of any administrator changes. However restoring key mappings only restores them back to the modified state created by the administrator for the current session.

### Adding or modifying mapped keys

- 1 From the toolbar, click **Settings**.
- 2 From the left navigation pane, open the **Key Mappings** panel. The mapped keys for the host type you are connecting to are visible.
- 3 To add a new key mapping:

- ♦ Click . You can choose to type the key sequence you want to use or use the keyboard by toggling  between the two options.
- ♦ From the **Action** drop down list, select the action you want to associate with the key selection. If you select **Send text**, enter the string you want sent to the host in the **Value** field. Likewise, if you select **Run Macro**, choose the macro you want triggered by the keyboard shortcut. You must create the macro before you can map it to the Run Macro action.

The Send text action supports mapping characters with codes less than or equal to 0xFFFF via Unicode escape sequences. The escape sequence begins with `\u` followed by exactly four hexadecimal digits. You can embed Unicode escape sequences in any string. For example, *this embedded \u0045* will be interpreted as *this embedded E*, since 45 is the hexadecimal code for the character *E*.



To pass Unicode escape sequences to the host, escape the sequence with a leading backslash. For example, to send the string literal `\u001C` to the host, map a key to `\\u001C`. Host Access for the Cloud will convert this to the string `\u001C` when that key is pressed and send the 6 characters of the resulting string to the host.

The **Disable** action renders the key inoperable. When pressed the key will not initiate any action. This differs from the **Unmap** action which removes the key mapping but preserves a browser short-cut if it is defined.

- ♦ Click the blue check mark to accept the mapping and add the key map to the session.
- 4 To modify an existing mapping:

Select the row containing the key you want to modify.



Follow the steps for adding a new key mapping, clicking  to save the new mapping. Alternatively, you can click away from the modified row and the change will be saved. All new and modified key maps are indicated in boldface type. You can restore the original key mapping at any time by clicking .

## Filtering the list

The Filter field makes it easy to see just those mappings you are interested in. The filter is based on keywords and affects each column of the table. For example, if you enter **Send text** in the Filter field, only keys mapped to the **Send text** action are displayed.

Using the **Show only modified mappings** option lets you see only those mappings that have been previously modified.

### Some things to remember:

- ◆ **Mapping right and left modifier keys to individual actions**

You can map the right and left modifier keys to individual actions. However when they are combined with other keys, there is no differentiation between the right and left keys. For example, Left-Alt can be mapped to Action-A while Right-Alt is mapped to Action-B, but Left-Alt + H will be stored as Alt+H and both Left-Alt+H and Right-Alt+H will be associated with a single mapped action.

- ◆ **Key stroke combinations and copy/paste operations**

Different key stroke combinations are also used for copy/paste operations. For example, on a VT host screen, **Ctrl+ Shift + A** initiates a Select All action. See [Copying and Pasting](#) for a list of copy/paste key actions.

- ◆ **Keyboard shortcuts and browsers**

Browsers use keyboard shortcuts to save both time and mouse clicks. When mapping keystrokes it is important to keep this in mind. [Handy Keyboard Shortcuts](#) gives a brief overview of the keyboard shortcuts used by different browsers. In most cases Host Access for the Cloud key mappings take precedence over browser key shortcuts. Occasionally, where this is not the behavior you want for a particular key combination, you can choose **Unmap** in the action list to unmap the short-cut. This lets the key event to pass through to the browser.

## Host Keyboard Mapping

The following tables provide the default keys, key name, and key description for the different host keyboard mappings.

[IBM 3270 Keyboard Mapping](#)

[IBM 5250 Keyboard Mapping](#)

[VT Keyboard Mapping](#)

[UTS Keyboard Mapping](#)

[T27 Keyboard Mapping](#)

[ALC Keyboard Mapping](#)

**Table 5-4** IBM 3270 Keyboard Mapping

Key	Maps to	Description
Ctrl + F1	Attention	Sends the ATTENTION key to the host
Shift + Tab	Backtab	Moves the cursor to the previous unprotected field
Ctrl + F2	Clear	Clears the screen and sends the CLEAR key to the host

<b>Key</b>	<b>Maps to</b>	<b>Description</b>
Alt + ArrowLeft	Cursor left double	Moves the cursor two positions to the left
Alt + ArrowRight	Cursor right double	Moves the cursor two positions to the right
Ctrl + F3	Cursor select	Simulates a lightpen select in the current field
Alt + Delete	Delete word	Deletes three characters from the current field
Ctrl + 5	Duplicate	Inserts the DUP character at the cursor location
Enter	Enter	Sends the ENTER key to the host
End	Erase end of field	Erases all data from the cursor location to the end of the current field
Alt + F5	Erase input	Erases all data in all unprotected fields of the current screen.
Ctrl + Alt + F	Field delimiter	Toggles whether field delimiters are displayed on screen
Ctrl + 6	Field mark	Inserts the Field Mark character at the cursor location
Home	Home	Moves the cursor to the first unprotected field on the screen
Insert	Insert	Toggles Insert mode
Shift + Enter	New line	Moves to the next unprotected field
Ctrl + 1	PA1	Sends the PA1 key to the host
Pageup	PA1	Sends the PA1 key to the host
Ctrl + 2	PA2	Sends the PA2 key to the host
Pagedown	PA2	Sends the PA2 key to the host
Ctrl + 3	PA3	Sends the PA3 key to the host
F1 - F10	PF1 - PF10	Sends the PF1, PF2...PF10 key to the host
Alt + 1	PF11	Sends the PF11 key to the host
F11	PF11	Sends the PF11 key to the host
Alt + 2	PF12	Sends the PF12 key to the host
F12	PF12	Sends the PF12 key to the host
Shift + F1	PF13	Sends the PF13 key to the host
Shift + F2	PF14	Sends the PF14 key to the host
Shift + F3	PF15	Sends the PF15 key to the host
Shift + F4	PF16	Sends the PF16 key to the host
Shift + F5	PF17	Sends the PF17 key to the host
Shift + F6	PF18	Sends the PF18 key to the host
Shift + F7	PF19	Sends the PF19 key to the host
Shift + F8	PF20	Sends the PF20 key to the host



Key	Maps to	Description
Shift + F9	PF21	Sends the PF21 key to the host
Shift + F10	PF22	Sends the PF22 key to the host
Alt3	PF23	Sends the PF23 key to the host
Shift + F11	PF23	Sends the PF23 key to the host
Alt4	PF24	Sends the PF24 key to the host
Shift + F12	PF24	Sends the PF24 key to the host
Ctrl + P	Print	Prints the contents of the screen to the printer
Escape	Reset	Resets keyboard error conditions
Ctrl + S	System request	Sends the SYSTEM REQUEST key to the host

**Table 5-5** IBM 5250 Keyboard Mapping

Key	Maps to	Description
Escape	Attention	Sends the ATTENTION key to the host
Ctrl + F2	Clear	Clears the screen and send the CLEAR key to the host
Ctrl + F3	Cursor select	Simulates a lightpen select in the current field
Ctrl + Backspace	Destructive backspace	Moves the cursor one position to the left
Ctrl + 5	Duplicate	Inserts the DUP character at the cursor location
Ctrl + End	End of field	Moves the cursor to the end of the field
End	Erase end of field	Erases all data from the cursor location to the end of the current field
Alt + End	Erase input	Erases all data in the all unprotected fields of the current screen
Alt + F5	Erase input	Erases all data in all unprotected fields of the current screen.
Ctrl + Enter	Field exit	Moves the cursor out of an input field
KP + Subtract	Field exit minus	Moves the cursor out of a signed-numeric or numeric-only field
Ctrl + Subtract	Field exit minus	Moves the cursor out of a signed-numeric or numeric-only field
KP + Add	Field exit plus	Moves the cursor out of a signed-numeric or numeric-only field
Ctrl + Add	Field exit plus	Moves the cursor out of a signed-numeric or numeric-only field
Ctrl + 6	Field mark	Inserts the field mark character at the cursor location

<b>Key</b>	<b>Maps to</b>	<b>Description</b>
Ctrl + H	Help	Sends the Help key to the host
Ctrl + X	Hex mode	Places the terminal in Hex mode
Home	Home	Moves the cursor to the first unprotected field on the screen
Insert	Insert	Toggles Insert mode
Shift + Enter	New line	Moves to the next unprotected field
Ctrl + 1	PA1	Sends the PA1 key to the host
Ctrl + 2	PA2	Sends the PA2 key to the host
Ctrl + 3	PA3	Sends the PA3 key to the host
F1 - F11	PF1 - PF11	Sends the PF1, PF2....PF11 key to the host
Alt + 1	PF11	Sends the PF11 key to the host
Alt + 2	PF12	Sends the PF12 key to the host
F12	PF12	Sends the PF12 key to the host
Shift + 1	PF13	Sends the PF13 key to the host
Shift + F2	PF14	Sends the PF14 key to the host
Shift + F3	PF15	Sends the PF15 key to the host
Shift + F4	PF16	Sends the PF16 key to the host
Shift + F5	PF17	Sends the PF17 key to the host
Shift + F6	PF18	Sends the PF18 key to the host
Shift + F7	PF19	Sends the PF19 key to the host
Shift + F8	PF20	Sends the PF20 key to the host
Shift + F9	PF21	Sends the PF21 key to the host
Shift + F10	PF22	Sends the PF22 key to the host
Alt + 3	PF23	Sends the PF23 key to the host
Shift + F11	PF23	Sends the PF23 key to the host
Alt + 4	PF24	Sends the PF24 key to the host
Shift + F12	PF24	Sends the PF24 key to the host
Ctrl + P	Print	Prints the contents of the screen to the printer
Control	Reset	Resets the keyboard error conditions
Pageup	RollDown	Sends the RollDown key to the host
Pagedown	RollUp	Sends the RollUp key to the host
Ctrl + Home	Start of field	Moves the cursor to the start of the field

Key	Maps to	Description
Ctrl + S	System request	Sends the SYSTEM REQUEST key to the host

**Table 5-6** VT Keyboard Mapping

Key	Maps to	Description
Ctrl + Cancel	Break	Sends the Break key to the host
Ctrl + Enter	Enter	Send the Enter key to the host
Alt + F1	F1	Sends the F1 key to the host
Ctrl + F1	F11	Sends the F11 key to the host
Ctrl + F2	F12	Sends the F12 key to the host
Ctrl + F3	F13	Sends the F13 key to the host
Ctrl + F4	F14	Sends the F14 key to the host
Ctrl + F5	F15	Sends the F15 key to the host
Ctrl + F6	F16	Sends the F16 key to the host
Ctrl + F7	F17	Sends the F17 key to the host
Ctrl + F8	F18	Sends the F18 key to the host
Ctrl + F9	F19	Sends the F19 key to the host
Ctrl + F10	F20	Sends the F20 key to the host
Home	Find	Sends the Find key to the host
F1	Hold	Sends the Hold Screen to the host
Pause	Hold	Sends the Hold Screen to the host
Insert	Insert	Sends the Insert key to the host
Ctrl + Insert	Keypad 0	Sends the numeric keypad 0 key to the host
Ctrl + End	Keypad 1	Sends the numeric keypad 1 key to the host
Ctrl + ArrowDown	Keypad 2	Sends the numeric keypad 2 key to the host
Ctrl + Pagedown	Keypad 3	Sends the numeric keypad 3 key to the host
Ctrl + ArrowLeft	Keypad 4	Sends the numeric keypad 4 key to the host
Ctrl + Clear	Keypad 5	Sends the numeric keypad 5 key to the host
Ctrl + ArrowRight	Keypad 6	Sends the numeric keypad 6 key to the host
Ctrl + Home	Keypad 7	Sends the numeric keypad 7 key to the host
Ctrl + ArrowUp	Keypad 8	Sends the numeric keypad 8 key to the host
Ctrl + Pageup	Keypad 9	Sends the numeric keypad 9 key to the host
Ctrl + Alt-add	Keypad comma	Sends the numeric keypad Comma key to the host

<b>Key</b>	<b>Maps to</b>	<b>Description</b>
Ctrl + add	Keypad minus	Sends the numeric keypad Minus key to the host
Ctrl + decimal	Keypad period	Sends the numeric keypad Period key to the host
Ctrl + Delete	Keypad period	Sends the numeric keypad Period key to the host
Ctrl + Alt + ArrowUp	Row up	In the scrollbar buffer moves up a row
Ctrl + Alt + ArrowDown	Row down	In the scrollbar buffer moves down a row
Pagedown	Next	Sends the Next Screen key to the host
Ctrl + Pause	PF1	Sends the PF1 key to the host
Ctrl + Divide	PF2	Sends the PF2 key to the host
Ctrl + Multiply	PF3	Sends the PF3 key to the host
Ctrl + Subtract	PF4	Sends the PF4 key to the host
Pageup	Previous	Sends the Prev Screen key to the host
Delete	Remove	Sends the Remove key to the host
End	Select	Sends the Select key to the host
Shift + F6	UDK6	Sends the User Defined Key 6 to the host
Shift + F7	UDK7	Sends the User Defined Key 7 to the host
Shift + F8	UDK8	Sends the User Defined Key 8 to the host
Shift + F9	UDK9	Sends the User Defined Key 9 to the host
Shift + F10	UDK10	Sends the User Defined Key 10 to the host
Shift + Ctrl + F1	UDK11	Sends the User Defined Key 11 to the host
Shift + Ctrl + F2	UDK12	Sends the User Defined Key 12 to the host
Shift + Ctrl + F3	UDK13	Sends the User Defined Key 13 to the host
Shift + Ctrl + F4	UDK14	Sends the User Defined Key 14 to the host
Shift + Ctrl + F5	UDK15	Sends the User Defined Key 15 to the host
Shift + Ctrl + F6	UDK16	Sends the User Defined Key 16 to the host
Shift + Ctrl + F7	UDK17	Sends the User Defined Key 17 to the host
Shift + Ctrl + F8	UDK18	Sends the User Defined Key 18 to the host
Shift + Ctrl + F9	UDK19	Sends the User Defined Key 19 to the host
Shift + Ctrl + F10	UDK20	Sends the User Defined Key 20 to the host

**Table 5-7** UTS Keyboard Mapping

<b>Key</b>	<b>Maps to</b>	<b>Description</b>
F4	Clear Change Bit	Sends the CLEARCHANGEBIT key to the host.
Keypad+Enter	Carriage Return	Sends a carriage return to the host.
Ctrl+PageDown	Clear End of Display	Clears text from the cursor location to the end of the display.
Ctrl+PageUp	Clear End of Display FCC	Clears all data (including FCC information) from the cursor to the end of the display
Ctrl+End	Clear End of Field	Clears text from the cursor location to the end of the field.
Ctrl+Shift+end	Clear End of Line	Clears text from the cursor location to the end of the row.
F7	Clear FCC	Clears the field control character
Ctrl+Home	Clear Home	Sends the CLEAR_HOME key to the host.
Ctrl+H	Column Separator Right	Sends the COLUMN_SEP_RIGHT key to the host.
Ctrl+F1	Control Page	Sends the CONTROL_PAGE key to the host.
Keypad+2	Cursor Down	Moves the cursor one row down.
Keypad+4	Cursor Left	Moves the cursor one column to the left.
Keypad+6	Cursor Right	Moves the cursor one column to the right.
Keypad+8	Cursor Up	Moves the cursor one row up.
Delete	Delete in Line	Sends the DELETE_IN_LINE key to the host.
Ctrl+Delete	Delete in Page	Sends the DELETE_IN_PAGE key to the host.
Ctrl+Shift+Delete	Delete Line	Deletes the row at the cursor location.
Ctrl+ArrowDown	Duplicate Line	Duplicates the row at the cursor location.
F8	Enable FCC	Enables the field control character.
Keypad+-	End of Display and Transmit	Sends the EOD_AND_TRANSMIT key to the host.
Shift+End	End of Field	Moves the cursor to the end of the field.
End	End of Line	Moves the cursor to the end of the row.
Ctrl+ArrowRight	End of Page	Moves the cursor to the end of the page.
Shift+Space	Erase Character	Erases the character at the cursor location.
Ctrl+Shift+E	Euro Character	Sends the Euro character to the host.
Ctrl+1 - Ctrl+9	F1 - F9	Sends the F1 - F9 key to the host
Ctrl+0	F10	Sends the F10 key to the host.
Ctrl+-	F11	Sends the F11 key to the host.
Ctrl+=	F12	Sends the F12 key to the host.

<b>Key</b>	<b>Maps to</b>	<b>Description</b>
Ctrl+Q	F13	Sends the F13 key to the host.
Ctrl+W	F14	Sends the F14 key to the host.
Ctrl+E	F15	Sends the F15 key to the host.
Ctrl+R	F16	Sends the F16 key to the host.
Ctrl+T	F17	Sends the F17 key to the host.
Ctrl+Y	F18	Sends the F18 key to the host.
Ctrl+U	F19	Sends the F19 key to the host.
Ctrl+I	F20	Sends the F20 key to the host.
Ctrl+O	F21	Sends the F21 key to the host.
Ctrl+P	F22	Sends the F22 key to the host.
Shift+F3	FF	Sends a formfeed to the host.
F9	Generate FCC	Generates a field control character.
Home	Home	Moves the cursor to the first field in the display.
Ctrl+Shift+Space	Insert in Line	Sends the INSERT_IN_LINE key to the host.
ICtrl+Space	Insert in Page	Sends the INSERT_IN_PAGE key to the host.
Ctrl+Shift+Insert	Insert Line	Inserts a new row into display memory.
Insert	Insert Mode	Toggles insert character mode.
F5	Locate FCC	Disables the field control characters and moves to the first character of the next field to the right of the cursor.
F3	Message Wait	Sends the MESSAGE_WAIT key to the host.
Shift+F2	New Line	Moves the cursor to a new row.
Keypad+Shift+2	Next Field	Moves the cursor to the next field.
Keypad+Shift+4	Next Field	Moves the cursor to the next field.
PageDown	Page Down	Sends the Page Down key to the host.
PageUp	Page Up	Sends the Page Up key to the host.
Keypad+Shift+6	Previous Field	Moves the cursor to the previous field.
Keypad+Shift+8	Previous Field	Moves the cursor to the previous field.
Clear	SOE Character	Sends the SOE character to the host.
F12	SOE Character	Sends the SOE character to the host.
Ctrl+Clear	Set Tab	Sends the SET_TAB key to the host.
Ctrl+Tab	Set Tab	Sends the SET_TAB key to the host.
Shift+Home	Start of Field	Moves the cursor to the start of the field.

<b>Key</b>	<b>Maps to</b>	<b>Description</b>
Ctrl+ArrowLeft	Start of Line	Moves the cursor to the start of the row
Ctrl+[	System Mode	Sends the SYSTEM_MODE key to the host.
Ctrl+J	Toggle Column Separator	Toggles the column separator.
Ctrl+F12	Toggle Message Wait Beep	Sends the TOGGLEMSGWAITBEEP key to the host.
Ctrl+L	Toggle Strike Thru	Toggles strike thru mode.
Ctrl+K	Toggle Underline	Toggles underline mode.
Ctrl+Enter	Transmit	Transmits the contents of the display to the host.
ScrollLock	Transmit	Transmits the contents of the display to the host.
Keypad++	Transmit	Transmits the contents of the display to the host.
Keypad+Ctrl+	Transmit	Transmits the contents of the display to the host.
Escape	Unlock	Sends the UNLOCK key to the host.
Ctrl+]	Workstation Mode	Sends the WORKSTATION_MODE key to the host.

**Table 5-8** T27 Keyboard Mapping

<b>Key</b>	<b>Maps to</b>	<b>Description</b>
Backspace	Backspace	Moves the cursor one column to the left.
Shift+tab	back tab	Moves the cursor to the previous field.
Ctrl+Delete	Clear End of Line	Clears text from the cursor location to the end of the row.
Shift+Home	Clear Page Home	Clears the page and homes the cursor.
Left Ctrl	Control Page	Puts the session in control mode.
Down arrow	Cursor Down	Moves the cursor one row down.
Left arrow	Cursor Left	Moves the cursor one column to the left.
Right arrow	Cursor Right	Moves the cursor one column to the right.
Up arrow	Cursor Up	Moves the cursor one row up.
Ctrl+left arrow	Cursor Word Left	Moves the cursor to the previous word.
Ctrl+right arrow	Cursor Word Right	Moves the cursor to the next word.
Ctrl+D	Delete Line	Deletes the row at the cursor location.
Ctrl+End	End of Line	Moves the cursor to the end of the row.
End	End of Page	.Moves the cursor to the last field on the page.
Shift+Ctrl+E	Euro Character	.Sends a Euro character to the host.
Home	Home	Moves the cursor to the first field in the display.

<b>Key</b>	<b>Maps to</b>	<b>Description</b>
Insert	Insert Mode	Puts the session in insert mode.
Ctrl+I	Insert Line	Inserts a new row into display memory.
Ctrl+1	PF1	Sends the PF1 key to the host.
Ctrl+10	PF10	Sends the PF10 key to the host.
Ctrl+2	PF2	Sends the PF2 key to the host.
Ctrl+3	PF3	Sends the PF3 key to the host.
Ctrl+4	PF4	Sends the PF4 key to the host.
Ctrl+5	PF5	Sends the PF5 key to the host.
Ctrl+6	PF6	Sends the PF6 key to the host.
Ctrl+7	PF7	Sends the PF7 key to the host.
Ctrl+8	PF8	Sends the PF8 key to the host.
Ctrl+9	PF9	Sends the PF9key to the host.
PageDown	Page Down	Displays the next page.
PageUp	Page Up	Displays the previous page.
Ctrl+E	Put ETX	Inserts an end-of-text character and homes the cursor.
Keypad /	Put Local	Puts the session in local mode.
Keypad *	Put Receive	Puts the session into receive mode.
Enter	Return	Sends the return key to the host.
Keypad Enter	Return	Sends the return key to the host.
Ctrl+A	Select All	Selects all text.
Shift+down arrow	Select Down	Selects text down.
Shift+left arrow	Select Left	Selects text left.
Shift+right arrow	Select Right	Selects text right.
Shift+up arrow	Select Up	Selects text up.
Shift+Ctrl+1	Shift F1	Sends the Shift F1 key to the host.
Shift+Ctrl+0	Shift F10	Sends the Shift F10 key to the host.
Shift+Ctrl+2	Shift F2	Sends the Shift F2 key to the host.
Shift+Ctrl+3	Shift F3	Sends the Shift F3 key to the host.
Shift+Ctrl+4	Shift F4	Sends the Shift F4 key to the host.
Shift+Ctrl+5	Shift F5	Sends the Shift F5 key to the host.
Shift+Ctrl+6	Shift F6	Sends the Shift F6 key to the host.
Shift+Ctrl+7	Shift F7	Sends the Shift F7 key to the host.



<b>Key</b>	<b>Maps to</b>	<b>Description</b>
Shift+Ctrl+8	Shift F8	Sends the Shift F8 key to the host.
Shift+Ctrl+9	Shift F9	Sends the Shift F9 key to the host.
F5	Specify	Transmits the cursor location to the host.
Tab	Tab	Moves the cursor to the next field.
F2	Transmit	Transmits the page to the host.
Keypad +	Transmit	Transmits the page to the host.
Ctrl+F2	Transmit Line	Transmits the current row to the host.
Keypad -	Transmit Line	Transmits the current row to the host.

**Table 5-9** ALC Keyboard Mapping

<b>Key</b>	<b>Maps to</b>	<b>Description</b>
Ctrl+M	Auto Move Down	Toggles the session ability to receive multiple pages
Backspace	Backspace	Moves the cursor one column to the left.
Shift+tab	back tab	Moves the cursor to the previous field.
Ctrl+Home	Clear	Clears the screen and sends the CLEAR key to the host
Ctrl+B	Clear Broadcast	Clears the SITA broadcast message
:	Colon	Inserts a colon character at the cursor position.
Ctrl+L	Cross of Lorraine	Inserts the Cross of Lorraine character at the cursor position
↓	Cursor Down	Moves the cursor down a row
Keypad ↓	Cursor Down	Moves the cursor down a row
←	Cursor Left	Moves the cursor to the previous word
Keypad ←	Cursor Left	Moves the cursor to the previous word
→	Cursor Right	Moves the cursor to the next word
Keypad →	Cursor Right	Moves the cursor to the next word
↑	Cursor Up	Moves the cursor up a row
Keypad ↑	Cursor Up	Moves the cursor up a row
Delete	Delete character	Deletes the character at the cursor location.
Ctrl+Delete	Delete Line	Deletes the line at the cursor position.
=	Display	Inserts the display character at the cursor position.
Ctrl+N	Display New Line	Inserts the display character at a new line

<b>Key</b>	<b>Maps to</b>	<b>Description</b>
]	Dollar	Inserts the U.S. dollar sign character at the cursor position
.	End Item	Inserts the end item character at the cursor position
End	End of Line	Moves the cursor to the end of the line
Ctrl+T	End Transaction	Closes the PNR
Ctrl+E	Erase End of Display	Erases all data from the cursor position to the end of display
Ctrl+End	Erase End of Line	Erases all data from the cursor position to the end of line
Home	Home	Moves the cursor to the first unprotected field on the screen
Ctrl+I	Ignore	Cancels any changes made to the current PNR
Ctrl+Instert	Insert Line	Inserts a new line into display memory
Insert	Insert Space	Inserts a space into display memory
\	New Line	Inserts the newline character at the cursor position
[	Pillow	Inserts the pillow character at the cursor position
Ctrl+G	Pound	Inserts a British pound mark at the cursor position
Ctrl+Enter	Print Enter	Sends the response to the printer
Ctrl+P	Protected Reset	Moves the cursor to the first unprotected field
Ctrl+↑	Recall Next Input	Recalls the next input or entry
Ctrl+↓	Recall Previous Input	Recalls the previous input or entry
Ctrl+Z	Reenter	Resends the previously sent message to the host
Ctrl+R	Repeat	Redisplays the last message sent by the host
Escape	Reset	Resets keyboard error conditions
Shift+Ctrl+↓	Scroll Line Down	Scrolls the display down one line
Shift+Ctrl+↑	Scroll Line Up	Scrolls the display up one line
PageDown	Scroll Page Down	Scrolls the display down one page
PageUp	Scroll Page Up	Scrolls the display up one page
Ctrl+A	Select All	Selects all text
Shift+↓	Select Down	Selects all text down
Shift+↑	Select Up	Selects all text up
Shift+←	Select Left	Selects all text left
Shift+→	Select Right	Selects all text right

Key	Maps to	Description
'	Start of Message	Inserts a start-of-message character at the cursor position
F12	Statistics	Displays communication statistics
Tab	Tab	Moves the cursor to the next unprotected field
Ctrl+F	Toggle CODACOM	Toggles CODACOM mode
Enter	Transmit	Transmits page to the host
Keypad Enter	Transmit	Transmits page to the host
Shift+Enter	Transmit	Transmits page to the host
Shift+Escape	Unlock Keyboard	Unlocks the keyboard
Ctrl+U	Unsolicited Message	Retrieves an unsolicited message from the host

## Configure User Macros

Use the Macro panel to select which macros to run and when to run them.

- ♦ **Run macro on startup** - Choose a macro to run automatically when the session is opened.
- ♦ **Run macro on connect** - Choose a macro to run automatically when the session connects to the host.
- ♦ **Run macro on disconnect** - Choose a macro to run automatically when the session disconnects from the host.

---

### Related Topics

[Creating Macros](#)

[Using the Macro API](#)

[Sample Macros](#)

## Transfer Files

Host Access for the Cloud supports three different file transfer protocols; IND\$FILE for 3270 host transfers, AS/400 for 5250 host transfers, and File Transfer Protocol (FTP) which allows a local computer to act as an FTP client. Once connected, you can view files on the server and use the File Transfer Protocol (FTP) to transfer files between your local computer (or any networked drive) and the FTP server.

Batch file transfer is available for FTP transfers. Using this option you can download and upload multiple files in one operation.

Before you can transfer or send files, the administrator must enable the transfer, send options for the current session, and make the necessary configurations. This is done on the File Transfer settings panel.

Depending on the host file system and transfer method you want to use, you will see different configuration options. Once configured, the file transfer dialog box is available from the tool bar.

- ◆ [IND\\$FILE](#)
- ◆ [AS/400](#)
- ◆ [FTP](#)
- ◆ [Batch transfers](#)

## IND\$FILE

IND\$FILE is a file transfer program from IBM which you can use to transfer information between your computer and a 3270 host computer.

From the **Host file system** drop down list, select which IBM 3270 operating environment the host is running. Host Access for the Cloud supports TSO (Time Sharing Option), CMS (Conversational Monitor System) and CICS. The default selection is None.

There is support for ASCII or binary transfers and, if you connected to a TSO host, you can navigate directly to a particular TSO dataset.

### General options for CICS, CMS, and TSO host file types

**Automatically show host files** - By default, the host file list contains all the host files that are available to transfer. To retrieve host files only when you request them, disable this option. On the Transfer dialog box, click **Show host files** to retrieve the host files.

### Transfer options for CICS, CMS, and TSO host file types

Option	Description
Transfer method	<ul style="list-style-type: none"><li>◆ Binary Use for program files and other types of files that should not be translated, such as files that have already been formatted for a particular type of printer or files with application-specific formatting. Binary files contain non-printable characters; using this method, a file is not converted or translated during the transfer.</li><li>◆ ASCII Use to transfer text files with no special formatting. ASCII files on the PC are translated to the EBCDIC character set on the host and host text files are converted from EBCDIC to ASCII when they are downloaded.</li></ul>
CR/LF processing	If this option is selected, carriage return - line feed pairs will be stripped from files sent to the host and added to the end of each line on files received from the host.
Startup command	Specifies the host program used to initiate the file transfer. IND\$File, the default, is appropriate for CMS and TSO hosts. For CICS hosts, IND\$File may be appropriate, or you may need to specify your site's CICS transaction (for example, CFTR).
Startup parameters	Use this field for any parameters specific to the IND\$File program on your host system. The contents of this field are appended to the end of the transfer command generated by Host Access for the Cloud. Host Access for the Cloud does not validate the parameters.

Option	Description
Max field size	<p>Select a field size to use with the Write Structured Field protocol. The default value is 4 kilobytes. Typically, the larger the buffer size, the faster the transfer. Most systems support 8K; if you choose a value that is too large for your host, it will disconnect your session when you first attempt to send a file big enough to fill the buffer.</p> <p>The person who installs the host communication software usually supplies this value. For example, IBM's host TCP/IP product gets this value from the DATABUFFERPOOLSIZ parameter, which defaults to 8K buffers. See your system administrator if you don't know what to enter here.</p>
Lead key	You can specify certain actions before transferring or listing files. Your choices are None, Auto Sense, and Clear. If set to None, LISTCAT is issued automatically. If set to Auto Sense, the current screen contents are examined to determine if a LISTCAT or TSO LISTCAT should be sent. If set to Clear, the Clear key is sent before issuing command. For TSO, Clear also means "TSO" will not be prepended to the request files command.
PC code page	The character set to use when reading or writing local files during a file transfer. The value <b>Default</b> uses the code page corresponding to your operating systems locale. If you need a different character set to specify the PC code page, select it from the list.
Host code page	The character set to use when translating EBCDIC characters while transferring files to or from the host. The default, <b>Use NCS setting</b> , uses the national character set specified on the Display panel under Terminal. If you need a different character set to specify the host code page, select it from the list.
Response timeout (seconds)	Specifies how many seconds Host Access for the Cloud should wait for a host response before timing out and returning an error. The default value is 60 seconds.
Startup timeout (seconds)	Specifies the number of seconds Host Access for the Cloud should wait for a host response when attempting to connect to a host. If the specified amount of time elapses with no response from the host, Host Access for the Cloud times out and returns an error. The default value is 25 seconds.

### Send options for CICS, CMS, and TSO host file types

Option	Description	Applies to this host type
Record format	<p>Use this option to specify the record format for files sent to the host.</p> <ul style="list-style-type: none"> <li>◆ Default - The host determines the record format. This is the default option.</li> <li>◆ Fixed - Forces the host to create fixed-length records.</li> <li>◆ Undefined - Forces the host to create files without a specific record format (this value is only relevant for TSO systems).</li> <li>◆ Variable - Forces the host to create variable-length records and preserves the format of a binary file.</li> </ul>	TSO, CMS

Option	Description	Applies to this host type
Allocation units	Specifies the disk subdivisions for your primary and secondary space allocations. If you select Default (default), the unit is determined by the host. You can also select Cylinder, Track, or Block. If you select Block, use the Average block box to specify the size for an average block (in bytes).	TSO
Logical record length	The record size (in bytes) for the file being created on the host. If you leave this box blank, the record size is determined by the host. You can set any value between 0 and 32767 to accommodate any range accepted by your host. This option is not available on CICS hosts. For ASCII files, set this value to accommodate the longest line in your file. When you leave this box blank, the host usually accepts lines of up to 80 characters.	TSO, CMS
If host file exists	Specifies how the transfer should operate if a file with the same name already exists. <ul style="list-style-type: none"> <li>◆ <b>Append</b> - Append the contents of the local file to the existing host file.</li> <li>◆ <b>Overwrite</b> - Overwrite the contents of the host file With CICS systems there is no way to tell if a host file already exists, so Overwrite is the only available option for sending files to a CICS system.</li> </ul>	TSO, CMS
Block size (bytes)	On TSO hosts, specifies the block size for the file being created on the host. For files with fixed-length records, this value must be a multiple of the Logical record length (because blocks are divided into logical records). You can set any value between 0 and 32767, to accommodate any range accepted by your host	TSO
Average block (bytes)	The size for an average block. This value is only relevant if you are using blocks as your allocation unit.	TSO
Primary allocation (allocation units)	The size of the primary allocation for the host file being created.	TSO
Secondary allocation (allocation units)	The size of any additional allocations in the event that the primary allocation is not sufficient. Multiple secondary allocations (known as "extents") are allowed, up to a host-specified limit (generally 15).	TSO

---

**NOTE:** When using CICS as the host system you must enter the names of the files you are transferring manually. A list of files to choose from is not available.


---

## Transferring files

- ♦ [Downloading files](#)
- ♦ [Uploading files](#)
- ♦ [Troubleshooting your file transfers](#)

You must be connected and logged into the host to transfer files for the current 3270 session.

1 Verify that the host is in a 'ready' state to accept the IND\$FILE command.

2 From the tool bar, click the **IND\$File** icon .

3 The File Transfer dialog box displays, containing a list of host files and directories that are available to transfer. Directories and files are indicated by an icon when you select the file. For CICS hosts, type in the names of the files you want to transfer.

4 Select the transfer method. The options are:

- ♦ Binary

Use for program files and other types of files that should not be translated, such as files that have already been formatted for a particular type of printer or files with application-specific formatting. Binary files contain non-printable characters; using this method, a file is not converted or translated during the transfer.

- ♦ ASCII

Use to transfer text files with no special formatting. ASCII files on the PC are translated to the EBCDIC character set on the host and host text files are converted from EBCDIC to ASCII when they are downloaded.

5 If you are connected to a TSO host, click **Level** to type in the new dataset you want to view. Host Access for the Cloud updates the remote file list using the dataset level you specify.

---

**NOTE:** When specifying files using `_Upload As_` or `_Download_`, a fully qualified data set name needs to be enclosed in single quotes. Data set names not enclosed in single quotes will, by default, be prefixed with a high level qualifier specified in the TSO PROFILE.

---

You can refresh the file list at any time by clicking the **Refresh** icon in the upper left corner of the File Transfer dialog box.

## Downloading files

You can select files to download from the list of available files or use the **Download** button to identify a specific file using the host file name.

1 From the list, select the file to initiate the transfer by clicking on the name of the file in the list.  
or

- 2 Click **Download** and enter the name of the host file you want to transfer. You can download from both TSO and CMS host types. However, TSO and CMS represent host files differently; this means the format of the file name you enter into the message prompt will vary.
  - ♦ **TSO** - Wrap the name of the host path in single quotes to specify the complete dataset name. For example, ' BVTST03 .DATA .TXT ' . To specify a file location relative to the dataset level you set above, omit the single quotes. For example, DATA .TXT, which identifies the same dataset but relative to BVTST03.
  - ♦ **CMS** - A typical CMS input would be BVTSTT01 DATA A1. Single quotes are not needed.
- 3 If necessary, you can cancel the transfer from the transfer progress panel.

## Uploading files

---

**NOTE:** IBM mainframe computer systems impose certain naming conventions for files. For detailed information on naming requirements, see the [IBM documentation](#).

---

There are two methods for uploading files:

- 1 From the File Transfer dialog box, click **Upload**.
- 2 You can specify a different name for the uploaded file. Click **Upload as**, browse to the file you want to upload, and when prompted type the name you want to use. Remember that when connected to a TSO host, a fully qualified data set named needs to be enclosed in single quotes. See Step 5 under [Transferring files](#).

Or:

- 1 Drag the file you want to upload from its location to the File Transfer dialog box.
- 2 Click **Refresh** to verify the file was successfully uploaded.

If you cancel the upload process before a file has been completely transferred, a partial file will be left behind on the host.

## Troubleshooting your file transfers

Occasionally you might encounter errors when attempting a file transfer. These errors may be mainframe issues or may be caused by browser security settings.

If a transfer completes but the file doesn't contain the data expected, verify that the transfer method is properly set to either Binary or ASCII.

There is a 50MB file size limit on file transfer upload operations. You can [modify this value](#).

For host-specific errors, see [IBM File Transfer Error Messages](#).

## AS/400

Using AS/400 file transfer you can transfer data between your computer and an iSeries host.

Generally, AS/400 file transfers are straightforward and not complex. However, since the host data is managed as a DB2 database, you can, using the SQL Editor, create fairly complex queries.



## To configure AS/400 file transfer

1. Create an HACloud 5250 terminal session, enter a host name or address and name the session.
2. On the Settings panel, choose **File Transfer**.
3. Select **Enable AS/400** and proceed with the configuration.
  - ◆ **Host**

The host address that you provided for the terminal session is pre-populated in the host field. You can, if needed, use a different host. To specify a different port, append the port number to the host address. For example, `host.mycompany.com:23`.
  - ◆ **TLS/SSL Security**

From the drop down list, select the TLS security option you want to use. To use this option:


    - The AS/400 database server's certificate must be added to the list of trusted certificates in MSS. If the certificate has not already been added, then see [Trusted Certifications](#) in the MSS documentation for instructions.
  - ◆ **Default transfer method**

Set your preferred default transfer method; fixed width Text, or Comma Separated Values (CSV). The transfer method can be changed when you perform a transfer.
4. Click Save and connect to the session.


## Transferring files


- ◆ [Downloading files](#)
- ◆ [Downloading using SQL](#)
- ◆ [Uploading files](#)
- ◆ [Adding a library](#)



After the session has been configured to use AS/400 file transfer functionality, click  on the toolbar to open the file transfer dialog box. This dialog contains a list of host files that are available to transfer. If prompted, you may need to enter your AS/400 login credentials.

## Downloading files

The AS/400 file system consists of Libraries, Files and Members. Libraries are identified by the icon . While you cannot download libraries, you can click on the library to see the files and members contained within.

1. Open the library containing the files (  ).
2. Expand the file that contains the member you want to download.
3. Click on a member to download it.
4. Open the browser's download folder to confirm the file is there. Open the file in a text editor.

## Downloading using SQL

You can create SQL queries to obtain only the data you need from a file member on the host. This lets you select specific fields and ignore others.

1. Open the library and file you want to download.
2. Open the options menu and click **SQL**.



3. The SQL Editor opens and contains the SELECT statement that is used to download the whole member. The file member is referenced as LIBRARYNAME/FILENAME(MEMBERNAME).
4. Click **Run** to download the whole member. or edit the SQL and click Run to retrieve a subset of the data.

## Uploading files

You can only upload data into files as either new or replacement members. The AS/400 file contains a specification describing the data in members and each member in a given file has the same structure. You typically cannot (or should not) download a member from one file and upload it to another unless both files have the same data specification. Since data can only be uploaded as members, you need to open a file and display its members in the file list dialog before the Upload button is enabled.

1. Open the file that you want to upload to. The Upload button is now available.
2. You can:
  - ♦ Click the Upload button and select a file from your local file system to upload.
  - or
  - ♦ Click the down arrow on the Upload button and select Upload as..., then select the file, give it a new name and click OK.

## Adding a library

Typically, as an AS/400 user, you will have access to a certain set of libraries that has been assigned by a system administrator. These libraries appear as the top level entries in the file transfer dialog. If you need to access a library that is not on your list, your system administrator can update your configuration so that the new library is added to your list. Occasionally you may need to work with a library on a temporary basis; you do not need it added permanently to your library list.

### To add a library:

On the AS/400 file transfer dialog box, click **Add Library**. This button is available from the library list panel. This addition is not permanent and you will have to add the library again if you close and reopen the file transfer dialog box.

# FTP

With Host Access for the Cloud your local computer can act as an FTP client. Using the FTP client, you can connect to an FTP server running on another machine. Once connected, you can view files on the server and use FTP to transfer files between your local computer (or any networked drive) and the FTP server. Using FTP, a client can upload, download, delete, rename, move and copy files on a server, either singly or as a batch transfer, where you can build lists of files to be transferred as one operation.

---

**TIP:** If you plan on using a batch transfer, first select and configure the **Enable FTP** option.

---

## To configure FTP

Select **Enable FTP** and proceed with the configuration:

- ◆ **Protocol**

Use FTP to start a standard FTP session. Use SFTP to start an SFTP session.

You can set up an FTP client to use the SFTP protocol and perform all operations over an encrypted secure shell transport. Host Access for the Cloud uses user name and password to authenticate.

- ◆ **Host**

Specify the host name or IP address of the FTP server to which you want to connect.

- ◆ **Port**

The port of the FTP server specified.

- ◆ **If remote files exists when uploading file**

Specify how you want to handle the transfer if a file with the same name already exists. You can select:

<b>This option</b>	<b>Does this...</b>
Append	Append the file being sent to the existing file
Ask user (default)	Prompt for a decision on how to handle the duplicate file name
Cancel	Cancel the file transfer
Fail	Cancel the file transfer and receive a notification of failure
Overwrite	Overwrite the existing file on the remote machine
Skip	When multiple files are in a request, skip the file matching an existing file name, but proceed with the transfer for other files.
Unique	Create a new file with a unique file name

- ◆ **Initial remote directory**

Specify the path to a home or default directory for the FTP site. When a connection to the FTP site is opened, the server working directory is set automatically to the specified home path. The files and folders in the server home directory appear in the FTP session window. If the initial remote directory is not found, a warning is reported and the connection continues.

- ◆ **Anonymous user**

Select this option to log onto the specified FTP server as a guest, with the user name “Anonymous”. If the host you are connecting to does not support anonymous users, it may be necessary to supply your credentials.

- ◆ **Session timeout (seconds)**

This value tells the FTP client the maximum number of seconds to wait for data packets being transferred to or from the host. If nothing is received within the period specified, a timeout error displays and the transfer terminates; in this case, try the operation again. If you receive repeated timeout errors, increase the timeout value. Entering 0 (zero) in this box prevents the FTP client from ever timing out when waiting for a response. For SFTP sessions, the default is 0 (zero).

- ◆ **Keep Alive time (seconds)**


Select this option and enter a time in seconds if you want to continue your connection to the server beyond the server’s automatic timeout value for inactivity. Most servers have an idle time value that specifies how long a user’s FTP session can last when no activity is detected. When the user exceeds the time limit, the server connection is closed.

This setting allows you to direct the FTP client to send a NOOP command to the server at timed intervals to prevent the server from closing the connection due to inactivity. Be aware that by continuing your session you may prevent another user from making a connection to the FTP server.

- ◆ **Host encoding**

Specifies the character set used by the host to display the names of files that are transferred. By default Host Access for the Cloud uses UTF-8 (Unicode). If you transfer files with the default setting and the file names are unrecognizable, change the Host encoding option to the character set used by the host. (This option does not affect the encoding for the contents of the files that are transferred; it applies to the file names only.)

## Transferring files

After the administrator configures a session to include FTP functionality, click  on the toolbar to open the FTP File Transfer window containing a list of host files that are available to transfer. Directories and files are indicated by an icon when you select the file.

- 1 Select the transfer method. The options are:


- ◆ Binary

Use for program files and other types of files that should not be translated, such as files that have already been formatted for a particular type of printer or files with application-specific formatting. Binary files contain non-printable characters; using this method, a file is not converted or translated during the transfer.

- ◆ ASCII

Use to transfer text files with no special formatting. ASCII files on the PC are translated to the EBCDIC character set on the host and host text files are converted from EBCDIC to ASCII when they are downloaded.

- 2 You can rename, delete, or download a file from the list of files.



- 3 Refresh the file list at any time by clicking the **Refresh** icon in the upper left corner of the File Transfer dialog box.

## Downloading files

- 1 From the list, select the file to initiate the transfer.
- 2 If necessary, you can cancel the transfer from the transfer progress panel.

## Uploading files

There are two methods for uploading files:

- 1 From the File Transfer dialog box, click **Upload**.
- 2 Choose the file you want to upload from the Browse window.

Or:

- 1 Drag the file you want to upload from its location to the File Transfer dialog box.
- 2 Click **Refresh** to verify the file was successfully uploaded.

Click **New Directory** to create a new directory on the remote server. You are prompted to enter the new directory name.

## Batch transfers



---

**NOTE:** You must first enable FTP on the File Transfer settings panel FTP tab before you can configure batch transfers.

---

To transfer multiple files in one operation, use the **Batch** option.

1. From the Settings > File Transfer > FTP panel, check **Enable FTP**.
2. Click **FTP BATCH** to open the **Batch** file transfer panel.
3. Select **Cancel batch when single failure occurs** to stop the transfer if a file fails to transfer.

4. Click  to create the list of files you want to transfer.
  - a. Name the list. To aid in building similar lists, you can copy an existing list, rename it, and then add or delete files as needed using the options available when the original list is highlighted.
  - b. From the right panel, click  to open the **Add transfer request** dialog box.
5. On the **Add transfer request** panel, begin building the list:

Option	Description
Transfer	Choose whether to upload or download the file.
Local file name	Identify the file you want to transfer. You can enter the name of the file or browse to it.
Remote file path	Provide a location to name and store the file after transfer. You can: <ul style="list-style-type: none"> <li>◆ <b>Keep original file name and use the initial remote directory</b> - leave the field blank</li> <li>◆ <b>Use a new file name</b> - enter <code>newfilename.txt</code>. Puts the file in the initial remote directory using the given name.</li> <li>◆ <b>Keep original file name but use a new directory path</b> - <code>/folder/</code>. Uses the original file name with the new path.</li> <li>◆ <b>Use new directory and a new file name</b> - <code>/folder/newfilename.txt</code>.</li> </ul>
Transfer method	You can choose from Binary or ASCII transfer methods.
If remote file exists	Decide how to handle file transfer if a remote file already exists. The options are: <ul style="list-style-type: none"> <li>◆ <b>Overwrite (default)</b> - Overwrite the existing file on the remote machine</li> <li>◆ <b>Append</b> - Append the file being sent to the existing file</li> <li>◆ <b>Ask user</b> - Prompt for a decision on how to handle the duplicate file name</li> <li>◆ <b>Cancel</b> - Cancel the file transfer</li> <li>◆ <b>Fail</b> - Cancel the file transfer and send notification of the failure</li> <li>◆ <b>Skip</b> - The file matching an existing file name is skipped, but the transfer proceeds for the other files in the batch</li> <li>◆ <b>Unique</b> - Create a new file with a unique file name</li> </ul>

6. Click **Save**.


## Transferring files

---







**TIP:** Administrators grant permission to transfer files using the **User Preference Rules** option from the Settings panel.

---



Click  on the tool bar to open the list that contains the files you want to transfer.

1. Due to browser requirements, you need to specify the location of all files that you want to upload. Locate files as needed using the Search icon. Those files are easily identified with a yellow icon as such:

Local file name	Transfer	Remote file path
<input checked="" type="checkbox"/>  Locate "aed.jpg"	<input type="text" value=""/>   Upload	aed.jpg
<input checked="" type="checkbox"/>  Locate "ascii.txt"	<input type="text" value=""/>   Upload	ascii.txt

2. Files in the batch list are selected by default. To edit the file prior to transfer, you can eliminate files from the transfer operation by clearing their respective check boxes, or by selecting **All** from the drop down menu. You can also filter the list of transferable files based on their download or upload status.
3. Click **Start** to initiate the transfer.

## Specify Copy and Paste Options

You can specify different options to use for copy and paste operations.

### Copy options

Select text by dragging over it with the mouse. By default, different host types use different selection modes when copying text; IBM 3270, 5250 and UTS hosts use a block selection mode, while VT hosts use a linear selection mode. To toggle between block and linear selection modes, press and hold down the **Alt** key, then select the text.

- ♦ **Copy input fields only** -. Select this option to only copy data from input fields. Data from protected fields is replaced with spaces when placed on the clipboard.
- ♦ **Use entire display when there is no selection** - This option applies the Copy command to the entire terminal display when nothing is selected.

### Paste options

Click Paste to paste the contents of the clipboard at the cursor location.

- ♦ **Restore starting cursor position after paste**- By default, the host cursor is positioned at the end of the data following a paste operation. Select this option to restore the host cursor to its starting position after the paste operation is complete.
- ♦ **Mask protected fields** - Specifies how pasted text is mapped onto the screen:
  - If unselected (the default), the text is interpreted as a linear stream that can contain new lines and delimiters, and is pasted accordingly.
  - If selected, the text is interpreted as a host screen data and overlaid onto the current screen starting at the current cursor position. Where the current screen contains an unprotected field, the source text is pasted; where the current screen contains a protected field, the source text is skipped.

## Key combinations

There are certain key combinations that map to different copy/paste actions.

Key Combination	Host type	Action
Ctrl + A	UTS, 3270, 5250	Select all
Shift + Arrow key	UTS, 3270, 5250, VT	Change the extent of the current selection
Ctrl + C	UTS, 3270, 5250	Copy
Ctrl + V	UTS, 3270, 5250	Paste
Ctrl + Shift + A	VT	Select all
Ctrl + Shift + C	VT	Copy
Ctrl + Shift + V	VT	Paste

## Related Topics

[Copying and Pasting](#)

# Working with Sessions

All the sessions you have access to are available in the **Available Sessions** list. Sessions are initially created and configured by your system administrator and accessed through a distributed URL (for example, <https://<sessionserver>:7443>).

- ♦ [“Using Quick Keys” on page 113](#)
- ♦ [“Copying and Pasting” on page 113](#)
- ♦ [“Logging Out” on page 113](#)

## To open a session

- 1 Select the session and click to open.
- 2 Interact with your host application using the open session.
- 3 You can create multiple instances of a configured session.

You can have multiple sessions open at a time and easily switch between them using the tabs arranged across the top of the screen. The current session is always the left-most tab and is indicated by a white background and bold text. Each session remains active for 30 minutes.

Use the toolbar to access the various options available to you as you interact with the session. You can disconnect from a session, close the session, turn on Quick Keys, and access other settings. Some options may be only available once your administrator has granted permission.



## Using Quick Keys

The Quick Key terminal keyboard provides a graphical representation of the keys on a host keyboard and gives you quick access to terminal keys. Click a terminal key on the Quick Key keyboard to send the key to the host. Tool tips, which are available by hovering over a key, provide a description of the mapping.

Quick keys are available for each supported host type and are accessed by clicking the tool bar icon



## Copying and Pasting

---

**NOTE:** Each browser handles copy and paste functions differently and in some cases will not support the use of either the copy and paste toolbar buttons or the right-click context menu. It is highly recommended that you use keyboard commands for those functions. Although keyboard commands vary depending on your operating system, in Windows they are: **CTRL+C** to copy and **CTRL+V** to paste.

It is far more common to encounter problems with the paste function rather than copy. If the Paste toolbar button is not visible, it is likely that browser security is preventing read access to the system clipboard. Different browsers behave differently when it comes to providing access to the clipboard. However, pasting is almost always available using the keyboard commands, (Control + V on Windows and Command + V on Macs). This assumes you have not remapped those keys. You can also use the browser's built-in paste menu item or button.

---

### To copy from the terminal

- 1 Highlight the area on the terminal screen that you want to copy.
- 2 Click **Copy** from the toolbar or select **Copy** from the right-click context menu available within the terminal screen. You can alternatively use the keyboard command, **CTRL+C**.

### To paste into the terminal screen

- 1 Position the cursor where you want to paste content.
- 2 If the browser supports the paste function, click **Paste** from the toolbar or select **Paste** from the right-click context menu available within the terminal screen. If your browser does not support this functionality, these options will not be available and you should use the keyboard command, **CTRL+V**.

### Related Topics

[Specify Copy and Paste Options](#)

## Logging Out

In the upper right corner of the screen, open the drop down list associated with your user name and select **Logout** to stop working with the host application.

# Creating Macros

A macro is a series of keyboard actions that you record and then run. You can use these JavaScript macro programs to automate user interactions with the terminal. You can access and run macros from all supported devices.

Host Access for the Cloud records and saves advanced macros as JavaScript, making it easy to edit and enhance your recorded macros. You can record macros to playback later, run macros at startup or when the session connects or disconnects from the host. You can also write macros from scratch to perform complex tasks that the recorder cannot capture.

Macros are made available to users in two ways; created by an administrator or recorded by users for their own private use. All advanced macros are associated with a session and they all accomplish the same goal, automating host interaction. The only difference between the two flavors is simply who can access them and who manages their creation and availability:

- ◆ **Macros created by administrators**

Administrators create macros when they create the session. They are specific to a session and are available to all users who have access to the session from the Macro icon on the toolbar. Administrators can designate macros to run at startup or when the session connects or disconnects from the host.

- ◆ **Macros created by users**

End-user macros are created by individuals for sessions they are authorized to access. The administrator grants permission to create macros by setting a User Preference Rule. Users can access the session under their own credentials or in a **Guest** role. Macros that Guest users create are available to all Guest users. Users who are logged in using their own credentials can only see macros that they have created.

Advanced macros are listed in alphabetical order in the drop down list available from the toolbar. Macros created by the end-user are listed first and followed by an indicator of three vertical grey dots, which when selected, displays the Edit and Delete options. Macros created by the administrator are listed without the indicator as those macros cannot be modified by the end-user.

## Working with macros



Recording, editing, and playing back macros.


## How do I....

### Procedure

#### Record


1. Click the Macro icon on the toolbar, and then click **Record New Macro**.




2. Navigate the host application to record the series of steps you want included in the macro.
3. Click  on the toolbar to stop recording. The red dot pulses to indicate the recording is in process.
4. When prompted, type a name for the macro.


#### Edit

1. From the Macro drop down list, select the macro you want to edit.



2. Click the three vertical dots to expand the field.
3. Click  **Edit** to open the Macro Editor.  
The Macro Editor opens in the left panel.
4. Use JavaScript to make whatever changes are necessary. You can run and save the modified macro using the toolbar icons in the upper panel of the editor.


#### Run

To run a macro, choose the macro from the drop down list and click .

You can also map keys that will automatically trigger an already recorded macro. In the Key Map settings dialog box, choose **Run Macro** from the **Action** drop down list. Choose a macro to associate with the key mapping from the **Value** list.

#### Stop

You can stop a macro before it completes from either the Macro Editor or the toolbar.


Click  to stop the macro. To rerun the macro, navigate back to the macro starting screen.

## How do I.....

## Procedure

Delete

1. From the Macro drop down list, select the macro you want to delete.
2. Expand the field, by clicking the three vertical dot icon.



3. Click **Delete**.

View

The Macro drop down list is available from the toolbar to all users who have permission to record macros or are accessing a session where macros have been pre-recorded by the administrator for use with that session.

Macros are listed under either **MY MACROS** or **MACROS** depending on how they were recorded.

All users, whether they are logged in using their credentials or as Guest, can see the macros associated with the session. Macros listed under the MY MACROS heading are listed in alphabetical order by name and are visible to those users that recorded them. Macros recorded by the administrator and attached to a session are listed alphabetically under MACROS.

## Debugging macros

Since macros are written in JavaScript and executed in the browser, the best way to debug and troubleshoot them is by using your web browser's built-in tools. Modern browsers come with a very capable set of tools for debugging JavaScript code. You can place breakpoints, step through code, and output debug information.

---

**TIP:** JavaScript is case sensitive. Keep that in mind when editing JavaScript code.

---

To debug a macro:

1. Open the macro for editing. See [Working with macros](#) for instructions.
2. Open your browser's development tools.

**Table 5-10** Browser debugging support

Browser	Open debugger
Mozilla Firefox 40.0.3	<ul style="list-style-type: none"><li>◆ From the toolbar, open the Menu, and choose Developer.</li><li>◆ From the Web Developer menu, choose Debugger. The debugger opens in a lower panel.</li></ul>
Google Chrome 45.0	<ul style="list-style-type: none"><li>◆ From the toolbar, open the Menu, and choose More tools.</li><li>◆ Choose Developer Tools to open the Debugger.</li></ul>
Microsoft Internet Explorer 11	<ul style="list-style-type: none"><li>◆ From the toolbar, open Settings, and choose F12 Developer Tools.</li><li>◆ Open the Debugger tab.</li></ul>

These instructions are for supported browsers and are dependent on the versions used.

3. Use one of the these tools in your macro code, and run the code.

◆ *debugger*

The most thorough approach to debugging is to use the 'debugger;' statement. When you insert these statements into your macro code then run it, with the browser's development tools open, the execution will stop on those lines. You can step through your macro, view the value of local variables and whatever else you need to check.

You are encouraged to place multiple debugger; statements in your code to help get to the correct line. The asynchronous nature of JavaScript can make stepping through code challenging. This can be offset by using multiple, carefully placed debugger; statements.

**Example 5-1** Debugger

```
-----  
var hostCommand = menuSelection + `[enter]`;  
debugger; // <- Browser's debugger will stop here  
ps.sendKeys(hostCommand);  
-----
```

◆ `console.log()`, `alert()`

These two functions are commonly used for debugging JavaScript. While not as flexible as the debugger statement they provide a quick way to output debug information. These functions output the information to the JavaScript "Console" tab in the browser's developer tools.

**Example 5-2** `console.log()`, `alert()`

```
-----  
var hostCommand = menuSelection + `[enter]`;  
console.log('Command:' + hostCommand); // <- Will output the string  
to "Console" tab  
alert('Command:' + hostCommand); // Will pop up a small window  
containing the data  
ps.sendKeys(hostCommand);  
-----
```

◆ `ui.message()`

The Host Access for the Cloud Macro API provides an `ui.message()` function that is very similar to JavaScript's `alert()` function. You can also use `ui.message()` to output debug information.

**Example 5-3** `ui.message()`

```
-----  
var hostCommand = menuSelection + '[enter]';  
ui.message('Command:' + hostCommand); // <- Will pop up a message  
window  
ps.sendKeys(hostCommand);  
-----
```

Keep in mind:

- ◆ Stepping and “yields”

While the `yield` statements in macros make them easier to understand, they can make the code more challenging to step through with the debugger. Consider either using multiple debugger statements or carefully placed debugger statements of `console.log()` calls to output the right debug information.

- ◆ Internet Explorer

Debugging in Internet Explorer involves transformed code and may be more difficult than on other browsers.

## Using the Macro API

In Host Access for the Cloud macros are recorded and written using JavaScript. JavaScript is a popular and prevalent programming language. There are a wide variety of learning resources and tools available to you.

The Macro API consists of a set of objects which you can use to interact with the host, wait for screen states, and interact with the user.

### About promises and yields

Because JavaScript is single threaded and uses 'callback functions' and 'promises' to help manage the flow of execution through code, often code can be difficult to follow. Host Access for the Cloud combines the concept of 'promises' with the 'yield' keyword so macro code can be organized in a more linear fashion.

- ◆ Promises

Promises are patterns to help simplify functions that return their result asynchronously, at some point in the future. All 'wait' and 'ui' functions in the Macro API return promise objects.

- ◆ Yield

Macros use the `yield` keyword to block the execution of the macro until a promise is resolved, or done. So putting `yield` in front of any 'wait' or 'ui' function makes the macro execution pause until that function has finished executing. You can place the `yield` keyword in front of any function that returns a promise, even your own custom functions.

---

**NOTE:** The ability to make macro execution block by combining `yield` with promises is enabled by the `createMacro()` function.

---

## Errors

Errors are handled in macros using a `try / catch` statement. Some API functions may throw errors if, for example, conditions can't be met or a timeout occurs. The thrown error is 'caught' in the catch statement. You can wrap smaller blocks of code in a `try / catch` statement to handle errors at a more granular level. Macro developers can also throw errors with `throw new Error('Helpful error message');`

## Related Topics

- ◆ [“Macro API Objects” on page 119](#)
- ◆ [“Sample Macros” on page 148](#)

## Macro API Objects

You can create macros using the Macro API. By default for use in macros, there are four primary objects available:

- ◆ [Session](#)

Session is the main entry point for access to the host. You use the Session object to connect, disconnect and provide access to the PresentationSpace object.

- ◆ [PresentationSpace](#)

The PresentationSpace object represents the screen and provides many common capabilities such as getting and setting the cursor location, sending data to the host and reading from the screen. It is obtained by calling `session.getPresentationSpace()`.

- ◆ [Wait](#)

Provides a simple way to wait for various host states to occur before continuing to send more data or read from the screen. For example, you can wait for the cursor to be located at a certain position, text to be present in a position on the screen or simply wait for a fixed amount of time. All 'Wait' function calls require the `yield` keyword, which is explained below.

- ◆ [User Interface](#)

The UI object is made automatically available in your macro as the `“ui”` variable. It provides basic user interface capabilities. You can use this object to display data to the user or prompt them for information. All 'UI' function calls require the `yield` keyword.

## Other available objects

- ◆ [Attribute](#)
- ◆ [AttributeSet](#)
- ◆ [Color](#)
- ◆ [ControlKey](#)
- ◆ [DataCell](#)
- ◆ [Dimension](#)
- ◆ [Field](#)

- ◆ [FieldList](#)
- ◆ [FileTransferFactory](#)
- ◆ [FileTransfer](#)
- ◆ [HostFile](#)
- ◆ [Host File Type](#)
- ◆ [File Transfer Options](#)
- ◆ [OIA](#)
- ◆ [OIAStatus](#)
- ◆ [AutoSignon](#)
- ◆ [Position](#)
- ◆ [PresentationSpace](#)
- ◆ [Session](#)
- ◆ [SessionType](#)
- ◆ [StatusSet](#)
- ◆ [User Interface](#)
- ◆ [Wait](#)

## Attribute

Use the Attribute, along with the AttributeSet, to decode the formatting information present on the data cell.

*Table 5-11 Attributes*

Attribute	Description
PROTECTED	Indicates a protected data cell.
MODIFIED	Indicates a modified data cell.
NUMERIC_ONLY	Indicates the beginning of a numeric only data cell.
ALPHA_NUMERIC	Indicates an alpha numeric data cell.
HIGH_INTENSITY	Indicates whether the data cell contains high intensity text.
HIDDEN	Indicates whether the data cell contains hidden text
PEN_DETECTABLE	Indicates whether the data cell is pen detectable
ALPHA_ONLY	Indicates an alpha only data cell.
NUMERIC_SHIFT	Indicates the beginning of a numeric shift. field
NUMERIC_SPECIAL	Indicates the data cell marks the beginning of a numeric special field
KATAKANA_SHIFT	Indicates a section of Katakana text.
MAGNETIC_STRIPE	Indicates the data cell marks the beginning of a magnetic strip field.
SIGNED_NUMERIC_ONLY	Indicates the data cell is a signed numeric field.



<b>Attribute</b>	<b>Description</b>
TRANSMIT_ONLY	Indicates the data cell is a transmit only field
FIELD_END_MARKER	Indicates the data cell marks the end of a modified field.
FIELD_START_MARKER	Indicates the data cell marks the start of a modified field.
SPECIAL_EMPHASIS_PROTECTED	Indicates a special emphasis protected field.
TAB_STOP	Indicates that the data cell contains a tab stop.
REVERSE	Indicates the data cell displays in reverse video mode.
BLINKING	Indicates the data cell contains blinking text
RIGHT_JUSTIFIED	Indicates the data cell marks the beginning of a right justified field.
LEFT_JUSTIFIED	Indicates the data cell marks the beginning of a left justified field.
LOW_INTENSITY	Indicates the data cell contains low intensity text
UNDERLINE	Indicates the data cell contains underlined text.
DOUBLE_BYTE	Indicates the data cell contains double byte text.
COLUMN_SEPARATOR	Indicates the data cell contains a column separator.
BOLD	Indicates the data cell contains bold text.
DOUBLE_WIDTH	Indicates the data cell marks a double width field.
DOUBLE_HEIGHT_TOP	Indicates a double height top data cell.
DOUBLE_HEIGHT_BOTTOM	Indicates a double height bottom data cell.
CONTROL_PAGE_DATA	Indicates the data cell contains control page data.
RIGHT_COLUMN_SEPARATOR	Indicates the data cell contains a right column separator.
LEFT_COLUMN_SEPARATOR	Indicates a data cell containing a left column separator.
UPPERSCORE	Indicates the data cell contains an upperscore.
STRIKE_THROUGH	Indicates the data cell contains strike through text.

## **AttributeSet**

The AttributeSet object allows the user to decode the attributes that are present on the data cell. The AttributeSet object returns values defined in the [Attribute](#) object and when used together, you can get formatting information from the data cell.

**Table 5-12** *AttributeSet*

## METHODS

<code>contains(attribute)</code>	Determines if the set contains the specified <a href="#">Attribute</a> . <b>Parameters</b> {Number} attribute to check <b>Returns</b> {Boolean} True if the attribute is in the set.
<code>isEmpty()</code>	Determines if the attribute set is empty. <b>Returns</b> {Boolean} True if the set is empty.
<code>size()</code>	Indicates the number of attributes in a set. <b>Returns</b> {Number} The attribute count.
<code>toArray()</code>	Converts the internal attribute set to an array. <b>Returns</b> {Number[]} Array of values of attributes in the set.
<code>toString()</code>	Converts the internal attribute set to a string. <b>Returns</b> {String} Space-delimited names of attributes in the set.
<code>forEach(callback, thisArg)</code>	Function to iterate over each element in the attribute set. <b>Parameters</b> {forEachCallback} Callback to perform the specific operation. Called with the name of each attribute in the set. {Object} this Arg optional pointer to a context object.
<code>forEachCallback(string, object)</code>	A user provided callback function where you provide the behavior, to be used as the callback parameter to <code>forEach</code> . <b>Parameters</b> {String} String name of an attribute in the attribute set. {Object} thisArg optional pointer to a context object.

## Color

Color constants to use for the DataCell object foreground and background colors.

**Table 5-13** Color constants

Color	Description	Numeric Value
BLANK_UNSPECIFIED	No color specified	0
BLUE	Blue	1
GREEN	Green	2
CYAN	Cyan	3
RED	Red	4
MAGENTA	Magenta	5
YELLOW	Yellow	6
WHITE_NORMAL_INTENSITY	Normal intensity white	7
GRAY	Gray	8
LIGHT_BLUE	Light blue	9
LIGHT_GREEN	Light green	10
LIGHT_CYAN	Light cyan	11
LIGHT_RED	Light red	12
LIGHT_MAGENTA	Light magenta	13
BLACK	Black	14
WHITE_HIGH_INTENSITY	High intensity white	15
BROWN	Brown	16
PINK	Pink	17
TURQUOISE	Turquoise	18

## ControlKey

The ControlKey object defines constants for sending cursor control keys and host commands using the sendKeys method. Constants are available for these host types:

- ◆ [IBM 3270](#)
- ◆ [IBM 5250](#)
- ◆ [VT](#)
- ◆ [UTS](#)

## IBM 3270

**Table 5-14** IBM 3270

Key word	Description
ALTVIEW	Alternate view

<b>Key word</b>	<b>Description</b>
ATTN	Attention
BACKSPACE	Back space
BACKTAB	Back tab
CLEAR	Clear or clear display
CURSOR_SELECT	Cursor select
DELETE_CHAR	Delete, delete character
DELETE_WORD	Delete word
DEST_BACK	Destructive backspace
DEV_CANCEL	Device cancel
DOWN	Cursor down
DSPSOSI	display SO/SI
DUP	Duplicate field
END_FILE	End of field
ENTER	Enter
ERASE_EOF	Erase end of field
ERASE_FIELD	Erase field
ERASE_INPUT	Erase input
FIELD_MARK	Field mark
HOME	Cursor home
IDENT	Ident
INSERT	Insert
LEFT_ARROW	Cursor left
LEFT2	Left two positions
NEW_LINE	New line
PA1 - PA3	PA1 - PA3
PF1 - PF24	PF1 - PF24
PAGE_DOWN	Page down
PAGE_UP	Page up
RESET	Reset, reset terminal
RIGHT2	Right 2 positions
RIGHT_ARROW	Cursor right, right
SYSTEM_REQUEST	System request

<b>Key word</b>	<b>Description</b>
TAB	Tab key
UP	Cursor up

## **IBM 5250**

*Table 5-15 IBM 5250*

<b>Key word</b>	<b>Description</b>
ALTVIEW	Alternate view
ATTN	Attention
AU1 - AU16	AU1 - AU16
BACKSPACE	Back space
BACKTAB	Back tab
BEGIN_FIELD	Begin field
CLEAR	Clear
DELETE_CHAR	Delete, delete character
DEST_BACK	Destructive backspace
DOWN	cursor down
DSPSOSI	Display SO/SI
DUP	Duplicate field
END_FILE	End of field
ENTER	Enter
ERASE_EOF	Erase end of field
ERASE_FIELD	Erase field
ERASE_INPUT	Erase input
FIELD_EXT	Field exit
FIELD_MINUS	Field minus
FIELD_PLUS	Field plus
FIELD_MARK	Field mark
HELP	Help request
HEXMODE	Hex mode
HOME	cursor home
INSERT	Insert

<b>Key word</b>	<b>Description</b>
LEFT_ARROW	Cursor left
NEW_LINE	New line
PA1 - PA3	PA1 - PA3
[PF1 - PF24	PF1 - PF24
[print]	Print
RESET	Reset, reset terminal
RIGHT_ARROW	Cursor right, right
PAGE_UP	Page up
PAGE_DOWN	Page down
SYSTEM_REQUEST	System request
TAB	Tab
UP	Cursor up

## **VT**

*Table 5-16 VT*

<b>Keywords</b>	<b>Description</b>
BACKSPACE	Back space
BREAK	Break
CLEAR	Clear or clear display
CURSOR_SELECT	Cursor select
DELETE_CHAR	Delete, delete character
DOWN	Cursor down
EK_FIND	Edit keypad find
EK_INSERT	Edit keypad insert
EK_NEXT	Edit keypad next
EK_PREV	Edit keypad previous
EK_REMOVE	Edit keypad remove
EK_SELECT	Edit keypad select
ENTER	Enter
END_FILE	End of field
F1 - F24	F1 - F24

<b>Keywords</b>	<b>Description</b>
HOLD	Hold
HOME	Home
INSERT	Insert
KEYPAD_COMMA	Keypad comma
KEYPAD_DOT	Keypad decimal
KEYPAD_MINUS	Keypad minus
KEYPAD_ENTER	Keypad enter
KEYPAD0 - KEYPAD9	Keypad 0 - Keypad 9
LEFT_ARROW:	Cursor left
PF1 - PF20	PF1 - PF20
PAGE_DOWN	Page down
PAGE_UP	Page up
RESET	Reset, reset terminal
RETURN	Return, carriage return
RIGHT_ARROW	Cursor right, right
TAB	Tab key
UDK16 - UDK20	User defined key 6 - User defined key 20
UP	Cursor up

## **UTS**

*Table 5-17 UTS*

<b>Key word</b>	<b>Description</b>
BACKSPACE	Moves the cursor to the previous tab position on the screen.
BACKTAB	Back tab <Shift> <Tab>
CHAR_ERASE	Erases character at the cursor and advances the cursor.
CLEAR_DISPLAY	Clear display
CLEAR_EOD	Clear to end of display
CLEAR_EOF	Clear to end of field
CLEAR_EOL	Clear to end of line
CLEAR_FCC	Clear Field Control Character
CLEAR_HOME	Clear display and cursor home

<b>Key word</b>	<b>Description</b>
CONTROL_PAGE	Toggles the control page
DELETE_LINE	Deletes the line containing the cursor and shifts remaining lines up one row
DOWN	Moves the cursor down one line. Wraps at bottom.
DELIN_LINE	Deletes character under cursor and shifts remaining characters on line to the left.
DELIN_PAGE	Deletes character under cursor and shifts remaining characters on page to the left.
DUP_LINE	Creates a copy of the current line and overwrites the next line with the duplicate.
EURO	Inserts the Euro character
END_FIELD	Moves the cursor to the end of the current field.
END_PAGE	Moves the cursor to the end of the current page.
F1 - F22	Function keys F1-F22
HOME	Moves the cursor to beginning of current page (row 1, col 1)
INSERT	Toggles insert/overwrite mode.
INSERT_IN_LINE	Inserts space at cursor position and shifts the remaining characters on the line to the right. The character in the far right column on the line is discarded.
INSERT_IN_PAGE	Inserts space at cursor position and shifts the remaining characters on the page to the right. The character in the far right column on each line is discarded.
INSERT_LINE	Inserts a new line at the cursor row and shifts the remaining lines down. The last row on the page is discarded.
LEFT_ARROW	Moves the cursor one position to the left wrapping if necessary.
LOCATE_FCC	Finds the next field control character on the screen.
MSG_WAIT	Retrieves messages queued to the terminal.
RETURN	Carriage return
RIGHT_ARROW	Moves the cursor one position to the right, wrapping if necessary.
SOE	Inserts the Start of Entry character
START_OF_FIELD	Moves the cursor to the beginning of the field.
START_OF_LINE	Moves the cursor to column 1 of current line.
TAB	Moves the cursor to the next tab position of the screen.
TOGGLE_COL_SEP	Toggles the column separator attribute.
TOGGLE_STRIKE_THRU	Toggles the strike-through attribute on the current data cell.



Key word	Description
TOGGLE_UNDERLINE	Toggles the underline attribute on the current data cell.
TRANSMIT	Transmits changed field data to the host.
UNLOCK	Sends the UNLOCK key to the host.
UP	Moves the cursor up one row, wrapping if necessary.

## DataCell

The DataCell object provides information about a particular position on a terminal screen.

**Table 5-18** DataCell

### METHODS

getPosition()	Returns the position of this data cell on the screen.  <b>Returns</b> {Position} the position of the data cell on the screen
getChar()	Obtains the character associated with the cell.  <b>Returns</b> {String} The character associated with the cell.
getAttributes()	Returns the set of attributes specified for this data cell instance. See <a href="#">AttributeSet</a> .  <b>Returns</b> {AttributeSet} Of attributes for this data cell instance.
getForegroundColor()	Returns the foreground color, as defined in the Color object, for this data cell.  <b>Returns</b> {Number} Foreground color for this data cell. The color is defined in the <a href="#">Color</a> object.
getBackgroundColor()	Returns the background color, as defined in the Color object, for this data cell.  <b>Returns</b> {Number} Background color for this data cell. The color is defined in the <a href="#">Color</a> object.
toString	Converts the internal data cell to a string.  <b>Returns</b> {String} The string representation of a data cell.

## METHODS

`isFieldDelimiter()` Tests if this cell represents a field delimiter.

### Returns

{Boolean} True if this cell is a field delimiter, false if otherwise.

## Dimension

Represents the size of the screen or screen area.

*Table 5-19 Dimension*

---

Method	
<code>Dimension(rows, cols)</code>	Creates a new Dimension instance.
<b>Parameters</b>	
	{Number} rows screen rows dimension
	{Number} cols screen columns dimension

---

## Field

Use the Field object, along with [FieldList](#), to obtain the information present in a field on the screen.

*Table 5-20 Field*

---

Method	
<code>getAttributes()</code>	Returns the set of attributes specified for this field instance. See <a href="#">AttributeSet</a> .
<b>Returns</b>	
	{AttributeSet} The set of attributes for this field
<code>getForegroundColor()</code>	Returns the foreground color of the field.
<b>Returns</b>	
	{Number} the foreground color for this field. These values are defined in the <a href="#">Color</a> object.
<code>getBackgroundColor()</code>	Returns the background color of the field.
<b>Returns</b>	
	{Number} the background color for this field. These values are defined in the <a href="#">Color</a> object.

---

---

**Method**

---

<code>getStart()</code>	<p>Returns the starting position of the field. The starting position is the position of the first character of the field. Some host types use a character position to store field level attributes. In this case, the attribute position is not considered the start position.</p> <p><b>Returns</b></p> <p>{Position} Starting position of the field.</p> <p><b>Throws</b></p> <p>{RangeError} For zero length fields.</p>
<code>getEnd()</code>	<p>Returns the ending position of the field. The ending position is the position in the presentation space containing the last character of the field.</p> <p><b>Returns</b></p> <p>{Position} Ending position of the field.</p> <p><b>Throws</b></p> <p>{RangeError} For zero length fields.</p>
<code>getLength()</code>	<p>Returns the length of the field. For host types that use a character position to store the field attributes, the field length does not include the field attribute position.</p> <p><b>Returns</b></p> <p>{Number} Length of the field.</p>
<code>getDataCells()</code>	<p>Obtains the data cells that comprise this field. See <a href="#">DataCell</a>.</p> <p><b>Returns</b></p> <p>{DataCell[]} Data cells that comprise this field.</p>
<code>getText()</code>	<p>Obtains the text from the field.</p> <p><b>Returns</b></p> <p>{String} field text.</p>
<code>setText()</code>	<p>Sets the field text. For certain host types, like VT, the text is transmitted to the host right away, but in other host types, the text is not transmitted to the host until an Aid key is invoked. If the text is shorter than the field, the text is placed in the host field, and the remainder of the field is cleared. If the text is longer than the host field, then as much text as will fit is placed in the field.</p> <p><b>Parameters</b></p> <p>{String} Text to set on the field.</p> <p><b>Throws</b></p> <p>{Error} If the field is protected.</p>

---

---

**Method**

---

<code>clearField()</code>	Clears the current field in an emulation-specific manner. <b>Throws</b> {Error} If the field is protected or clear is not supported.
<code>getPresentationSpace()</code>	Obtains the <a href="#">PresentationSpace</a> which created this field. <b>Returns</b> {PresentationSpace} Parent of this field instance.
<code>toString()</code>	Creates a user-friendly description of the field. <b>Returns</b> {String} A user readable rendition of the field.

---

**FieldList**

Use the FieldList object, along with Field object, to obtain field list information.

*Table 5-21 FieldList*

---

**Method**

---

<code>getPresentationSpace()</code>	Obtains the <a href="#">PresentationSpace</a> which created this field list. <b>Returns</b> {PresentationSpace} Parent of this field list instance.
-------------------------------------	---

---

---

**Method**

---

`findField(position, text, direction)`

Returns the field containing the specified text. The search starts from the specified position and proceeds either forward or backward. If the string spans multiple fields, the field containing the starting position is returned. When searching forward the search will not wrap to the top of the screen. When searching backward the search will not wrap to the bottom of the screen.

**Parameters**

{Position} Position from which to start the search. See [Position](#) object.

{String} The text to search for (optional). If not provided, returns the next field to the right of or below the specified position.

{Number} direction of the search (optional). Use [PresentationSpace](#). SearchDirection constants for this parameter. For example, `PresentationSpace.SearchDirection.FORWARD` or `PresentationSpace.SearchDirection.BACKWARD`. If not provided, searches forward.

**Returns**

{Field} containing the string or null if a field meeting the given criteria is not found.

**Throws**

{RangeError} If the position is out of range.

`get(index)`

Obtains the field at the given index.

**Parameters**

{Number} index into the field list.

**Returns**

{Field} located at the specified index.

**Throws**

{RangeError} If the index is out of range.

`isEmpty()`

Determines if the field list is empty.

**Returns**

{Boolean} True if the list is empty.

`size()`

Indicates the number of fields in the list.

**Returns**

{Number} The field count

---

---

**Method**

---

`toString()` Creates a user-friendly description of the field list.

**Returns**

`{String}` User readable rendition of the field list.

---

**FileTransferFactory**

A `fileTransferFactory` object is available to all macros. If file transfers are configured for the session, you can use it to get a reference to a `FileTransfer` object.

*Table 5-22 fileTransferFactory*

---

**Method**

---

`getIND$File()` Returns a `FileTransfer` object for interacting with the configured `Ind$File` type for the session.

**Returns**

`{FileTransfer}`

**Throws**

`{Error}` If the session hasn't been configured to allow `IND$File` transfers.

---

**FileTransfer**

Use the `FileTransfer` object to list and transfer files between the host system and the client.

The Host Access for the Cloud file transfer API abstracts the file path conventions used by different host file implementations. Follow URL or Linux file system path formats when formatting file paths used by the API. For example, `/root/directory/file`. It is important to observe any rules specific to host systems, such as allowable characters or name lengths.

---

**NOTE:** Browsers place significant security restrictions around the ability of Javascript to interact with client file systems.

---

**Table 5-23** *FileTransfer*

---

<b>Method</b>	
<code>getHostFileListing(remotePath)</code>	<p>Request a listing of host files. If <code>remotePath</code> is omitted, a file listing for the current remote working directory is shown.</p> <p><b>Parameters</b></p> <p>{String} (optional) If specified will get file listing for specified remote path. If not specified, will get file listing for current remote working directory.</p> <p><b>Returns</b></p> <p>{Promise} Resolves to an array of <code>HostFile</code> objects contained at <code>remoteName</code>. Rejected if the remote path can not be read.</p>
<code>sendFile(localFile, remoteName)</code>	<p>Sends specified file to the host.</p> <p><b>Parameters</b></p> <p>{File} Javascript file object pointing to local file to send.</p> <p>{String} Fully-qualified remote file name as allowed by remote system (Unix, Windows, MVS, VAX).</p> <p><b>Returns</b></p> <p>{Promise} fulfilled with a <code>HostFile</code> object representing the sent file on success. Rejected if an error occurred sending the file.</p>
<code>getDownloadURL(remoteName)</code>	<p>Constructs a link to download a file from a host system.</p> <p><b>Parameters</b></p> <p>{String} Fully-qualified remote file name as allowed by remote system (Unix, Windows, MVS, VAX).</p> <p><b>Returns</b></p> <p>{URL} that can be used to retrieve the file from the Host Access for the Cloud session server.</p>
<code>setTransferOptions(options)</code>	<p>Set transfer options for current <code>FileTransfer</code> session. The transfer options are applied to all future transfers until the session is either exited or overridden by another call to <code>setTransferOptions</code>.</p> <p><b>Parameters</b></p> <p>{JSON} see <code>FileTransferOptions</code> for allowed names and values.</p> <p><b>Returns</b></p> <p>{Promise} fulfilled when the call completes. Rejected if an error occurred setting the options.</p>

---

---

**Method**

---

`cancel()` Cancels the current transfer in progress.

**Returns**

{`Promise`} fulfilled when the call completes. Rejected if an error occurred canceling the transfer.

---

**HostFile**

A `HostFile` object represents a file on the host file system.

*Table 5-24 HostFile*

---

**Method**

---

`getName()` Gets the file name

**Returns**

{`String`} the file name.

`getParent()` Gets the parent of this host file

**Returns**

{`String`} the parent of this host file. This means different things on different host types. For example on TSO this is the name of the catalog in which the file resides.

`getSize()` The byte size of the file

**Returns**

{`Number`} the size of the file in bytes.

`getType()` The type of file represented

**Returns**

---

**Host File Type**

The `HostFileType` object defines constants for determining the type of a `HostFile` object.

*Table 5-25 HostFileType*

---

Value	Description
FILE	Represents a file on the host system.
DIR	Represents a directory on the host system.
UNKNOWN	Represents a host file of unknown origin.

---



## File Transfer Options

File transfer option object specification.

Example: `fileTransfer.setTransferOptions({ transferMethod : 'ascii' });`

**Table 5-26** *FileTransferOptions*

Method	
<code>transferMethod</code>	{String} Allowed values: <ul style="list-style-type: none"><li>◆ 'ascii'</li><li>◆ 'binary'</li></ul>

## OIA

Operator Information Area (OIA) interface. The OIA object returns values which are defined in the [OIAStatus](#) object.

**Table 5-27** *OIA*

Method	
<code>getStatus()</code>	Returns the set of enabled status flags. See <a href="#">StatusSet</a> . <b>Parameters</b> <b>Returns</b> {StatusSet} Containing the status information.
<code>getCommErrorCode()</code>	Returns the current communication error code. <b>Returns</b> {Number} the current communication error code. If one doesn't exist, it will be 0.
<code>getProgErrorCode()</code>	Returns the current program error code <b>Returns</b> {Number} the current program error code. If one doesn't exist, it will be 0.

## OIAStatus

**Table 5-28** *OIAStatus*

OIAStatus	Description
CONTROLLER_READY	Controller ready
A_ONLINE	Online with a non-SNA connection

<b>OIAStatus</b>	<b>Description</b>
MY_JOB	Connected to a host application
OP_SYS	Connected to a SSCP (SNA)
UNOWNED	Not connected
TIME	Keyboard inhibited
SYS_LOCK	System lock following AID key
COMM_CHECK	Communication check
PROG_CHECK	Program check
ELSEWHERE	Keystroke invalid at cursor location
FN_MINUS	Function not available
WHAT_KEY	Keystroke invalid
MORE_THAN	Too many characters entered in the field
SYM_MINUS	Symbol entered not available
INPUT_ERROR	Operator input error (5250 only)
DO_NOT_ENTER	Do not enter
INSERT	Cursor in insert mode
GR_CURSOR	Cursor in graphics mode
COMM_ERR_REM	Communications error reminder
MSG_WAITING	Message waiting indicator
ENCRYPT	Session is encrypted
NUM_FIELD	Invalid character in numeric only field

### **AutoSignon**

Some mainframe hosts have a Digital Certificate Access Server (DCAS). You can request a temporary, one-time pass ticket from DCAS for logging into a host application. Using this object, you can write and configure a macro to run when the session starts and to automatically log you in using the credentials of the currently logged in user.

**Table 5-29** AutoSignon

---

<b>Method</b>	
<code>getPassTicket()</code>	<p>Obtains a pass ticket to be used for signing onto a mainframe application. Multiple pass tickets may be requested using different application IDs.</p> <p><b>Parameters</b></p> <p>{String} application ID tells the host which application the sign on is for</p> <p><b>Returns</b></p> <p>{Promise} fulfilled with the pass ticket key or rejected if the operation fails. The pass ticket obtained from DCAS only works with the current host session and is valid for ten minutes.</p>
<code>sendUserName()</code>	<p>Applies the user name contained in the pass ticket to the field at the current cursor location on the current host screen. The user name must be sent before the password. Sending the password first will invalidate the pass ticket, and you will need to get another one.</p> <p><b>Parameters</b></p> <p>{String} passTicketKey opbtained from getPassTicket</p> <p><b>Returns</b></p> <p>{Promise} fulfilled if the user name is successfully sent. Rejected if the operation fails.</p>
<code>sendPassword()</code>	<p>Applies the password contained in the pass ticket to the field at the current cursor location on the current host screen. The user name must be sent before the password. Sending the password first will invalidate the pass ticket, and you will need to get another one.</p> <p><b>Parameters</b></p> <p>{String} passTicketKey obtained from getPassTicket</p> <p><b>Returns</b></p> <p>{Promise} fulfilled if the password is successfully sent. Rejected if the operation fails.</p>

---

**Position**

Represents a row and column on the screen.

**Table 5-30** *Position*

---

<b>Method</b>	
<code>Position(row, col)</code>	Creates a new Position instance.
<b>Parameters</b>	
	{Number} row screen row coordinate
	{Number} col screen column coordinate

---

## PresentationSpace

Use the PresentationSpace object to interact with the terminal screen. Setting and getting the cursor position, sending keys, and reading text are some of the interactions available.

**Table 5-31** *PresentationSpace*

### METHODS

<code>getCursorPosition()</code>	Returns a <a href="#">Position</a> instance representing the current cursor position. An unconnected session has a cursor position of 0,0.
	<b>Returns</b>
	{Position} current cursor location
<code>setCursorPosition(position)</code>	Moves the host cursor to the specified row and column position. For some hosts, such as VT, the host may constrain the movements of the cursor.
	<b>Parameters</b>
	{Position} <a href="#">Position</a> new cursor position.
	<b>Returns</b>
	None
	<b>Throws</b>
	{RangeError} If the position is not valid on the current screen.
<code>isCursorVisible()</code>	Tests that the cursor is currently visible in the presentation space. The cursor is considered not visible if the session is not connected.
	<b>Returns</b>
	{Boolean} True if the cursor is visible. False if the cursor is not visible.

## METHODS

`sendKeys (keys)` Transmits a text string or [ControlKey](#) to the host at the current cursor position in the presentation space. If the cursor is not in the desired position, then use `setCursorPosition` function first.

The text string can contain any number of characters and [ControlKey](#) objects.

For example: `"myname" + ControlKey.TAB + "mypass" + ControlKey.ENTER` will transmit a user ID, tab to the next field, transmit a password, and then transmit the Enter key.

If you need to transmit a square bracket, double the brackets (`[[` or `]]`).

### Parameters

`{String}` keys text and/or control keys to transmit

`getText (start, length)` Returns a string representing a linear area of the presentation space. No new line characters are inserted if row boundaries are encountered.

### Parameters

`{Position}` start position from which to retrieve text

`{Number}` length the maximum number of characters to return. If the length parameter causes the last position of the presentation space to be exceeded then only those characters up to the last position will be returned.

### Returns

`{String}` representing a linear area of the presentation space which may be empty if the session is not connected.

### Throws

`{RangeError}` If the position or length are not valid on the current screen.

`getSize()` Gets the dimensions of the screen as a `Dimension` object.

### Returns

`{Dimension}` Containing the number of rows and columns. The screen size is `[row:0, col:0]` if the session is not connected.

## METHODS

`getDataCells(start, length)`

Returns [DataCell](#) instances where the first member will be for the position specified by the start parameter. The maximum number of DataCell instances in the list is specified by the length parameter.

### Parameters

{Position} start the first position on the host screen in which to retrieve DataCell instances. See [Position](#).

{Number} length of the maximum number of DataCell instance to be retrieved. If not specified, returns DataCells from the start position to the end of the screen.

### Returns

{DataCell[]} Instances which may be empty if the session is not connected. If position is not specified, returns all DataCells. If length is not specified, returns DataCells from the start position to the end of the screen.

### Throws

{RangeError} if start or length are out of range.

`getFields()`

Returns a list of the fields in the presentation space. If the host type does not support fields or the current screen is not formatted then the return value will always be an empty list. See [FieldList](#).

### Returns

{FieldList} of host defined fields in the presentation space.

## Session

The session object is the main entry point for interacting with the host. It contains functions for connecting, disconnecting, and obtaining the PresentationSpace object.

**Table 5-32** Session object functions

## METHODS

`connect()`

Connects to the configured host. If needed, use `wait.forConnect()` to block macro execution until the session is connected.

### Returns

None

`disconnect()`

Disconnects from the configured host. If needed, use `wait.forDisconnect()` to block macro execution until the session is connected.

### Returns

None

## METHODS

<code>isConnected()</code>	Determines whether the connection to the host is connected. <b>Returns</b> {Boolean} true if host connection is established; false if not
<code>getPresentationSpace()</code>	Provides access to the <a href="#">PresentationSpace</a> instance for this session. <b>Returns</b> {PresentationSpace} instance associated with this session.
<code>getDeviceName()</code>	Returns the device name for a connected session or an empty string if the session is disconnected or doesn't have device name. <b>Returns</b> {String} The connected device name.
<code>getType()</code>	Returns the type of host session. See <a href="#">SessionType</a> . <b>Returns</b> {String} The type of host session.
<code>setDeviceName()</code>	Provides a means to modify the device name on a session instance. <b>Parameters</b> {String} name Device name to use when connecting to a host. <b>Throws</b> {Error} If an attempt is made to set the device name while the session is connected.
<code>getOIA()</code>	Provides access to the <a href="#">OIA</a> instance for this session. <b>Returns</b> {OIA} Associated with this session

## SessionType

Constants used to identify the type of host to which the connection is being made. See [Session](#) object.

**Table 5-33** *SessionType*

Host Type	Description
IBM_3270	Indicates an IBM 3270 terminal session.
IBM_5250	Indicates an IBM 5250 terminal session.
VT	Indicates a VT session.

## StatusSet

You can use the StatusSet object to decode the OIA status. The StatusSet object returns values defined in the [OIAStatus](#) object and when used together, you can get status information from the OIA.

**Table 5-34** StatusSet

Method	
<code>contains(statusFlag)</code>	<p>Determines if the set contains the specified status flag from <a href="#">OIAStatus</a> constants.</p> <p><b>Parameters</b></p> <p>{Number} statusFlag status to check</p> <p><b>Returns</b></p> <p>{Boolean} True if the status flag is present in the set.</p>
<code>isEmpty()</code>	<p>Determines if the status set is empty.</p> <p><b>Returns</b></p> <p>{Boolean} True if the set is empty.</p>
<code>size()</code>	<p>Indicates the number of status flags in the set.</p> <p><b>Returns</b></p> <p>{Number} The status count</p>
<code>toArray()</code>	<p>Converts the internal status set to an array.</p> <p><b>Returns</b></p> <p>{Object []} Array of status flags in the set.</p>
<code>toString()</code>	<p>Converts the internal status set to a string.</p> <p><b>Returns</b></p> <p>{String} Space delimited names of status flags in the set.</p>
<code>forEach(callback, thisArg)</code>	<p>Function to iterate over each element in the status set.</p> <p><b>Parameters</b></p> <p>{forEachCallback} Callback to perform the specific operation. Called with the name of each status in the set.</p> <p>{Object} thisArg optional pointer to a context object.</p>
<code>forEachCallback(string, thisArg)</code>	<p>A user provided callback function where you provide the behavior, to be used as the callback parameter to <code>forEach</code>.</p> <p><b>Parameters</b></p> <p>{String} String The name of a status in the status set.</p> <p>{Object} thisArg Optional pointer to a context object</p>



## User Interface

The user interface object provides functions for interacting with the user, prompting for and displaying basic information. The UI object is made automatically available in your macro as the “ui” variable”.

---

**NOTE:** Important! All UI functions require the ‘yield’ keyword in front of them. This allows the macro to block execution until the conditions of the UI function have been met.

[parameter] denotes an optional parameter.

---

**Table 5-35** *User Interaction*

### METHODS

`prompt(message, [defaultAnswer], [mask])` Prompt the user for information in the user interface,

#### Parameters

{String} message title to display to the user. Default: blank String.

{String} defaultAnswer to use if user leaves it blank. Default: blank String

{Boolean} mask indicates whether to hide the prompt (as with a password).

#### Returns

{Promise} Fulfilled when the user closes the dialog window. Returns the users input on “OK” or null on “Cancel”.

`message([message])`

Display a message in the user interface.

#### Parameters

{String} message to display to the user. Default: blank String.

#### Returns

{Promise} Fulfilled when the user closes the message window.

## Wait

Use the wait object to wait for a particular session or screen state. For example, you can wait until the cursor is found at a particular location or text is present at a certain location before continuing with the macro execution.

Wait functions are often used in conjunction with asynchronous functions such as `connect()` and `sendKeys()`.

---

**NOTE:** All functions take timeouts as an optional parameter and have a default time out value of 10 seconds (10000ms).

**Important:** All wait functions require the 'yield' keyword in front of them. This allows the macro to block execution until the conditions of the wait function are met.

[parameter] denotes an optional parameter.

---

**Table 5-36** *Waiting for the host*

## METHODS

<code>setDefaultTimeout(timeout)</code>	Sets the default timeout value for all functions.
	<b>Parameters</b>
	{Number} default timeout to use for all wait functions in milliseconds.
	<b>Returns</b>
	None
	<b>Throws</b>
	{RangeError} If the specified timeout is less than zero.
<code>forConnect([timeout])</code>	Waits for a connect request to complete.
	<b>Parameters</b>
	{Number} in milliseconds.
	<b>Returns</b>
	{Promise} Fulfilled if the session is already connected or when connection occurs. Rejected if the wait times out.
<code>forDisconnect([timeout])</code>	Waits for a disconnect request to complete.
	<b>Parameters</b>
	{Number} timeout in milliseconds.
	<b>Returns</b>
	{Promise} Fulfilled if the session is already disconnected or when it finally disconnects. Rejected if the wait times out.
<code>forFixedTime([timeout])</code>	Waits unconditionally for fixed time. Time is in milliseconds (ms)
	<b>Parameters</b>
	{Number} timeout in milliseconds.
	<b>Returns</b>
	{Promise} Fulfilled after time elapses

## METHODS

`forScreenChange([timeout])` Waits for the host screen to change. This function returns when a screen update is detected. It makes no guarantees about the number of subsequent updates that may arrive before the screen is complete. Waiting repeatedly until the screen contents match some known stopping criteria is advisable.

### Parameters

{Number} timeout in milliseconds.

### Returns

{Promise} Resolved if the screen change. Rejected if the wait times out.

`forCursor(position,  
[timeout])`

Waits for the cursor to arrive at the specified position.

### Parameters

{Position} The position specifying the row and column,

{Number} timeout in milliseconds

### Returns

{Promise} Fulfilled if the cursor is already located or when it is finally located. Rejected if the wait times out.

`forText(text, position,  
[timeout])`

Wait for text located at a specific position on the screen

### Parameters

{String} text to expect

{Position} position specifying the row and column

{Number} timeout in milliseconds

### Returns

{Promise} Fulfilled if the text is already at the specified position or whenever it is located. Rejected if the wait times out.

### Throws

{rangeError} if the position is not valid.

## METHODS

`forHostPrompt(text, column, [timeout])`

Waits for a command prompt located at a particular column on the screen.

### Parameters

{String} text prompt to expect

{Number} column where cursor is expected

{Number} timeout in milliseconds.

### Returns

{Promise} Fulfilled if the conditions are already met or when the conditions are finally met. Rejected if the wait times out.

### Throws

{rangeError} if the column is out of range.

## Sample Macros

To help you create successful macros that take advantage of all the capabilities of the Macro Editor, these samples are available as a starting point.

- ♦ [“Basic Host Interaction” on page 148](#)
- ♦ [“User Interaction” on page 150](#)
- ♦ [“Paging Through Data” on page 152](#)
- ♦ [“Invoking a Web Service” on page 153](#)
- ♦ [“Working with DataCells and Attributes” on page 155](#)
- ♦ [“Using Fields and Field Lists” on page 157](#)
- ♦ [“Automatic Sign-On Macro for Mainframes” on page 158](#)
- ♦ [“Using File Transfer \(IND\\$File\)” on page 159](#)

## Basic Host Interaction

This sample illustrates basic host interaction, including:

- ♦ Sending data to the host
- ♦ Waiting for screens to display
- ♦ Using the `yield` keyword to wait for asynchronous functions
- ♦ Reading text from the screen
- ♦ Displaying basic information to the user
- ♦ Handling error basics

All macros have the following objects available by default:

1. **session** - Main entry point for access to the host. Can connect, disconnect and provides access to the PresentationSpace.

The PresentationSpace object obtained from the session represents the screen and provides many common capabilities such as getting and setting the cursor location, sending data to the host and reading from the screen.

2. **wait** - Provides a simple way to wait for various host states before continuing to send more data or read from the screen.
3. **UI** - Provides basic user interface capabilities. Display data to the user or prompt them for information.

```
// Create a new macro function
var macro = createMacro(function*(){
    'use strict';

    // All macros have the following objects available by default:
    // 1. session - Main entry point for access to the host. Can connect,
    disconnect and provides access to the PresentationSpace.
    // The PresentationSpace object obtained from the session represents
    the screen and provides many common capabilities such as getting and
    setting the
    // cursor location, sending data to the host and reading from the
    screen.
    // 2. wait - Provides a simple way to wait for various host states before
    continuing to send more data or read from the screen.
    // 3. ui - Provides basic User Interaction capabilities. Display data to
    the user or prompt them for information.

    // Declare a variable for reading and displaying some screen data.
    // As a best practice all variables should be declared near the top of a
    function.
    var numberOfAccounts = 0;

    // Start by obtaining the PresentationSpace object, which provides many
    common screen operations.
    var ps = session.getPresentationSpace();

    try {
        // Can set and get the cursor location
        ps.setCursorPosition(new Position(24, 2));

        // Use the sendKeys function to send characters to the host
        ps.sendKeys('cics');

        // SendKeys is also used to send host keys such as PA and PF keys.
        // See "Control Keys" in the documentation for all available options
        ps.sendKeys(ControlKey.ENTER);

        // Wait for the cursor to be at the correct position.
        // The wait object provides various functions for waiting for certain
        states to occur
        // so that you can proceed to either send more keys or read data from
        the screen.
        yield wait.forCursor(new Position(24, 2));

        // You can mix characters and control keys in one sendKeys call.
        ps.sendKeys('data' + ControlKey.TAB + ControlKey.TAB + 'more data' +
```

```

ControlKey.ENTER);

    // The "yield" keyword must be used in front of all "wait" and "ui"
function calls.
    // It tells the browser to pause execution of the macro until the
    // (asynchronous) wait function returns. Consult the documentation for
which functions
    // require the yield keyword.
yield wait.forCursor(new Position(10, 26));
ps.sendKeys('accounts' + ControlKey.ENTER);

    // Can also wait for text to appear at certain areas on the screen
yield wait.forText('ACCOUNTS', new Position(3, 36)) ;
ps.sendKeys('1' + ControlKey.ENTER);

    // All wait functions will timeout if the criteria is not met within a
time limit.
    // Can increase timeouts with an optional parameter in the wait
functions (in milliseconds)
    // All timeouts are specified in milliseconds and the default value is
10 seconds (10000ms).
yield wait.forCursor(new Position(1, 1), 15000);
ps.sendKeys('A' + ControlKey.ENTER);

    // PS provides the getText function for reading text from the screen
numberOfAccounts = ps.getText(new Position(12, 3), 5);

    // Use the ui object to display some data from the screen
ui.message('Number of active accounts: ' + numberOfAccounts);

    // The try / catch allows all errors to be caught and reported in a
central location
    } catch (error) {
    // Again we use the ui object to display a message that an error
occurred
yield ui.message('Error: ' + error.message);
    }
    //End Generated Macro
});

// Run the macro and return the results to the Macro Runner
// The return statement is required as the application leverages
// this to know if the macro succeeded and when it is finished
return macro();

```

## User Interaction

This sample illustrates how to use the provided API methods to prompt the user for input or alert them with a message.

```

var macro = createMacro(function*(){
    'use strict';

    // The "ui" object provides functions for prompting the user for
    information and displaying information

    // Declare variables for later use
    var username;
    var password;
    var flavor;
    var scoops;

    //Begin Generated Macro
    var ps = session.getPresentationSpace();

    try {
        // Prompt the user to enter their name and store it in a variable.
        // Note that 'yield' keyword is needed to block execution while waiting
        for the user input.
        username = yield ui.prompt('Please enter your username');

        // Prompt the user to enter a value with a default provided to them.
        flavor = yield ui.prompt('What is your favorite flavor of ice cream?',
        'Chocolate');

        // Prompt the user to enter private information by using the 'mask'
        option and the input field will be masked as they type.
        // If a parameter is not used, 'null' can be used to specify that it
        isn't to be used.
        // Here we illustrate that by specifying that we don't need to show a
        default value .
        password = yield ui.prompt('Please enter your password', null, true);

        // The prompt function returns null if the user clicks the 'Cancel'
        button instead of the 'OK' button.
        // One way to handle that case is to wrap the call in a try/catch block.
        scoops = yield ui.prompt('How many scoops would you like?');
        if (scoops === null) {
            // This will exit the macro.
            return;
            // Alternatively could throw an Error and have it be caught in the
            "catch" below
        }
        // Use the collected values to order our ice cream
        ps.sendKeys(username + ControlKey.TAB + password + ControlKey.ENTER);
        yield wait.forCursor(new Position(5, 1));
        ps.sendKeys(flavor + ControlKey.TAB + scoops + ControlKey.ENTER);
    }
}

```

```

    // Display a message to the user. Using the 'yield' keyword in front
of the call will block
    // further execution of the macro until the user clicks the 'OK' button.
    yield ui.message('Order successful. Enjoy your ' + scoops + ' scoops
of ' + flavor + ' ice cream ' + username + '!');
  } catch (error) {
    // Here we use the ui object to display a message that an error occurred
    yield ui.message(error.message);
  }
//End Generated Macro

});

return macro();

```

## Paging Through Data

This sample illustrates how to page through a variable number of screens and process the data on each screen.

```

// Create a new macro function.
var macro = createMacro(function*(){
  'use strict';

  // Create variable(s) for later use
  var password;
  var accountNumber;
  var transactionCount = 0;
  var row = 0;

  // Obtain a reference to the PresentationSpace object.
  var ps = session.getPresentationSpace();

  try {
    // Enter Username and Password to log on to the application.
    yield wait.forCursor(new Position(19, 48));
    ps.sendKeys('bjones' + ControlKey.TAB);

    yield wait.forCursor(new Position(20, 48));
    password = yield ui.prompt('Password:', null, true);
    ps.sendKeys(password);
    ps.sendKeys(ControlKey.ENTER);

    // Enter an application command.
    yield wait.forCursor(new Position(20, 38));
    ps.sendKeys('4');
    ps.sendKeys(ControlKey.ENTER);

    // Going to list transactions for an account.
    yield wait.forCursor(new Position(13, 25));
    ps.sendKeys('2');
    // Input an account number. Hard coded here for simplicity.
    yield wait.forCursor(new Position(15, 25));
    accountNumber = yield ui.prompt('Account Number:', '167439459');
    ps.sendKeys(accountNumber);
    ps.sendKeys(ControlKey.ENTER);

    // Wait until on account profile screen
    yield wait.forText('ACCOUNT PROFILE', new Position(3, 33));

    // Search for text that indicates the last page of record has been reached
    while (ps.getText(new Position(22, 12), 9) !== 'LAST PAGE') {

```



```

    // While the last page of record has not been reached, go to the next page of
records.
    ps.sendKeys(ControlKey.PF2);
    yield wait.forCursor(new Position(1, 1));

    // If the cursor position does not change between record screens, and there
is no text
    // on the screen you can check to confirm a screen is updated, you may wait
for a
    // fixed time period after an aid key is sent for the screen to settle.
    // For example:
    // yield wait.forFixedTime(1000);

    // For each of the rows, increment the count variable if it contains data.
for (row = 5; row <= 21; row++) {

    // There are 2 columns on the screen. Check data on column 1.
    // In this example we know that if there is a space at a particular
    // position then there is a transaction.
    if (ps.getText(new Position(row, 8), 1) != ' ') {
        transactionCount++;
    }
    // Check data on column 2.
    if (ps.getText(new Position(row, 49), 1) != ' ') {
        transactionCount++;
    }
}
}

    // After going through all record pages, display the number of records in a
message box.
    yield ui.message('There are ' + transactionCount + ' records found for account
' + accountNumber + '.');

    // Log out of the application
    ps.sendKeys(ControlKey.PF13);
    ps.sendKeys(ControlKey.PF12);

    // The try / catch allows all errors to be caught and reported in a central
location
    } catch (error) {
        // Here we use the ui object to display a message that an error occurred
        yield ui.message(error.message);
    }
});

// Here we run the macro and return the results to the Macro Runner
// The return statement is required as the application leverages
// this to know if the macro succeeded
return macro();

```

## Invoking a Web Service

This sample illustrates how to make an AJAX / REST call directly from a macro to a web service. You can integrate data from your host application into the web service call or from the web service into your host application.

In this example, we are calling the Verastream Host Integrator (VHI) CICSAcctsDemo REST service. However, you can easily adapt the code to call any web service. You are not limited to VHI.

In the example the call goes through a proxy configured in the session server (shown below) to avoid a “Same Origin Policy” complication. If you are using a web service that supports [Cross-origin Resource Sharing \(CORS\)](#) and are using a modern browser, the proxy is unnecessary.

Since the jQuery library is available in macros, so you may use the \$.post() function directly to invoke REST services.

This example also demonstrates how to wrap a jQuery REST call in a new Promise. The promise returned from the custom function below allows "yield" to be used in the main macro code. This allows the main macro execution to wait until the service call is complete before continuing.

```
var macro = createMacro(function*() {
  'use strict';

  // Create a few variables for later user
  var username;
  var password;
  var accountNumber;
  var accountDetails;

  // Create a function that will make an AJAX / REST call to a VHI Web Service.
  // Could be adjusted to call any web service, not just VHI.
  // If not using CORS, the request will likely need to pass through a
  // proxy on the session server. See sample notes for more information.
  /**
   * Hand-coded helper function to encapsulate AJAX / REST parameters, invoke the
   * REST service and return the results inside a Promise.
   * @param {Number} acctNum to send to the REST query.
   * @param {String} username to access the REST service.
   * @param {String} password to access the REST service.
   * @return {Promise} containing $.post() results that are compatible with yield.
   */
  var getAccountDetails = function (acctNum, username, password) {
    var url = "proxyl/model/CICSAcctsDemo/GetAccountDetail";
    var args = {"filters": {"AcctNum": acctNum}, "envVars": {"Username": username,
"Password": password}};

    // Wrap a jQuery AJAX / HTTP POST call in a new Promise.
    // The promise being returned here allows the macro to yield / wait
    // for its completion.
    return Promise.resolve($.post(url, JSON.stringify(args)))
      .catch(function (error) {
        // Map errors that happen in the jQuery call to our Promise.
        throw new Error('REST API Error: ' + error.statusText);
      });
  };

  // Begin Generated Macro
  var ps = session.getPresentationSpace();
  try {
    // Could interact with the host here, log into a host app, etc...
    // Gather username and password
    username = yield ui.prompt('Username:');
    password = yield ui.prompt('Password:', null, true);
    accountNumber = yield ui.prompt('Account Number:');
    if (!username || !password || !accountNumber) {
      throw new Error('Username or password not specified');
    }

    // Invoke external REST service, and yields / waits for the call to complete.
    accountDetails = yield getAccountDetails(accountNumber, username, password);

    // We now have the data from our external service.
    // Can integrate the data into our local host app or simply display it to the
    user.
    // For this sample we simply display the resulting account details.
    if (accountDetails.result && accountDetails.result.length > 0) {
```

```

        yield ui.message(accountDetails.result[0].FirstName + ' $' +
accountDetails.result[0].AcctBalance);
    } else {
        yield ui.message('No records found for account: ' + accountNumber);
    }
} catch (error) {
    // If an error occurred during the AJAX / REST call
    // or username / password gathering we will end up here.
    yield ui.message(error.message);
}
});

// Run our macro
return macro();

```

## Cross Origin Scripting Proxy Support

If you have web services that do not support CORS, AJAX/REST calls will fail if they attempt to access a different server than the one where the Host Access for the Cloud application originated. This is a browser security feature.

The Host Access for the Cloud server provides a way explicitly to proxy to trusted remote servers.

- ◆ Open  
`..\<install_dir>\sessionserver\microservice\sessionserver\service.yml`  
for editing.

- ◆ In the env section add:

```

name: zfe.proxy.mappings
value: proxy-path=proxy-to-address

```

Where proxy-path refers to the desired url-mapping and proxy-to-address refers to the URL where the call will be proxied.

- ◆ In this example:

```

name: zfe.proxy.mappings
value: proxy1=http://remote-vhi-server:9680/vhi-rs/

```

Calls made to `<server:port>/proxy1` will be proxied to `http://remote-vhi-server:9680/vhi-rs/`

- ◆ Multiple proxy mappings can be specified using a comma to separate the individual proxy mappings
- ◆ Keep in mind that even when a REST server supports CORS headers, some older browsers may not, so this example may still be relevant.

---

**TIP:** Your `service.yml` file may be replaced whenever you redeploy Host Access for the Cloud. Always back up your files.

---

## Working with DataCells and Attributes

This macro illustrates how to use DataCells and AttributeSet to inspect a given row/column on the screen for text and attributes. In this sample you can see:

- ◆ How to get a collection of DataCells for a given position and length.
- ◆ How to iterate through DataCells to build up a text string

- ♦ How, for comparison, you can also do a similar thing using `getText()`.
- ♦ And finally, how to work with attributes, get a string listing, or determine whether specific ones are set at a given screen location.

```

var macro = createMacro(function*() {
  'use strict';

  // Obtain the PresentationSpace for interacting with the host
  var ps = session.getPresentationSpace();

  // Declare variables for later use
  var cells;
  var text;
  var attrs;

  // Set the default timeout for "wait" functions
  wait.setDefaultTimeout(10000);

  // Sample macro for working with DataCells and Attributes
  try {
    yield wait.forCursor(new Position(24, 2));

    // Get DataCells from the presentation space.
    // Row 19, col 3 is the prompt, 35 characters long
    // "Choose from the following commands:"
    cells = ps.getDataCells({row:19, col:3}, 35);
    text = '';

    // You can display text using getText
    yield ui.message("Screen text: " + ps.getText({row:19, col:3}, 35));

    // Or you can assemble the text from the DataCells at each position
    for(var index = 0; index < cells.length; index++) {
      text = text.concat(cells[index].getChar());
    }
    // And display the text
    yield ui.message("Cells text: " + text);

    // Get the attributes for the first DataCell (cell[0])
    attrs = cells[0].getAttributes();

    // Display whether we have any attributes on the data cell
    yield ui.message("Attribute set is empty: " + attrs.isEmpty());

    // Display how many attributes are set
    yield ui.message("Number of attributes: " + attrs.size());

    // Display which attributes are set
    yield ui.message("Attributes: " + attrs.toString());

    // Now display whether the high intensity attribute is set
    yield ui.message("Is high intensity: " +
      attrs.contains(Attribute.HIGH_INTENSITY));

    // Now display whether the underline attribute is set
    yield ui.message("Is underline: " +
      attrs.contains(Attribute.UNDERLINE));

    // Now display whether alphanumeric, intensified and pen-detectable
    // attributes are set
    yield ui.message("Is alphanumeric, intensified and pen-detectable: " +
      attrs.containsAll([Attribute.ALPHA_NUMERIC,
      Attribute.HIGH_INTENSITY, Attribute.PEN_DETECTABLE]));
  }
}

```

```

        // Now display whether underline, intensified and pen-detectable attributes
        are set
        yield ui.message("Is underline, intensified and pen-detectable: " +
            attrs.containsAll([Attribute.UNDERLINE,
Attribute.HIGH_INTENSITY, Attribute.PEN_DETECTABLE]));
    } catch (error) {
        yield ui.message(error);
    }
}
//End Generated Macro
});

// Run the macro
return macro();

```

## Using Fields and Field Lists

This macro sample illustrates how to use common functions to interact with the fields in the Macro API. For example, how to get field text, view field information, and how to use `field.setText` as an alternative to `sendKeys` to interact with the host.

---

**NOTE:** Due to browser considerations `ui.message` collapses strings of spaces down to a single space. The spaces are preserved in the actual JavaScript.

---

```

var macro = createMacro(function*() {
    'use strict';

    // Obtain the PresentationSpace for interacting with the host
    var ps = session.getPresentationSpace();

    // Declare variables for later use
    var fields;
    var field;
    var searchString = 'z/VM';

    // Set the default timeout for "wait" functions
    wait.setDefaultTimeout(10000);

    // Sample macro for working with FieldList and Fields
    try {
        yield wait.forCursor(new Position(24, 2));

        // Get the field list.
        fields = ps.getFields();

        // Run through the entire list of fields and display the field info.
        for(var index = 0; index < fields.size(); index++) {
            field = fields.get(index);

            yield ui.message("Field " + index + " info: " + field.toString());
        }

        yield ui.message("Now, find a field containing the text '" + searchString +
            "'");
        field = fields.findField(new Position(1, 1), searchString);

        if(field !== null) {
            yield ui.message("Found field info: " + field.toString());
            yield ui.message("Found field foreground is green? " + (Color.GREEN ===
field.getForegroundColor()));
            yield ui.message("Found field background is default? " +
(Color.BLANK_UNSPECIFIED === field.getBackgroundColor()));
        }
    }
}

```

```

// Now, find command field and modify it.
field = fields.findField(new Position(23, 80));
if(field != null) {
    field.setText("cics");
}

yield ui.message("Click to send 'cics' to host.");
ps.sendKeys(ControlKey.ENTER);

// Wait for new screen; get new fields.
yield wait.forCursor(new Position(10, 26));
fields = ps.getFields();

// Find user field and set it.
field = fields.findField(new Position(10, 24));
if(field != null) {
    field.setText("myusername");
}

// Find password field and set it.
field = fields.findField(new Position(11, 24));
if(field != null) {
    field.setText("mypassword");
}

yield ui.message("Click to send login to host.");
ps.sendKeys(ControlKey.ENTER);

// Wait for new screen; get new fields.
yield wait.forCursor(new Position(1, 1));
fields = ps.getFields();

// Find command field and set logoff command.
field = fields.findField(new Position(24, 45));
if(field != null) {
    field.setText("cesf logoff");
}

yield ui.message("Click to send logoff to host.");
ps.sendKeys(ControlKey.ENTER);

} catch (error) {
    yield ui.message(error);
}
//End Generated Macro
});

// Run the macro
return macro();

```

## Automatic Sign-On Macro for Mainframes

In this example the Autosignon object is used to create a macro that uses the credentials associated with a user to obtain a pass ticket from the Digital Certificate Access Server (DCAS).

```

var macro = createMacro(function*() {
  'use strict';

  // Obtain the PresentationSpace for interacting with the host
  var ps = session.getPresentationSpace();

  // Variable for login pass ticket
  var passTicket;

  // Login application ID
  var appId = 'CICSV41A';

  // Set the default timeout for "wait" functions
  wait.setDefaultTimeout(10000);

  // Begin Generated Macro
  try {
    yield wait.forCursor(new Position(24, 2));

    // Obtain a pass ticket from DCAS.
    passTicket = yield autoSignon.getPassTicket(appId);

    ps.sendKeys('cics');
    ps.sendKeys(ControlKey.ENTER);

    yield wait.forCursor(new Position(10, 26));

    // Replace generated username with sendUserName(passTicket) ...
    yield autoSignon.sendUserName(passTicket);

    // ps.sendKeys('bvtst01' + ControlKey.TAB + ControlKey.TAB);
    ps.sendKeys(ControlKey.TAB + ControlKey.TAB);

    yield wait.forCursor(new Position(11, 26));

    // Replace generated password with sendPassword(passTicket) ...
    yield autoSignon.sendPassword(passTicket);

    // var userInput3 = yield ui.prompt('Password:', '', true);
    // if (userInput3 === null) {
    //   // throw new Error('Password not provided');
    // }
    // ps.sendKeys(userInput3);
    ps.sendKeys(ControlKey.ENTER);

    yield wait.forCursor(new Position(1, 1));
    yield ui.message('Logged in. Log me off.');
```

## Using File Transfer (IND\$File)

This series of sample macros demonstrate how to use the File Transfer API to retrieve a list of files, download a file, and upload a file to a 3270 host.

---

**NOTE:** You must be logged in and at a ready prompt before running these macros.

---

### List files

This macro demonstrates how to use the File Transfer API to retrieve a list of files on a 3270 host using IND\$File transfer. The IND\$File transfer object is retrieved from the file transfer factory and then used to obtain an array of HostFile objects from either TSO or CMS.

```
var macro = createMacro(function*() {
  'use strict';

  try {
    var fileTransfer = fileTransferFactory.getInd$File();
    var hostFiles = yield fileTransfer.getHostFileListing();

    yield ui.message('Found ' + hostFiles.length + ' files');
    if (hostFiles.length > 0) {
      var firstFile = hostFiles[0];
      var msg1 = 'The catalog name is ' + firstFile.getParent() + '. ';
      var msg2 = 'The first file is ' + firstFile.getName();
      yield ui.message(msg1 + msg2);
    }
  } catch (error) {
    yield ui.message(error);
  }
});

// Run the macro
return macro();
```

### Download file

This macro shows how to use the File Transfer API to download a file from a 3270 host using IND\$File transfer. The IND\$File transfer object is retrieved from the file transfer factory. In this example the transfer method is set to ASCII to demonstrate use of the setTransferOptions function. The sample macro downloads the first file returned from a call to getHostFileListing by creating a download URI with a call to the getDownloadUrl function. The macro can be used in either a CMS or TSO environment but the choice must be specified on the first line or the code modified slightly for the intended system.

```
var hostEnvironment = 'CMS'; // 'TSO'
// Construct file path, ie catalog/file.name or catalog/partition/file
function getPath (fileNode) {
  var prefix = fileNode.getParent() ? fileNode.getParent() + '/' : '';
  return prefix + fileNode.getName();
}

var macro = createMacro(function*() {
  'use strict';

  try {
    var fileTransfer = fileTransferFactory.getInd$File();

    // The transferMethod options are 'binary' and 'ascii'
    fileTransfer.setTransferOptions({transferMethod: 'ascii'});

    // This demo retrieves the first file returned in the listing
    var hostFiles = yield fileTransfer.getHostFileListing();
    var firstHostFile = hostFiles[0];

    if (hostEnvironment === 'CMS') {
      yield wait.forText('Ready', new Position(1,1), 5000);
    }
  }
});
```



```

    }

    // Download
    // If you already know the path of the file you want, just pass that to
getDownloadURL()
    var downloadUrl = fileTransfer.getDownloadURL(getPath(firstHostFile));

    // This changes the browser location. You may experience different results
on different browsers
    window.location = downloadUrl;

    // If you want to read the file contents into a variable instead of
downloading
    // it, you can use jQuery
    // var fileContents = yield $.get(downloadUrl);

    } catch (error) {
        yield ui.message(error);
    }
});

// Run the macro
return macro();

```

### Upload file

This macro illustrates how to use the File Transfer API to upload a file to a 3270 host using IND\$File transfer. The sample macro prompts the user to choose a file from the local file system by triggering the browser's file selection dialog. It then retrieves the current catalog on TSO or drive identifier on CMS by calling `getHostFileListing`. Finally, the `sendFile` function is called to deliver the selected local file to the host. The macro can be used in either a CMS or TSO environment but the choice should be specified on the first line. In this example, the transfer method is set to `ascii`; you may want to change this to `binary`.

```

var hostEnvironment = 'CMS'; // 'TSO'
// Open the browser's file chooser dialog programmatically
function promptForFileToUpload () {
    return new Promise(function (resolve, reject) {
        // We are not notified if the user cancels the file chooser dialog so reject
after 30 seconds
        var timerId = setTimeout(reject.bind(null, 'Timed out waiting for file
selection'), 30000);
        var fileSelector = document.createElement('input');
        fileSelector.setAttribute('type', 'file');
        fileSelector.onchange = function (evt) {
            var file = evt.target.files[0];
            clearTimeout(timerId);
            resolve(file);
        };
        fileSelector.click();
    });
}

var macro = createMacro(function*() {
    'use strict';

    try {
        var fileTransfer = fileTransferFactory.getInd$File();

        // The transferMethod options are 'binary' and 'ascii'
        fileTransfer.setTransferOptions({transferMethod: 'ascii'});

        var localFile = yield promptForFileToUpload();
    }
}

```

```

// Retrieve the current catalog name and append the selected file name to it
var hostFiles = yield fileTransfer.getHostFileListing();
var destination = hostFiles[0].getParent() + '/' + localFile.name;

if (hostEnvironment === 'CMS') {
  yield wait.forText('Ready', new Position(1,1), 5000);
}

var result = yield fileTransfer.sendFile(localFile, destination);

} catch (error) {
  yield ui.message(error);
}
});

// Run the macro
return macro();

```

## Printing


There are various printing options available for 3270, 5250, and UTS hosts. You can take screen captures, print a selected screen and enable and configure host printing capabilities:

- ◆ [Capture a screen](#)
- ◆ [Print a screen](#)
- ◆ [Host printing](#)

The settings available to you regarding page setup and orientation are dependent on your browser options.

### Capture a screen

Use the screen capture feature to capture multiple screens then save them as a file for printing or sharing. This option is available to all users once the administrator selects it using [User Preferences](#).

- 1 Navigate to the screen you want to capture.
- 2 Click  to capture the screen. The counter displays the number of captures you've taken. Each capture will print to a separate page.
- 3 Click Save to browse to the location where you want to save the capture. Your browser determines how the save option functions. For example, in Chrome, depending on your browser settings, the file will be saved in the download file or you will see a Save As dialog to select a location to save the captured file.
- 4 To append your newly saved screens to an existing screen capture file, click [Append and save](#). When you print the appended file, each screen capture is printed to a separate page.
- 5 You can clear the captures whenever you want by clicking Clear.

## Print a screen

The print screen option prints the contents of the terminal screen. It does not print the toolbar or other display information.

- 1 Navigate to the screen you want to print.
- 2 Click Print Screen on the tool bar.
- 3 Use your browser's print dialog to select the printer and page setup options.

## Host printing

This feature is available to 3270, 5250, and UTS host sessions. You can create one or more printer sessions and associate them with the current terminal session. Each printer session is bound to a Device ID on the host system and any subsequent print jobs sent to that Device ID will be directed to the Host Access for the Cloud web client.

The host session builds a PDF file that contains the file to print and sends it to the web client. After receiving the file, the web client downloads the file following your browser's configured download options. Different browsers provide different options for handling downloaded files. When the PDF file is received, you can direct it to any printer that you have access to.

---

**NOTE:** An administrator can provide end users with the ability to print by setting the **Host Printing User Preferences** option.

---

---

### Related Topics

[Connection settings](#)

[Page Setup settings](#)

[Advanced settings](#)

[To print your host printer session](#)

## To configure host printing

- 1 From a host session, click **Settings** on the tool bar to open the left navigation panel.
- 2 In the left panel, click **Print**.
- 3 Click **Add** to open the configuration dialog box. There are three tabs; [Connection settings](#), [Page Setup settings](#), and [Advanced settings](#). Each tab has different settings available to customize your printer session.
- 4 Click **Save** to return to your session. The settings take effect when the session is reopened.

---

### Related Topics

[Connection settings](#)

[Page Setup settings](#)

[Advanced settings](#)

## Connection settings

By default, printer sessions are available from the printer icon on the terminal session tool bar. If you do not want end users to have access to this printer session, clear **Enable this printer session** on the Connection tab.

These settings differ depending on your host type.

[3270 connection settings](#)

[5250 connection settings](#)

[UTS connection settings](#)

### 3270 connection settings

Setting	Description
Name	Provide an easily identifiable name for your printer session. Required.
Protocol	Select the protocol to use. The options are: <ul style="list-style-type: none"><li>◆ <b>TN3270E</b> - TN3270E of Telnet Extended, is for users of TCP/IP software who connect to their IBM mainframe through a Telnet gateway that implements RFC 1647.</li><li>◆ <b>TN3287</b> - TN3287 is for users of TCP/IP software who connect to their IBM mainframe through a Telnet gateway that implements RFC 1646.</li></ul>
Device ID	Specify whether you want to use a Device ID, prompt for Device Name or, if you select TN3270E, a TN Association, to link the terminal session with the print session. Required. Select one: <ul style="list-style-type: none"><li>◆ <b>Specify Device ID</b> - Specify the Device ID to use when the printer session connects to the host.</li><li>◆ <b>Use TN Association</b> - (TN3270E) If you choose to use a TN association, Host Access for the Cloud uses the device name specified in the connection settings to link the 3270 and 3287 session together. TN Association is only available if you select TN3270E as the protocol.</li><li>◆ <b>Prompt the user</b> - When the printer session connects, the user is prompted to supply the Device ID for the printer session.</li></ul>

## 5250 connection settings

Setting	Description
Name	Provide an easily identifiable name for your printer session. Required.
Device ID	Specify whether you want to use a Device ID or prompt for a Device ID: <ul style="list-style-type: none"><li>◆ <b>Specify Device ID</b> - Specify the Device ID to use when the printer session connects to the host.</li><li>◆ <b>Prompt the user</b> - When the printer session connects, the user is prompted to supply the Device ID for the printer session.</li></ul>

## UTS connection settings

Setting	Description
Name	Provide an easily identifiable name for your printer session. Required.
Protocol	<p>The choice of DEMAND or MAPPER protocols depends on the type of UTS session you create. UTS session types are determined by the values you supply for the TSAP and Application options on the Connection panel. For example, if you enter values that create a UTS MAPPER or DEMAND session, you should select MAPPER or DEMAND as the protocol.</p> <p>Specify what protocol you want to use:</p> <ul style="list-style-type: none"><li>◆ <b>MAPPER</b> - You can choose to specify the Device ID to use when the printer session connects to the host or prompt the user to supply the Device ID for the printer session, then continue configuring the session.</li><li>◆ <b>DEMAND</b> - After providing a name for the session, you can continue configuring the session using Page Setup and Advanced tabs,</li></ul>

## Page Setup settings

The Page Setup tab contains setting options for paper size and orientation, along with dimensions, margins, and scaling values.

Setting	Description
Paper size	Select the size of paper used by the printer.
Orientation	There are three modes you can choose; <b>Portrait</b> (vertical), <b>Landscape</b> (horizontal) or <b>Auto</b> , which is the default. With Auto selected, the printer evaluates the print job and uses the most appropriate format.
Units of measurement	Select the unit of measurement you want to use for page margins and page sizes. The values are inches or millimeters.
Dimensions	Enter the number of rows and columns to display per printed page. 60 is the default row value and the column value defaults to 80.
Margins	Sets the left, right, top, and bottom page margins.
Scaling	Sets the horizontal and vertical scaling for printed output. Increase the percentage to increase the horizontal or vertical space used by the printout.

---

#### Related Topics

[Connection settings](#)

[Advanced settings](#)

[To print your host printer session](#)

## Advanced settings

There are three options available to you when deciding when to download the PDF file.

- ♦ **Automatically** - (default) The PDF is downloaded automatically when the print job is complete. When this option is selected, the Inactivity timeout setting is not available.
- ♦ **Manually** - Once a print job commences, you can initiate a download anytime by locating the print job in the download list available from the Print icon on the tool bar and clicking **Flush**. The print job is aggregated into a single PDF file and downloaded.
- ♦ **After inactivity timeout** - Using this option you can print multiple print jobs, have them aggregated into a single PDF, and then automatically downloaded when you specify.

If you decide on a value greater than 0 (for example, 5 seconds) any print jobs assigned to a printer that arrive within 5 seconds of each other will be appended to the same PDF. After 5 seconds and no remaining print jobs, the PDF is downloaded. If you specify 0 for the inactivity timeout, each print job is downloaded immediately upon completion. You can always interrupt a print job by clicking **Flush**.

---

#### Related Topics

[Connection settings](#)

[Page Setup settings](#)

[To print your host printer session](#)

## To print your host printer session

When the terminal session opens, you can now:

- 1 Select the printer session you want to use. All print sessions associated with the opened

terminal session are available to you. Click  on the tool bar to see a list.

- 2 The host session receives the print data from the host and builds a PDF file to print. A link to this file is sent to the web client indicating it is available for download.

You can monitor the various print jobs using the tool bar page counter or the counter associated with separate printers in the print drop down list.

The page counter on the tool bar reflects the total number of pages either being actively printed or complete but waiting for the file to download from the server. You can trigger a download by selecting **Flush** from the printer list.

The page counter attached to printers in the printer drop down list displays the same value but on a per printer basis. The sum of these separate print jobs is reflected in the tool bar count. The count is cleared once the print jobs are downloaded.

- 3 After the PDF file becomes available, the file either begins downloading or waits for you to trigger a download using the Flush option, depending on the options you configured.

If necessary, due to an overlong running print job or some other issue, you can flush your current print job. The **Flush** option is available from the list of printer sessions accessed from the printers icon on the tool bar. When you flush a print job, whatever has been accumulated so far is printed and processing of print data continues.

## Customize Sessions

You can use these features to customize sessions for your end users:

- ♦ **Plus** - Enable custom controls to provide a more efficient work flow and a more modern and friendly interface. See Use Plus to customize screens.

Using this option, you can add tool tips to fields, replace old-style numbered lists with more modern drop-down lists, add buttons to the host interface and program them to start macros or perform other actions, and replace manual date entry with a graphical calendar date-picker.

- ♦ **Server-side Events** - Supply procedural Java code that extends and improves the presentation of host data.

Using server side events, you can define specific events and suspend the host application, replacing or interrupting it with code that you have supplied to the session, as well as extend error handling options. For example, you can add an event that recognizes when an error occurs and then implements the code to intercept the error, take control, and correct the error. See Use server side events.

- ♦ **Advanced** - Only use as directed by Micro Focus Technical Support.

These options are configured on the Customization panel.

- 1 Click Settings on the toolbar to open the left navigation panel.
- 2 Click Customization.

---

## Related Topics

[Use Plus to customize screens](#)

[Use server side events](#)

# Use Plus to customize screens

---

**NOTE:** The Plus feature requires archive files (.rdar) produced by Micro Focus Screen Designer version 9.5 or higher. The Screen Designer is available in Micro Focus Rumba Desktop 9.5. Reflection Desktop 16.1 includes a limited version of the Screen Designer. To get access to more controls and full use of Plus and the Screen Designer, you can purchase and install the Micro Focus Reflection Desktop Plus add-on.


---

- 1 On the **Customization** panel, click **Enable Plus**.
- 2 Select the Plus archive file you want to use from the drop down list or upload a file from a different location. Plus archive files are identified by a `rdar` file extension.

Archive files are the output of a Screen Designer project and are used to provide the custom control criteria.

If you are updating the Plus archive (.rdar) file associated with your Plus enabled session, you must first delete the folder containing the old .rdar file from the session server. After you delete the folder, you can open your Plus enabled session and the new rdar file will be downloaded to the session server.

- 3 Verify the number of milliseconds for the host settle delay time is accurate. This is the time that the server waits for a synchronous connection before deciding that the host has finished sending data.

- 4 When you return to your session, Plus is available. Click  on the toolbar to turn off the custom controls.

When you enable Plus for a session, all end users of that session see the Plus icon on the toolbar and any controls made available through the Screen Designer customization file.

---

## Related Topics

[Customize Sessions](#)



## Use server side events

Using server side events, you can supply procedural Java code that can extend and improve the presentation of host data.

The **Customization** panel tells the web client where to find the event after you've configured it. See [Using the Java SDK](#) for instructions on using the SDK and the samples available to you.

- 1 Open the **Customization** panel.
- 2 Under **Server Side Events** type the fully qualified class name to the event.
- 3 Launch the session and test the event.

[Access API documentation and event samples](#)

---

### Related Topics

[Customize Sessions](#)

[Using the Java SDK](#)

[Developing](#)

## Set User Preferences

As an administrator you can choose what options users can configure for their sessions. These options are set on a per session basis and all users who have access to a particular session can configure their own session instance.

- 1 From the left navigation panel, choose **User Preference Rules**.
- 2 Select which options you want to allow your users to configure.
- 3 Click Save.

Each user's configurations are specific to their instance of the session and will not conflict with those of other users.

There is a **Restore Defaults** option available on the various settings and display panels. As an administrator, this option restores the web client back to its default settings. For end users this option will restore the values set by the administrator when the session was created.

---

### Related Topics

[Display Settings](#)

[Specify Copy and Paste Options](#)

[Transfer Files](#)

[Configure User Macros](#)



# 6 Developing

Host Access for the Cloud has a collection of APIs and libraries that help you develop efficient client/server and Web applications that integrate host data into various development environments.

You can also extend the web client without affecting the installed files. This ability provides you with a wide range of options to tailor the web client to your own needs.

- ♦ [Using the Java SDK](#) you can use the provided Java API to enhance the presentation of host data using server side events.
- ♦ [Using the Connector for Windows](#) you can interact with host sessions in your .NET application or within Visual Basic for Applications using the API and samples provided.
- ♦ [Using the JavaScript API](#) you can embed the web client in your own web site.
- ♦ [Extending the Web Client](#) you can enhance and broaden the scope of the web client using custom code, such as CSS or JavaScript.

[View API Documentation](#)

---

## Related Topics

[Customize Sessions](#)

[Logging](#)

## Using the Java SDK

Working with [server side events](#) and the Host Access for the Cloud SDK you can supply procedural Java code that can extend and improve the presentation of host data. To help you create server side events, Host Access for the Cloud has an SDK and samples that can provide you with a starting point.

The Javadocs are available in your installation directory (`<install-dir>\sessionserver\sdk\java\javadocs\index.html`) as well as [online](#).

- 1 Make the Host Access for the Cloud SDK available to your development environment. The SDK is available at `install-dir\sessionserver\sdk`.
- 2 Write the Java code necessary to accomplish the task and compile the code into a Java class within a JAR (Java Archive) file.
- 3 Copy the JAR file to `<install-dir>\sessionserver\microservices\extensions\server` and restart the session server.

If you have more than one session server on which you want the event to run, you must copy the JAR file to this location on each server.

- 4 Add the session you want to associate with the event in the Administrative Console.

- 5 As you configure the session in the web client, open the **Customization** panel and type the fully qualified class name to the event.
- 6 Launch the session and test the event.

## Examples and documentation

To access the SDK for direct viewing and to import to your IDE:

- 1 Navigate to `<install-dir>\sessionserver\sdk\java`.
- 2 In the SDK directory, access:
  - ♦ `\javadoc`. This directory contains javadoc files for direct viewing.
  - ♦ `\samples` - This directory contains Java sources for direct viewing.
  - ♦ `\zfe-sdk.jar` - The JAR file contains the Java classes to import into your IDE.
  - ♦ `\zfe-sdk-javadoc.jar` - The JAR file contains JavaDoc files to import into your IDE.

## Using the Connector for Windows

Host Access for the Cloud Connector for Windows is a separate installation which you can find on the Micro Focus [download site](#). Using the Connector for Windows, you can interact with host sessions in your .NET application or within Visual Basic for Applications.

The API documentation is available in your installation directory (`<install dir>\sessionserver\sdk\csharp\apidocs\index.html`) as well as [online](#).

Here are a few things to keep in mind as you prepare to install:

- ♦ Two install platforms are available: a 32-bit version and a 64-bit version. Depending on which one you install, the default base install path will be `C:\Program Files (x86)\Micro Focus\HACloud\Connector for Windows` or `C:\Program Files\Micro Focus\HACloud\Connector for Windows`.
- ♦ The installation platform you choose also determines the solution platform in which you can develop. For example: If you have installed the 32-bit version of Microsoft Office® and want to use Visual Basic for Applications with the connector, then you must install the 32-bit version of the Host Access for the Cloud Connector for Windows.
- ♦ API documentation is available here: `<install dir>\sessionserver\sdk\csharp\apidocs\index.html`.
- ♦ .NET 4.5.2 is required.

## Examples and connector documentation

Documentation is available to reference from your IDE. There are also samples to help you take advantage of the connector. Both are located here:

- 1 Navigate to the install directory. In a default install, either `C:\Program Files (x86)\Micro Focus\HACloud\Connector for Windows` or `C:\Program Files\Micro Focus\HACloud\Connector for Windows` depending on your platform.
- 2 In the `Connector for Windows` directory you will find:
  - ◆ `MicroFocus.ZFE.Connector.dll` - a .NET Framework assembly to reference in your C# or .NET project.
  - ◆ `MicroFocus.ZFE.Connector.tlb` - a Type Library to use in your COM or Visual Basic for Applications project.
  - ◆ `\help` - this directory contains information which will aid in using the connector.
  - ◆ `\samples` - this directory contains the code samples that provide a starting point for developing your own applications.

## Using the connector with Microsoft Visual Studio

If you are using Microsoft Visual Studio to develop applications, keep these things in mind:

- ◆ When using Microsoft Visual Studio with Connector for Windows, make sure your solution platform is set to either x86 or x64, depending on your installation. Because of the native components used within the Connector for Windows SDK, the **Any CPU** platform is not supported. Use the Configuration Manager for your Visual Studio Solution to create a platform for x86 or x64.
- ◆ When adding a reference to the Connector for Windows library, Visual Studio may set the **Copy Local** reference property to **True**. This should be set to **False** so that the library and its dependencies are executed from the SDK install directory.

## Using the JavaScript API

Using JavaScript in a browser you can embed the web client in a web page. Your end users, by accessing a common web page, can interact with the web client and connect to the host application providing the ability to:

- ◆ Programmatically interact with host sessions.
- ◆ Run it “headlessly”, meaning you can access all its functionality without having a visible interface embedded in the web page.

There are getting started and other tutorials available for your use. The API documentation, along with the tutorials, is available [online](#) and in `<install dir>\sessionserver\sdk\javascript`.

---

### Related Topics

[Host Access for the Cloud API documentation](#)

- [Adding an extension](#)
- [Using the Connector for Windows](#)
- [Using the Java SDK](#)

## Extending the Web Client

You can update, modify, and customize the presentation of the web client by using your own HTML, CSS, or JavaScript from within the browser.

You can take advantage of extensions to make visual changes to the web client and to customize the application. The web client hosts your custom HTML or CSS code, making it easy to modify and support.

Learn more about:

- ♦ [Adding an extension](#)
- ♦ [Extension sample](#)
- ♦ [See how extensions can be used within Docker](#)

### Adding an extension

Before proceeding keep in mind that although Host Access for the Cloud provides the ability to plan and use custom code, the code itself must be supported by the team that produced it.

---

**WARNING:** During a product upgrade extensions are disabled. This means that, after an upgrade, you must verify that the product is working as expected without extensions, and then re-enable the extensions using the steps to add custom code.

---

When you add extensions to the web client, the modifications are visible to all your users and apply to all sessions.

#### To add an extension

- 1 Open `<install_dir>/sessionserver/microservices/sessionserver/service.yml`.
- 2 Append `extensions-enabled` to the existing value of the `SPRING_PROFILES_ACTIVE` property. Use a comma to separate the values.

For example:

```
env:  
  - name: SPRING_PROFILES_ACTIVE  
    value: tls,extensions-enabled
```

- 3 Restart the session server.
- 4 Create `<install_dir>/sessionserver/microservices/sessionserver/extensions/client/index.html` to act as your entry point. This is where you add any HTML, CSS, or JavaScript (including references to external scripts).

## Making extensions available without client authentication

Files within the `/client` directory are protected using the level of authentication you selected in MSS.

### To share files without requiring authentication:

Create `<install_dir>/sessionserver/microservices/sessionserver/extensions/public/`. Place your code in that directory, calling it using the URL `/public/*`.

## Extension sample

In this example, once extensions are enabled (see Step 2 above), you can add some custom CSS and JavaScript code to change the menu label font color and print text to the JavaScript console.

You will create three files; `custom.css`, `custom.js`, and `index.html`.


### Step 1.

Locate `index.html`, which you created in step 4 above. This is where you will be placing your extension files, creating an entry point:

```
<!-- Define the link to the external style sheet -->
<link href="client/custom.css" rel="stylesheet">
<!-- Define the external JavaScript file -->
<script src="client/custom.js"></script>
```

### Step 2.

Change the default black menu labels to orange:



Create `custom.css` to change the color to orange:

```
/* Change link text to Orange */
a span {
    color: #ff5d28;
}
```


### Step 3.

Create `custom.js` to send text to the JavaScript console:

```
//Print message to the JavaScript console
console.log('Hello World!');
```

### Step 4.

When the files are in place, `<install_dir>/sessionserver/microservices/sessionserver/extensions/client/index.html`, the results should look like this:



And the “Hello World” text is visible in the JavaScript console:



### Related Topics

[API documentation](#)

[Using the JavaScript API](#)

[Using the Connector for Windows](#)

[Using the Java SDK](#)



# 7 Technical References

In this section you can find information on specific issues that you may encounter. In the [Micro Focus Technical Support Handbook](#) you will find information about how to get technical support for your product, access to our online resources, and how to contact and work with our worldwide technical support organization.

- ♦ [Monitoring Session Servers using Prometheus and Grafana](#)
- ♦ [Modifying the Size Limit on Upload File Transfer Operations](#)
- ♦ [Copying Sessions between Management and Security Servers](#)
- ♦ [How to Change Ports](#)
- ♦ [How to Start and Stop Services Automatically](#)
- ♦ [Allowing Session Server Access via HTTP](#)
- ♦ [Connecting to MSS using HTTP](#)
- ♦ [Adjusting the URL Path for the Session Server](#)
- ♦ [Configuring User Names when Using Anonymous Access Control](#)
- ♦ [Accessing Host Access for the Cloud using the IIS Reverse Proxy](#)
- ♦ [Improving Connection Times on Non-Windows Platforms](#)
- ♦ [Advanced Settings](#)
- ♦ [Known Issues](#)
- ♦ [MSS Administrative Console Reference](#)

## Monitoring Session Servers using Prometheus and Grafana

You can monitor Host Access for the Cloud session servers using Prometheus and Grafana. Both of these tools are free, open source, and can be run in Docker containers which makes for easy deployment. Each session server provides a Prometheus endpoint that exposes metrics about that server. Prometheus can be configured to scrape data from this endpoint and store the metrics on an ongoing basis, even from multiple session servers. Grafana then provides a dashboard to query and visualize this data, with very little setup.

### Prerequisites:

You must have Docker and Docker Compose installed.

### Steps:

1. Create a Docker Compose file (.yml) that contains both Grafana and Prometheus images.
2. Link Prometheus to your session server Prometheus endpoint.
3. Configure your Grafana data source to communicate with Prometheus and import the pre-configured dashboards.

4. Configure the Grafana dashboards.
5. Access Grafana.

---

### Step 1. Create a Docker Compose file

Create a `docker-compose.yml` file containing Grafana and Prometheus images.

*docker-compose.yml*

```
version: "3.1"
services:
  grafana:
    build: grafana
    ports:
      - '3000:3000'
  prometheus:
    image: prom/prometheus:v2.6.1
    ports:
      - '9090:9090'
    volumes:
      - ./config/prometheus.yml:/etc/prometheus/prometheus.yml
      - ./prometheus:/prometheus
    networks:
      monitoring:
        aliases:
          - prometheus
networks:
  monitoring:
```

### Step 2. Link Prometheus to your HACloud Prometheus endpoint

To link Prometheus to your endpoint, generate a `prometheus.yml` file.

- ◆ In our example, the `prometheus.yml` file is saved in the `config` directory.
- ◆ This example config allows you to scrape the Prometheus endpoint using either HTTP or HTTPS (TLS).  
If TLS is disabled on the session server, remove `tls_config` and change the scheme to `http` in the example config.
- ◆ Configure the `session-server-hostname`.

---

**NOTE:** Due to Docker networking, this must be the actual IP or hostname of your session server host computer. This IP can typically be obtained using `ifconfig/ipconfig`.

---

- ◆ Adjust ports if needed.

*config/prometheus.yml*

```

scrape_configs:
  - job_name: ' HAcloud Session Server with TLS '
    scrape_interval: 15s
    scheme: https
    tls_config:
      insecure_skip_verify: true
    metrics_path: actuator/prometheus
    static_configs:
      - targets: ['session-server-hostname:7443']

```

### Step 3. Configure communication between Prometheus and the data source

Communication can be configured within the Grafana Docker image between the local instance of Prometheus and your Grafana data source. Pre-loaded dashboards are also available to you at startup.

#### *grafana/Dockerfile*

```

FROM grafana/grafana:5.3.2
ADD ./provisioning /etc/grafana/provisioning
ADD ./config.ini /etc/grafana/config.ini
ADD ./dashboards /var/lib/grafana/dashboards

```

#### *grafana/config.ini*

```

[paths]
provisioning = /etc/grafana/provisioning

```

#### *grafana/provisioning/datasources/all.yml*

```

datasources:
- name: 'Prometheus'
  type: 'prometheus'
  access: 'browser'
  url: 'http://localhost:9090'
  is_default: true
  editable: false

```

#### *grafana/provisioning/dashboards/all.yml*

```

- name: 'default'
  org_id: 1
  folder: ''
  type: 'file'
  options:
    folder: '/var/lib/grafana/dashboards'

```

### Step 4. Configure the Grafana dashboards

There is a sample JSON file to help you get started configuring your Grafana dashboards.

To have your Docker container load the dashboard on startup:

- ◆ Locate HAcloudSessionservers.json in the hacloud/utilities/grafana directory.
- ◆ Copy HAcloudSessionservers.json to your grafana/dashboards directory.

## Step 5. Access Grafana

- ♦ Start the Docker container with the command `docker-compose up -d`.
- ♦ Verify Prometheus targets are successfully scraping the session servers using `http://localhost:9090/targets`.
- ♦ Access Grafana using `http://localhost:3000`.
- ♦ Both the user name and password = admin. The user name and password can be configured using Docker environment variables.
- ♦ Use the command `docker-compose down` to stop the Docker container.

## Modifying the Size Limit on Upload File Transfer Operations

There is a 50MB file size limit on file transfer upload operations. To modify the file size limit, set `spring.servlet.multipart.maxfilesize` and `spring.servlet.multipart.maxrequestsize` in `HACloud/sessionserver/microservices/sessionserver/service.yml`, and restart the session server.

For example:

- name: `spring.servlet.multipart.maxfilesize`  
value: "100MB"
- name: `spring.servlet.multipart.maxrequestsize`  
value: "100MB"

## Copying Sessions between Management and Security Servers

You can copy and convert Reflection for the Web sessions and make them available to another Management and Security Server (MSS) and Host Access for the Cloud.

---

**NOTE:** In the following procedure the Management and Security Server you are copying sessions from is the **source**, and the Management and Security Server you are copying to is the **destination**.

---

To copy sessions from the source server to the destination server follow these steps:

- 1 Stop the destination MSS server, if necessary.
- 2 On both source and destination MSS servers, open *SessionDS.xml*, located:
  - ♦ On Windows: `C:\ProgramData\Micro Focus\MSS\MSSData`
  - ♦ On Linux: `/var/opt/microfocus/mss/mssdata`
- 3 In the source XML file, locate the `OBJECT_ARRAY` element.
- 4 Still in the source XML file, under `OBJECT_ARRAY`, locate and copy the Reflection for the Web child *Session* elements.
- 5 Open the destination XML file and paste them under the destination file's `OBJECT_ARRAY` element.

- 6 Still in the destination file, locate the OBJECT\_ARRAY size attribute that corresponds to the number of sessions. Increase that value by the number of session elements you added. For example, if you pasted six *Session* elements in the destination file and the existing OBJECT\_ARRAY size attribute value is 4; increase the value by six. The size attribute should now be ten. And you should now have 10 *Session* elements listed under the OBJECT\_ARRAY element.
- 7 Session names must be unique. Check the destination file for duplicate session names. You can find session names in the *Session* child element, *SessionName*.
- 8 Copy the configuration files for every session added to *SessionDS.xml* from the source to the destination server. The names of the configuration files are located under the *Session* element in the child element, *configuration*. The files themselves are located:
  - ♦ On Windows: C:\ProgramData\Micro Focus\MSS\MSSData\deploy\dyncfgs
  - ♦ On Linux: /var/opt/microfocus/mss/mssdata/deploy/dyncfgs
- 9 If you stopped the destination MSS server, restart it. Open the Administrative Console. You should see all your copied Reflection for the Web sessions in the **Manage Sessions** list.
- 10 The next step is to save the Reflection for the Web session as a Host Access for the Cloud session. In Manage Sessions, right-click the session you want to export. Session types are identified by an icon in the Type column.
- 11 See [Export a Reflection for the Web session](#) for information on saving a Reflection for the Web session to a Host Access for the Cloud session in the Administrative Console.

## How to Change Ports

See [Ports](#) for a list of the default ports used by Host Access for the Cloud.

To change the default ports:

Component	Instructions
Host Access for the Cloud session server	Open <code>sessionserver/microservices/sessionserver/service.yml</code> to modify: <pre>-name : SERVER_PORT value: "7443"</pre>
Management and Security Server	The SSL port MSS uses to make an HTTPS connection is set to 443 by default. If you need to change the port number, start the Management Server. This creates the default <code>PropertyDS.xml</code> file. Then, open <code>PropertyDS.xml</code> in the <code>MssData</code> directory. Change the value from 443 to the appropriate port number in the section below, and then restart the Management Server. <pre>&lt;CORE_PROPERTY NAME="sslport"&gt; &lt;STRING&gt;443&lt;/STRING&gt;</pre>

## How to Start and Stop Services Automatically

All server components are installed as services and can be configured to start during installation.

If you are running on Linux platforms, follow these steps to set the session server to start automatically when your system first boots up.

Create a file called `sessionserver` containing the following and using your installation directory:

```
#!/bin/sh
#
#This script manages the service needed to run the session server
#chkconfig:235 19 08
#description: Manage the Host Access for the Cloud session server

###BEGIN INIT INFO
# Provides:          sessionserver
# Required-Start:    $all
# Required-Stop:     $all
# Default-Start:     2 3 4 5
# Default-Stop:      0 1 6
# Description:       Start the Host Access for the Cloud Session Server
### END INIT INFO

INSTALL_DIR=<enter installation directory>
BIN_DIR=$INSTALL_DIR/sessionserver/bin
case "$1" in
start)
echo "Starting Host Access for the Cloud Session Server"
$BIN_DIR/server start

RETVAL=0
;;
stop)
echo "Stopping Host Access for the Cloud Session Server"
$BIN_DIR/server stop

RETVAL=0
;;
status) echo "Current Host Access for the Cloud Session Server status"
$BIN_DIR/server status

RETVAL=0
;;
restart) echo "Restart Host Access for the Cloud Session Server"
$BIN_DIR/server restart

RETVAL=0
;;
*)
echo "Usage: $0 (start|stop|status|restart)"

RETVAL=1
;;
esac
exit $RETVAL
```

Then complete the relevant steps.

Platform	Follow these steps
Linux	<ol style="list-style-type: none"> <li>1. Copy the file to the <code>/etc/init.d</code> directory.</li> <li>2. Set the file permission. Run <code>chmod</code> using the value 755. For example, <code>chmod 755 sessionserver</code></li> <li>3. Run <code>chkconfig</code> to add the initialization script. For example, <code>/sbin/chkconfig --add sessionserver</code></li> </ol>

## Allowing Session Server Access via HTTP

By default HACloud uses TLS (HTTPS) to communicate between the web client and the session server. You can change this option during the installation process. However, it may be necessary to make this change after installation.

### To change the protocol (HTTPS or HTTP) post-install:

1. Open and edit `<session-server>/microservices/sessionserver/service.yml`.
2. Modify the `SPRING_PROFILES_ACTIVE` environment variable.
  - ♦ To use HTTP - set the variable to `no-tls`.
  - ♦ To use HTTPS - set the variable to `tls`.
3. Restart the session server.

For example:

```
env:
  - name: SPRING_PROFILES_ACTIVE
    value: no-tls
```

---

**NOTE:** Changing the protocol from HTTPS to HTTP does not change the server port. HACloud uses 7443 as the default port. To change the port being used see [How to Change Ports](#).

---

## Connecting to MSS using HTTP

An HACloud installation requires that all components trust each other through the exchanging of certificates. However there may be use cases where some connections need to be in the clear for packet inspection. See [Your default secure installation](#).

---

**NOTE:** Using HTTP does not eliminate the requirement that trust be established. Other components will still use TLS behind the scenes to register and discover services.

---

To enable session server interaction with MSS using HTTP instead of HTTPS for the majority of the communications:

Connecting to...	Do this...
An existing remote MSS Administrative Server	<ol style="list-style-type: none"> <li>1. During the installation, after you accept the license agreement and choose a destination directory, select Use remotely hosted MSS. Click Next.</li> <li>2. Enter either the host name, DNS name, or IP address.</li> <li>3. Change the port to the HTTP port of the MSS server (for example, 80).</li> <li>4. Select HTTP and complete the installation process.</li> </ol>
The MSS Administrative Server that is installed with Host Access for the Cloud	<ol style="list-style-type: none"> <li>1. After the installation, open <code>&lt;install-directory&gt;\sessionserver\conf\container.properties</code> in a text editor and update the <code>management.server.url</code> property. For example, <code>management.server.url=http://yourmachine:80/mss</code></li> <li>2. Restart the session server service.</li> </ol>

## Adjusting the URL Path for the Session Server

You can adjust the URL path used to access the session server.

For example, you can change `https://myserver:7443/` to `https://myserver.com:7443/hacloud/`

1. Open `<install_dir>/sessionserver/microservices/sessionserver/service.yml`.
2. Add the following entry (maintain formatting) where *path* is replaced with the value you want to use.

```
-name: SERVER_SERVLET_CONTEXTPATH
value: "/<path>"
```

3. Restart the session server.
4. Access your session server at `https://<session server>:7443/<path specified>/`

## Configuring User Names when Using Anonymous Access Control

Users need access to their macros, user configurations, and other personalized settings whether they are authenticated through Management and Security Server or not. These settings are collectively referred to as User Preferences.

When MSS is configured for authentication, using LDAP or SAML for example, a username is determined when a user logs in. The user's settings are centrally saved in MSS using that username for all future logins.



However when the MSS Authentication Method is set to None, also known as anonymous mode, no unique username is available for the system to identify that particular user when they return in the future. In this configuration, all users share the same settings. If one user changes a setting, that setting will be changed for all other users.

Because that may not always be the desired behavior, Host Access for the Cloud supports a number of ways that, as an administrator, you can configure a unique identifier for each user so their customized settings can be stored and retrieved during future logins.

---

**NOTE:** These configuration modifications do not alter the security considerations of using Management and Security Server in anonymous mode.

---

## Configuration options

There are four different configuration options you can choose from when configuring user name identifiers. You must restart the session server before any changes take effect.

- ◆ **To use an HTTP request cookie value as the user name**

Add the following lines to `<session-server>/conf/container.properties`:

```
zfe.principal.name.provider=com.microfocus.zfe.webclient.security.mss.  
    CookieKeyAnonymousPrincipalNameProvider  
zfe.principal.name.identifier=<the-cookie-key-to-be-used>
```

- ◆ **To use an HTTP request header value as the user name**

Add the following lines to: `<session-server>/conf/container.properties`:

```
zfe.principal.name.provider=com.microfocus.zfe.webclient.security.mss.  
    HeaderKeyAnonymousPrincipalNameProvider  
zfe.principal.name.identifier=<the-header-key-to-be-used>
```

- ◆ **To use an HTTP request URL parameter as the user name**

Add the following lines to: `<session-server>/conf/container.properties`

```
zfe.principal.name.provider=com.microfocus.zfe.webclient.security.mss.  
    UrlParameterAnonymousPrincipalNameProvider  
zfe.principal.name.identifier=<the-url-parameter-key-to-be-used>
```

- ◆ **To use the client IP address as the user name**

Add the following line to: `<session-server>/conf/container.properties`

```
zfe.principal.name.provider=com.microfocus.zfe.webclient.security.mss.  
    RemoteAddrAnonymousPrincipalNameProvider
```

## Troubleshooting the configuration

If any of your users experience problems when connecting to a Host Access for the Cloud web application after you have made the configuration changes, check the following:

- ♦ Users experience a **503 Service Unavailable** message when connecting to a Host Access for the Cloud web application. First check the log file (`<session-server>/logs/sessionserver.log`), then:
  - If the log file contains this message: **“Unable to create AnonymousPrincipalNameProvider instance for class...”**, then the `zfe.principal.name.provider` property is probably mistyped. Check the spelling and letter case to remedy this issue.
  - If the log file contains this message: **“zfe.principal.name.identifier is not defined”**, then the property is missing. Ensure the property is defined to remedy this issue.
- ♦ Users are unable to properly authenticate.

Users should receive an error message indicating the initial HTTP request to the Host Access for the Cloud web application did not contain the required information.

## Accessing Host Access for the Cloud using the IIS Reverse Proxy

This note describes how to use the IIS Reverse Proxy with Host Access for the Cloud. In order to comply with Common Criteria security requirements, it is necessary to place the Host Access for the Cloud server behind a proxy in this manner.

### Prerequisites


- ♦ Internet Information Services (IIS) 8.0 or later is required.
- ♦ The IIS **WebSockets protocol** must be enabled. See [IIS 8.0 WebSocket Protocol Support](#) for information on how to enable this protocol.
- ♦ IIS **Application Request Routing (ARR) 3.0** or later is required.
- ♦ The IIS **URL Rewrite** module must be installed.

## Configure the IIS Reverse Proxy for Host Access for the Cloud


This example illustrates configuring an IIS server with the IP address of 192.168.1.1 to proxy connections to the Host Access for the Cloud session server at `http://10.10.10.1:7070`.

### Configuring IIS

- 1 Launch the Internet Information Services (IIS) Manager, navigate to the web site you want to use, and open the **URL Rewrite** feature.



- 2 Choose the **Add Rule(s)** action and add a Reverse Proxy rule.



- 3 For the inbound rule, enter the Host Access for the Cloud server's IP address or host name and port. For example, if the session server is on the same machine as IIS and is using its default port, enter `localhost:7443`.
- 4 Check the outbound rule **Rewrite the domain names...** and enter the host name or IP address of the IIS server in the To: box
- 5 Click OK to create the new Reverse Proxy Rule.

## Configuring Host Access for the Cloud

In order to proxy connections, the IIS **URL Rewrite** module must inspect and rewrite the web pages and WebSocket connections that pass through the proxy. For rewriting to succeed, these items must be sent in an uncompressed form. Note that, if configured, compression will still occur from the IIS server to the client's browser. The session server must also be configured to allow WebSocket connections to originate from the proxy.

- 1 Open `container.properties` in a text editor. The default location for this file is: `<install dir>/sessionserver/conf`.
- 2 Add the following lines to `container.properties`:


```
websocket.compression.enable=false
server.compression.enabled=false
websocket.allowed.origins=http://<IIS server name or IP address>. For
example: 192.168.1.1.
```

Save changes to the file. The **Allowed Origins** property is a comma-delimited list of URLs. If web clients will be connecting to your website using an HTTPS connection, adjust the URL accordingly. If both secure and non-secure connections will be used, use both URLs as the value: `websocket.allowed.origins=http://192.168.1.1,https://192.168.1.1`. To avoid errors, make sure that all possible address formats are included in the Allowed Origins list.

- 3 Restart the web site and restart the session server and test the proxy by connecting to: `http(s)://192.168.1.1`.

## Troubleshooting

If you receive web server errors, enabling detailed errors may help diagnose the problem. In the IIS Manager, open the **Error Pages** feature and check **Detailed errors**:



Typically errors in the 5XX range are caused by issues with compression being enabled or mistakes in the **Allowed Origins** value.

If the IIS proxy will be connecting to the session server with HTTPS, then the certificate used with the session server must be trusted by the IIS server. If the session server is using a self-signed certificate, this certificate must be added to the Windows trust store. If the session server is using a signed certificate, then the signer must be a trusted CA.

# Improving Connection Times on Non-Windows Platforms

To improve connection times on non-Windows platforms, follow these steps after installing the Host Access for the Cloud session server, particularly when the system is virtualized or otherwise headless:

- 1 Stop the session server service.
- 2 Open the `<installation folder>/sessionserver/conf/container.conf` file in a text editor.
- 3 Locate this line, and edit as follows:  

```
#wrapper.java.additional.x=-Djava.security.egd=file:///dev/urandom
```

  - ♦ Remove the # to uncomment the line.
  - ♦ Replace x with `<n+1>`, where `<n>` is the highest number noted in the other `wrapper.java.additional.<n>` lines.
  - ♦ Save the file.
- 4 Restart the session server service.

## Advanced Settings

The following are some post-installation configurations you may want to make.

- ♦ [How to Adjust HTTP Session Timeout](#)
- ♦ [How to enable FIPS level security](#)

### How to Adjust HTTP Session Timeout

The default timeout value for an inactive user session is 30 minutes. This means that when a user closes their browser without logging out first, their user session and any open host sessions will be cleaned up after 30 minutes. You can configure this setting on the server.

- 1 Open `<install directory>/sessionserver/microservices/sessionserver/service.yml`.
- 2 Adjust the session timeout value in the `env` section of the file:

```
- name: server.servlet.session.timeout
  value: <desired-time-in-seconds>
```

---

**TIP:** The indentation formatting is important.

---

- 3 Restart the server.

## How to enable FIPS level security

The Federal Information Processing Standards (FIPS) 140-2 validated cryptographic modules are used by the US federal government as a security regulation standard. Host Access for the Cloud supports this standard and you can easily enable FIPS mode by editing a file in the session server.

- ◆ Open  
`<install_directory>\sessionserver\microservice\sessionserver\service.yml`.
- ◆ Add the flag `-Dcom.attachmate.integration.container.FIPS.enabled=true` to the appropriate OS specific Java command; for Unix - `start-command`, for Windows - `start-command-win`.
- ◆ Restart the server.
- ◆ To ensure that FIPS mode is enabled, open  
`<install_directory>\sessionserver\logs\sessionserver.log` and verify that FIPS mode is set to true; FIPS mode: true.

## Known Issues

These issues have been identified in previous releases and are known issues.

- ◆ [Browser issues](#)
- ◆ [Host specific issues](#)
- ◆ [Installation issues](#)

### Browser issues

The following notes are specific to different web browsers.

- ◆ [Recommended browsers](#)
- ◆ [Key mapping issues with different browsers](#)

### Recommended browsers

It is highly recommended that you use Google Chrome or Mozilla Firefox. While Host Access for the Cloud supports Microsoft Internet Explorer (IE) 11, there are known performance issues with Internet Explorer's JavaScript engine that may negatively affect the end user experience with Host Access for the Cloud.

These issues have been identified and have remedies, however the easiest solution is to use a different browser.

## Internet Explorer Unable to Play Recorded Macros

When using certain older versions of Microsoft Internet Explorer (IE) web browser with Host Access for the Cloud, attempts to playback macros may fail with an error. The error message reads: *Macro Error: Error transpiling macro code: TypeError: unknown: Circular reference in value argument not supported.*

This is a problem with this version of Internet Explorer and JavaScript. It may be possible to avoid this error if you delete the createMacro() function and replace it using JavaScript Promises (for example, then() ).

Because this issue is specific to early versions of Internet Explorer, the easiest solution to this problem is to use a different browser (Chrome or Firefox) or a more recent version of Internet Explorer. You can successfully play back macros using Internet Explorer version 11.0.9600.18161, update version 11.0.27. Run Windows Update to update Internet Explorer.

## HTTPS connections between Apple iOS mobile devices and the session server

Host Access for the Cloud users cannot connect to a session server over HTTPS from their Apple iPad when using a self-signed certificate. If feasible, the quickest solution is to use HTTP instead of HTTPS.

If HTTPS is needed, you have the following options:

- ◆ Obtain a valid certificate signed by a trusted CA and install it on the session server.
- ◆ Find an alternate browser that will accept the self-signed certificate. See [Browser and operating system support](#) for a list of supported browsers.
- ◆ Leverage a custom certificate authority:
  1. Create a custom CA, CA root certificate, and a server certificate signed by that CA's root certificate.
  2. Install the server certificate on the session server.
  3. Install the custom CA root certificate on the iPad by means of a profile. The iPad should now accept the server certificate as it was signed by a "trusted CA".

For a list of CAs trusted by Apple iOS, see [Lists of available trusted root certificates in iOS \(https://support.apple.com/en-us/HT204132\)](https://support.apple.com/en-us/HT204132).

## Internet Explorer Displays Blank Screens

When using the Microsoft Internet Explorer (IE) web browser with Host Access for the Cloud or Management and Security Server (MSS), you may see a blank screen instead of the expected session.

When using Microsoft Internet Explorer to access Host Access for the Cloud sessions or Management & Security Server, you may experience issues such as the following:

- ◆ Host Access for the Cloud renders properly for some URLs and not others (a blank screen is displayed). The behavior varies depending on whether the session is using an IP address, short hostname, or fully-qualified name.
- ◆ In MSS, you can't create or open a Host Access for the Cloud session unless that session is on the same server as MSS. A blank screen displays where you expect to see the session.

### Explanation

This issue is specific to the way Internet Explorer toggles various settings depending on its interpretation of website security. The settings in question are Compatibility View and Third-party Cookies. Depending on what “zone” Internet Explorer determines your web site to be in, these settings need to be either enabled or disabled. Internet Explorer bases its determination on the site URL. For example, if the server name in the URL does not contain dots (for example, `http://mycorporateserver/mss/AdminStart.html`), Internet Explorer assumes the address belongs in the Local Intranet zone. If it does, the site is assigned to the Internet zone.

<b>Zone</b>	<b>Internet Explorer Default Settings</b>
Local Internet Zone	Compatibility View enabled (not desired) Third-party Cookies enabled (desired)
Internet Zone	Compatibility View disabled (desired) Third-party Cookies disabled (not desired)

While it is possible for a website to override Compatibility View by specifying Document Mode with an X-UA-Compatible meta HTML tag, and Host Access for the Cloud does use that particular mode, MSS does not. Thus, if a Host Access for the Cloud server and a Management and Security Server are both in the Local Intranet zone (with default Compatibility View enabled), it is likely that Host Access for the Cloud would still perform correctly, but MSS would not.

### **Solution**

To use Internet Explorer 10 or 11 with Host Access for the Cloud and MSS servers, you need:

- ◆ Compatibility View disabled
- ◆ Third-party Cookies enabled

You need to determine what zone your web site is in and then make the necessary adjustments to the Internet Explorer settings. Because Internet Explorer can be configured in so many different ways depending on your situation, it is hard to provide one solution for successfully using Internet Explorer with Host Access for the Cloud and MSS. These are some possible configurations to follow:

- ◆ If both Host Access for the Cloud and MSS are in the Internet zone, manually add the Host Access for the Cloud server to the Local Intranet or Trusted Sites zone (Internet Options > Security > Local intranet > Sites). Use fully qualified host names or IP addresses.
- ◆ If both servers are in the Internet zone, change the default behavior for that zone and enable Third-party Cookies (Internet Options > Privacy > Advanced > Override automatic cookie handling).
- ◆ If both servers are in the Local Intranet zone, change the default behavior for that zone and disable Compatibility View (Tools > Compatibility View settings).

### **Key mapping issues with different browsers**

Certain keys on a numeric keypad and some browser-specific keys cannot be mapped. For example, in Chrome, Ctrl+n and Ctrl+w cannot be mapped.



## Host specific issues

The following are issues that are specific to different host types.

### Displaying the Euro character

If the EURO character does not display correctly on the terminal screen, talk to your system administrator to make sure the host character set for the session is setup correctly. By default, Host Access for the Cloud uses a character set which does not support the Euro character (€). To display the Euro character, change the character set to one that supports the Euro character.

### Issues encountered with VT hosts

Type	Description
Performance issues	<ul style="list-style-type: none"><li>◆ Heavy text output, such as form “Is-IR” may cause slow performance</li><li>◆ Scrolling regions may appear slow or choppy</li><li>◆ Cursor movement may be slow or choppy</li><li>◆ Internet Explorer is particularly slow, and performance degrades further when used for rows and columns.</li></ul>
Character sets	<ul style="list-style-type: none"><li>◆ Graphical characters and some character sets are not supported.</li><li>◆ Some non-English characters may cause the terminal display to freeze.</li></ul>
Other VT issues	<ul style="list-style-type: none"><li>◆ Insert/delete column (DECIC, DECDL) may fail.</li><li>◆ VT400 will not recognize DECSCL.</li></ul>

### Field outlines in 3270 sessions

The 3270 attributes for field outlines are not fully supported. Host Access for the Cloud currently supports underline and overline; however, left vertical line, right vertical line, and combinations of the four line types are not yet supported.

### Installation issues

The [Installing and Upgrading](#) topics include a troubleshooting section which may help diagnose and remedy specific installation issues.

### Installation fails due to server preventing access to TEMP directory

HACloud requires access to a temp directory to successfully install. Previously, if the default temp directory was not available, for example in a locked down server environment, the install was compromised.

## Setting a TEMP directory for the installation program

The installer requires a writable temp directory. If the default temp directory is not suitable, the installer can be run with an alternate temp directory.

### ♦ Windows

If the default temp directory is not writable, set the environment variables `TMP` or `TEMP` to an alternate location temporarily while running the installer. Restore the variables when the installation is complete.

### ♦ Linux/Unix

The environment variable `INSTALL4J_TEMP` determines the base directory that the installer uses for self-extraction. As the installer extracts files and launches Java to perform other tasks, the Java temp location (`/tmp`) is used.

To run the Linux installers with an alternate temp directory:

- Define the variable `INSTALL4J_TEMP`, specifying the value as the desired temp location.
- Create the temp directory specified for the installer. The installer requires that the directory already exist.
- Add the command line switch `-J-Djava.io.tmpdir={tmpdir}` when launching the installer. For example:

```
abcd@linux:~$ INSTALL4J_TEMP=/home/abcd/i4jtemp
abcd@linux:~$ export INSTALL4J_TEMP
abcd@linux:~$ sudo ./hacloud-2.4.2.12345-linux-x64.sh -J-
Djava.io.tmpdir=/home/abcd/i4jtemp
```

- ♦ The installer must be run with administrative permission.

## Chained HACloud and MSS installations

On **Windows**, a chained installation of HACloud and MSS will need no other adjustments, if you temporarily set the `TMP` or `TEMP` environment variables described above.

On **Linux/Unix** - You cannot run a chained installer on this platform; run them separately, each with administrative permissions, the `INSTALL4J_TEMP` variable set and with the `-J-Djava.io.tmpdir` switch.

---

**NOTE:** If both MSS and HACloud are being installed “unchained”, MSS must be installed first, then HACloud.

---

## Setting a TEMP directory for the product

HACloud uses an internal temp directory that should be suitable in all cases. However, this directory can be changed if necessary by editing the `container.conf` file.

### *Changing the TMP location*


This location is configurable:

1. Open `<installation folder>/sessionserver/conf/container.conf` in a text editor.

2. Edit the `wrapper.java.additional` property to specify the new location. If the path contains spaces, enclose it in quotes on Windows or use the appropriate syntax for Linux/Unix platforms. For example, `wrapper.java.additional.9=-Djava.io.tmpdir=./tmp`
3. If needed, you can set an additional property to delete the temp directory when the server shuts down.
4. Restart the server.

## MSS Administrative Console Reference

The Host Access Management and Security Server (MSS) provides an Administrative Console, a web-based centralized location where you can manage sessions, assign sessions to users, configure authentication, and much more. Work flows that include configuring additional settings in the MSS Administrative Console are marked with this icon

 in the HACloud documentation.

This list includes the MSS Administrative Console functionality that is used by HACloud, including direct links to the associated sections in the MSS documentation. You can find these settings in the MSS Administrative Console left navigation panel.

- ◆ **Manage Sessions**

On this panel, [Add and configure a Host Access for the Cloud session](#).

- ◆ **Assign Access**

Use [Assign Access](#) to specify which sessions each user has access to. When LDAP authorization is enabled, different sessions can be assigned to specific users and groups. With other types of authorization, all users get all authorized sessions. See [Assign Access](#)

- ◆ **Configure Settings - Authentication and Authorization**

Use to configure how users are authenticated when accessing the system and which method to use for authorizing their access to sessions. See [Select a method to authenticate users](#).

- ◆ **Configure Settings - Automated Sign-on**

This feature enables an end user to automatically log on to a mainframe host application using a terminal emulation client. Settings must be configured in the MSS Administrative Console, in the HACloud client, and on z/OS. See these references.

- [Automated Sign-on for Mainframe](#) in the MSS Administrative Console help.
- [Automated Sign-On for Mainframe - Administrator Guide](#)
- [How to Set Up Automated Single Sign-On for Mainframe](#).


- ◆ **Metering**

MSS provides metering capabilities to monitor host sessions. See: .

- [Metering](#) in the MSS Administrator Guide.
- [How to Set Up Metering](#).

- ◆ **Kerberos automatic sign-on (IBM 5250 only)**

Kerberos is an authentication protocol that uses cryptographic tickets to avoid transmitting plain text passwords. To configure Kerberos, open the MSS Administrative Console and select Host Access for the Cloud from the drop down list:



When you configure HACloud to use the Kerberos authentication protocol there are terms that you should understand and prerequisites to adhere to in advance of configuring this option. These options are explained in detail in the MSS Administrative Console > Host Access for the Cloud panel documentation. Choose Host Access for the Cloud from the drop down list, then select Kerberos Settings, and click the Help button.



#### ◆ Terminal ID Manager

MSS provides a Terminal ID Manager to pool terminal IDs, track ID usage, and manage inactivity timeout values for specific users, thus conserving terminal ID resources and significantly reducing operating expenses. An additional license is required. See these references:

- [Setting up the Terminal ID Manager](#)
- [Terminal ID Manager Guide](#)
- [How to Set Up the Terminal ID Manager](#)