



Micro Focus Relativity Data Client for UNIX

Installation

Micro Focus
The Lawn
22-30 Old Bath Road
Newbury, Berkshire RG14 1QN
UK
<http://www.microfocus.com>

Copyright © Micro Focus 2018. All rights reserved.

MICRO FOCUS, the Micro Focus logo, and Micro Focus product names are trademarks or registered trademarks of Micro Focus Development Limited or its subsidiaries or affiliated companies in the United States, United Kingdom, and other countries. All other marks are the property of their respective owners.

Revised 2018-06-11 for version 12.15

Contents

Preface.....	1
About this Guide	1
Introducing Relativity Data Client for UNIX	1
Understanding ODBC.....	2
ODBC Terminology	2
ODBC and Relativity Data Client for UNIX	3
Related Relativity Documentation	4
Conventions Used in this Document	5
Technical Support.....	5
Support Guidelines	5
Test Cases	6
Contact information	6
Chapter 1: Installation and Verification of Relativity Data Client for UNIX	9
System and Setup Requirements.....	10
End-User Requirements	10
Installing the Relativity Data Client for UNIX.....	11
Distribution Media Options.....	11
Electronic Product Delivery Installation	12
Installing from CD-ROM Media	13
Load the CD-ROM on the UNIX Client	14
HP-UX	14
IBM AIX	14
Linux	14
Sun Solaris SPARC and Intel x86	15
Installing from GUNZIP TAR file.....	15
Installing the Relativity Data Client	16
Step 1: Create the Staging Directory.....	16
Step 2: Start the Installation Script	16
Step 3: Answer the Installation Prompts	17
Step 4: Perform the Installation	19
Step 5: Unload the Distribution Media.....	22
Unload the CD-ROM on the UNIX Client.....	22
HP-UX and IBM AIX	22
Linux	23
Sun Solaris SPARC and Intel x86	23
Step 6: Remove the Staging Directory	23
Verifying Installation of the Relativity Data Client for UNIX.....	23
Configuring a Relativity Data Server Data Source from the UNIX Client	23
Configuring a Relativity Data Client Data Source on the UNIX Client	24
Testing the Relativity Data Client Data Source.....	25
Removing the Relativity Data Client for UNIX.....	25
Customizing the Relativity Data Client for UNIX Installation	26

Formatting the relativity.ini Definition File	26
Creating a Media Image Directory	27
Unpacking the Data Client Installation Media	27
Installing Server Definitions	28
Installing Predefined Data Sources	28
Bypassing Installation Prompts.....	30
Overriding Installation Prompts Defaults	30
Creating New Installation Media	31
Chapter 2: Utility Programs	33
Command-Line Interface	33
Conventions	34
Displaying Help	35
RelServerAdmin Utility.....	35
Using the RelServerAdmin Utility Commands and Parameters	35
Adding a Data Source	36
Adding a Server Definition.....	38
Listing Character Sets	39
Listing Data Sources	40
Listing Server Definitions.....	41
Modifying a Data Source	41
Removing a Data Source	44
Removing a Server Definition.....	44
Showing a Data Source.....	45
Showing the Status of a Data Server	46
Shutting Down a Data Server.....	47
Terminating a Connection to a Data Server.....	47
RM/COBOL File Manager Configuration Parameters.....	48
Buffer Pool.....	48
File Process Count	48
Micro Focus COBOL File Manager Configuration Parameters	48
Catalog Format.....	49
New File Format	49
Data Compression.....	49
Key Compression – Trailing Spaces	49
Key Compression – Leading Characters.....	49
Key Compression – Duplicates	50
Key Compression – Sparse Byte	50
RelClientAdmin Utility	50
Using the RelClientAdmin Utility Commands and Parameters.....	50
Adding a Data Source	51
Adding a Server Definition.....	52
Listing Data Sources	52
Listing Server Character Sets	53
Listing Server Data Sources.....	54
Listing Server Definitions.....	55
Modifying a Data Source	56
Removing a Data Source	57
Removing a Server Definition.....	57
Showing a Data Source.....	58
RelClientTest Utility	59
Using the RelClientTest Utility Command and Parameters	59
Testing Client Data Sources.....	59
RelDriverAdmin Utility.....	60
Using the RelDriverAdmin Utility Commands and Parameters	61

Installing the Relativity Data Client Driver	61
Listing the ODBC Drivers	62
Uninstalling the Relativity Data Client Driver.....	62
Appendix A: UNIX ODBC Driver Managers.....	63
Driver Managers on UNIX	63
Differences	63
unixODBC.....	64
Data Source Search Sequence	64
Driver Search Sequence.....	64
iODBC.....	65
Data Source Search Sequence	65
Driver Search Sequence.....	65

Preface

This section of the *Relativity Data Client for UNIX Installation Guide* provides an introduction to the Relativity Data Client for UNIX component and fundamental concepts of the ODBC (Open Database Connectivity) environment and the relationship of Relativity Data Client for UNIX to the various ODBC components, including UNIX Driver Managers. Other topics in the Preface describe related documentation, define conventions used in the documentation, and point out registration and technical support options.

About this Guide

The *Relativity Data Client for UNIX Installation Guide* is intended for a System Administrator and describes the following topics:

Chapter 1: Installation and Verification of Relativity Data Client for UNIX. This chapter describes the installation procedures for the Relativity Data Client for UNIX including system and setup requirements, how to create data sources, the verification procedure, and the uninstall procedure. It also details how to customize the installation process.

Chapter 2: Utility Programs. This chapter describes the utility programs that are supplied with the Relativity Data Client for UNIX. These utilities are used to facilitate the creation of data sources, and the testing of the connection between the UNIX client and the server machines running the Relativity Data Server.

Appendix A: UNIX ODBC Driver Managers. This appendix provides information about the two ODBC Driver Managers that are available on UNIX.

Introducing Relativity Data Client for UNIX

The Relativity Data Server and Data Client components are used in the two-tier (or client/server) configuration of Relativity. In the two-machine configuration, the Relativity Data Server component of the Relativity Database Management System (DBMS) resides on a remote UNIX machine (called the UNIX server) or Windows machine (called the Windows server) close to the data files that the DBMS accesses. The Relativity Data Client for UNIX component of the Relativity DBMS resides on a UNIX machine (called the UNIX client), close to the ODBC-enabled application that needs to access the data.

Note This document uses the term “UNIX server” to indicate the UNIX machine on which the Relativity Data Server is installed. The term “UNIX client” indicates the UNIX machine on which the Relativity Data Client is installed. It is possible to have the Relativity Data Client and the Relativity Data Server installed on the same

physical UNIX machine, in which case the terms UNIX server and UNIX client refer to the same machine. Thus, the term UNIX client does not *always* indicate a workstation class of machine.

Relativity provides for a *true* relational database view of your COBOL application data. It also provides an Open DataBase Connectivity (ODBC)-compliant relational database engine that allows SQL-based access to your COBOL application data without moving, converting replicating, or re-engineering your legacy data files. With Relativity, you can choose virtually any modern ODBC-enabled development tool to build applications for ad hoc reporting, decision support, and specialized data processing functions. Moreover, using Relativity, you do not have to rewrite or migrate any of your working applications in order to benefit from a client/server environment.

Understanding ODBC

The Relativity document, *The Theory of Relativity*, provides an overview of the Relativity product. However, that guide does not cover the Open Database Connectivity (ODBC) environment in depth, particularly the concept of Driver Managers. The Driver Manager is an integral part of ODBC, and it is included as part of the Microsoft Windows operating system. As a result, on Windows, installation of the ODBC Driver Manager is not visible to the end user. On UNIX, however, the ODBC Driver Manager is not a standard part of any UNIX operating system, although two groups have written open source implementations of it. To assist in familiarizing you with the use of these implementations, see [Appendix A: UNIX ODBC Driver Managers](#) (on page 63).

The following section defines some of the terms and components used in ODBC.

ODBC Terminology

A *database* is a system that stores information in the form of tables. Each table in the database contains rows. Each row in a table contains columns. It is an over simplification to say that a table is like a file, a row is like a record, and a column is like a data item, but there are similarities in these concepts. To access information from a database, you need a *database management system (DBMS)*, a collection of programs that enable you to store, modify, and extract data from the database in the form of a *query*, which is a stylized question conforming to a set of query language rules. Examples of database management systems include SQLServer, Oracle, and MySQL.

Each DBMS has its own specific *Application Program Interface (API)* to access data within it. An API is the set of procedure calls, within the DBMS, that are needed to connect to a database, access the tables within it, and return the results to the application program.

A *database application program* is one that uses a database management system's API to retrieve the data from a database and perform useful work with it. Because each DBMS has its own proprietary API, a specific database application program generally works with only one DBMS. Unless specifically written otherwise, conversion of a database application to a different DBMS is usually a large and often error-prone task.

ODBC, the acronym for Open Database Connectivity, was created by Microsoft Corporation to provide independence for a database application program from the DBMS that it accesses. ODBC provides a consistent API for accessing databases. ODBC accomplishes this by inserting a middle layer, called a database *driver*, between an application and the DBMS. Calls made to this API are passed to a driver specifically written for a database. It is important to note that a driver is not itself a database. Instead, a driver takes the requests made to the ODBC API and makes the appropriate API calls for a particular database management system. Thus, each driver is tailored to a specific DBMS, and internally, the drivers are each very different.

A database application program that is written to use the ODBC API is called an ODBC-enabled (or ODBC-compliant) application. Calls to the ODBC API are routed to the proper driver by a library called the *Driver Manager*.

The Driver Manager contains routines for the entire ODBC API. However, the Driver Manager does not actually carry out most of the functions of the API. Instead, when the ODBC-enabled application connects to a database, the application loads the library for the Driver Manager and calls the Connect API option using a data source name. This name indicates to the ODBC Driver Manager not only the proper driver to use to access the database, but any information needed by the driver to connect to that database. The Driver Manager will load the library for the proper driver, and then call the proper routine within the driver to connect to the actual database. Furthermore, ODBC API calls made to the Driver Manager are subsequently passed to the driver for execution.

Thus, the Driver Manager provides a layer of indirection, relieving the ODBC-enabled application of the need to be tied to driver, as well as a specific database. In theory, an application that is using a SQLServer database one day, could be using MySQL the next merely by changing the driver associated with the name of the data source.

As noted, on Windows there is only one Driver Manager, which is the one supplied by Microsoft. Consequently, ODBC-enabled applications on Windows need only be concerned with accessing the library for that Driver Manager. However, on UNIX, two Driver Managers are available, which adds some complexity when using ODBC on this platform. For more in-depth information, see [Appendix A: UNIX ODBC Driver Managers](#) (on page 63).

ODBC and Relativity Data Client for UNIX

In ODBC terms, the Relativity Data Server is the database, and the Relativity Data Client is the driver for the Relativity Data Server. Although the Relativity Data Server implements the ODBC API directly, the Relativity Data Client is still needed to manage the network communication to the Relativity Data Server.

The Relativity Data Client for UNIX is capable of communicating with a Relativity Data Server for UNIX or a Relativity Data Server for Windows. It is also capable of communicating with a Relativity Data Server on the same UNIX machine as itself.

Micro Focus supplies command line-based tools for creation, modification, and deletion of data sources, for both the Relativity Data Client for UNIX and the Relativity Data Server. These tools will facilitate creation of data sources from installation scripts. There is also a tool for testing a client data source and its connection to a server data source.

Related Relativity Documentation

In addition to the *Relativity Data Client for UNIX Installation Guide* and *The Theory of Relativity, A Primer*, the Relativity documentation set consists of the following items:

- **Relativity Client/Server Installation Guide.** A document (one for UNIX and one for Windows) that is intended for a System Administrator. It describes the following:
 - How to install the Relativity Data Server software component on a computer running either a UNIX or Windows operating system and verify that the installation was successful.
 - How to:
 - Install the Relativity Data Client software component on a secure Windows workstation (such as the workstation belonging to a Database Administrator) for the purpose of catalog development.
 - Install the Relativity Server Administrator utility program in order define a server for the client and configure a server data source.
 - Verify communications between the client and the server.
 - How to install the Relativity Data Client software component on an end user's Windows workstation and verify that the installation was successful by configuring a client data source and associating it with a server data source.
 - How to run the RM/COBOL Indexed File Recovery utility (**recover1**) to recover an RM/COBOL indexed file.
- **Relativity Designer Installation Guide.** A document that describes how to install the Relativity Designer software component and verify that the installation was successful.
- **Relativity DBA Installation Guide.** A document that describes how to install and verify the Relativity DBA (Database Administrator) software component on a Windows-based workstation.
- **Relativity Java Client User's Guide.** An HTML document, located in the JDBC directory of the Relativity Java Client Electronic Product Delivery download file and on the Relativity product CD, that describes the installation and verification of the Relativity Java Client as well as information about deploying it with Java applications and applets, and setting up data source connections. The Java Client is a Java Database Connectivity (JDBC) component that resides in a Java runtime environment (JRE).
- **Relativity Online Help.** An online HTML help documentation system that provides fast access to detailed information on Relativity features and options. The help system also contains step-by-step presentations on how to accomplish specific tasks with Relativity and an extensive glossary. A separate help file is provided for each of the various Relativity tools: the DBMS (Data Client and Data Manager), the Designer, the DBA (Database Administrator), the Relativity Configuration Utility, and the Server Administrator.
- **Relativity README Files.** A set of online HTML documents that lists any changes to the Relativity documentation since its publication and contains new technical information that supplements the documentation.

- **RM-Install Program User's Reference.** A document that describes how to configure and control the installations of RM/COBOL products, including Relativity.

Conventions Used in this Document

This document contains visual cues to help the reader identify important information.

Table Convention	Indicates
Initial Capitals	Menu names, command names, and dialog box, window, and form titles.
Bold	Menu, command, and button names. Other elements to be selected or typed to accomplish an action. Label on input media used during installation.
<i>Italic</i>	Reference to a topic in the current document or another Relativity document. Reference to another document. Emphasis.
<i>Bold Italic</i>	Variables.

Technical Support

Micro Focus is dedicated to helping you achieve the highest possible performance from the RM/COBOL family of products. The technical support staff is committed to providing prompt and professional service to you when you have problems or questions about your Micro Focus products.

Technical support services are subject to Micro Focus's prices, terms, and conditions in place at the time the service is requested.

While it is not possible to maintain and support specific releases of all software indefinitely, we offer priority support for the most current release of each product. . For customers who elect not to upgrade to the most current release of the products, there is free support available on the Micro Focus Community Forum:
community.microfocus.com

Support Guidelines

When you need assistance, you can expedite your call by having the following information available for the technical support representative:

- Company name and contact information.
- Micro Focus Relativity product serial number (found in the Electronic Product Delivery email, or in the License Certificate).
- Micro Focus Relativity product version number.

- Operating system and version number.
- Type of files (RM/COBOL or Micro Focus COBOL) being used when the problem occurred.
- Hardware, related equipment, and terminal type.
- Exact message appearing on screen.
- Concise explanation of the problem and process involved when the problem occurred.

Test Cases

You may be asked for an example (test case) of the source that demonstrates the problem.

- The smaller the test case is, the faster we will be able to isolate the cause of the problem.
- Do not send full applications.
- Reduce the test case to the smallest possible combination of components required to reproduce the problem.
- If you have very large data files, write a small program to read in your current data files and to create new data files with as few records as necessary to reproduce the problem.
- Test the test case before sending it to us to ensure that you have included all the necessary components to run the test case.

When submitting your test case, please include the following items:

1. **README text file that explains the problems.** This file must include information regarding the hardware, operating system, and versions of all relevant software (including the operating system and all Micro Focus products). It must also include step-by-step instructions to reproduce the behavior.
2. **Program source files.** We require source for any program that is called during the course of the test case. Be sure to include any copy files necessary for recompilation.
3. **Data files required by the programs.** These files should be as small as possible to reproduce the problem described in the test case.

Contact information

Our Web site gives up-to-date details of contact numbers and addresses.

Additional technical information or advice is available from several sources.

The product support pages contain considerable additional information, including the WebSync service, where you can download fixes and documentation updates. To connect, enter <http://www.microfocus.com> in your browser to go to the Micro Focus home page.

If you are a Micro Focus SupportLine customer, please see your SupportLine Handbook for contact information. You can download it from our Web site or order it

in printed form from your sales representative. Support from Micro Focus may be available only to customers who have maintenance agreements.

You may want to check these URLs in particular:

- <https://www.microfocus.com/products/relativity/> (trial software download and Micro Focus Community files)
- <https://www.microfocus.com/support-and-services/documentation/> (documentation updates and PDFs)

Chapter 1: Installation and Verification of Relativity Data Client for UNIX

This chapter lists the [system and setup requirements](#) (see page 10) and describes the procedures for [installing the Relativity Data Client for UNIX](#) (see page 11) software on a computer having one of the UNIX operating systems listed under [System and Setup Requirements](#) (see page 10).

This chapter also discusses the following topics:

How to	See page
Verify that the installation of the Relativity Data Client for UNIX was successful by:	23
• Configuring a Relativity Data Server data source from the UNIX client.	23
• Configuring a Relativity Data Client data source on the UNIX client.	24
• Testing the Relativity Data Client data source.	25
Remove the Relativity Data Client for UNIX.	25
Customize the Relativity Data Client for UNIX installation.	26

System and Setup Requirements

Installation of the Relativity Data Client for UNIX software requires the following minimum software and hardware.

Component	Requirement
Operating System	HP-UX 11.31 (PA-RISC and Itanium) IBM AIX 7.2 (RS6000) Linux (2.6 kernel or later) Sun Solaris SPARC (2.10) and Intel x86 (2.10)
Disk Space	5 MB recommended
Network Software	TCP/IP network
Driver Managers	unixODBC 2.2.7 or later iODBC 3.51.1 or later

Installation of the Relativity Data Client for UNIX software also includes the following prerequisites:

- One of the Driver Managers is installed, and the PATH environment variable and the system library search path environment variable contain the library directory of the Driver Manager that is to be used. The library search path environment variables for the different UNIX versions are as follows:

Operating System	Variable
HP-UX	LIBPATH
IBM AIX	SHLIB_PATH
Linux (2.6 kernel or later)	LD_LIBRARY_PATH
Sun Solaris SPARC and Intel x86	

- The user account installing the software must have the necessary permissions to alter the control files of the Driver Manager that is in use.
- The user account installing the software must have the necessary permissions to create the installation directories. The default location for these directories is in **/usr/local/liant**.
- If there is currently a version of the software in the installation directory, all processes currently using the Relativity Data Client for UNIX, should be terminated first.

End-User Requirements

End users of the Relativity Data Client that utilize the Relativity Data Client for UNIX have the following requirements:

- The system library search path environment variable must contain the directory containing the Driver Manager Library. For more information, see [Appendix A: UNIX ODBC Driver Managers](#) (on page 63).

- The end user must have read permission to the directory containing the Driver Manager Library and the Driver Manager control files.
- The end user must have read permission to the directory containing the library for the Relativity Data Client for UNIX. The default location is `/usr/local/iant/lib`.
- If the end user is to run any of the Micro Focus-supplied tools for creating server or client data sources, then the end user must have read permission to the installation directory containing those tools, and that directory must be in the end user's PATH environment variable, or the end user must supply the complete pathname of the tool when invoking it.

Installing the Relativity Data Client for UNIX

This section discusses the [distribution media options](#) (see the following topic) and the steps on how to install the Relativity Data Client for UNIX software, including the following:

- [Step 1: Create the Staging Directory](#) (see page 16)
- [Step 2: Start the Installation Script](#) (see page 16)
- [Step 3: Answer the Installation Prompts](#) (see page 17)
- [Step 4: Perform the Installation](#) (see page 19)
- [Step 5: Unload the Distribution Media](#) (see page 22)
- [Step 6: Remove the Staging Directory](#) (see page 23)

Note 1 The staging directory is a temporary directory that is used during the installation process. No permanent files are placed here. The installation script uses this directory to contain files that it will use to control the installation process. An installation prompt is provided to remove these control files following a successful installation. The staging directory is not required to be on the same UNIX file system as the installation directory. Because the bulk of the files on the Data Client are read directly from the installation media into the installation directory, the space requirements for the staging directory are small.

Note 2 For information on customizing the installation procedures of the Data Client, refer to [Customizing the Relativity Data Client for UNIX Installation](#) (on page 26).

Distribution Media Options

The Relativity Data Client for UNIX software is available on CD-ROM media and via Electronic Product Delivery. For the CD-ROM option, the Relativity Data Client for UNIX is delivered on the same CD-ROM media for the Relativity Data Server for UNIX or the Relativity Data Server for Windows. Electronic Product Delivery allows the Relativity Data Client for UNIX to be downloaded from the Micro Focus Electronic Product Delivery web site. From the Electronic Product Delivery website, the download file is associated with the Invoice Line for the Relativity Data in any of the following two formats.

- **ISO CD Image.** There is not a separate ISO CD Image for the Relativity Data Client for UNIX. It is part of the Relativity product ISO CD Image. If you have chosen to download the ISO CD Image option for a Relativity product and

created the physical CD-ROM media, then proceed with normal CD installation. See [Installing from CD-ROM Media](#) (on page 13).

- **UNIX GUNZIP TAR.** The download format for UNIX GUNZIP TAR contains *only* the Relativity Data Client for UNIX.

After the deliverable has been downloaded and uncompressed, and the installation components have been created from the GUNZIP TAR distribution format, follow the instructions in [Installing from GUNZIP TAR file](#) (see page 15) to install the Relativity Data Client for UNIX software.

Note 1 The UNIX GUNZIP TAR format is decompressed on a UNIX machine. The Relativity Data Client for UNIX product contains only UNIX components.

Note 2 The instructions that follow refer to an installation components directory, which is the directory to where the deliverable file, via Electronic Product Delivery, was downloaded and decompressed.

Electronic Product Delivery Installation

Note You must have an Internet connection and an Internet browser installed to proceed with this method of installation.

All Relativity orders generate an Electronic Product Delivery (EPD) email that contains links to download the product. It also contains a link to download the product's License Certificate (also called the license file) for the order, which will be necessary to install Data Server, although it is not necessary to install a Data Client. Finally, there are instructions about how to decompress the download file and begin the installation. This section will elaborate on the process of downloading the order and preparing to install the product.

All Relativity EDP orders contain links to download the product as a CD-ROM image, in the form of a compressed .iso file, and links to download a smaller installation, in the form of a tape archive (.tar) file that has been compressed using gzip. And you can also elect to have a physical CD-ROM shipped to you. (You can also use a CD-ROM burner drive to create your own physical CD-ROM using the .iso file, if you do not wish to wait for it to be shipped.) The CD-ROM (both .iso and physical) contains installation files for all the supported platforms. The smaller GUNZIP TAR version contains the installation for only the platform purchased by the order.

(Although using the CD-ROM image is not common, this section will cover it, for sake of completeness.)

The process begins with the arrival of a [Micro Focus Electronic Product Delivery](#) email which was generated when your order was complete. There is a link in this email on which to click to browse to the Electronic Product Delivery website. Once you have clicked on that link, a login page will appear in your browser. Use this page to login with your Micro Focus account. After a successful login, a page will display containing your order, on which there will be an individual invoice line for each item in the order. Locate the invoice line for the *Relativity Data Server* (the Data Client download is bundled with the Data Server), and click on the + in the left hand column. The invoice line will expand, displaying three tabs: **Software/Licenses**, **Documentation**, and **Legal Information**, with **Legal Information** selected. After you review the End User License Agreement in the Legal Information tab, click on the checkbox in **Step 2** at the beginning of the email. (This is necessary to acknowledge the acceptance of the End User License Agreement. You will not be able to proceed until the checkbox has been checked.) Next, select the **Software/License** tab and click on the + to the left of the serial number. You will then be presented with the lines

for downloading the complete CD-ROM image (.iso), for downloading a smaller GUNZIP TAR file (.tgz), and for downloading the license key, although the License Certificate is not required to install a Data Client.

The next two sections deal with downloading, decompressing, and installing the desired installation media.

Installing from CD-ROM Media

If you elected to receive physical media, proceed to the steps described in [Load the CD-ROM on the UNIX Client](#) below.

If you elected to download the compressed .iso file, it will be compressed using gzip and will need to be decompressed before installation, although the Chrome browser may decompress it automatically. (Click on the **Documentation** tab in your EDP order to obtain up to date details on this process. Use the *Installation Guide to Installing an ISO Image* instructions.) The downloaded file will have a name similar to **rmrelativity12xx.igz**.

Note 1: The following instructions assume that the gzip utility has been installed on the machine and is in your PATH. (If the following instructions are unclear to you, please use the [Installing from GUNZIP TAR File](#) option below.)

Note 2: The following instructions describe the process on a UNIX machine. If the .igz file was downloaded to a Windows machine, the steps are very similar.

Login to your UNIX machine, and, if necessary, open a terminal window. In the terminal window, change directory to the directory where the .igz was downloaded, and use the following command to rename the file's extension from .igz to iso.gz.

```
mv rmrelativity12xx.igz rmrelativity12xx.iso.gz
```

Then decompress the file with the command:

```
gunzip rmrelativity12xx.iso.gz
```

If this command results in an error, then the .igz file has already been decompressed by the browser, in which case, all that needs to be done is rename the file without the .gz extension.

```
mv rmrelativity12xx.iso.gz rmrelativity12xx.iso
```

An .iso file is useful for burning a CD with the Relativity installation. On Windows 10 and later, use the .iso image burning feature, or third-party CD-ROM Burning software, such as Nero (<http://www.nero.com>) or Roxio's Easy CD Creator (<http://www.roxio.com>), to create physical media.

After you create a CD, proceed to the instructions at the beginning of the next section for how to start the installation.

Alternatively, if the UNIX machine is a virtual machine, .iso files can also be mounted as a virtual CD. See your virtual machine's instructions for more detail.

Load the CD-ROM on the UNIX Client

Use this option to load the distribution media if your UNIX hardware has a CD-ROM drive installed and the Relativity Data Client was delivered on this type of media. Instructions for loading the distribution media on specific versions of UNIX are provided in the following sections.

On most modern UNIX platforms, simply placing the CD-ROM media into the CD-ROM drive and closing the door is all that is necessary to mount the media and make it accessible from the UNIX file system. The instructions that follow are for systems where this does not occur automatically.

Note In the instructions that follow, the standard mount directory names are used where the UNIX operating system has such a standard. If the operating system does not follow a standard, the name `/cdrom` is used. It will be necessary either to create the directory `/cdrom` or substitute the preferred mount directory name for `/cdrom`.

After you have loaded the CD-ROM, proceed to the [Installing the Relativity Data Client](#) section (on page 16).

HP-UX

1. Insert the CD into the CD-ROM drive.
2. Log in as root and enter:

```
mount -F cdfs -o ro,cdcase /dev/dsk/cd0t4d0 /cdrom
```

Note 1 It may be necessary to create the mount directory `/cdrom` before executing this command.

Note 2 The device name, `c0t4d0`, is dependent on the hardware configuration of your UNIX server. It may be necessary to substitute the proper value for your system. Consult your UNIX System Administrator.

IBM AIX

1. Insert the CD into the CD-ROM drive.
2. Log in as root and enter:

```
mount -o ro -v cdrfs /dev/cd0 /cdrom
```

Note It may be necessary to create the mount directory `/cdrom` before executing this command.

Linux

1. Insert the CD into the CD-ROM drive.
2. Log in as root and enter:

```
mount -o ro -t iso9660 /dev/cdrom /mnt/cdrom
```

Sun Solaris SPARC and Intel x86

1. Insert the CD into the CD-ROM drive.
2. If Solaris does not automatically load the CD-ROM, log in as root and enter:

```
volcheck
```

Installing from GUNZIP TAR file

The most common case is to use the .tgz file download. When downloaded, the file will have a name similar to **rmrelativity12xx_dclient_os_32.tgz**. (Where 12xx is the version of Relativity and os is the UNIX platform on which to install the Data Client.) If it is not there already, copy the .tgz file into an empty directory on the target UNIX machine. The remaining instructions refer to this directory as your installation components directory. Then follow the instructions below to prepare the .tgz file for usage.

Login to your UNIX machine, and, if necessary, open a terminal window. In the terminal window, change directory to the installation components directory (where the .tgz was downloaded), and use the following command to rename the file's extension from .tgz to tar.gz. We'll also shorten the name as well.

```
mv rmrelativity12xx_dclient_os_32.tgz rmrelativity12xx_dclient.tar.gz
```

Next, decompress the GUNZIP file with the following command:

```
gunzip rmrelativity12xx_dclient.tar.gz
```

Finally extract the Data Client's installation files with the following command:

```
tar xvf rmrelativity12xx_dclient.tar
```

Now, proceed to the **Installing the Relativity Data Client** section below.

Installing the Relativity Data Client

Step 1: Create the Staging Directory

It is necessary to create an empty, temporary staging directory to contain the files used to control the installation process. This directory need not be on the file system where the Relativity Data Client ultimately will be installed; nor will the file system of the staging directory require more than 100 blocks for free storage. The majority of the Data Client's files will be installed directly from the distribution media into its installation directory.

Note If the UNIX client is unable to read the installation media directly, it will be necessary to load the media on a machine what can read the installation media and then copy the installation file into the staging directory. In this case, the file system of the staging directory will need 9000 blocks of free storage.

To create the staging directory, enter:

```
mkdir /RelStage
```

The name *RelStage* will be used throughout the remainder of this document to refer to the staging directory. You may, however, choose any name you wish.

Step 2: Start the Installation Script

To start the installation script for the Relativity Data Client for UNIX:

- a. Login as root.

Note Make sure the directory containing the Driver Manager to use is in the library search path environment variable. See [System and Setup Requirements](#) (on page 10) for more information.

- b. Change the directory to the staging directory:

```
cd /RelStage
```

- c. Do one of the following:

- If you have a CD-ROM installation on UNIX, invoke the following installation script on the CD-ROM:

```
sh /cdrom/install.sh
```

where *cdrom* is the mount directory specified in the procedures in [Load the CD-ROM on the UNIX Client](#) (see page 14). For those operating systems with standard mount directory names, choose the appropriate name from the following:

- HP-UX: `/cdrom/install.sh`
- IBM AIX: `/cdrom/install.sh`
- Linux: `/mnt/cdrom/install.sh`
- Sun Solaris SPARC and Sun Solaris Intel x86:
`/cdrom/relativity12/install.sh`
- If you have an Electronic Product Delivery on the UNIX Server, invoke the following installation script in the installation components directory:

```
sh /InstallationComponentsDirectory/install.sh
```

- d. The installation script will display a message indicating the operating system on which it is running and a list of the products available to install. The script will then prompt for the directory of the product to install:

```
Please enter the directory name of the product to
install: [exit]
```

Enter the directory name **dclient** and proceed to Step 3.

Step 3: Answer the Installation Prompts

The installation script prompts you for all the information that it needs before beginning the actual installation of the Relativity Data Client. If there is a failure during the installation, the responses to these prompts will be presented as the defaults for the prompts when the script is started again. The defaults appear in the square brackets at the end of the prompt. Pressing the Return or Enter key at the prompt will result in the value within the square brackets being used as the response to the prompt.

Each prompt is discussed below in the order in which it appears.

a. Name of the installation file or the CD mount directory:

This prompt requests the name of the installation device containing the UNIX Data Client installation file. The installation script will locate the installation file in the directory containing the installation script. If there is an installation file in that directory, the name of that file will be presented as the default for this prompt. If you wish to specify a different installation file, enter the name of that file in response to this prompt. You may enter only the mount directory or the installation components directory in response to this prompt. In this case, the installation script will choose an installation file appropriate to the target operating system.

The default name, as appropriate for your UNIX system, is shown in the following list:

- HP-UX PA-RISC: `/cdrom/dserver/061/dclncpio`.
- HP-UX Itanium: `/cdrom/dserver/065/dclncpio`
- IBM AIX: `/cdrom/dserver/066/dclncpio`.
- Linux: `/mnt/cdrom/dserver/063/dclncpio`

- Sun Solaris SPARC:
`/cdrom/relativity12/dserver/056/dclncpio.`
- Sun Solaris Intel x86:
`/cdrom/relativity12/dserver/057/dclncpio.`
- Electronic Product Delivery on UNIX server:
`/InstallationComponentsDirectory/DServer/nnn/dclncpio`

b. Do you accept this license?

The Micro Focus license agreement prompt will be displayed via the UNIX command, **more**.

Please read this license agreement carefully. If you agree with the terms, enter **y**. Enter **n** to terminate the installation. There is no default.

c. Directory in which the Driver Manager Library files are installed [/usr/local/liant/lib]:

A Driver Manager must be present on the UNIX client in order to install the Data Client, and this prompt requests the name of the directory where the Library files for a previously installed Driver Manager were installed.

Enter the name of the directory for the Driver Manager Library files. The default is **/usr/local/liant/lib**.

d. Directory in which to install the Data Client [/usr/local/liant/lib]:

This prompt requests the name of the directory where the Data Client is to be installed.

Enter the name of the directory. The default is **/usr/local/liant/lib**.

e. /usr/local/liant/lib does not exist. Do you wish to create it? [y]:

This prompt does not appear if the directory specified for the Data Client installation directory (see Step 3d) already exists.

To create the directory, enter **y**. To specify a different directory, enter **n**.

f. Directory in which to install the Data Client utilities [/usr/local/liant/bin]:

This prompt requests the name of the directory to install the [RelClientAdmin utility](#) (see page 50), [RelDriverAdmin utility](#) (see page 60), and [RelClientTest utility](#) (see page 59) to manage local client data sources, manage local drivers, and verify the installation.

Enter the name of the directory in which to install these Data Client utilities. The default is **/usr/local/liant/bin**.

g. /usr/local/liant/bin does not exist. Do you wish to create it? [y]:

This prompt does not appear if the directory in which to install the RelClientAdmin, RelClientTest, and RelDriverAdmin utilities (see Step 3f) already exists.

To create the directory, enter **y**. To specify a different utility directory, enter **n**.

h. Do you wish to install the Data Server administration utility? [n]:

This prompt requests to install a [RelServerAdmin utility](#) (see page 35) to manage Data Server data sources. The Relativity Server Administrator utility needs to be

installed only on an Administrator's machine. It will be installed in the same directory as the Data Client utilities, which were specified in Step 3f.

Enter **y** to install this utility. Enter **n** not to install the utility. The default is **n**.

i. User name under which to install the Data Client [*CurrentUser*]:

This prompt requests the user name under which the Data Client is installed.

Enter the user name of the Data Client (for example, Relativity). The default is the current user.

j. Default Server's Network Name [*ServerName*]:

This prompt requests the network name of a Window or UNIX server machine on which a Relativity Data Server is running. This server will be the default server when creating new data sources.

Enter the network name of the desired machine or **none** not to create a default server. The default is **none**.

k. Default Server's Service Port [1583]:

This prompt appears only if the response to the Default Server's Network Name in Step 3j is any value other than **none**. This prompt requests the service port number of the Relativity Data Server that is running on the machine specified in Step 3j.

Enter the service port number of the Relativity Data Server. The default is **1583**.

I. When installation is finished, do you wish to remove the temporary files from /RelStage? [n]:

This prompt requests whether you want to clean up the temporary files that the Data Client installation placed in the staging directory. This will include the file that is storing the values entered in response to the installation prompts and the INSTALL script. These files are removed *only* following a successful installation.

To remove the temporary files, enter **y**. To cause the temporary files to remain, enter **n**. The default is **n**.

Step 4: Perform the Installation

The following messages may appear during the installation of the Relativity Data Client:

- **Creating directory X...Directory already exists, using existing directory.**
This message indicates that directory X, which was to be created, already exists.
- **Creating directory X...Success.**
This message indicates that directory X was successfully created.
- **Creating directory X...Failed to create directory.**
This message indicates that directory X was not created.
- **Cannot determine Operating System type. Please contact Customer Support.**
OS_NAME=name
OS_RELEASE=number
ARCH_TYPE=architecture

This message indicates that the installation cannot determine the current operating system, and that the installation may not be compatible with this operating system. Contact Micro Focus Customer Support with the information indicated by the *name*, *number*, and *architecture* fields.

- **Attempt to install Relativity Data Client for *ProductOperatingSystem* on *ActualOperatingSystem***

This message indicates that the installation was able to determine the current operating system (*ActualOperatingSystem*), and that it is not the correct operating system for the product (*ProductOperatingSystem*). Obtain the correct version of the Relativity Data Client for the operating system on which you are attempting the installation.

- **./install.sh must be run as root equivalent.**

This message indicates that the current user does not have sufficient privileges to install the Relativity Data Client.

- **/cdrom is not a file or directory.**

This message is in response to Step 3a and indicates that the value entered for that prompt is not a valid file or directory name. Enter either a valid filename, which will be treated as a Data Client installation file, or a directory name, which will be treated as a CD-ROM device mount directory or installation components directory.

- **Cannot find installation file using /cdrom**

This message indicates that the directory name entered for Step 3a does not contain the Data Client installation file.

- **Cannot access installation file.**

This message indicates that the installation file, which was either entered directly in Step 3a or located within the directory entered in Step 3a, cannot be opened. Before this message is displayed, another error message will be printed that indicates the source of the problem.

- **Installation does not contain the required files.**

This message indicates that the installation file, which was either entered directly in Step 3a or located within the directory entered in Step 3a, could be opened, but it did not contain the expected files within it. It is probably the wrong installation file for this installation script.

- **Please respond with y for yes or n for no.**

This message is in response to a prompt that requires a yes or no answer. Simply use the lower case first letter of the word in your response.

- **This installation will use the Driver Manager. If the installation fails with the message 'error loading ODBC library libiodbc.so', place the Driver Manager's Library directory into LD_LIBRARY_PATH and perform the installation again.**

This message indicates that a directory containing the Driver Managers Library was not specified in Step 3c. In this case, it is assumed that there is a Driver Manager already installed, and the directory containing the Driver Manager Library is already in the library directory search path environment variable (usually LD_LIBRARY_PATH). If this is not the case, the installation will fail and either the library directory search path must be corrected, or the directory name must be entered in response to Step 3c.

- **DirectoryName does not exist.**

This message is in response to Step 3c and indicates that *DirectoryName* given to that prompt does not exist.

- **DirectoryName does not contain Driver Manager Library files.**

This message is in response to Step 3c and indicates that *DirectoryName* exists, but does not contain the Driver Manager Library files. Only the unixODBC libraries, **libodbc.so** and **libodbcinst.so**, are searched for. (The iODBC installation usually creates symbolic links with these names to its **libiodbc.so** and **libiodbcinst.so** files.)

- **UserName is not a valid user name.**

This message is in response to Step 3i and indicates that *UserName* cannot be located in the **/etc/passwd** file.

- **???? is not a valid service port number.**

This message is in response to Step 3k and indicates that the service port number entered was not valid. The service port number must be greater than 0, and it must be a valid integer. If the number is not a valid integer, this message will be preceded by a system error message.

- **Beginning installation.**

This message indicates that the installation script is beginning installation of the Relativity Data Client.

- **Installing Data Client.**

This message precedes the execution of the **cpio** command that will read the Data Client's installation files from the installation device and place them into the installation directory. If the **cpio** command fails, a message indicating the source of the failure will appear instead, and the installation will terminate.

- **Installing Data Client utility programs.**

This message precedes the execution of the **cpio** command that will read the utility installation files from the installation device and place them into the installation directory. If the **cpio** command fails, a message indicating the source of the failure will appear instead, and the installation will terminate. The utility programs include the client administration utilities (RelClientAdmin, RelClientTest, and RelDriverAdmin) and the server administration utility (RelServerAdmin). For more information, see [Chapter 2: Utility Programs](#) (on page 33).

- **Installing Data Client in Driver Manager.**

This message indicates that the Relativity Client Driver Administrator utility program (RelDriverAdmin) is being executed to record the location of the Data Client's installation files with the Driver Manager.

- **Storing default Server Name ServerName**

This message indicates that the Relativity Client Data Source Administrator utility program (RelClientAdmin) is being executed to record the default server specified in prompts 3j and 3k.

- **Install was successful.**

This message indicates that the installation was successful.

- **In order to use the Data Client utility programs, add `/usr/local/liant/bin` to the PATH environment variable.**

This message is a reminder that it is necessary to change your PATH environment variable in order to execute the Data Client utility programs. The directory `/usr/local/liant/bin` is the name of the directory in which they were installed.

- **Files removed.**

This message indicates that, per your request, the temporary files in the staging directory have been removed.

Step 5: *Unload the Distribution Media*

This step removes the Data Client installation media from the hardware. Use any of the following options to unload the distribution media:

- a. If the installation involved a CD-ROM drive installed on the UNIX client, see [Unload the CD-ROM on the UNIX Client](#) (as described in the next topic).
- b. If the distribution of the media was via Software Download using UNIX GUNZIP TAR, remove the installation components directory with the following command:

```
rm -rf /InstallationComponentsDirectory
```

Unload the CD-ROM on the UNIX Client

Use this option to unload the distribution media if the Relativity Data Client for UNIX installation involved a CD-ROM drive installed on the UNIX client. Instructions for specific versions of UNIX are provided. Most modern UNIX machines have a graphical interface that can be used to unload a CD-ROM, and it is recommended to use that method. However, if was necessary to issue a command described in [Load the CD-ROM on the UNIX Client](#), then use the instructions below to unload the CD-ROM.

HP-UX and IBM AIX

The instructions for these platforms are identical:

1. Enter the following command:

```
umount /cdrom
```

where `/cdrom` is the mount directory used in the **mount** command.

2. Remove the installation media from the CD-ROM drive.

If you had to create the mount directory `/cdrom` for this installation, you may remove it at this time.

Linux

1. Enter the following command:

```
umount /mnt/cdrom
```

2. Remove the installation media from the CD-ROM drive.

Sun Solaris SPARC and Intel x86

1. Enter the following command:

```
eject cdrom
```

2. Remove the installation media from the CD-ROM drive.

Step 6: Remove the Staging Directory

You may now remove the staging directory from the UNIX client by entering:

```
cd ..
rm -rf /RelStage
```

Verifying Installation of the Relativity Data Client for UNIX

The procedure to verify communications between the Relativity Data Client and the Data Server consists the following tasks:

- [Configuring a Relativity Data Server data source from the UNIX client](#) (see below)
- [Configuring a Relativity Data Client data source on the UNIX client](#) (see page 24)
- [Testing the Relativity Data Client data source](#) (see page 25)

Configuring a Relativity Data Server Data Source from the UNIX Client

In order to configure a Relativity Data Server data source from the UNIX client, the [RelServerAdmin utility](#) (see page 35) must have been installed during installation. Note that if the Relativity Server Administrator utility was installed on a different

machine and the server data source (named Verify) has already been configured, then this step may be omitted and you may proceed to [Configuring a Relativity Data Client Data Source on the UNIX Client](#) (see page 24).

To configure a Relativity Data Server data source from the UNIX client, log in as a user on the UNIX client that has the directory containing the Relativity Server Administrator utility in its PATH environment variable and enter the following command on the command line:

```
relserveradmin --add-data-source Verify
  --server-name ServerName
  --catalog samples/??/verify/verify.rcg
  --data-source-desc "Relativity C/S Data Source."
```

This command will create a data source named Verify on the Relativity Data Server specified by *ServerName*. The values for the command-line parameters are as follows:

- For the *ServerName* value, supply the network name of the UNIX or Windows server on which the Relativity Data Server is installed. If the Relativity Data Server is configured to run on a service port other than 1583, *ServerName* will have the form *NetworkName.ServicePort*. If the Relativity Data Server is running on the default server, as specified in steps 3j and 3k in [Step 3: Answer the Installation Prompts](#) (on page 17), --server-name *ServerName* may be omitted from the command.
- For the samples/??/verify/verify.rcg value, substitute one of the following for ??:
 - rm, if the Relativity Data Server supports RM/COBOL data files.
 - mf, if the Relativity Data Server supports Micro Focus COBOL data files.
- If the Relativity Data Server supports both types of COBOL files, it is necessary to provide one additional parameter on the command line:

--type ??

where the value of ?? is either **rm** or **mf**, depending on the desired COBOL product. The value of ?? in this parameter must match the value of ?? in samples/??/verify/verify.rcg, as described above.

Note A valid data source name must have a length within the range of 1 through 32 characters. The characters [] { } () , ; * = ! @ \ must not appear in a data source name. The data source name must also begin with a letter.

Tip It is helpful to use the same name for the Data Client and the Data Server data sources that will be associated with one another.

Configuring a Relativity Data Client Data Source on the UNIX Client

To configure a Relativity Data Client data source on the UNIX client, log in as a user on the UNIX client that has the directory containing the Relativity Client Data Source Administrator utility program (RelClientAdmin) in its PATH environment variable, the directory containing the Driver Manager in the library search environment variable,

and the appropriate permissions to modify the Driver Manager's data source configuration file, **odbc.ini**, and enter the following command on the command line:

```
relclientadmin --add-data-source Verify
    --server-name ServerName
    --server-data-source-name Verify
    --data-source-desc "Relativity C/S Data Source."
```

This command will create a data source named Verify on the UNIX client and associate with a server data source named Verify on the Relativity Data Server specified by *ServerName*. The values for the command-line parameters are as follows:

- For the *ServerName* value, supply the network name of the UNIX or Windows server on which the Relativity Data Server is installed. If the Relativity Data Server was configured to run on a service port other than 1583, *ServerName* will have the form *NetworkName.ServicePort*. If the Relativity Data Server is running on the default server, as specified in steps 3j and 3k in [Step 3: Answer the Installation Prompts](#) (see page 17), --server-name *ServerName* may be omitted from the command.

Note A valid data source name must have a length within the range of 1 through 32 characters. The characters [] { } () , ; * = ! @ \ must not appear in a data source name. The data source name must also begin with a letter.

Tip It is helpful to use the same name for the Data Client and the Data Server (see Step 3 on page 24) data sources that will be associated with one another.

Testing the Relativity Data Client Data Source

1. To test a Relativity Data Client data source on the UNIX client, Log in as a user on the UNIX client that has the directory containing the Relativity Data Client Data Source test utility in its PATH environment variable, and the directory containing the Driver Manager Library in the library search environment variable.
2. Enter the following command on the command line:

```
relclienttest -d Verify -u sales -s "select * from backorder"
```

where Verify is the name of the data source, as described in [Configuring a Relativity Data Client Data Source on the UNIX Client](#) (on page 24).

A list of rows from the BackOrder table is displayed.

Removing the Relativity Data Client for UNIX

The Relativity Data Client for UNIX program can be removed from the UNIX client on which it was installed. This may be necessary if the Data Client is to be moved to a

different UNIX client machine, or if a new release of the Data Client is to be installed on the same UNIX client machine.

To remove the Relativity Data Client from the UNIX client:

1. Log in as root.
2. Add the directory containing the Relativity Data Client Data Source Administrator utility in the PATH environment variable.
3. Change directory to the
4. Invoke the uninstall script to remove the Relativity Data Client.

```
relclientuninstall.sh
```

This command will remove the files installed for the Relativity Data Client.

Customizing the Relativity Data Client for UNIX Installation

You may customize the installation of the Relativity Data Client for UNIX to install your application's client data sources. You also may predefine answers to the installation prompts and change the installation defaults. This section discusses the various ways you can customize the installation process, including:

- [Formatting the relativity.ini definition file](#) (see page 26)
- [Creating a media image directory](#) (see page 27)
- [Unpacking the Data Client installation media](#) (see page 27)
- [Installing server definitions](#) (see page 28)
- [Installing predefined data sources](#) (see page 28)
- [Bypassing installation prompts](#) (see page 30)
- [Overriding installation prompts defaults](#) (see page 30)
- [Creating new installation media](#) (see page 31)

Note The first, second, and last procedures are required if you choose any of the other options to customize the Data Client installation process.

Formatting the relativity.ini Definition File

The core of customizing the Relativity Data Client for UNIX installation is the definition file, **relativity.ini**. When this file is present in the installation media, it is consulted for server definitions, data source definitions, predefined answers to installation prompts, and installation defaults.

This file is a standard text file, with new line characters terminating each line. Lines are grouped into sections. Each section begins with a section name, which is

enclosed in square brackets, “[]”, with the left square bracket at the beginning of the line. Section names may contain spaces. Each section ends with a blank line.

Each line of a section contains keyword value pair with the format:

```
Keyword=Value
```

A *keyword* must be at the start of a line, and it may not contain a space or an equal sign, “=”. Duplicate keywords within the same section are not allowed.

No spaces are allowed before or after the equal delimiter.

The *value* may not contain an equal sign, but may contain spaces, and it extends to the end of the line.

The following example illustrates the format of a **relativity.ini** definition file:

```
[Section Name 1]
FirstKeyword=First Value
SecondKeyword=Second Value

[Section Name 2]
AKeyword=A Value
AnotherKeyword=Another Value
```

Creating a Media Image Directory

Use the following command to create an empty directory in which to place the installation media’s contents:

```
mkdir /RelMedia
```

To make this directory your current directory, enter:

```
cd /RelMedia
```

You may change RelMedia to be any appropriate directory.

Unpacking the Data Client Installation Media

In the media image directory, unload files from the installation media into the directory using commands such as the following:

```
cpio -icBvdum </cdrom/dclient/nnn/dclncpio*
```

Change */cdrom* to be the name of the device that holds the Relativity Data Client for UNIX distribution media. See [Step 3: Answer the Installation Prompts](#) (on page 17). Change *nnn* to be the proper directory for the operating system on which the Data Client is to be installed from the set of operating system codes below:

- - 061 - HP-UX for PA-RISC
- - 065 - HP-UX for Itanium
- - 066 - IBM AIX
- - 070 - Large File Linux (Intel)
- - 072 - Solaris Intel x86
- - 073 - Solaris SPARC

Installing Server Definitions

If you wish to predefine server definitions on the UNIX client, add a section named [Server Definitions] to the **relativity.ini** file in the media image directory. If this section is present within the **relativity.ini** file, it will cause the servers defined within this section to be defined automatically on the UNIX client.

The keyword value pairs within the [Server Definitions] section have the format:

```
ServerNetworkName . ServicePort=
```

where:

- *ServerNetworkName* is the name of the UNIX server on the local network.
- *ServicePort* is the service port number of the Relativity Data Server that is running on the machine *ServerNetworkName*. If this entry is missing, the service port is assumed to be 1583.

If Step 3j and 3k specify no default server, the server definition that is defined by the first keyword value pair is treated as the default server name.

The following is an example of a [Server Definitions] section:

```
[Server Definitions]
UNIXServer.1583=
WindowsServer.1583=
```

Installing Predefined Data Sources

If you wish to predefine data sources on the UNIX client, add a section named [ODBC Data Sources] to the **relativity.ini** file definition.

The keyword value pairs within the [ODBC Data Sources] section have the following format:

DataSourceSection=

where:

- *DataSourceSection* is the name of a section within the **relativity.ini** file that contains the details of the data source to create.

For each data source section specified in [ODBC Data Sources] by *DataSourceSection*, there must be a separate section in the **relativity.ini** with that name. The keyword value pairs within each of these sections define the actual data sources.

The recognized keywords are:

- **ClientDataSource**. The value of this keyword is the name of the client data source to create.
- **Server**. The value of this keyword is the name of the UNIX server to which the client data source is associated. This keyword is optional. If it is not present, the client data source is associated with the default server. The format of this entry is *ServerNetworkName.ServicePortNumber*. *ServicePortNumber* is optional and the default is 1583.
- **ServerDataSource**. The value of this keyword is the name of the server data source on the UNIX server. This keyword is required.
- **Description**. The value of this keyword is the description to give to the client data source. This keyword is optional.
- **CharacterSet**. The value of this keyword is the character set number to give to the client data source. This keyword is optional.

The following is an example of defining data sources within the **relativity.ini**:

```
[ODBC Data Sources]
FirstClientDataSource=
SecondClientDataSource=

[FirstClientDataSource]
ClientDataSource=First Client Data Source
Server=UNIXServer.1583
ServerDataSource=UNIXServer DataSourceName
Description=Data Source on UNIX Server

[SecondClientDataSource]
ClientDataSource=Second Client Data Source
Server=WindowsServer
ServerDataSource=WindowsServer DataSourceName
Description=Data Source on Windows Server
```

This example creates two client data sources: FirstClientDataSource and SecondClientDataSource. The first client data source is to a server data source named UNIXServer DataSourceName on the machine with the network name UNIXServer. The second data source is to a server data source named WindowsServer DataSourceName on the machine with the network name WindowsServer.

Bypassing Installation Prompts

If you wish to prevent the installation prompts from appearing, add a section named [Parameters] to the **relativity.ini** file. Each keyword in this section corresponds to a particular prompt in [Step 3: Answer the Installation Prompts](#) (see page 17). The value of each keyword supplies the answer to the prompt.

The supported keywords are:

- **OWNER.** This keyword contains the user name with which the Data Client is installed. Installed files will be owned by this user name. This keyword corresponds to Step 3i.
- **INSTALL_DIR.** This keyword contains the name of the directory in which the Data Client's shared library is to be installed. This keyword corresponds to Step 3d.
- **INSTALL_CREATE.** This keyword contains **y** if the directory indicated by INSTALL_DIR can be created. This keyword corresponds to Step 3e.
- **DM_DIR_LIB.** This keyword contains the directory in which the Driver Manager Library is already installed. This keyword corresponds to Step 3c.
- **UTIL_DIR.** This keyword contains the directory in which the client data source administration and server administration utilities will be installed. This keyword corresponds to Step 3f.
- **UTIL_CREATE.** This keyword contains **y** if the directory indicated by UTIL_DIR can be created. This keyword corresponds to Step 3g.
- **SRVADMIN_UTIL.** This keyword contains **y** if the Relativity Server Administrator utility (RelServerAdmin) is to be installed. This keyword corresponds to Step 3h.
- **SRV_NAME.** This keyword contains the name of the default server. This keyword corresponds to Step 3j.
- **SRV_PORT.** This keyword contains the service port number of the Relativity Data Server running on the machine indicated by SRV_NAME. This keyword corresponds to Step 3k.
- **REMOVESRC.** This keyword contains **y** if the temporary files created by the installation are to be removed following a successful installation. This keyword corresponds to Step 3l.

Overriding Installation Prompts Defaults

If you wish to change the default values for installation prompts, add a section named [Defaults] to the **relativity.ini** file. Each keyword in this section corresponds to a particular prompt in [Step 3: Answer the Installation Prompts](#) (see page 17). The value of each keyword supplies the default answer to the prompt.

The supported keywords are:

- **DEFAULT_OWNER.** This keyword contains the default user name with which the Data Client is installed. This keyword corresponds to Step 3i.
- **DEFAULT_INSTALL_DIR.** This keyword contains the default name of the directory in which the Data Client's shared library is to be installed. This keyword corresponds to Step 3d.

- **DEFAULT_INSTALL_CREATE.** This keyword contains the default value for Step 3e, which indicates whether the Data Client's installation directory can be created.
- **DEFAULT_DM_DIR_LIB.** This keyword contains the default directory in which the Driver Manager is installed. This keyword corresponds to Step 3c.
- **DEFAULT_UTIL_DIR.** This keyword contains the default directory in which the client data source administration and server administration utilities will be installed. This keyword corresponds to Step 3f.
- **DEFAULT_UTIL_CREATE.** This keyword contains the default value for Step 3g, which indicates whether the directory containing the administration utilities can be created.
- **DEFAULT_SRVADMIN_UTIL.** This keyword contains the default for Step 3h, which indicates whether the Relativity Server Administrator utility (RelServerAdmin) is to be installed.
- **DEFAULT_SRV_NAME.** This keyword contains the default name of the default server. This keyword corresponds to Step 3j.
- **DEFAULT_SRV_PORT.** This keyword contains the default service port number of the default Relativity Data Server. This keyword corresponds to Step 3k.
- **DEFAULT_REMOVE_SRC.** This keyword contains the default for Step 3l, which indicates whether the temporary files created by the installation are to be removed following a successful installation.

Creating New Installation Media

Once the media image directory contains the modified **relativity.ini**, new installation media can be created with the following **cpio** command.

```
find * -print | cpio -ocBv >dclncpio
```

The resulting **dclncpio** file will then need to be placed on a CD-ROM. Use the ISO 9660 file system and CD-ROM mode 1 for greatest portability.

Chapter 2: Utility Programs

Several utility programs are supplied with the Relativity Data Client for UNIX to facilitate the creation of client and server data sources, the testing of the connection between the UNIX client and the server machine running the Relativity Data Server, and maintaining the drivers.

They include the following:

- [RelServerAdmin utility](#) (see page 35). Use the Relativity Server Administrator utility program (**relserveradmin**) to manage data sources on the server and store server definitions on the UNIX client.
- [RelClientAdmin utility](#) (see page 50). Use the Relativity Client Data Source Administrator utility program (**relclientadmin**) to manage client data sources and server definitions on the UNIX client.
- [RelClientTest utility](#) (see page 59). Use the Relativity Client Data Source Test utility program (**relclienttest**) to test a client data source and its connection to a server data source, and to issue simple SQL statements to the Relativity Data Server.
- [RelDriverAdmin utility](#) (see page 60). Use the Relativity Client Driver Administrator utility program (**reldriveradmin**) to maintain the Relativity Data Client driver on a UNIX client. This utility is primarily used during the install and uninstall processes of the Relativity Data Client.

Command-Line Interface

The utility programs that are supplied with the Relativity Data Client for UNIX employ a command-line interface. Technically, each element typed on the command line is a parameter; however, the following terminology is used in order to distinguish among the various types of parameters:

- *programname* refers to the name of the utility program; for example, `relserveradmin`, `relclientadmin`, `relclienttest`, and `reldriveradmin`.

Note On the command line, all utility program names must be entered in lowercase characters. However, this document uses a mixed case convention when referring to the abbreviated names of the utilities. For example, the shortened name of the Relativity Server Administrator utility is `RelServerAdmin` utility.

- *command* refers to the administrative function to be performed by the utility; for example, --add-data-source.
- *parameter* refers to additional information associated with a command; for example, --server-name *ServerName*.

Each of the utility programs is invoked by typing its program name on the command line, followed by a command or one or more parameters. Each command and parameter supported by the utility program has two forms: a verbose form, which is introduced by two dashes, and a terse form, which is introduced by a single dash. Both forms may be used on the same command line.

Most, but not all, parameters have values that are associated with them. The meanings of these values are discussed below:

- *ServerName* identifies a Relativity Data Server on the network. *ServerName* is composed of two components: *NetworkName* and *ServicePort*.
 - *NetworkName* is the name of the UNIX or Windows server on the network. A *NetworkName* is composed of alphanumeric characters.
 - *ServicePort* is the TCP/IP service port that a Relativity Data Server running on the server *NetworkName* is configured to use. A *ServicePort* is an unsigned decimal number. The default for *ServicePort* is 1583.

The format for *ServerName* is *NetworkName*.*ServicePort*. When *ServicePort* is omitted, the delimiting period should be omitted as well.

- *FileName* specifies a filename, in the format for the operating system on which the Relativity Data Server is running.
- *Text* indicates one or more words of text. If *Text* contains spaces, delimit *Text* with quotation marks. See the individual parameters under each command for the meaning of the *Text* value.
- *UnsignedInteger* specifies a zero or positive decimal number.
- *SignedInteger* specifies a decimal number, which may contain a leading dash to indicate a negative number.

Conventions

In this chapter, the following conventions for using command-line parameters are observed:

1. Parameters or values that are optional are enclosed in square brackets, “[]”.
2. Parameters or values that are required, and where only one may appear, are enclosed in braces, { }, with the individual items in the list separated by vertical bars, “ | ”.
3. Each parameter is described using its verbose form, with the terse form following in parentheses. Many, but not all, of the terse forms are merely the first letter of each word of the verbose form.

Displaying Help

If you supply the parameter --help (-h) in every command, the utility requests and displays additional information and documentation on the command and its parameters. If you supply the --help parameter without a command, only a list of the supported commands is displayed.

The syntax of this command is as follows:

```
programname [command] --help
```

RelServerAdmin Utility

The Relativity Server Administrator utility program, **relserveradmin**, supports many administrative functions on the Relativity Data Server and can be used to maintain data sources on a Relativity Data Server. This utility can also be used to store the server definitions (server network names and service port numbers) of Relativity Data Servers on the local client machine, so that the [RelClientAdmin utility](#) (see page 50), can display the servers in its list.

The following sections describe how to use the commands and associated parameters for this utility, and the additional [RM/COBOL file manager configuration parameters](#) (see page 48) and [Micro Focus COBOL file manager configuration parameters](#) (see page 48) you may need.

Using the RelServerAdmin Utility Commands and Parameters

Each administrative function, or *command*, performed by the RelServerAdmin utility is addressed separately, in order to document clearly the additional parameters that the command supports.

The following table lists the commands supported by the RelServerAdmin utility.

Verbose	Terse	Description
--add-data-source	-ads	Adds a new server data source.
--add-server	-as	Adds a data server definition.
--list-character-sets	-lcs	Lists all of the character sets that a data server supports.
--list-data-sources	-lds	Lists all existing server data sources.
--list-servers	-ls	Lists all data server definitions.
--modify-data-source	-mds	Modifies an existing server data source.
--remove-data-source	-rds	Removes an existing server data source.
--remove-server	-rs	Removes a data server definition.

--show-data-source	-sds	Shows an existing server data source definition.
--show-server-status	-sss	Shows a data server's current status and lists all of its current connections.
--shutdown-server	-ss	Shuts down a data server.
--terminate-server-connection	-tsc	Terminates a current connection on a data server.

Adding a Data Source

A data source contains information necessary for the Relativity Data Server to open a data source requested by a Relativity Data Client. The --add-data-source command creates a new data source on the Relativity Data Server.

To add a new data source on the Relativity Data Server, use the following command:

```
relserveradmin --add-data-source Text
  [--server-name ServerName]
  [--catalog FileName]
  [--type {RM|MF}]
  [--data-source-desc Text]
  [--create]
  [--query-plan {Y|N|C}]
  [--query-plan-file FileName]
  [--character-set SignedInteger]
  [--pool UnsignedInteger]
  [--file-process-count UnsignedInteger]
  [--cat-format {IDX4|IDX8|DEFAULT|BTRIEVE|
    CISAM|LEVELII|UnsignedInteger}]
  [--new-table-format {IDX4|IDX8|DEFAULT|BTRIEVE|
    CISAM|LEVELII|UnsignedInteger}]
  [--data-compress UnsignedInteger]
  [--sparse-byte UnsignedInteger]
  [--trailing-spaces {Y|N}]
  [--leading-chars {Y|N}]
  [--compress-duplicate-keys {Y|N}]
```

where:

- The value of the --add-data-source (-ads) command specifies the name of the new data source.
- The value of the --server-name (-s) parameter indicates the Relativity Data Server on which to add the data source.
- The value of the --catalog (-c) parameter specifies the filename of the data source's catalog.
- The value of the --type (-t) parameter specifies the type of files to be accessed by the data source. The value **RM** indicates that RM/COBOL files are to be accessed. The value of **MF** indicates that Micro Focus COBOL files are to be accessed. This parameter is required only if the Relativity Data Server is running on a Windows server, and the Data Server has been installed to manage both types. Otherwise, the value of the type parameter must match the type of files that the Relativity Data Server can access.

- The value of the --data-source-desc (-desc) parameter specifies the description to give to the new data source.
- The presence of the --create (-cr) parameter specifies that the new data source's catalog file should be created.
- The value of the --query-plan (-qp) parameter specifies whether the new data source should generate query plans. The value of **Y** will cause query plans always to be generated. The value of **N** will cause query plans never to be generated. The value of **C** will allow the generation of query plans to be controlled by the --query-plan parameter of the client data source (see page 51).
- The value of the --query-plan-file (-qpf) parameter specifies the filename to receive generated query plans. This parameter is required only if the value of the --query-plan parameter is **Y** or **C**.
- The value of the --character-set (-cs) parameter specifies the number of the character set to use with the new data source. If this parameter is absent, the default character set will be used.
- The value of the --pool (-p) parameter is for use only with RM/COBOL files. It specifies the number of 1024 byte pages that the RM/COBOL file manager should allocate in its buffer pool. This parameter can have the value from 16 to 649. The default is **256**. For more information, see [Buffer Pool](#) (on page 48).
- The value of the --file-process-count (-fpc) parameter is for use only with RM/COBOL files. It specifies the maximum number of processes—including RM/COBOL run units—that can have a file opened at the same time. This parameter can have the value from 8 to 4096. The default is **1024**. For more information, see [File Process Count](#) (on page 48).
- The value of the --cat-format (-cf) parameter is for use only with Micro Focus COBOL files. It specifies the type of Micro Focus COBOL file that should be used when creating a new catalog file. The valid values are **DEFAULT**, **BTRIEVE**, **CISAM**, **LEVELII**, **IDX4**, and **IDX8**. For more information, see [Catalog Format](#) (on page 49).
- The value of the --new-table-format (-ntf) parameter is for use only with Micro Focus COBOL files. It specifies the type of Micro Focus COBOL file that should be used when creating a new file because of a CREATE TABLE SQL statement. The valid values are **DEFAULT**, **BTRIEVE**, **CISAM**, **LEVELII**, **IDX4**, and **IDX8**. For more information, see [New File Format](#) (on page 49).
- The value of the --data-compress (-dc) parameter is for use only with Micro Focus COBOL files. It specifies the decimal value of the data compression algorithm to be configured for a new data file created as the result of a CREATE TABLE SQL statement. For more information, see [Data Compression](#) (on page 49).
- The value of the --sparse-byte (-sb) parameter is for use only with Micro Focus COBOL files. It specifies the decimal value of the sparse byte to be configured for key compression in a new data file created as the result of a CREATE TABLE SQL statement. For more information, see [Key Compression – Sparse Byte](#) (on page 50).
- The value of the --trailing-spaces (-ts) parameter is for use only with Micro Focus COBOL files. It specifies whether trailing spaces are to be compressed in keys in a new data file created as the result of a CREATE TABLE SQL statement. For more information, see [Key Compression – Trailing Spaces](#) (on page 49).

- The value of the --leading-chars (-lc) parameter is for use only with Micro Focus COBOL files. It specifies whether leading characters are to be compressed in keys when creating a new file because of a CREATE TABLE SQL statement. For more information, see [Key Compression – Leading Characters](#) (on page 49).
- The value of the --compress-duplicate-keys (-cdk) parameter is for use only with Micro Focus COBOL files. It specifies whether duplicate keys are to be compressed in a new data file created as the result of a CREATE TABLE SQL statement. For more information, see [Key Compression – Duplicates](#) (on page 50).

Example

```
$ relserveradmin --add-data-source Verify
  --server-name aix43
  --catalog samples/verify/rm/verify.rcg

Data source 'Verify' added on aix43.
```

Adding a Server Definition

A server definition is merely a *ServerName* that has been recorded using this command. The Relativity Server Administrator utility can maintain a set of server definitions for the current user.

Note The set of server definitions is for a future enhancement of the Relativity Server Administrator utility. This set of definitions and this command are of limited use at this time. However, this command's --default parameter is very helpful, particularly if you are dealing with only one Relativity Data Server. Setting a *ServerName* as the default will eliminate the need to supply the --server-name parameter in other commands.

To add a new server definition, use the following command:

```
relserveradmin --add-server ServerName [--default]
```

where:

- The value of the --add-server (-as) command, *ServerName*, is the network name and service port of the Relativity Data Server to add to the list of server definitions.
- The presence of the --default (-d) parameter indicates that *ServerName* is to be the default for the --server-name parameter in other commands.

Example

```
$ relserveradmin --add-server aix53.1583 --default

Created Relativity data server definition for aix53.1583.
```

Listing Character Sets

A character set is an interpretation of the bytes within a data file that represent characters, typically the items with a picture clause of X. Each data file has a character set associated with it, and this information is stored as a fixed attribute within a Relativity database. Relativity is capable of translating these characters from the character set of the data file to the character set of the ODBC application. This command supplies a list of the character sets for which the data server can supply translation.

To display a list of the character sets that a Relativity Data Server supports, use the following command:

```
relserveradmin --list-character-sets [ServerName]
[--server-name ServerName]
```

where:

- The value of the --list-character-sets (-lcs) command indicates the Relativity Data Server for which to list character sets.
- The value of the --server-name (-s) parameter may also be used to indicate the Relativity Data Server for which to list character sets.

Example

The number to the left of each character set name is the identifier of the character set. Use this value in the --character-set parameter of the --add-data-source command and the --modify-data-source command.

```
$ relserveradmin --list-character-sets aix53

Character sets on data server aix53.
-28. Hebrew 7-bit Old Code
-25. MF EBCDIC (UNIX)
-24. MF EBCDIC (DOS)
-23. RM EBCDIC
-22. IBM-850
-21. SCO Latin 1
-20. STANDARD-2
-16. ISO 8859-16
-15. ISO 8859-15
-14. ISO 8859-14
-13. ISO 8859-13
-11. ISO 8859-11
-10. ISO 8859-10
-9. ISO 8859-9
-8. ISO 8859-8
-7. ISO 8859-7
-6. ISO 8859-6
-5. ISO 8859-5
-4. ISO 8859-4
-3. ISO 8859-3
-2. ISO 8859-2
-1. ISO 8859-1
```

```
37. EBCDIC US Canada
.
.
.
1250. Windows Latin 2
1251. Windows Cyrillic
1252. Windows Latin 1
1253. Windows Greek
1254. Windows Latin 5
1255. Windows Hebrew
1256. Windows Arabic
1257. Windows Baltic Rim
1258. Windows 1258
```

Note Those character sets that represent Windows codepages have a positive value the same as their codepage number. Negative numbers represents all other character sets.

Listing Data Sources

A data source name is an identifier that ODBC applications use to access a Relativity database. This list of data source names represents the data sources on the Relativity Data Server to which a Relativity Data Client data source may be associated.

To display a list of the data source names on a Relativity Data Server, use the following command:

```
relserveradmin --list-data-sources [ServerName]
[--server-name ServerName]
```

where:

- The value of the --list-data-sources (-lds) command indicates the Relativity Data Server for which to list data sources.
- The value of the --server-name (-s) parameter may also be used to indicate the Relativity Data Server for which the data sources are to be listed.

Example

```
$ relserveradmin --list-data-sources aix53

Data sources on data server aix53.
Shirt-3
Verify
```

Listing Server Definitions

A server definition is simply a *ServerName* that has been recorded using the --add-server command. The RelServerAdmin utility can maintain a set of server definitions for the current user.

Note The set of server definitions is for a future enhancement of the Relativity Server Administrator utility. This set of definitions and this command are of limited use at this time.

To display a list of the current set of server definitions defined on the UNIX client, use the following command:

```
relserveradmin --list-servers
```

Example

```
$ relserveradmin --list-servers

Relativity data servers defined on this client.
tcp:aix43.1583
tcp:aix43.1584
tcp:hp825.1584
tcp:sco5.1583
tcp:ncr3000.1583
tcp:sunx86.1583
tcp:uw711.1583
tcp:valhalla.1583
tcp:valhalla.1584
```

Modifying a Data Source

A data source contains information necessary for the Relativity Data Server to open a data source requested by a Relativity Data Client. This command alters an existing data source on the data server.

To modify a data source on a Relativity Data Server, use the following command. Note that parameter values that are not specified in the command retain their previous value in the data source.

```

relserveradmin --modify-data-source Text
  [--server-name ServerName]
  [--new-data-source-name Text]
  [--catalog FileName]
  [--type {RM|MF}]
  [--data-source-desc Text]
  [--create]
  [--query-plan {Y|N|C}]
  [--query-plan-file FileName]
  [--character-set SignedInteger]
  [-pool UnsignedInteger]
  [--file-process-count UnsignedInteger]
  [--cat-format {IDX4|IDX8|DEFAULT|BTRIEVE|
    CISAM|LEVELII|UnsignedInteger}]
  [--new-table-format {IDX4|IDX8|DEFAULT|BTRIEVE|
    CISAM|LEVELII|UnsignedInteger}]
  [--data-compress UnsignedInteger]
  [--sparse-byte UnsignedInteger]
  [--trailing-spaces {Y|N}]
  [--leading-chars {Y|N}]
  [--compress-duplicate-keys {Y|N}]

```

where:

- The value of the --modify-data-source (-mds) command specifies the current name of the data source.
- The value of the --server-name (-s) parameter indicates the Relativity Data Server on which to modify the data source.
- The value of the --new-data-source-name (-ndsn) parameter specifies the new name of the data source.
- The value of the --catalog (-c) parameter specifies the filename of the data source's catalog.
- The value of the --type (-t) parameter specifies the type of files to be accessed by the data source. The value of **RM** indicates that RM/COBOL files are to be accessed. The value of **MF** indicates that Micro Focus COBOL files are to be accessed. This parameter, if specified, must match the --type parameter originally used to create the data source.
- The value of the --data-source-desc (-desc) parameter specifies the description to give to the data source.
- The presence of the --create (-cr) parameter specifies that the data source's catalog file should be created.
- The value of the --query-plan (-qp) parameter specifies whether the data source should generate query plans. The value of **Y** will cause query plans always to be generated. The value of **N** will cause query plans never to be generated. The value of **C** will allow the generation of query plans to be controlled by the --query-plan parameter of the client data source (see page 51).
- The value of the --query-plan-file (-qpf) parameter specifies the filename to receive generated query plans. This parameter is required only if the value of the --query-plan parameter is **Y** or **C**.

- The value of the --character-set (-cs) parameter specifies the number of the character set to use with the data source.
- The value of the --pool (-p) parameter is for use only with RM/COBOL files. It specifies the number of 1024 byte pages that the RM/COBOL file manager should allocate in its buffer pool. This parameter can have the value from 16 to 649. For more information, see [Buffer Pool](#) (on page 48).
- The value of the --file-process-count (-fpc) parameter is for use only with RM/COBOL files. It specifies the maximum number of processes, including RM/COBOL run units, which can have a file opened at the same time. This parameter can have a value from 8 to 4096. For more information, see [File Process Count](#) (on page 48).
- The value of the --cat-format (-cf) parameter is for use only with Micro Focus COBOL files. It specifies the type of Micro Focus COBOL file that should be used when creating a new catalog file. The valid values are **DEFAULT**, **BTRIEVE**, **CISAM**, **LEVELII**, **IDX4**, and **IDX8**. For more information, see [Catalog Format](#) (on page 49).
- The value of the --new-table-format (-ntf) parameter is for use only with Micro Focus COBOL files. It specifies the type of Micro Focus COBOL file that should be used when creating a new data file as a result of the CREATE TABLE SQL statement. The valid values are **DEFAULT**, **BTRIEVE**, **CISAM**, **LEVELII**, **IDX4**, and **IDX8**. For more information, see [New File Format](#) (on page 49).
- The value of the --data-compress (-dc) parameter is for use only with Micro Focus COBOL files. It specifies the decimal value of the data compression algorithm to be configured for a new data file created as the result of the CREATE TABLE SQL statement. For more information, see [Data Compression](#) (on page 49).
- The value of the --sparse-byte (-sb) parameter is for use only with Micro Focus COBOL files. It specifies the decimal value of the sparse byte to be configured for key compression in a new data file created as a result of the CREATE TABLE SQL statement. For more information, see [Key Compression – Sparse Byte](#) (on page 50).
- The value of the --trailing-spaces (-ts) parameter is for use only with Micro Focus COBOL files. It specifies whether trailing spaces are to be compressed in keys in a new data file created as a result of the CREATE TABLE SQL statement. For more information, see [Key Compression – Trailing Spaces](#) (on page 49).
- The value of the --leading-chars (-lc) parameter is for use only with Micro Focus COBOL files. It specifies whether leading characters are to be compressed in keys in a new data file created as a result of the CREATE TABLE SQL statement. More information is available in [Key Compression – Leading Characters](#) (on page 49).
- The value of the --compress-duplicate-keys (-cdk) parameter is for use only with Micro Focus COBOL files. It specifies whether duplicate keys are to be compressed in a new data file created as a result of the CREATE TABLE SQL statement. For more information, see [Key Compression – Duplicates](#) (on page 50).

Example

```
$ relserveradmin --modify-data-source Verify  
    --server-name aix53 --new-data-source-name "New Verify"  
  
Data source 'Verify' modified on server aix53.
```

Removing a Data Source

To remove a data source on a Relativity Data Server, use the following command:

```
relserveradmin --remove-data-source Text  
[--server-name ServerName]
```

where:

- The value of the --remove-data-source (-rds) command specifies the name of the data source to remove.
- The value of the --server-name (-s) parameter indicates the Relativity Data Server from which to remove the data source.

Example

```
$ relserveradmin --remove-data-source "New Verify"  
    --server-name aix53  
  
Removed data source 'New Verify' from aix53.
```

Removing a Server Definition

A server definition is merely a *ServerName* that has been recorded using the --add-server command. The RelServerAdmin utility can maintain a set of server definitions for the current user.

Note The set of server definitions is for a future enhancement of the Relativity Server Administrator utility. This set of definitions and this command are of limited use at this time.

To remove a server definition, use the following command:

```
relserveradmin --remove-server ServerName
```

where:

- The value of the --remove-server (-rs) command, *ServerName*, is the network name and service port of the Relativity Data Server to remove from the list of server definitions.

Example

```
$ relserveradmin --remove-server aix53.1583
Relativity data server definition for aix53.1583 removed.
```

Showing a Data Source

A data source contains information necessary for the Relativity Data Server to open a data source requested by a Relativity Data Client. This command shows the current contents of the data source.

To display a data source on a Relativity Data Server, use the following command:

```
relserveradmin --show-data-source Text
[--server-name ServerName] [-env]
```

where:

- The value of the --show-data-source (-sds) command specifies the name of the data source to show.
- The value of the --server-name (-s) parameter indicates the Relativity Data Server for which to show the data source.
- The presence of the --env (-e) parameter specifies that the information from the data source be printed to standard output in the form of Bourne shell environment variable assignments. The purpose is to emit the information in a form that will be usable in a script to manipulate or copy an existing data source. The environment variable names and their corresponding parameter options are given in the following table:

Variable Name	Parameter
DS_CATALOG	--catalog
DS_TYPE	--type
DS_DESC	--data-source-desc
DS_QP	--query-plan
DS_QPF	--query-plan-file
DS_CS	--character-set
DS_POOL	--pool
DS_FPC	--file-process-count
DS_CATF	--cat-format
DS_NEWF	--new-table-format
DS_DC	--data-compress
DS_SB	--sparse-byte
DS_TS	--trailing-spaces
DS_LC	--leading-chars

```
DS_DUP          --compress-duplicate-keys
```

Example

```
$ relserveradmin --show-data-source Shirt-3
--server-name aix53

Data source 'Shirt-3' on aix53:
DBQ=Shirt_3
Description=Sample Shirt-3 Data Source
Catalog=samples/rm/shirt-3/shirt3.rcg
FileMgr=RM
```

Showing the Status of a Data Server

A Relativity Data Server's status consists of several pieces of information, including when it started, the number of clients that are connected to it, the maximum number of clients that can connect to it, the number of connections that it is servicing, and the actual connections themselves. (Only version 6 Relativity Data Servers and later supply the number of clients and maximum number of clients status information.) The connection information consist of the ID of the UNIX or Windows process that is servicing the connection, the name of the client machine, the user name of client, and the name of ODBC application program. (Not all ODBC applications supply the application name.)

To show the status of a Relativity Data Server, and to display a list of connections it is currently servicing, use the following command.

```
relserveradmin --show-server-status [ServerName]
[--server-name ServerName]
```

where:

- The value of the --show-server-status (-sss) command indicates which Relativity Data Server's status to show.
- The value of the --server-name (-s) parameter may also be used to indicate which Relativity Data Server's status to show.

Example

```
$ relserveradmin --show-server-status aix43

Status of server aix43.
Server Start Time: Thu Jun 24 13:58:43 2004.
Current number of connections: 2.
Process ID Client Machine (User Name) Application
      28446 ncr3000 (db3 owner)      Microsoft Access for Windows
      28450 ncr3000 (db3 owner)      Unknown app
```

Shutting Down a Data Server

The --shutdown-server command will terminate a Relativity Data Server. This command has the same effect as executing the ./STOP script on the Relativity Data Server for UNIX or stopping the service on the Relativity Data Server for Windows.

Note If a Relativity Data Server for UNIX is configured to start automatically at machine boot, the --shutdown-server command will shut down the data server, but the UNIX operating system will automatically restart it.

To shut down or stop a running Relativity Data Server, use the following command:

```
relserveradmin --shutdown-server [ServerName]
  [--server-name ServerName]
  {--immediately | --gracefully}
```

where:

- The value of the --shutdown-server (-ss) command may also be used to indicate the Relativity Data Server to shut down.
- The value of the --server-name (-s) parameter may also be used to indicate the Relativity Data Server to shut down.
- The presence of the --immediately parameter indicates that the Relativity Data Server is to shut down immediately, summarily disconnecting existing client connections.
- The presence of the --gracefully parameter indicates that the Relativity Data Server is to refuse new connections and allow existing connections to disconnect normally, before terminating itself.

Example

```
$ relserveradmin --shutdown-server aix53 --gracefully
Server aix53 requested to shut down gracefully.
```

Terminating a Connection to a Data Server

Each client connection to a Relativity Data Server has a unique ID that can be used to identify the connection. This ID is supplied when terminating a client's connection.

Note The --terminate-server-connection command will not force the client connection to terminate. It will merely request that the connection be terminated. This request will be honored when the current request from the client is complete, or if the Relativity Data Server is idle waiting for the next request from the client. This command will not interrupt a current client request.

To terminate a client's connection to a Relativity Data Server, first use the --show-server-status command to determine the process ID of the connection to terminate, and then use the following command:

```
relserveradmin --terminate-server-connection  
UnsignedInteger  
[--server-name ServerName]
```

where:

- The value of the –terminate-server-connection (-tsc) command specifies the process ID of the connection to terminate.
- The value of the --server-name (-s) parameter indicates the Relativity Data Server on which to terminate a connection.

Example

```
$ relserveradmin --terminate-server-connection 28446  
--server-name aix43  
  
Terminated connection for process ID 28446.
```

RM/COBOL File Manager Configuration Parameters

This section explains the configuration parameters for access to RM/COBOL files in more depth. See the *RM/COBOL User's Guide* for more information.

Buffer Pool

This configuration parameter sets the size of the buffer pool to be used by the RM file manager for buffer allocation. Note that only the value specified for the first data source connection takes effect when a single application connects to multiple data sources. The value specifies an integer number of kilobytes (1024 bytes) of memory to be allocated for the buffer pool. A value of zero indicates that the default value of 256K bytes should be used. If specified, the value must be a decimal integer from 16 to 649.

File Process Count

This configuration parameter sets the maximum number of processes, including RM/COBOL run units, which can have a file open at the same time. It applies to all file organizations. For record and file locks to perform correctly, all processes opening a file must use the same file process count. The maximum value is 4096. The minimum value is 8. The default value is 1024.

Micro Focus COBOL File Manager Configuration Parameters

This section explains the configuration parameters for access to Micro Focus COBOL files. See the Micro Focus documentation for more information.

Catalog Format

This configuration parameter controls the format of the Micro Focus COBOL index file that will be used when opening or creating a catalog. The available entries are **DEFAULT**, **BTRIEVE**, **CISAM**, **LEVELII**, **IDX4**, and **IDX8**. This configuration parameter cannot be used to change the format of an existing catalog. **DEFAULT** specifies the default Micro Focus COBOL file format for this operating system. **BTRIEVE** specifies the Btrieve file format. **CISAM** specifies the C-ISAM file format. **LEVELII** specifies the Micro Focus COBOL Level II indexed file format. **IDX4** specifies the catalog as an optimized form of the format used by this system, for fast duplicate key handling. **IDX8** specifies the catalog as a large file format file.

New File Format

This configuration parameter controls the format of the Micro Focus COBOL index file that will be used when creating new files because of a CREATE TABLE SQL statement. The available entries are **DEFAULT**, **BTRIEVE**, **CISAM**, **LEVELII**, **IDX4**, and **IDX8**. **DEFAULT** specifies the default Micro Focus COBOL file format for this operating system. **BTRIEVE** specifies the Btrieve file format. **CISAM** specifies the C-ISAM file format. **LEVELII** specifies the Micro Focus COBOL Level II indexed file format. **IDX4** specifies the catalog as an optimized form of the format used by this system for fast duplicate key handling. **IDX8** specifies the file as a large file format file.

Data Compression

This configuration parameter controls the type of data compression to be used when new files are created because of a CREATE TABLE SQL statement. This parameter is the same as the Micro Focus COBOL DATACOMPRESS compiler parameter. The value of **0** indicates that no compression of data records is to take place. The value of **1** indicates that compression algorithm 1 is to be used.

Key Compression – Trailing Spaces

This configuration parameter controls whether compression of trailing spaces is to occur on the keys of new files that are created because of a CREATE TABLE SQL statement. The value **Y** indicates that trailing spaces are to be compressed. The default is **N**, which indicates not to compress trailing spaces.

Key Compression – Leading Characters

This configuration parameter controls whether compression of leading characters is to occur on the keys of new files that are created because of a CREATE TABLE SQL statement. The value **Y** indicates that leading characters that are the same as in the previous key are compressed. The default is **N**, which indicates not to compress leading characters.

Key Compression – Duplicates

This configuration parameter controls whether compression of duplicate keys is to occur on the keys of new files that are created because of a CREATE TABLE SQL statement. The value **Y** indicates that the repetitions of duplicate keys are compressed. The default is **N**, which indicates not to compress duplicate keys.

Key Compression – Sparse Byte

This configuration parameter specifies the decimal number of the sparse character for keys of new files that are created because of creating tables. If this parameter is specified, keys in the file that contain only this value are suppressed. The default is not to suppress keys made up of the sparse character.

RelClientAdmin Utility

The Relativity Client Data Source Administrator utility program, **relclientadmin**, is used to maintain data sources on a UNIX client. This utility can also be used to store the server network name and service port number of Relativity Data Servers on the UNIX client.

The following sections describe the commands and their associated parameters for this utility.

Using the RelClientAdmin Utility Commands and Parameters

Each administrative function, or *command*, performed by the RelClientAdmin utility is addressed separately, in order to document clearly the additional parameters that the command supports.

The following table lists the commands supported by the RelClientAdmin utility.

Verbose	Terse	Description
--add-data-source	-ads	Adds a new client data source.
--add-server	-as	Adds a data server definition.
--list-data-sources	-lds	Lists all existing client data sources.
--list-server-character-sets	-lscs	Lists all of the character sets that a data server supports.
--list-server-data-sources	-lsds	Lists all existing data sources on a data server.
--list-servers	-ls	Lists all data server definitions.
--modify-data-source	-mds	Modifies an existing client data source.
--remove-data-source	-rds	Removes an existing client data source.
--remove-server	-rs	Removes a data server definition.

--show-data-source	-sds	Shows an existing client data source definition.
--------------------	------	--------------------------------------------------

Adding a Data Source

A data source contains information necessary for the Relativity Data Client to open a data source requested by an ODBC application. This command creates a new data source on the client.

To add a data source to a UNIX client, use the following command:

```
relclientadmin --add-data-source Text
  [--driver-name Text]
  [--server-name ServerName]
  --server-data-source-name Text
  [--type {U|S}]
  [--data-source-desc Text]
  [--query-plan {Y|N}]
  [--character-set SignedInteger]
```

where:

- The value of the --add-data-source (-ads) command specifies the name of the new data source.
- The value of the --driver-name (-drv) parameter indicates the name of the ODBC Driver with which to create the new data source. The default is “Relativity Client”.
- The value of the --server-name (-s) parameter indicates the Relativity Data Server to which to associate the data source.
- The value of the --server-data-source-name (-sdsn) parameter indicates the server data source on the data server to which to associate the data source. Use the --list-server-data-sources command to obtain a list of data sources on the data server.
- The value of the --type (-t) parameter specifies the type of the data source. The value **U** indicates a user data source. The value of **S** indicates a system data source.
- The value of the --data-source-desc (-desc) parameter specifies the description to give to the new data source.
- The value of the --query-plan (-qp) parameter specifies whether the new data source should generate query plans. The value of **Y** will cause query plans always to be generated. The value of **N** will cause query plans never to be generated. In order for this parameter to be effective, the server data source must have a --query-plan parameter of **C** (see page 37), which allows the client data source to control the creation of query plans.
- The value of the --character-set (-cs) parameter specifies the number of the character set to use with the new data source. If this parameter is absent, the default character set will be used. Use the --list-server-character-sets command to obtain a list of character sets on the data server.

Example

```
$ relclientadmin --add-data-source Verify  
--server-name aix53  
--server-data-source-name Verify  
  
Data source 'Verify' added.
```

Adding a Server Definition

A server definition is merely a *ServerName* that has been recorded using this command. The Relativity Client Data Source Administrator utility can maintain a set of server definitions for the current user.

Note The set of server definitions is for a future enhancement of the Relativity Client Administrator utility. This set of definitions and this command are of limited use at this time. However, this command's --default parameter is very helpful, particularly, if you are dealing with only one Relativity Data Server. Setting a *ServerName* as the default will eliminate the need to supply the --server-name parameter in other commands.

To add a new server definition, use the following command:

```
relclientadmin --add-server ServerName [--default]
```

where:

- The value of the --add-server (-as) command, *ServerName*, is the network name and service port of the Relativity Data Server to add to the list of server definitions.
- The presence of the --default (-d) parameter indicates that this server is to be the default for the --server-name parameter in other commands.

Example

```
$ relclientadmin --add-server aix53.1583  
Created Relativity data server definition for aix43.1583.
```

Listing Data Sources

A data source name is an identifier that ODBC applications use to access a Relativity database. This list of data source names represents the data sources on the UNIX client that an ODBC application may open.

To display a list of the data sources on a UNIX client, use the following command:

```
relclientadmin --list-data-sources
[--type {U|S|B}]
```

where:

- The value of the --type (-t) parameter specifies the type of data sources to list. The value **U** indicates a user data source. The value of **S** indicates a system data source. The value **B** indicates both user and system data sources. The default is to list both.

Example

```
$ relclientadmin --list-data-sources
Data sources on data client.
____User Data Sources_____
Shirt-3
____System Data Sources_____
Verify
```

Listing Server Character Sets

A character set is an interpretation of the bytes within a data file that represent characters, typically the items with a picture clause of X. Each data file has a character set associated with it, and this information is stored as a fixed attribute within a Relativity database. Relativity is capable of translating these characters from the character set of the data file to the character set of the ODBC application. This command supplies a list of the character sets for which the data server can supply translation.

To display a list of the character sets that a Relativity Data Server supports, use the following command:

```
relclientadmin --list-server-character-sets [ServerName]
[--server-name ServerName]
```

where:

- The value of the --list-server-character-sets (-lscs) command indicates the Relativity Data Server for which to list character sets.
- The value of the --server-name (-s) parameter may also be used to indicate the Relativity Data Server for which to list character sets.

Example

The number to the left of each character set name is the character set's identifier. Use this value in the --character-set parameter of the --add-data-source and --modify-data-source commands.

```
$ relclientadmin --list-server-character-sets aix53

Character sets on data server aix53.
-28. Hebrew 7-bit Old Code
-25. MF EBCDIC (UNIX)
-24. MF EBCDIC (DOS)
-23. RM EBCDIC
-22. IBM-850
-21. SCO Latin 1
-20. STANDARD-2
-16. ISO 8859-16
-15. ISO 8859-15
-14. ISO 8859-14
-13. ISO 8859-13
-11. ISO 8859-11
-10. ISO 8859-10
-9. ISO 8859-9
-8. ISO 8859-8
-7. ISO 8859-7
-6. ISO 8859-6
-5. ISO 8859-5
-4. ISO 8859-4
-3. ISO 8859-3
-2. ISO 8859-2
-1. ISO 8859-1
37. EBCDIC US Canada
.
.
.
1250. Windows Latin 2
1251. Windows Cyrillic
1252. Windows Latin 1
1253. Windows Greek
1254. Windows Latin 5
1255. Windows Hebrew
1256. Windows Arabic
1257. Windows Baltic Rim
1258. Windows 1258
```

Note Those character sets that represent Windows codepages have a positive value the same as their codepage number. Negative numbers represents all other character sets.

Listing Server Data Sources

A data source name is an identifier that ODBC applications use to access a Relativity database. This list of data source names represents the data sources on the Relativity Data Server to which a Relativity Data Client data source may be associated.

To display a list of the data source names on a Relativity Data Server, use the following command:

```
relclientadmin --list-server-data-sources [ServerName]
[--server-name ServerName]
```

where:

- The value of the --list-server-data-sources (-lsds) command indicates the Relativity Data Server for which to list the data sources.
- The value of the --server-name (-s) parameter may also be used to indicate the Relativity Data Server for which to list the data sources.

Example

```
$ relclientadmin --list-data-sources aix53

Data sources on data server aix43.
Shirt-3
Verify
```

Listing Server Definitions

A server definition is merely a *ServerName* that has been recorded using the --add-server command of the Relativity Client Data Source Administrator utility. The Relativity Client Data Source Administrator utility can maintain a set of server definitions for the current user.

Note The set of server definitions is for a future enhancement of the Relativity Client Data Source Administrator utility. This set of definitions and this command are of limited use at this time.

To display a list of the current set of server definitions defined on the UNIX client, use the following command:

```
relclientadmin --list-servers
```

Example

```
$ relclientadmin --list-servers

Relativity data servers defined on this client.
tcp:aix43.1583
tcp:aix43.1584
tcp:hp825.1584
tcp:sco5.1583
tcp:ncr3000.1583
tcp:sunx86.1583
tcp:uw711.1583
tcp:valhalla.1583
tcp:valhalla.1584
```

Modifying a Data Source

A data source contains information necessary for the Relativity Data Client to open a data source requested by an ODBC application. This command alters an existing data source on the client.

To modify a data source on a UNIX client, use the following command. Note that parameter values that are not specified in the command retain their previous value in the data source.

```
relclientadmin --modify-data-source Text
    [--new-data-source-name Text]
    [--driver-name Text]
    [--server-name ServerName]
    [--server-data-source-name Text]
    [--type {U|S}]
    [--data-source-desc Text]
    [--query-plan {Y|N}]
    [--character-set SignedInteger]
```

where:

- The value of the --modify-data-source (-mds) command specifies the current name of the data source.
- The value of the --new-data-source-name (-ndsn) parameter specifies the new name of the data source.
- The value of the --driver-name (-drv) parameter indicates the name of the ODBC Driver with which to create the modify data source. The default is the driver that was used to create the data source.
- The value of the --server-name (-s) parameter indicates the Relativity Data Server to which to associate the data source.
- The value of the --server-data-source-name (-sdsn) parameter indicates the server data source on the data server to which to associate the data source. Use the --list-server-data-sources command to obtain a list of data sources on the data server.
- The value of the --type (-t) parameter specifies the type of the data source indicated by the --modify-data-source parameter. The value **U** indicates a user data source. The value of **S** indicates a system data source. The default is a system data source.
- The value of the --data-source-desc (-desc) parameter specifies the description to give to the data source.
- The value of the --query-plan (-qp) parameter specifies whether the data source should generate query plans. The value of **Y** will cause query plans always to be generated. The value of **N** will cause query plans never to be generated. In order for this parameter to be effective, the server data source must have a --query-plan parameter value of **C** (see page 37), which allows the client data source to control the creation of query plans.
- The value of the --character-set (-cs) parameter specifies the number of the character set to use with the data source. If this parameter is absent, the default

character set will be used. Use the --list-server-character-sets command to obtain a list of character sets on the data server. For more information, see [Listing Server Character Sets](#) (on page 53).

Example

```
$ relclientadmin --modify-data-source Verify --query-plan Y
Data source 'Verify' modified.
```

Removing a Data Source

A data source contains information necessary for the Relativity Data Client to open a data source requested by an ODBC application. This command removes an existing data source on the client.

To remove a data source from a UNIX client, use the following command:

```
relclientadmin --remove-data-source Text
[--driver-name Text]
[--type {U|S}]
```

where:

- The value of the --remove-data-source (-rds) command specifies the name of the data source to remove.
- The value of the --driver-name (-drv) parameter indicates the name of the ODBC Driver with which to remove the new data source. The default is the driver that was used to create the data source.
- The value of the --type (-t) parameter specifies the type of the data source indicated by the --remove-data-source parameter. The value **U** indicates a user data source. The value of **S** indicates a system data source. The default is a system data source.

Example

```
$ relclientadmin --remove-data-source Verify
Removed data source 'Verify'.
```

Removing a Server Definition

A server definition is merely a *ServerName* that has been recorded using the --add-server command of the Relativity Client Data Source Administrator utility . The Relativity Client Data Source Administrator utility can maintain a set of server definitions for the current user.

Note The set of server definitions is for a future enhancement of the Relativity Client Data Source Administrator. This set of definitions and this command are of limited use at this time.

To remove a server definition, use the following command:

```
relclientadmin --remove-server ServerName
```

where:

- The value of the --remove-server (-rs) command specifies the network name and service port of the server definition to remove.

Example

```
$ relclientadmin --remove-server aix53.1583
Relativity data server definition for aix53.1583 removed.
```

Showing a Data Source

A data source contains information necessary for the Relativity Data Client to open a data source requested by an ODBC application. This command shows the current contents of the data source.

To display a data source on a UNIX client, use the following command:

```
relclientadmin -show-data-source Text
[--type {U|S}]
[-env]
```

where:

- The value of the --show-data-source (-sds) command specifies the name of the data source.
- The value of the --type (-t) parameter specifies the type of the data source indicated by the --show-data-source parameter. The value **U** indicates a user data source. The value of **S** indicates a system data source. The default is a system data source.
- The presence of the --env (-e) parameter specifies that the information from the data source be printed to standard output in the form of Bourne shell environment variable assignments. The purpose is to emit the information in a form that will be usable in a script to manipulate or copy an existing data source. The environment variable names and their corresponding parameters are given in the following table:

Variable Name	Parameter
DS_SERVER	--server-name

Variable Name	Parameter
DS_SERVER_DS	--server-data-source-name
DS_DESC	--data-source-desc
DS_QP	--query-plan
DS_TYPE	--type
DS_CS	--character-set

Example

```
$ relclientadmin --show-data-source Verify

Data source 'Verify':
Driver=Relativity Client
Description=Relativity C/S Data Source.
ServerName=aix53.1583
ServerDSN=Verify
QryPlan=0
ArrayFetchOn=1
ArrayBufferSize=8
```

RelClientTest Utility

The Relativity Client Data Source Test utility program, **relclienttest**, is used to test a client data source on the UNIX client and its connection to a server data source. This utility can also be used to issue limited SQL statements to the Relativity Data Server.

The following section describes the command and associated parameters for this utility.

Using the RelClientTest Utility Command and Parameters

The testing function, or *command*, performed by the RelClientTest utility is addressed separately, in order to document clearly the additional parameters that the command supports.

The following table lists the command supported by the RelClientTest utility.

Verbose	Terse	Description
--sql	-s	Executes an SQL SELECT statement on a client data source.

Testing Client Data Sources

To test a data source on a UNIX client, use the following command:

```
relclienttest --sql Text
  --data-source-name Text
  [--user-name Text]
  [--password Text]
  [--rows UnsignedInteger]
```

where:

- The value of the --sql (-s) command is the SQL statement to execute. Only SELECT statements are supported.
- The value of the --data-source-name (-dsn or -d) parameter is the name of the client data source. The value of the --user-name (-u) parameter is the user name with which to connect to the data source. If the --user-name parameter is not present, a connection will be attempted without a user name.
- The value of the --password (-p) parameter is the password with which to connect to the data source. If the --password parameter is not present, a connection will be attempted without a password.
- The value of the --rows (-r) parameter is the maximum number of rows to print from the SELECT statement specified with the --sql parameter. The default value for this parameter is **500**.

Example

```
$ relclienttest --sql "select * from backorder"
  --data-source-name Verify

ProductNumber|ProductSize|Color|PricePerUnit|Price4OrMore|
  BackOrderQuantity|DateStockExpected|
AP1927367D|20W |17|32|29.99|22|19940803|
AP1927466D|24W |03|12|10|0|19940705|
AP2823987D|ML |03|19.99|17|20|19940721|
AP2824597D|ML |17|28|25.99|30|19940701|
AP2824621D|MS |45|20|16.99|120|19940824|
AP2824712D|MM |03|12|10|26|19940724|
PF5430319B|S |37|18|15.3|120|19940615|
PF5430442B|S |37|16|13.6|100|19940615|
PF5430467B|M |73|16|13.6|50|19940601|
PF5431036D|L |78|22.99|18.79|2|19940630|
PF5432000D|L |26|24|20.4|102|19940715|
PG5430418D|XLXT|34|20|17|40|19940630|
PG5430418D|XLXT|37|20|17|10|19940614|
PG5430418D|XLXT|73|20|17|130|19940701|
14 rows returned.
```

RelDriverAdmin Utility

The Relativity Client Driver Administrator utility program, **reldriveradmin**, can be used to maintain the Relativity Data Client driver on a UNIX client. The primary use

of this utility occurs during the install and uninstall processes of the Relativity Data Client.

The following sections describe the commands and their associated parameters for this utility.

Using the RelDriverAdmin Utility Commands and Parameters

Each administrative function, or *command*, performed by the RelDriverAdmin utility is addressed separately, in order to document clearly the additional parameters that the command supports.

The following table lists the commands supported by the RelDriverAdmin utility.

Verbose	Terse	Description
--install-driver	-id	Installs the Relativity Data Client's driver.
--list-drivers	-ld	Lists all drivers installed on the UNIX client.
--uninstall-driver	-ud	Uninstalls the Relativity Data Client's driver.

Installing the Relativity Data Client Driver

“Installing a driver” is the ODBC terminology for this function. This command does not actually install the library files for the Relativity Data Client; the installation script performs that function. Instead, this command registers the Relativity Data Client with the ODBC Driver Manager, so that data sources may be created with the Relativity Data Client.

To install the Relativity Data Client driver, use the following command:

```
reldriveradmin --install-driver [Text]
    --directory Text
    [--driver-library Text]
    [--setup-library Text]
```

where:

- The value of the --install-driver (-id) command specifies the name of the driver. The default value is Relativity Client.
- The value of the --directory (-dir) parameter specifies the name of the directory in which the driver library files are located.
- The value of the --driver-library (-dl) parameter specifies the filename of the main driver library. Note that on HP-UX, the default value is **relclient.sl**. On all other operating systems, the default value is **relclient.so**.
- The value of the --setup-library (-sl) parameter specifies the filename of the driver data source setup library. Note that on HP-UX, the default value is **relclnsu.sl**. On all other operating systems, the default value is **relclnsu.so**.

Example

```
$ reldriveradmin --install-driver "Relativity Client"  
--directory /usr/local/lient/lib  
  
Driver 'Relativity Client' installed.
```

Listing the ODBC Drivers

This command prints a list of all the drivers installed in the Driver Manager, including the Relativity Data Client.

To list the installed ODBC drivers, use the following command:

```
reldriveradmin --list-drivers
```

Example

```
$ reldriveradmin --list-drivers  
  
Drivers on client.  
Relativity Client
```

Uninstalling the Relativity Data Client Driver

This command does not actually uninstall the library files for the Relativity Data Client; the uninstall script performs that function. Instead, this command deregisters the Relativity Data Client with the ODBC Driver Manager.

To uninstall the Relativity Data Client driver, use the following command:

```
reldriveradmin --uninstall-driver [Text]
```

where:

- The value of the --uninstall-driver (-ud) command specifies the name of the driver. The default value is Relativity Client.

Example

```
$ reldriveradmin --uninstall-driver "Relativity Client"  
  
Removed driver 'Relativity Client'.
```

Appendix A: UNIX ODBC Driver Managers

This appendix discusses some of the implementation issues and differences between the ODBC Driver Managers available on UNIX.

Driver Managers on UNIX

An ODBC Driver Manager is not a standard part of any UNIX operating system. Two groups, however, have written open source implementations of a Driver Manager for UNIX, both of which have been tested with the Relativity Data Client for UNIX. These two open source implementations are:

- **iODBC.** iODBC was written by Ke Jin and enhanced by OpenLink Software, Inc. It was released as Open Source under GNU's Lesser General Public License (LGPL) in 1999. More information is available from the web site at <http://www.iodbc.org>.
- **unixODBC.** unixODBC was written by Peter Harvey and enhanced by Easysoft Limited. It was released under GNU's Lesser General Public License (LGPL) and General Public License (GPL). Further information is available from the web site at <http://www.unixodbc.com>.

Note You can read more about the GNU General Public License at <http://www.gnu.org/copyleft/gpl.html> and about the GNU Lesser General Public License at <http://www.gnu.org/copyleft/lesser.html>. These licenses essentially grant the right to distribute the software protected by the license, as long as the source of the original software is also distributed, or made available for the duration of three years.

Differences

In general, these two Driver Managers, iODBC and unixODBC, implement the exact same Application Program Interface (API). However, there are some differences between the two implementations, which are discussed here and in the following topics.

Note Micro Focus does not recommend one implementation over the other.

Because of UNIX compilation mechanisms, an ODBC application that is linked with a specific Driver Manager library should load that same Driver Manager library when the application is executed. It is possible for an ODBC application to be able to load either Driver Manager, but most applications do not use this technique.

It is possible, using UNIX links, to allow an ODBC-enabled application to use a Driver Manager other than the one to which it was linked. However, because an application should use a Driver Manager with which it was tested, and given that the two Driver Manager libraries have different names,

unixODBC

The unixODBC Driver Manager uses a set of files to store information about the data sources and drivers that it manages. Furthermore, it supports both user data sources (those that are visible only to the current user) and system data sources (those that are visible to all users). This section discusses how the unixODBC Driver Manager locates these control files.

Data Source Search Sequence

unixODBC stores information about data sources in a file named **odbc.ini**. There is a pair of these files: one for user data sources and one for system data sources. This section describes how unixODBC locates these files.

When unixODBC searches for a data source, it uses the following search sequence:

1. unixODBC looks for the environment variable, ODBCINI. If it is present, unixODBC retrieves its value and attempts to open a file by that name. If the file is present, unixODBC reads all of the data sources within that file into memory.
2. If the environment variable ODBCINI is not present, unixODBC looks up the home directory for the current user name. (Note that unixODBC is not using the HOME environment variable to do this.) unixODBC attempts to open a file with the name, **.odbc.ini**, in the home directory. If that file is present, unixODBC reads all of the data sources within that file into memory.
3. The system data source file is opened, and the data sources that are within it are appended to the data sources already in memory. The Driver Manager contains the location of the system data source file. If you compile unixODBC yourself, this location will be the directory specified to the configure script by the --prefix parameter, plus “/etc/odbc.ini”. If the –prefix parameter is not specified, the location will be **/usr/local/etc/odbc.ini**.
4. The requested data source is located from within the list of data sources stored in memory.

Driver Search Sequence

unixODBC stores information about drivers in a file named **odbcinst.ini**. This file is used to store the location of the Relativity Data Client driver shared library, among other things.

unixODBC expects this file to be in the same directory where the system data source file is located. If you compile unixODBC yourself, this location will be the directory

specified to the configure script by the --prefix parameter, plus “/etc/odbcinst.ini”. If the --prefix parameter is not specified, the location will be “**/usr/local/etc/odbcinst.ini**”.

iODBC

The iODBC Driver Manager uses a set of files to store information about the data sources and the drivers that it manages. Furthermore, it supports both user data sources (those that are visible only to the current user) and system data sources (those that are visible to all users). iODBC also supports both the user and system driver control files. This section discusses how the iODBC Driver Manager locates the control files.

Data Source Search Sequence

iODBC stores information about data sources in a file named **odbc.ini**. There is a pair of these files: one for user data sources and one for system data sources. This section describes how iODBC locates these files.

When iODBC searches for a data source, it uses the following search sequence:

1. iODBC looks for the environment variable, ODBCINI. If it is present, iODBC retrieves its value and attempts to open a file by that name. If it succeeds, iODBC searches for the data source in this file.
2. If the environment variable ODBCINI is not present, iODBC retrieves the value of the HOME environment variable and appends “/.odbc.ini” to it and attempts to open a file by that name. If it succeeds, iODBC searches for the data source in this file.
3. If the data source has not been located, and searching the system data sources is permitted, iODBC looks for the environment variable, SYSODBCINI. If it is present, iODBC retrieves its value and attempts to open a file by that name. If it succeeds, iODBC searches for the data source in this file.
4. If the environment variable SYSODBCINI is not present, and searching the system data sources is permitted, iODBC opens the configured system data source file and searches for the data source. The Driver Manager contains the location of the system data source file. If you compile iODBC yourself, this location will be the directory specified to the configure script by the --with-iodbc-inidir parameter. If the --with-iodbc-inidir parameter is not specified, the location will be “**/etc/odbc.ini**”.

Driver Search Sequence

iODBC stores information about drivers in a file named **odbcinst.ini**. This file is used to store the location of the Relativity Data Client driver shared library, among other things.

When iODBC searches for this file, it uses the following search sequence:

1. iODBC looks for the environment variable, ODBCINSTINI. If it is present, iODBC retrieves its value and attempts to open a file by that name. If it succeeds, iODBC searches for the driver in this file.

2. If the environment variable ODBCINSTINI is not present, iODBC retrieves the value of the HOME environment variable and appends “`/.odbcinst.ini`” to it and attempts to open a file by that name. If it succeeds, iODBC searches for the driver in this file.
3. If the driver has not been located, and searching the system `odbcinst.ini` file is permitted, iODBC looks for the environment variable, SYSODBCINSTINI. If it is present, iODBC retrieves its value and attempts to open a file by that name. If it succeeds, iODBC searches for the driver in this file.
4. If the environment variable SYSODBCINSTINI is not present, and if searching the system `odbcinst.ini` file is permitted, iODBC opens the configured system `odbcinst.ini` file and searches for the driver. The Driver Manager contains the location of the system `odbcinst.ini` file. If you compile iODBC yourself, this location will be the directory specified to the configure script by the `--with-iodbc-inidir` parameter. If the `--with-iodbc-inidir` parameter is not specified, the location will be “**/etc/odbcinst.ini**”.