

Micro Focus®

Modernization Workbench™

Installing MW Workgroup Edition



Copyright © 2010 Micro Focus (IP) Ltd. All rights reserved.

Micro Focus (IP) Ltd. has made every effort to ensure that this book is correct and accurate, but reserves the right to make changes without notice at its sole discretion at any time. The software described in this document is supplied under a license and may be used or copied only in accordance with the terms of such license, and in particular any warranty of fitness of Micro Focus software products for any particular purpose is expressly excluded and in no event will Micro Focus be liable for any consequential loss.

Micro Focus, the Micro Focus Logo, Micro Focus Server, Micro Focus Studio, Net Express, Net Express Academic Edition, Net Express Personal Edition, Server Express, Mainframe Express, Animator, Application Server, AppMaster Builder, APS, Data Express, Enterprise Server, Enterprise View, EnterpriseLink, Object COBOL Developer Suite, Revolve, Revolve Enterprise Edition, SOA Express, Unlocking the Value of Legacy, and XDB are trademarks or registered trademarks of Micro Focus (IP) Limited in the United Kingdom, the United States and other countries.

IBM®, CICS® and RACF® are registered trademarks, and IMS™ is a trademark, of International Business Machines Corporation.

Copyrights for third party software used in the product:

- The YGrep Search Engine is Copyright (c) 1992-2004 Yves Roumazielles
- Apache web site (<http://www.microfocus.com/docs/links.asp?mfe=apache>)
- Eclipse (<http://www.microfocus.com/docs/links.asp?nx=eclp>)
- Cyrus SASL license
- Open LDAP license

All other trademarks are the property of their respective owners.

No part of this publication, with the exception of the software product user documentation contained on a CD-ROM, may be copied, photocopied, reproduced, transmitted, transcribed, or reduced to any electronic medium or machine-readable form without prior written consent of Micro Focus (IP) Ltd. Contact your Micro Focus representative if you require access to the modified Apache Software Foundation source files.

Licensees may duplicate the software product user documentation contained on a CD-ROM, but only to the extent necessary to support the users authorized access to the software under the license agreement. Any reproduction of the documentation, regardless of whether the documentation is reproduced in whole or in part, must be accompanied by this copyright statement in its entirety, without modification.

U.S. GOVERNMENT RESTRICTED RIGHTS. It is acknowledged that the Software and the Documentation were developed at private expense, that no part is in the public domain, and that the Software and Documentation are Commercial Computer Software provided with RESTRICTED RIGHTS under Federal Acquisition Regulations and agency supplements to them. Use, duplication or disclosure by the U.S. Government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of The Rights in Technical Data and Computer Software clause at DFAR 252.227-7013 et. seq. or subparagraphs (c)(1) and (2) of the Commercial Computer Software Restricted Rights at FAR 52.227-19, as applicable. Contractor is Micro Focus (IP) Ltd, 9420 Key West Avenue, Rockville, Maryland 20850. Rights are reserved under copyright laws of the United States with respect to unpublished portions of the Software.

Contents

Chapter: 1	Overview	1
	Installation Tasks	2
	Deployment	3
Chapter: 2	Hardware and Software Requirements	5
	MW Repository Hardware Requirements	5
	MW Repository Software Requirements	6
	MW Server Hardware Requirements	7
	MW Server Software Requirements	7
	MW Client Hardware Requirements	8
	MW Client Software Requirements	9
Chapter: 3	Installing and Uninstalling Modernization Workbench	11
	Installing the Oracle Database	11
	Installing the MW Database Client	12
	Installing MW on the Server	13
	Installing the Java Add-On	14
	Installing the MW File Server (Optional)	15
	Installing MW on the Client	16
	Installing the MW File Server Client (Optional)	17
	Uninstalling Modernization Workbench	18

Chapter: 4	Post-Installation Administrative Tasks	19
	Configuring Modernization Workbench	19
	Licensing	20
	Oracle Database Setup	22
	Creating a Shared Folder for Workspaces	23
	File Server Setup	23
	Upgrading Workspaces	25
Chapter: 5	Troubleshooting the Installation	27
	Uninstalling Oracle	27
	Troubleshooting Oracle Errors	28
	Troubleshooting Workspace Access	30

This manual describes how to install and configure Modernization Workbench (MW) Workgroup Edition, a suite of software products for analyzing, mining, and re-architecting legacy applications:

- Application Analyzer is the base Modernization Workbench product, used to analyze and document legacy systems at both the application and program levels.
- Business Rule Manager mines business logic from program code and encapsulates the logic in *business rules*.
- Application Architect offers a variety of advanced algorithms for "slicing" logic from program source: all the code needed for a computation, for example, or to "specialize" a program based on the value of a variable.

All three products are installed with Modernization Workbench. Each product is separately licensed.

MW Workgroup Edition is deployed in a multiuser environment with access to a database of application repositories. Each repository defines the objects in an MW workspace and how they interact. Repository setup is the responsibility of a master user, leaving team members free to focus on their tasks.

MW Workgroup Edition installations consist of the following components:

- The MW Repository is an Oracle database containing up to seven repositories, one per MW workspace.
- The MW Server hosts MW workspace files and related support files.
- MW Clients host the link files used to connect to workspaces on the server.
- The MW Database Client is an Oracle client used to connect with the repository. The database client is packaged with both the MW client and MW server, and must be installed wherever the client or server is installed.
- The MW File Server is an optional product for sites that want to restrict Windows access to application source files. As long as you set up workspace folder privileges correctly, ordinary users can view and analyze source files in MW, but cannot access them otherwise. Only the master user has Windows access to the source files.


Installation Tasks

The table below describes the tasks involved in installing MW Workgroup Edition and the order in which the tasks must be performed.

Task	Order	Notes
Install Repository Server	1	
Install Database Client	2	Packaged with both the MW Client and MW Server, and must be installed wherever the client or server is installed.
Install MW on Server	3	
Install Java add-on on Server	4	Optional.
Install File Server	5	Optional.
Install MW on Clients	6	
Install File Server Clients	7	Optional.

Deployment

The figure below shows the standard MW deployment scenario. Nodes inside the blue lasso comprise the product. The role each machine performs and its key relationships are described in the following sections.



Mainframe and Network Server

The mainframe typically hosts the application to be modeled in MW. Application source files are downloaded from the mainframe (and, if necessary, a network server) to the MW server via FTP or SFTP.

Repository Server

The Repository Server hosts the database for one or more multiuser repositories, one repository per MW workspace. This server provides centralized, network-accessible storage for parsed data and analysis output.

MW Server

The MW Server hosts workspaces, workspace support files (including the copies of application source files the workbench creates at workspace loading), and workspace output. This server leverages multiple processes to enhance parsing performance in online or batch mode.

Parsed data is sent via ODBC to the repository server. Some analysis output is stored on the workbench server as well.

NOTE: The MW Server cannot reside on the same machine as the MW Repository. The installation program is the same for the MW client and MW server.

MW Client

MW Clients host the link files that let team members connect to workspaces on the workbench server. These clients access repository data stored in the repository server via ODBC.

NOTE: The installation program is the same for the MW client and MW server.

2

Hardware and Software Requirements

The following tables describe the hardware, disk space, operating system, and software requirements for MW installations.

NOTE: Hardware requirements for the database client are shown in the tables for the workbench client and workbench server. Software requirements for the database client are the same as the software requirements for the workbench client and workbench server. Hardware and software requirements for the file server are the same as the hardware requirements for the workbench client and workbench server.

MW Repository Hardware Requirements

The table below lists the hardware requirements for MW Repository installations. An embedded version of Oracle is installed with the repository. Hardware requirements may vary depending on the size of the application you are analyzing.

Type	Requirement	Notes
Processor	2 x 2.6 GHz	2 physical processors containing single or multiple cores. <i>NOTE: The MW Repository may not be installed on a machine with more than 2 physical processors (occupying 1 socket each).</i>

Type	Requirement	Notes
Physical Memory	4GB RAM	
Virtual Memory	1GB to 3GB	
Hard Drive Storage	Variable	Minimum of 20GB disk space needed for the software installation of the RDBMS and the MW template database. Plus approximately 60X the size in bytes of the application source code modeled in MW.
Hard Drive Requirements	2 or more physical hard drive partitions, fast drives recommended	Enables segmenting data I/O operations for performance-tuning optimizations.

MW Repository Software Requirements

The table below lists the software requirements for MW Repository installations. An embedded version of Oracle is installed with the repository.

Type	Requirement
Operating System	<p>Microsoft Windows XP Professional, Service Pack 3 or higher, 32-bit and 64-bit</p> <p><i>NOTE: Windows XP Professional has a limit of ten simultaneous connections, permitting no more than ten simultaneous MW sessions.</i></p> <p>Microsoft Windows Server 2003, 32-bit and 64-bit Microsoft Windows Vista, 32-bit Microsoft Windows Server 2008, 32-bit</p>

MW Server Hardware Requirements

The table below lists the hardware requirements for MW Server installations. Hardware requirements may vary depending on the size of the application you are analyzing.

Type	Requirement	Notes
Processor	2.6 GHz Dual Core or 2x 3.0+ GHz Processors	Dual processing capability with multiple cores in a processor or separate physical processors.
Physical Memory	3GB RAM	
Virtual Memory	1GB to 3GB	
Hard Drive Storage	Variable	For MW workspaces, approximately 40X size in bytes of the application source code modeled in MW (for example, 100MB source = 4GB). For MW software, minimum 200MB. For Java add-on, minimum 115MB. For database client, minimum 200MB disk space.

MW Server Software Requirements

The table below lists the software requirements for MW Server installations.

Type	Requirement
Operating System	Microsoft Windows XP Professional, Service Pack 3 or higher, 32-bit and 64-bit Microsoft Windows Server 2003, 32-bit and 64-bit Microsoft Windows Vista, 32-bit Microsoft Windows Server 2008, 32-bit Microsoft Windows 7, 32-bit

Type	Requirement
Database Client	For Oracle or DB/2, one configured ODBC data source name (DSN) per database instance.
Internet Explorer 6.0 or higher (optional)	Required to view HTML report outputs.
Microsoft Office (optional)	Required by MW tools with reporting capabilities to save to Microsoft Office file formats.
Microsoft Visio (optional)	Required to generate output as Microsoft Visio .VSD files. <i>NOTE: Visio .VDX files are XML-based and may be generated without Visio being installed on the MW client.</i>
JRE 1.5.0 or higher (optional)	Required for Java add-on. Can be installed after the add-on is installed.

MW Client Hardware Requirements

The table below lists the hardware requirements for MW Client installations. Hardware requirements may vary depending on the size of the application you are analyzing.

Type	Requirement	Notes
Processor	3.0 GHz Processor	Single processor (single or dual core).
Physical Memory	1GB RAM	
Virtual Memory	1GB to 3GB	
Hard Drive Storage	Variable	For MW software, minimum 200 MB. For database client, minimum 200 MB.

MW Client Software Requirements

The table below lists the software requirements for MW Client installations.

Type	Requirement
Operating System	Microsoft Windows XP Professional, Service Pack 3 or higher, 32-bit and 64-bit Microsoft Windows Server 2003, 32-bit and 64-bit Microsoft Windows Vista, 32-bit Microsoft Windows Server 2008, 32-bit Microsoft Windows 7, 32-bit
Database Client	For Oracle or DB/2, one configured ODBC data source name (DSN) per database instance.
Internet Explorer 6.0 or higher (optional)	Required to view HTML report outputs.
Microsoft Office (optional)	Required by MW tools with reporting capabilities to save to Microsoft Office file formats.
Microsoft Visio (optional)	Required to generate output as Microsoft Visio .VSD files. <i>NOTE: Visio .VDX files are XML-based and may be generated without Visio being installed on the MW Client.</i>

3 Installing and Uninstalling Modernization Workbench

Before running an installation program described in this section, make sure you have administrative permissions for the machine on which you are performing the installation. If you do not have administrative permissions, the installation program will not let you continue.

Installing the Oracle Database

The Oracle database packaged with Modernization Workbench stores up to seven MW repositories, one repository per predefined schema. The embedded version of Oracle supplied with the database limits the number of users and does not provide database administration tools. The repository should only be installed with the assistance of Micro Focus on-site personnel.

NOTE: Make sure that Oracle is not already installed. Failure to completely uninstall a previous version of Oracle will cause errors in MW operations.

TASK

1. In the repository installation folder, double-click the setup_32.cmd file. A command window opens.
2. Enter the drive for binary files in the **Select drive for binaries** field, or accept the default. Press Enter.
3. Enter the drive for data files in the **Select drive for data** field, or accept the default. Press Enter.

4. Enter the System Global Area (SGA) size in megabytes in the **SGA size field**, or accept the default. The SGA size must be at least 128 megabytes. Press Enter. The repository server installation begins transferring files to your machine.

*NOTE: If you receive a Windows Security Alert during the installation asking if you want to keep blocking the program, click **Unblock**.*

Installing the MW Database Client

Install the database client wherever you install the workbench client or workbench server. You will need the following information to install the repository client:

- The TCP/IP host name for the machine on which the repository resides.
- The TCP/IP port number for communications with the host, if it is not the standard port number, 1521.
- The SID of the database instance for the repository, RTI.

TASK

1. In the repository client installation folder, double-click the Oracle ODBC 11R1.msi program. The Welcome screen opens.
2. Click **Next**. The License Agreement screen opens. Read the License Agreement carefully. Click **I accept the terms in the license agreement** to accept its terms, then click **Next**.
3. The Destination Folder screen opens. Choose an installation folder. To accept the prefilled value, click Next. To specify a different folder, click **Change** and follow the substeps below:
 - a. Navigate the folder structure to find a suitable location. If the destination folder does not exist, the installation creates it.
 - b. Click **OK** to exit the Change Current Destination Folder screen and return to the Destination Folder screen.
 - c. Click **Next** in the Destination Folder screen.

4. The Database Server screen opens:
 - In the **Database Server** field, enter the TCP/IP host name for the machine on which the repository resides.
 - In the **Port** field, enter the TCP/IP port number for communications with the host, if it is not the standard port number, 1521.
 - In the **SID** field, enter the SID of the database instance for the repository, RTI.
 5. Click **Next**. The Ready to Install the Program screen opens. Click **Install** to begin transferring files to your PC. A progress meter indicates the progress of the transfer.

*NOTE: To make changes to the settings, click **Back** repeatedly until you find the information you are looking for, make the required changes, then click **Next** until you return to the Ready to Install the Program screen.*
 6. When the transfer is complete, the Setup Complete screen opens. Click **Finish**.
-

AFTER COMPLETING THIS TASK: If you need to modify database server information, run Change Program for the Repository Client in the Add or Remove Programs window in the Windows Control Panel.

Installing MW on the Server

The MW Server hosts MW workspace files and related support files. Follow the instructions in this section to install MW on the server. The Micro Focus License Manager is packaged with the installation.

NOTE: The MW Server cannot reside on the same machine as the MW Repository. The installation program is the same for the MW client and MW server.

TASK

1. In the installation folder for the product, double-click the setup.exe program.
 - If the prerequisite software is installed on your machine, the Welcome screen opens.
 - If the prerequisite software is not installed on your machine, the Modernization Workbench Setup screen prompts you to install the

missing software. Click **Install**. When the software been installed, the Welcome screen opens.

2. Click **Next**. The License Agreement screen opens. Read the License Agreement carefully. Click **I accept the terms in the license agreement** to accept its terms, then click **Next**.
3. The Customer Information screen opens. Enter your user name and organization in the **User Name** and **Organization** fields, respectively. Click **Next**.
4. The Destination Folder screen opens. Choose an installation folder. To accept the prefilled value, click **Next**. To specify a different folder, click **Change** and follow the substeps below.
 - a. Navigate the folder structure to find a suitable location. If the destination folder does not exist, the installation creates it.
 - b. Click **OK** to exit the Change Current Destination Folder screen and return to the Destination Folder screen.
 - c. Click **Next** in the Destination Folder screen.
5. The Ready to Install the Program screen opens. Click **Install** to begin transferring files to your machine. A progress meter indicates the progress of the transfer.

*NOTE: To make changes to the settings, click **Back** repeatedly until you find the information you are looking for, make the required changes, then click **Next** until you return to the Ready to Install the Program screen.*

6. When the transfer is complete, the Setup Complete screen opens. Click **Finish**.
-

Installing the Java Add-On

To install the Java add-on, double-click Java.Addon.exe in the installation folder for the product.

Installing the MW File Server (Optional)

The MW File Server is an optional product for sites that want to restrict Windows access to application source files. As long as you set up workspace folder privileges correctly, ordinary users can view and analyze source files in MW, but cannot access them otherwise. Only the master user has Windows access to the source files. If you use the file server, it must be installed on the same machine as the MW server.

TASK

1. In the file server installation folder, double-click the setup.exe program. The Welcome screen opens.
2. Click **Next**. The License Agreement screen opens. Read the License Agreement carefully. Click **I accept the terms in the license agreement** to accept its terms, then click **Next**.
3. The Destination Folder screen opens. Choose an installation folder. To accept the prefilled value, click **Next**. To specify a different folder, click **Change** and follow the substeps below.
 - a. Navigate the folder structure to find a suitable location. If the destination folder does not exist, the installation creates it.
 - b. Click **OK** to exit the Change Current Destination Folder screen and return to the Destination Folder screen.
 - c. Click **Next** in the Destination Folder screen.
4. The Setup Type screen opens. Choose **Custom**, then click **Next**.
5. The Custom Setup screen opens. Choose **RMW File Server**, then click **Next**.
6. The Ready to Install the Program screen opens. Click **Install** to begin transferring files to your machine. A progress meter indicates the progress of the transfer.

*NOTE: To make changes to the settings, click **Back** repeatedly until you find the information you are looking for, make the required changes, then click **Next** until you return to the Ready to Install the Program screen.*

7. When the transfer is complete, the Setup Complete screen opens. Click **Finish**.
-

Installing MW on the Client

MW Clients host the link files used to connect to workspaces on the server. Follow the instructions in this section to install MW on a client. The Micro Focus License Manager is packaged with the installation.

NOTE: The installation program is the same for the MW client and MW server.

TASK

1. In the installation folder for the product, double-click the setup.exe program.
 - If the prerequisite software is installed on your machine, the Welcome screen opens.
 - If the prerequisite software is not installed on your machine, the Modernization Workbench Setup screen prompts you to install the missing software. Click **Install**. When the software been installed, the Welcome screen opens.
2. Click **Next**. The License Agreement screen opens. Read the License Agreement carefully. Click **I accept the terms in the license agreement** to accept its terms, then click **Next**.
3. The Customer Information screen opens. Enter your user name and organization in the **User Name** and **Organization** fields, respectively. Click **Next**.
4. The Destination Folder screen opens. Choose an installation folder. To accept the prefilled value, click **Next**. To specify a different folder, click **Change** and follow the substeps below.
 - a. Navigate the folder structure to find a suitable location. If the destination folder does not exist, the installation creates it.
 - b. Click **OK** to exit the Change Current Destination Folder screen and return to the Destination Folder screen.
 - c. Click **Next** in the Destination Folder screen.
5. The Ready to Install the Program screen opens. Click **Install** to begin transferring files to your machine. A progress meter indicates the progress of the transfer.

*NOTE: To make changes to the settings, click **Back** repeatedly until you find the information you are looking for, make the required changes, then click **Next** until you return to the Ready to Install the Program screen.*

6. When the transfer is complete, the Setup Complete screen opens. Click **Finish**.
-

Installing the MW File Server Client (Optional)

The MW File Server is an optional product for sites that want to restrict Windows access to application source files. As long as you set up workspace folder privileges correctly, ordinary users can view and analyze source files in MW, but cannot access them otherwise. Only the master user has Windows access to the source files. If you use the file server, the file server client must be installed on the same machine as the MW client.

TASK

1. In the file server client installation folder, double-click the setup.exe program. The Welcome screen opens.
2. Click **Next**. The License Agreement screen opens. Read the License Agreement carefully. Click **I accept the terms in the license agreement** to accept its terms, then click **Next**.
3. The Destination Folder screen opens. Choose an installation folder. To accept the prefilled value, click **Next**. To specify a different folder, click **Change** and follow the substeps below.
 - a. Navigate the folder structure to find a suitable location. If the destination folder does not exist, the installation creates it.
 - b. Click **OK** to exit the Change Current Destination Folder screen and return to the Destination Folder screen.
 - c. Click **Next** in the Destination Folder screen.
4. The Setup Type screen opens. Choose **Custom**, then click **Next**.
5. The Custom Setup screen opens. Choose **RMW File Client**, then click **Next**.
6. The Ready to Install the Program screen opens. Click **Install** to begin transferring files to your machine. A progress meter indicates the progress of the transfer.

*NOTE: To make changes to the settings, click **Back** repeatedly until you find the information you are looking for, make the required changes, then click **Next** until you return to the Ready to Install the Program screen.*

7. When the transfer is complete, the Setup Complete screen opens. Click **Finish**.
-

Uninstalling Modernization Workbench

Follow the instructions below to uninstall a Modernization Workbench product. Make sure to close any open MW programs before running the uninstall program.

TASK

1. Choose **Start > Settings > Control Panel**.
 2. In the Control Panel window, double-click the **Add/Remove Programs** icon.
 3. In the Add/Remove Programs window, select the product you want to uninstall, then click **Remove**. You are prompted to confirm that you want to uninstall the product. Click **Yes**.
 4. When the uninstall process completes, it prompts you to restart your computer. Click **Yes** to restart immediately, click **No** if you plan to restart later.
-

4

Post-Installation Administrative Tasks

Before you can work in MW, you must complete the basic administrative tasks described in this section. You are prompted to perform the first of these tasks, configuring the workbench, when you complete the installation.

Configuring Modernization Workbench

Use the Configuration Manager in the Modernization Workbench Administration tool to configure workbench options and displays for the programming languages, dialects, character sets, and products in use at your site.


If you configure your workbench for Cobol, for example, you will see only the workbench options and displays appropriate for Cobol modernization. If it turns out that you need to configure your workbench for PL/I as well, you can always come back to the Configuration Manager and select PL/I in addition to Cobol.

TASK

1. Open the Configuration Manager window.
 - If you are installing MW, the Configuration Manager window opens after you finish the installation.
 - If you have previously installed MW and want to reconfigure it, choose **Start > Programs > Micro Focus > Modernization Workbench Administration**. The Modernization Workbench Administration

window opens. In the **Administer** menu, choose **Configure Workbench**. The Configuration Manager window opens.

*NOTE: If the workbench is open, you are prompted to exit. Click **OK**, then close the workbench.*



2. Select each programming language, dialect, and character set in use at your site. Select each workbench product you want to use at your site. The core Application Analyzer product is always selected. Select **Additional Tools** to enable tools not used in typical workbench configurations. When you are satisfied with your choices, click **OK**.

NOTE: If you modify your workbench configuration, make sure to upgrade workspaces created under the previous configuration.

Licensing

All three Modernization Workbench products (Application Analyzer, Business Rule Manager, and Application Architect) are installed with the workbench. Each product is separately licensed. Follow the instructions in the topics linked below to manage your licenses for MW products.

Application Analyzer Licensing

Application Analyzer users are issued 30-day trial licenses at installation, so that they can work in Modernization Workbench out-of-the-box. A Sentinel RMS license server is installed with the product.

Depending on the licensing model in use at your site, you can manage your license:

- Locally, using the installed Sentinel RMS license server.
- Remotely, using a Sentinel RMS license server that has been configured to manage licenses centrally.

NOTE: The remote license server uses the same software as the local license server that is installed with Modernization Workbench.

Each time you start Modernization Workbench during the trial period, the Micro Focus Licensing System Administration tool notifies you how much of the trial period remains and prompts you to enter a code authorizing a full license:

- If you use a local license server, enter the 16-character license authorization code for Application Analyzer in the **Authorization** field of the Trial License window, then click **Authorize**.
- If you use a remote license server, click **Advanced** on the Trial License window, then click **Change** in the **License server** field. Enter the IP address or server name of the license server, then click **Save**.

*NOTE: You can start the Licensing System Administration tool at any time by choosing **Start > Programs > Micro Focus License Manager > License Management System**.*

Your License System Administrator can tell you which licensing model your site uses and provide you with the name of the remote license server if needed. For complete information, including how to configure a remote license server, refer to the help provided with the Licensing System Administration tool.

NOTE: Application Analyzer licenses provide support for a subset of the parsers available in Modernization Workbench. If you need support for additional parsers, contact support services.

Business Rule Manager and Application Architect Licensing

Trial licenses are not provided for Business Rule Manager and Application Architect. Before you can work in these products, you must enter the 16-character license authorization code for the product. Each product is separately licensed.

Choose **Start > Programs > Micro Focus License Manager > License Management System**. In the Licensing System Administration tool, click the **Authorize** tab, then enter the authorization code in the **Enter authorization code** field and click **Authorize**.

Oracle Database Setup

The Oracle database packaged with Modernization Workbench supports up to seven workspace repositories, one repository per schema. The schema names and ODBC data source name (DSN) are predefined.

When you create an MW workspace, you provide three key pieces of information:

- The ODBC data source name (DSN). The data source name for all workspaces that use the Oracle database is RMW_Repository.
- A unique database schema name. Choose from seven predefined schema names:
 - RMWUSER1 through RMWUSER5, which together share a 30GB tablespace. Use these schemas for smaller workspaces that together contain no more than 75,000 source files.
 - RMWUSERM, which is assigned a 24GB tablespace. Use this schema for a workspace that contains between 25,000 and 50,000 source files.
 - RMWUSERL, which is assigned a 30GB tablespace. Use this schema for a workspace that contains between 50,000 and 75,000 source files.

NOTE: Tablespace usage may vary based on file complexity, type, programming language, and other characteristics. Tablespace limits are extensible, so check with Micro Focus support services before concluding that an application is too large for an available schema.

- A unique database user name, which must be the same as the database schema name. The password for the user name is identical to the user name. So the user name and password for the schema RMWUSER1 should both be RMWUSER1.

Each user who connects to the workspace must provide all three pieces of information. For complete instructions on creating and connecting to workspaces, see *Getting Started* in the workbench documentation set.

Creating a Shared Folder for Workspaces

The folder in which you plan to create workspaces must be shared with team members. It's typically more convenient to share the folder before you create workspaces, but you can do it afterward if necessary, then refresh the workspace path as described in *Getting Started* in the workbench documentation set.

Follow the instructions below to create a shared folder for workspaces. You must be an administrator to create a shared folder.

TASK

1. On the MW server, create a folder for MW workspaces.
2. Select the folder and choose **Sharing and Security** in the right-click menu. The Properties dialog for the folder opens. In the Sharing tab for the Properties dialog, select **Share this folder on the network** (or, on a machine in a Windows domain, **Share this folder**). Enter the share name in the **Share name** field and click **Apply**.

NOTE: Do not embed spaces in the share name. Doing so may cause other users to be unable to access the folder.

3. Click **Permissions**. The Permissions for *Folder* dialog opens. Specify the appropriate permissions for users sharing the folder and click **OK**.
-

File Server Setup

The MW File Server is an optional product for sites that want to restrict Windows access to application source files. As long as you set up workspace folder privileges correctly, ordinary users can view and analyze source files in MW, but cannot access them otherwise. Only the master user has Windows access to the source files.

Follow the instructions below to set up workspace folder privileges. You must be an administrator to perform the first two steps.

NOTE: If your site uses the MW File Server, you cannot configure master users on MW client machines. All users on client machines must be ordinary users.

TASK

1. On the MW server machine, open **Settings > Control Panel > Administrative Tools > Computer Management**. In the Computer Management window, create two groups, MWMasters and MWUsers. The MWMasters group should contain master users, including the administrator. The MWUsers group should contain ordinary users and, if you use the Three-Group Security Policy, subject matter experts (SMEs).

NOTE: Group names are arbitrary. You can use any names you want.

2. On the MW server machine, create a folder for MW workspaces. Select the folder and choose **Sharing and Security** in the right-click menu. The Properties dialog for the folder opens. In the Sharing tab for the Properties dialog, select **Share this folder on the network** (or, on a machine in a Windows domain, **Share this folder**). Enter the share name in the **Share name** field and click **Apply**.

NOTE: Do not embed spaces in the share name. Doing so may cause other users to be unable to access the folder.

3. On the Security tab for the Properties dialog, give full access permissions for the shared folder to the MWMasters and MWUsers groups and to the local SYSTEM account, then click **OK**.
4. Create a new workspace in the shared folder. After defining the connection parameters on the Connection tab, click the Security tab and choose **Secure sources access via RMW file server**. The server name should be the name of the MW server machine. Leave the port number value as is, then click **OK**.

*NOTE: For complete instructions on creating a new workspace, see **Getting Started** in the workbench documentation set.*

5. In the folder for the workspace, right-click the Sources subfolder and choose **Properties**. In the Sources Properties dialog, click the Security tab. On the Security tab, click **Advanced**. In the Advanced Security Settings for Sources dialog, deselect **Inherit from parent...** A Security dialog opens. In the Security dialog, click **Copy**. You are returned to the Advanced Security Settings for Sources dialog.
6. In the Advanced Security Settings for Sources dialog, select **Replace permission entries...** In the Permission entries list, select the MWUsers group and click **Remove**.
7. In the Advanced Security Settings for Sources dialog, click **Add**. The Select Computer, User, or Group dialog opens. In the Select Computer, User, or Group dialog, enter MWMasters (or whatever name you chose for the MW master users group) and click **OK**. The Permission Entry for Sources dialog opens. For the **Full Control** setting, check **Allow**, then

click **OK**. You are returned to the Advanced Security Settings for Sources dialog.

8. In the Advanced Security Settings for Sources dialog, click **OK**. You are prompted to continue. Click **Yes**. In the Sources Properties dialog, click **OK**.
-

Upgrading Workspaces

When you modify your workbench configuration, you must *upgrade* every workspace created with the previous configuration. Only the master user can upgrade a workspace.

TASK

1. Choose **Start > Programs > Micro Focus > Modernization Workbench Administration**. The Modernization Workbench Administration window opens.
 2. In the Administration window, choose **Administer > Upgrade Workspace**. The Upgrade workspace dialog opens, where you can choose the workspace to upgrade.
-

5

Troubleshooting the Installation

Follow the instructions in this section to troubleshoot a Modernization Workbench installation.

Uninstalling Oracle

Failure to completely uninstall a previous version of Oracle will cause errors in MW repository operations. Follow the instructions in this section to uninstall a previous version of Oracle.

NOTE: Uninstalling Oracle should only be undertaken by on-site support services personnel and only with the explicit permission of the client.

TASK

1. Make a backup of the tnsnames.ora and sqlnet.ora files in the `ORACLE_HOME\NETWORK\ADMIN` folder.
2. Choose **Start > Programs > Oracle Installation Products > Universal Installer**. In the Universal Installer dialog, click **Deinstall Products**, then follow the prompts.
3. Choose **Start > Settings > Control Panel > Add/Remove Programs**. In the Add or Remove Programs window, verify that Oracle has been removed. If Oracle still appears in the list, remove it.

4. Choose **Start > Run**. Type `regedit` in the **Open** combo box and click **OK**. Delete the folders `HKEY_CURRENT_USER\SOFTWARE\ORACLE` and `HKEY_LOCAL_MACHINE\SOFTWARE\ORACLE` from the registry.
ADDITIONAL INFORMATION: Under `HKEY_LOCAL_MACHINE\SOFTWARE\ODBC\ODBCINST.INI`, there may be keys `OraDbversion_home1`, `Oracle` in `OraDbversion_home2`, or other Oracle keys. Delete the registry entries with those keys.
Under `HKEY_LOCAL_MACHINE\SOFTWARE\ODBC\ODBCINST.INI\ODBC Drivers`, look for keys `Oracle` in `OraDbversion_home1` or `Oracle` in `OraDbversion_home2`. Delete the registry entries with those keys. Do not delete the entry with the key `Microsoft ODBC for Oracle`.
 5. Choose **Start > Settings > Control Panel > System**. In the System Properties window, click the Advanced tab, then click **Environment Variables**. In the System variables group box, delete the environment variables `ORACLE_HOME` and `TNS_ADMIN`. Edit the `PATH` environment variable to remove any folder path that contains the string `Oracle`. Edit the `PATH`, `CLASSPATH`, and `PERL5LIB` environment variables to remove any folder path that contains the string `Oracle`.
 6. Choose **Start > Settings > Control Panel > Administrative Tools > Services**. In the Services window, verify that Windows services with names starting with `Oracle` are not running. Some examples of such services are `OracleJobSchedulerORCL` and `OracleOraDbversionhome1TNSListener`. If the services still are running, stop them.
 7. Delete the `\Oracle` and `\Program Files\Oracle` folders on your hard drive.
-

Troubleshooting Oracle Errors

Follow the instructions in this section to troubleshoot common Oracle errors.

ORA-01034: ORACLE not available; ORA-27101: shared memory realm does not exist

These errors occur because the Oracle instance is not running. You could be receiving `ORA-27101` because you tried to modify database parameters such as `SGA size`.

ORA-12154: TNS could not resolve service name

This error is always related to your local copy of tnsnames.ora. Check the file in *REPOSITORY_CLIENT_HOME*\RMW Repository Client. It should contain the following entry:

```
RMW_REPOSITORY=  
(DESCRIPTION =  
(ADDRESS_LIST =  
(ADDRESS = (PROTOCOL = TCP)(HOST=hostname)(PORT = 1521))  
)  
(CONNECT_DATA = (SID=RTI))  
)
```

where *hostname* is the TCP/IP host name of the machine hosting the MW repository.

If tnsnames.ora exists in the correct location and does not contain syntax errors, then this error indicates that another Oracle version is installed on the machine. Uninstall the Oracle version.

ORA-12170: TNS: Connect timeout occurred

This error occurs because of firewall issues, database down, listener down, network trouble, and the like. Contact your system administrator or on-site support services personnel for assistance.

ORA-12505: TNS: listener could not resolve SID given in connection description

This error occurs when the SID specified in the connection was not found in the listener's tables. Check listener.ora in *ORACLE_HOME*\NETWORK\ADMIN on the machine hosting the MW repository. It should contain the following entries:

```
SID_LIST_LISTENER =  
(SID_LIST =  
(SID_DESC =  
(SID_NAME = PLSExtProc)  
(ORACLE_HOME = C:\Oracle\RMW21_10201\home)  
(PROGRAM = extproc)  
)  
)  
LISTENER =
```

```
(DESCRIPTION_LIST =  
(DESCRIPTION =  
(ADDRESS = (PROTOCOL = IPC)(KEY = EXTPROC1))  
(ADDRESS = (PROTOCOL = TCP)(HOST = hostname)(PORT = 1521))  
)  
)
```

If listener.ora exists in the correct location and does not contain syntax errors, then this error indicates that another Oracle version is installed on the machine. Uninstall the Oracle version.

Troubleshooting Workspace Access

The folder in which you plan to create workspaces must be shared with team members. If users are unable to access workspaces, it may be because:

- You have not shared the folder for workspaces. Share the folder, then refresh the workspace path as described in *Getting Started* in the workbench documentation set.
- You shared the folder for workspaces after creating a workspace. Refresh the workspace path as described in *Getting Started* in the workbench documentation set.
- You embedded spaces in the value of the **Share name** field for the folder. Remove the spaces, then refresh the workspace path as described in *Getting Started* in the workbench documentation set.